

Enterprise COBOL for z/OS  
6.1

*Programming Guide*



**Note**

Before using this information and the product it supports, be sure to read the general information under [“Notices” on page 829](#).

**First edition (30 June 2022 update)**

This edition applies to Version 6 Release 1 of IBM® Enterprise COBOL for z/OS® (program number 5655-EC6) and to all subsequent releases and modifications until otherwise indicated in new editions. Make sure that you are using the correct edition for the level of the product.

You can view or download softcopy publications free of charge in the [Enterprise COBOL for z/OS library](#). Because Enterprise COBOL for z/OS supports the continuous delivery (CD) model and publications are updated to document the features delivered under the CD model, it is a good idea to check for updates once every two months.

It is our intention to update the product documentation for this release periodically, without updating the order number. If you need to uniquely refer to the version of your product documentation, refer to the order number with the date of update.

© **Copyright International Business Machines Corporation 1991, 2022.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>Tables.....</b>	<b>xix</b>
--------------------	------------

<b>Preface.....</b>	<b>xxv</b>
---------------------	------------

About this information.....	xxv
How this information will help you.....	xxv
Abbreviated terms.....	xxv
Comparison of commonly used terms.....	xxvi
How to read syntax diagrams.....	xxvi
How examples are shown.....	xxvii
Additional documentation and support.....	xxviii
Summary of changes.....	xxviii
Version 6 Release 1 with PTFs installed.....	xxviii
Version 6 Release 1.....	xxix
How to send your comments.....	xxix

<b>Part 1. Coding your program.....</b>	<b>1</b>
---	----------

Chapter 1. Structuring your program.....	3
Identifying a program.....	3
Identifying a program as recursive.....	4
Marking a program as callable by containing programs.....	4
Setting a program to an initial state.....	4
Changing the header of a source listing.....	5
Describing the computing environment.....	5
Example: FILE-CONTROL entries.....	6
Specifying the collating sequence.....	6
Defining symbolic characters.....	8
Defining a user-defined class.....	8
Defining files to the operating system.....	8
Describing the data.....	10
Using data in input and output operations.....	11
Comparison of WORKING-STORAGE and LOCAL-STORAGE.....	13
Using data from another program.....	15
Processing the data.....	16
How logic is divided in the PROCEDURE DIVISION.....	17
Declaratives.....	20
Chapter 2. Using data.....	21
Using variables, structures, literals, and constants.....	21
Using variables.....	21
Using data items and group items.....	22
Using literals.....	23
Using constants.....	24
Using figurative constants.....	24
Assigning values to data items.....	25
Examples: initializing data items.....	26
Initializing a structure (INITIALIZE).....	29
Assigning values to elementary data items (MOVE).....	30
Assigning values to group data items (MOVE).....	31
Assigning arithmetic results (MOVE or COMPUTE).....	32

Assigning input from a screen or file (ACCEPT).....	33
Displaying values on a screen or in a file (DISPLAY).....	33
Displaying data on the system logical output device.....	34
Using WITH NO ADVANCING.....	35
Using intrinsic functions (built-in functions).....	36
Using tables (arrays) and pointers.....	37
Storage and its addressability.....	37
Chapter 3. Working with numbers and arithmetic.....	41
Defining numeric data.....	41
Displaying numeric data.....	43
Controlling how numeric data is stored.....	44
Formats for numeric data.....	45
Examples: numeric data and internal representation.....	48
Data format conversions.....	49
Conversions and precision.....	50
Sign representation of zoned and packed-decimal data.....	51
Checking for incompatible data (numeric class test).....	51
Performing arithmetic.....	53
Using COMPUTE and other arithmetic statements.....	53
Using arithmetic expressions.....	54
Using numeric intrinsic functions.....	54
Using math-oriented callable services.....	56
Using date callable services.....	57
Examples: numeric intrinsic functions.....	57
Fixed-point contrasted with floating-point arithmetic.....	59
Examples: fixed-point and floating-point evaluations.....	61
Using currency signs.....	61
Example: multiple currency signs.....	63
Chapter 4. Handling tables.....	65
Defining a table (OCCURS).....	65
Nesting tables.....	67
Example: subscripting.....	68
Example: indexing.....	68
Referring to an item in a table.....	68
Subscripting.....	69
Indexing.....	70
Putting values into a table.....	71
Loading a table dynamically.....	71
Initializing a table (INITIALIZE).....	71
Assigning values when you define a table (VALUE).....	72
Example: PERFORM and subscripting.....	74
Example: PERFORM and indexing.....	75
Creating variable-length tables (DEPENDING ON).....	76
Loading a variable-length table.....	78
Assigning values to a variable-length table.....	78
Complex OCCURS DEPENDING ON.....	79
Example: complex ODO.....	79
Effects of change in ODO object value.....	80
Searching a table.....	82
Doing a serial search (SEARCH).....	83
Doing a binary search (SEARCH ALL).....	84
Sorting a table.....	85
Processing table items using intrinsic functions.....	85
Example: processing tables using intrinsic functions.....	86
Working with unbounded tables and groups.....	86
Example: Using unbounded tables for parsing XML documents.....	87

Chapter 5. Selecting and repeating program actions.....	89
Selecting program actions.....	89
Coding a choice of actions.....	89
Coding conditional expressions.....	93
Repeating program actions.....	96
Choosing inline or out-of-line PERFORM.....	97
Coding a loop.....	97
Looping through a table.....	98
Executing multiple paragraphs or sections.....	99
Chapter 6. Handling strings.....	101
Joining data items (STRING).....	101
Example: STRING statement.....	102
Splitting data items (UNSTRING).....	103
Example: UNSTRING statement.....	104
Manipulating null-terminated strings.....	106
Example: null-terminated strings.....	106
Referring to substrings of data items.....	107
Reference modifiers.....	108
Example: arithmetic expressions as reference modifiers.....	109
Example: intrinsic functions as reference modifiers.....	109
Tallying and replacing data items (INSPECT).....	110
Examples: INSPECT statement.....	110
Converting data items (intrinsic functions).....	111
Changing case (UPPER-CASE, LOWER-CASE).....	112
Transforming to reverse order (REVERSE).....	112
Converting to numbers (NUMVAL, NUMVAL-C).....	113
Converting from one code page to another.....	114
Evaluating data items (intrinsic functions).....	114
Evaluating single characters for collating sequence.....	115
Finding the largest or smallest data item.....	115
Finding the length of data items.....	117
Finding the date of compilation.....	118
Chapter 7. Processing data in an international environment.....	119
COBOL statements and national data.....	120
Intrinsic functions and national data.....	123
Unicode and the encoding of language characters.....	123
Using national data (Unicode) in COBOL.....	124
Defining national data items.....	125
Using national literals.....	125
Using national-character figurative constants.....	126
Defining national numeric data items.....	127
National groups.....	127
Using national groups.....	128
Storage of character data.....	131
Converting to or from national (Unicode) representation.....	131
Converting alphanumeric, DBCS, and integer to national (MOVE).....	131
Converting alphanumeric or DBCS to national (NATIONAL-OF).....	132
Converting national to alphanumeric (DISPLAY-OF).....	133
Overriding the default code page.....	133
Conversion exceptions.....	133
Example: converting to and from national data.....	133
Processing UTF-8 data.....	134
Using intrinsic functions to process UTF-8 encoded data.....	135
Processing Chinese GB 18030 data.....	139
Comparing national (UTF-16) data.....	140

Comparing two class national operands.....	140
Comparing class national and class numeric operands.....	141
Comparing national numeric and other numeric operands.....	141
Comparing national and other character-string operands.....	142
Comparing national data and alphanumeric-group operands.....	142
Coding for use of DBCS support.....	142
Defining DBCS data.....	143
Using DBCS literals.....	143
Testing for valid DBCS characters.....	144
Processing alphanumeric data items that contain DBCS data.....	144
Chapter 8. Processing files.....	145
File organization and input-output devices.....	145
Choosing file organization and access mode.....	146
Format for coding input and output.....	147
Allocating files.....	148
Checking for input or output errors.....	149
Chapter 9. Processing QSAM files.....	151
Defining QSAM files and records in COBOL.....	151
Establishing record formats.....	152
Setting block sizes.....	158
Coding input and output statements for QSAM files.....	160
Opening QSAM files.....	160
Dynamically creating QSAM files.....	161
Adding records to QSAM files.....	161
Updating QSAM files.....	161
Writing QSAM files to a printer or spooled data set.....	162
Closing QSAM files.....	162
Handling errors in QSAM files.....	163
Working with QSAM files.....	163
Defining and allocating QSAM files.....	164
Retrieving QSAM files.....	166
Ensuring that file attributes match your program.....	167
Using striped extended-format QSAM data sets.....	169
Allocation of buffers for QSAM files.....	170
Accessing z/OS UNIX files using QSAM.....	170
Processing QSAM ASCII files on tape.....	171
Chapter 10. Processing VSAM files.....	173
VSAM files.....	174
Defining VSAM file organization and records.....	175
Specifying sequential organization for VSAM files.....	176
Specifying indexed organization for VSAM files.....	176
Specifying relative organization for VSAM files.....	177
Specifying access modes for VSAM files.....	178
Defining record lengths for VSAM files.....	179
Coding input and output statements for VSAM files.....	180
File position indicator.....	182
Opening a file (ESDS, KSDS, or RRDS).....	182
Reading records from a VSAM file.....	185
Updating records in a VSAM file.....	185
Adding records to a VSAM file.....	186
Replacing records in a VSAM file.....	187
Deleting records from a VSAM file.....	187
Closing VSAM files.....	187
Handling errors in VSAM files.....	188
Protecting VSAM files with a password.....	188

Example: password protection for a VSAM indexed file.....	189
Working with VSAM data sets under z/OS and z/OS UNIX.....	189
Defining VSAM files.....	190
Creating alternate indexes.....	190
Allocating VSAM files.....	192
Sharing VSAM files through RLS.....	193
Allocation of record areas for VSAM files.....	195
Improving VSAM performance.....	195
Extended addressability support.....	196
 Chapter 11. Processing line-sequential files.....	199
Defining line-sequential files and records in COBOL.....	199
Describing the structure of a line-sequential file.....	200
Control characters in line-sequential files.....	200
Allocating line-sequential files.....	200
Coding input-output statements for line-sequential files.....	201
Opening line-sequential files.....	202
Reading records from line-sequential files.....	202
Adding records to line-sequential files.....	203
Closing line-sequential files.....	203
Handling errors in line-sequential files.....	204
 Chapter 12. Sorting and merging files.....	205
Sort and merge process.....	206
Describing the sort or merge file.....	206
Describing the input to sorting or merging.....	207
Example: describing sort and input files for SORT.....	208
Coding the input procedure.....	208
Describing the output from sorting or merging.....	209
Coding the output procedure.....	210
Example: coding the output procedure when using DFSORT.....	210
Restrictions on input and output procedures.....	211
Defining sort and merge data sets.....	211
Sorting variable-length records.....	212
Requesting the sort or merge.....	212
Setting sort or merge criteria.....	213
Example: sorting with input and output procedures.....	214
Choosing alternate collating sequences.....	214
Preserving the original sequence of records with equal keys.....	215
Determining whether the sort or merge was successful.....	215
Stopping a sort or merge operation prematurely.....	216
Improving sort performance with FASTSRT.....	216
FASTSRT requirements for JCL.....	216
FASTSRT requirements for sort input and output files.....	216
Checking for sort errors with NOFASTSRT.....	218
Controlling sort behavior.....	219
Changing DFSORT defaults with control statements.....	220
Allocating storage for sort or merge operations.....	220
Allocating space for sort files.....	221
Using checkpoint/restart with DFSORT.....	221
Sorting under CICS.....	221
CICS SORT application restrictions.....	222
 Chapter 13. Handling errors.....	223
Requesting dumps.....	223
Handling errors in joining and splitting strings.....	224
Handling errors in arithmetic operations.....	224
Example: checking for division by zero.....	225

Handling errors in input and output operations.....	225
Using the end-of-file condition (AT END).....	228
Coding ERROR declaratives.....	228
Using file status keys.....	229
Example: file status key.....	230
Using VSAM status codes (VSAM files only).....	230
Example: checking VSAM status codes.....	231
Coding INVALID KEY phrases.....	232
Example: FILE STATUS and INVALID KEY.....	233
Handling errors when calling programs.....	233
Writing routines for handling errors.....	234

## **Part 2. Compiling and debugging your program.....235**

Chapter 14. Compiling under z/OS.....	237
Compiling with JCL.....	237
Using a cataloged procedure.....	238
Writing JCL to compile programs.....	242
Compiling under TSO.....	244
Example: ALLOCATE and CALL for compiling under TSO.....	245
Example: CLIST for compiling under TSO.....	245
Starting the compiler from an assembler program.....	246
Defining compiler input and output.....	248
Data sets used by the compiler under z/OS.....	248
Defining the source code data set (SYSIN).....	251
Defining a compiler-option data set (SYSOPTF).....	252
Specifying source libraries (SYSLIB).....	252
Defining the output data set (SYSPRINT).....	253
Directing compiler messages to your terminal (SYSTEM).....	253
Creating object code (SYSLIN or SYSPUNCH).....	253
Defining an associated-data file (SYSADATA).....	254
Defining the Java-source output file (SYSJAVA).....	254
Defining the library-processing output file (SYSMDECK).....	254
Specifying compiler options under z/OS.....	255
Specifying compiler options in the PROCESS (CBL) statement.....	256
Example: specifying compiler options using JCL.....	256
Example: specifying compiler options under TSO.....	256
Compiler options and compiler output under z/OS.....	257
Compiling multiple programs (batch compilation).....	258
Example: batch compilation.....	258
Specifying compiler options in a batch compilation.....	259
Example: precedence of options in a batch compilation.....	260
Example: LANGUAGE option in a batch compilation.....	261
Correcting errors in your source program.....	262
Generating a list of compiler messages.....	262
Messages and listings for compiler-detected errors.....	262
Format of compiler diagnostic messages.....	263
Severity codes for compiler diagnostic messages.....	263
Chapter 15. Compiling under z/OS UNIX.....	265
Setting environment variables under z/OS UNIX.....	265
Specifying compiler options under z/OS UNIX.....	266
Compiling and linking with the cob2 command.....	267
Creating a DLL under z/OS UNIX.....	268
Example: using cob2 to compile and link under z/OS UNIX.....	268
cob2 syntax and options.....	269
cob2 input and output files.....	270

Compiling using scripts.....	271
Chapter 16. Compiling, linking, and running OO applications.....	273
Compiling, linking, and running OO applications under z/OS UNIX.....	273
Compiling OO applications under z/OS UNIX.....	273
Preparing OO applications under z/OS UNIX.....	274
Example: compiling and linking a COBOL class definition under z/OS UNIX.....	275
Running OO applications under z/OS UNIX.....	275
Compiling, linking, and running OO applications in JCL or TSO/E.....	277
Compiling OO applications in JCL or TSO/E.....	277
Preparing and running OO applications in JCL or TSO/E.....	278
Example: compiling, linking, and running an OO application using JCL.....	279
Using Java SDKs for z/OS.....	280
Object-oriented syntax, and Java 6, Java 7, or Java 8.....	281
Chapter 17. Compiler options.....	283
Option settings for 85 COBOL Standard conformance.....	286
Conflicting compiler options.....	287
ADATA.....	288
ADV.....	288
AFP.....	289
APOST/QUOTE.....	289
ARCH.....	290
ARITH.....	291
AWO.....	292
BLOCK0.....	293
BUFSIZE.....	294
CICS.....	294
CODEPAGE.....	295
COMPILE.....	297
COPYLOC.....	298
COPYRIGHT.....	299
CURRENCY.....	299
DATA.....	300
DBCS.....	301
DECK.....	301
DIAGTRUNC.....	302
DISPSIGN.....	302
DLL.....	303
DUMP.....	304
DYNAM.....	305
EXIT.....	305
EXPORTALL.....	307
FASTSRT.....	308
FLAG.....	308
FLAGSTD.....	309
HGPR.....	310
INITCHECK.....	311
INLINE.....	312
INTDATE.....	313
LANGUAGE.....	313
LINECOUNT.....	314
LIST.....	315
MAP.....	316
MAXPCF.....	317
MDECK.....	318
NAME.....	319
NSYMBOL.....	319

NUMBER.....	320
NUMCHECK.....	320
NUMPROC.....	322
OBJECT.....	323
OFFSET.....	324
OPTFILE.....	324
OPTIMIZE.....	325
OUTDD.....	326
PARMCHECK.....	327
PGMNAME.....	328
QUALIFY.....	330
RENT.....	330
RMODE.....	331
RULES.....	332
SEQUENCE.....	333
SERVICE.....	334
SOURCE.....	334
SPACE.....	335
SQL.....	335
SQLCCSID.....	336
SQLIMS.....	337
SSRANGE.....	338
STGOPT.....	339
SUPPRESS.....	340
TERMINAL.....	340
TEST.....	340
THREAD.....	343
TRUNC.....	344
VBREF.....	347
VLR.....	347
VSAMOPENFS.....	349
WORD.....	349
XMLPARSE.....	350
XREF.....	350
ZONECHECK.....	352
ZONEDATA.....	353
ZWB.....	355
Chapter 18. Compiler-directing statements.....	357
Chapter 19. Debugging.....	361
Debugging with source language.....	361
Tracing program logic.....	362
Finding and handling input-output errors.....	362
Validating data.....	363
Moving, initializing or setting uninitialized data.....	363
Generating information about procedures.....	363
Debugging using compiler options.....	365
Finding coding errors.....	365
Finding line sequence problems.....	366
Checking for valid ranges.....	366
Selecting the level of error to be diagnosed.....	367
Finding program entity definitions and references.....	369
Listing data items.....	369
Using the debugger.....	370
Getting listings.....	370
Example: short listing.....	372
Example: SOURCE and NUMBER output.....	375

Example: MAP output.....	375
Reading LIST output.....	381
Example: XREF output: data-name cross-references.....	398
Example: OFFSET compiler output.....	402
Example: VBREF compiler output.....	403
<b>Part 3. Targeting COBOL programs for certain environments.....</b>	<b>405</b>
Chapter 20. Developing COBOL programs for CICS.....	407
Coding COBOL programs to run under CICS.....	407
Getting the system date under CICS.....	409
Calling to or from COBOL programs.....	409
Determining the success of ECI calls.....	410
Compiling with the CICS option.....	411
Separating CICS suboptions.....	412
Integrated CICS translator.....	412
Using the separate CICS translator.....	413
CICS reserved-word table.....	414
Handling errors by using CICS HANDLE.....	415
Example: handling errors by using CICS HANDLE.....	415
Chapter 21. Programming for a DB2 environment.....	417
DB2 coprocessor.....	417
Coding SQL statements.....	418
Using SQL INCLUDE with the DB2 coprocessor.....	418
Using character data in SQL statements.....	419
Using national decimal data in SQL statements.....	420
Using national group items in SQL statements.....	420
Using binary items in SQL statements.....	420
Determining the success of SQL statements.....	421
Compiling with the SQL option.....	421
Separating DB2 suboptions.....	422
COBOL and DB2 CCSID determination.....	422
Code-page determination for string host variables in SQL statements.....	423
Programming with the SQLCCSID or NOSQLCCSID option.....	423
Differences in how the DB2 precompiler and coprocessor behave.....	424
Choosing the DYNAM or NODYNAM compiler option.....	426
Chapter 22. Developing COBOL programs for IMS.....	427
IMS SQL coprocessor.....	427
Coding SQLIMS statements.....	428
Using SQLIMS INCLUDE with the IMS SQL coprocessor.....	428
Using character data in SQLIMS statements.....	428
Using binary items in SQLIMS statements.....	429
Determining the success of SQLIMS statements.....	429
Compiling with the SQLIMS option.....	429
Separating IMS suboptions.....	430
Compiling and linking COBOL programs for running under IMS.....	430
Using object-oriented COBOL and Java under IMS.....	431
Calling a COBOL method from a Java application under IMS.....	431
Building a mixed COBOL-Java application that starts with COBOL.....	432
Writing mixed-language IMS applications.....	432
Chapter 23. Running COBOL programs under z/OS UNIX.....	435
Running in z/OS UNIX environments.....	435
Setting and accessing environment variables.....	436
Setting environment variables that affect execution.....	437

Runtime environment variables.....	437
Example: setting and accessing environment variables.....	438
Calling UNIX/POSIX APIs.....	438
Accessing main program parameters under z/OS UNIX.....	440
Example: accessing main program parameters under z/OS UNIX.....	440
<b>Chapter 24. Developing COBOL programs in the mixed AMODE Language Environment.....</b>	<b>443</b>
COBOL programs in AMODE 31 interacting with Java programs in AMODE 64.....	443
Application calls between COBOL programs in AMODE 31 and Java programs in AMODE 64..	443
Building the mixed AMODE COBOL/Java interoperability application .....	444
Running the mixed AMODE COBOL/Java interoperability program.....	444
Examples for mixed AMODE COBOL/Java interoperability application .....	445
<b>Part 4. Structuring complex applications.....</b>	<b>447</b>
<b>Chapter 25. Using subprograms.....</b>	<b>449</b>
Main programs, subprograms, and calls.....	449
Ending and reentering main programs or subprograms.....	450
Transferring control to another program.....	451
Making static calls.....	452
Making dynamic calls.....	452
AMODE switching.....	454
Performance considerations of static and dynamic calls.....	456
Making both static and dynamic calls.....	456
Examples: static and dynamic CALL statements.....	456
Calling nested COBOL programs.....	458
Making recursive calls.....	461
Calling to and from object-oriented programs.....	461
Using procedure and function pointers.....	461
Deciding which type of pointer to use.....	463
Calling alternate entry points.....	464
Making programs reentrant.....	464
<b>Chapter 26. Sharing data.....</b>	<b>465</b>
Passing data.....	465
Describing arguments in the calling program.....	468
Describing parameters in the called program.....	468
Testing for OMITTED arguments.....	469
Coding the LINKAGE SECTION.....	469
Coding the PROCEDURE DIVISION for passing arguments.....	470
Grouping data to be passed.....	470
Handling null-terminated strings.....	471
Using pointers to process a chained list.....	471
Passing return-code information.....	474
Using the RETURN-CODE special register.....	474
Using PROCEDURE DIVISION RETURNING . . .	474
Specifying CALL . . . RETURNING.....	475
Sharing data by using the EXTERNAL clause.....	475
Sharing files between programs (external files).....	475
Example: using external files.....	476
Accessing main program parameters under z/OS.....	478
Example: accessing main program parameters under z/OS.....	479
<b>Chapter 27. Creating a DLL or a DLL application.....</b>	<b>481</b>
Dynamic link libraries (DLLs).....	481
Compiling programs to create DLLs.....	482
Linking DLLs.....	482

Example: sample JCL for a procedural DLL application.....	483
Using CALL identifier with DLLs.....	484
Search order for DLLs in the z/OS UNIX file system.....	484
Using DLL linkage and dynamic calls together.....	485
Using procedure or function pointers with DLLs.....	486
Calling DLLs from non-DLLs.....	486
Example: calling DLLs from non-DLLs.....	487
Using COBOL DLLs with C/C++ programs.....	488
Using DLLs in OO COBOL applications.....	488
Chapter 28. Preparing COBOL programs for multithreading.....	491
Multithreading.....	491
Choosing THREAD to support multithreading.....	492
Transferring control to multithreaded programs.....	493
Ending multithreaded programs.....	493
Processing files with multithreading.....	494
File-definition (FD) storage.....	494
Serializing file access with multithreading.....	495
Example: usage patterns of file input and output with multithreading.....	495
Handling COBOL limitations with multithreading.....	496
<b>Part 5. Using COBOL for Web Services.....</b>	<b>499</b>
Chapter 29. Web Services interface .....	501
Chapter 30. Producing JSON output .....	503
Chapter 31. Processing XML input.....	505
XML parser in COBOL.....	506
Accessing XML documents.....	507
Parsing XML documents.....	508
Writing procedures to process XML.....	509
XML events.....	511
Transforming XML text to COBOL data items.....	516
Parsing XML documents with validation.....	516
Parsing XML documents one segment at a time.....	519
Handling splits using the XML-INFORMATION special register.....	521
The encoding of XML documents.....	522
XML input document encoding.....	523
Parsing XML documents encoded in UTF-8.....	526
Handling XML PARSE exceptions.....	527
How the XML parser handles errors.....	529
Handling encoding conflicts.....	530
Terminating XML parsing.....	531
XML PARSE examples.....	531
Example: parsing a simple document.....	532
Example: program for processing XML.....	532
Example: parsing an XML document that uses namespaces.....	537
Example: parsing an XML document one segment at a time.....	540
Example: parsing XML documents with validation.....	542
Chapter 32. Producing XML output.....	545
Generating XML output.....	545
Controlling the encoding of generated XML output.....	550
Handling XML GENERATE exceptions.....	550
Example: generating XML.....	551
Enhancing XML output.....	555

Example: enhancing XML output.....	556
<b>Part 6. Developing object-oriented programs.....</b>	<b>559</b>
Chapter 33. Writing object-oriented programs.....	561
Example: accounts.....	562
Defining a class.....	564
CLASS-ID paragraph for defining a class.....	565
REPOSITORY paragraph for defining a class.....	566
WORKING-STORAGE SECTION for defining class instance data.....	567
Example: defining a class.....	568
Defining a class instance method.....	568
METHOD-ID paragraph for defining a class instance method.....	569
INPUT-OUTPUT SECTION for defining a class instance method.....	570
DATA DIVISION for defining a class instance method.....	570
PROCEDURE DIVISION for defining a class instance method.....	571
Overriding an instance method.....	572
Overloading an instance method.....	573
Coding attribute (get and set) methods.....	573
Example: defining a method.....	574
Defining a client.....	576
REPOSITORY paragraph for defining a client.....	577
DATA DIVISION for defining a client.....	578
Comparing and setting object references.....	579
Invoking methods (INVOKE).....	580
Creating and initializing instances of classes.....	584
Freeing instances of classes.....	585
Example: defining a client.....	586
Defining a subclass.....	586
CLASS-ID paragraph for defining a subclass.....	587
REPOSITORY paragraph for defining a subclass.....	588
WORKING-STORAGE SECTION for defining subclass instance data.....	588
Defining a subclass instance method.....	588
Example: defining a subclass (with methods).....	589
Defining a factory section.....	590
WORKING-STORAGE SECTION for defining factory data.....	591
Defining a factory method.....	591
Example: defining a factory (with methods).....	593
Wrapping procedure-oriented COBOL programs.....	598
Structuring OO applications.....	598
Examples: COBOL applications that run using the java command.....	599
Chapter 34. Communicating with Java methods.....	601
Accessing JNI services.....	601
Handling Java exceptions.....	602
Managing local and global references.....	603
Java access controls.....	605
Sharing data with Java.....	605
Coding interoperable data types in COBOL and Java.....	606
Declaring arrays and strings for Java.....	606
Manipulating Java arrays.....	608
Manipulating Java strings.....	610
Example: J2EE client written in COBOL.....	613
<b>Part 7. Specialized processing.....</b>	<b>617</b>
Chapter 35. Interrupts and checkpoint/restart.....	619

Setting checkpoints.....	619
Designing checkpoints.....	620
Testing for a successful checkpoint.....	620
DD statements for defining checkpoint data sets.....	620
Messages generated during checkpoint.....	622
Restarting programs.....	622
Requesting automatic restart.....	622
Requesting deferred restart.....	623
Formats for requesting deferred restart.....	623
Resubmitting jobs for restart.....	624
Example: restarting a job at a specific checkpoint step.....	624
Example: requesting a step restart.....	624
Example: resubmitting a job for a step restart.....	625
Example: resubmitting a job for a checkpoint restart.....	625

Chapter 36. Using zlib compression from a COBOL program.....	627
--	-----

## **Part 8. Improving performance and productivity.....631**

Chapter 37. Tuning your program.....	633
Using an optimal programming style.....	633
Using structured programming.....	634
Factoring expressions.....	634
Using symbolic constants.....	634
Choosing efficient data types.....	634
Choosing efficient computational data items.....	635
Using consistent data types.....	635
Making arithmetic expressions efficient.....	635
Making exponentiations efficient.....	636
Using VOLATILE clauses efficiently.....	636
Handling tables efficiently.....	636
Optimization of table references.....	637
Optimizing your code.....	638
Optimization.....	638
Choosing compiler features to enhance performance.....	639
Performance-related compiler options.....	640
Evaluating performance.....	643
Running efficiently with CICS, IMS, or VSAM.....	644
Choosing static or dynamic calls.....	645
Chapter 38. Simplifying coding.....	647
Eliminating repetitive coding.....	647
Example: using the COPY statement.....	648
Using Language Environment callable services.....	649
Sample list of Language Environment callable services.....	650
Calling Language Environment services.....	651
Example: Language Environment callable services.....	651
Using the format 2 SORT statement to sort a table.....	652

## **Appendix A. Intermediate results and arithmetic precision.....655**

Terminology used for intermediate results.....	656
Example: calculation of intermediate results.....	656
Fixed-point data and intermediate results.....	657
Addition, subtraction, multiplication, and division.....	657
Exponentiation.....	658
Example: exponentiation in fixed-point arithmetic.....	659
Truncated intermediate results.....	659

Binary data and intermediate results.....	660
Intrinsic functions evaluated in fixed-point arithmetic.....	660
Integer functions.....	660
Mixed functions.....	661
Floating-point data and intermediate results.....	662
Exponentiations evaluated in floating-point arithmetic.....	662
Intrinsic functions evaluated in floating-point arithmetic.....	663
Arithmetic expressions in nonarithmetic statements.....	663
<b>Appendix B. Converting double-byte character set (DBCS) data.....</b>	<b>665</b>
DBCS notation.....	665
Alphanumeric to DBCS data conversion (IGZCA2D).....	665
IGZCA2D syntax.....	665
IGZCA2D return codes.....	666
Example: IGZCA2D.....	667
DBCS to alphanumeric data conversion (IGZCD2A).....	667
IGZCD2A syntax.....	667
IGZCD2A return codes.....	668
Example: IGZCD2A.....	669
<b>Appendix C. XML reference material.....</b>	<b>671</b>
XML PARSE exceptions with XMLPARSE(XMLSS) in effect.....	671
XML PARSE exceptions with XMLPARSE(COMPAT) in effect.....	673
XML PARSE exceptions that allow continuation.....	673
XML PARSE exceptions that do not allow continuation.....	676
XML GENERATE exceptions.....	679
<b>Appendix D. JSON GENERATE exceptions.....</b>	<b>681</b>
<b>Appendix E. EXIT compiler option.....</b>	<b>683</b>
Using the user-exit work area.....	683
Calling from exit modules.....	684
Processing of INEXIT.....	684
INEXIT parameters.....	684
Processing of LIBEXIT.....	685
Processing of LIBEXIT with nested COPY statements.....	686
LIBEXIT parameters.....	687
Processing of PRTEXTIT.....	688
PRTEXTIT parameters.....	689
Processing of ADEXIT.....	690
ADEXIT parameters.....	690
Processing of MSGEXIT.....	691
MSGEXIT parameters.....	692
Customizing compiler-message severities.....	693
Example: MSGEXIT user exit.....	695
Error handling for exit modules.....	700
Using the EXIT compiler option with CICS, SQL and SQLIMS statements.....	701
<b>Appendix F. JNI.cpy copybook.....</b>	<b>705</b>
<b>Appendix G. COBOL SYSADATA file contents.....</b>	<b>711</b>
Compiler options that affect the SYSADATA file.....	711
SYSADATA record types.....	712
Example: SYSADATA.....	713
SYSADATA record descriptions.....	714
Common header section.....	715

Job identification record: X'0000'	717
ADATA identification record: X'0001'	718
Compilation unit start   end record: X'0002'	718
Options record: X'0010'	719
External symbol record: X'0020'	729
Parse tree record: X'0024'	730
Token record: X'0030'	755
Source error record: X'0032'	782
Source record: X'0038'	782
COPY REPLACING record: X'0039'	783
Symbol record: X'0042'	784
Symbol cross-reference record: X'0044'	796
Nested program record: X'0046'	798
Library record: X'0060'	798
Statistics record: X'0090'	799
EVENTS record: X'0120'	799

## **Appendix H. Using sample programs..... 805**

IGYTCARA: batch application.....	805
Input data for IGYTCARA.....	806
Report produced by IGYTCARA.....	807
Preparing to run IGYTCARA.....	808
IGYTCARB: interactive program.....	809
Preparing to run IGYTCARB.....	809
IGYTSALE: nested program application.....	811
Input data for IGYTSALE.....	812
Reports produced by IGYTSALE.....	814
Preparing to run IGYTSALE.....	818
Language elements and concepts that are illustrated.....	819

## **Appendix I. Accessing JCL parameters.....825**

## **Appendix J. Accessibility features for Enterprise COBOL for z/OS.....827**

## **Notices.....829**

Trademarks.....	830
-----------------	-----

## **Glossary.....833**

## **List of resources..... 873**

Enterprise COBOL for z/OS.....	873
Related publications.....	873

## **Index..... 877**



---

# Tables

1. FILE-CONTROL entries.....	6
2. FILE SECTION entries.....	12
3. Assignment to data items in a program.....	25
4. Effect of RMODE and RENT compiler options on the RMODE attribute.....	39
5. Ranges in value of COMP-5 data items.....	47
6. Internal representation of numeric items.....	48
7. NUMCLS(PRIM) and valid signs.....	52
8. NUMCLS(ALT) and valid signs.....	52
9. Order of evaluation of arithmetic operators.....	54
10. Numeric intrinsic functions.....	55
11. Compatibility of math intrinsic functions and callable services.....	56
12. INTDATE(LILIAN) and compatibility of date intrinsic functions and callable services.....	57
13. INTDATE(ANSI) and compatibility of date intrinsic functions and callable services.....	57
14. Hexadecimal values of the euro sign.....	62
15. COBOL statements and national data.....	120
16. Intrinsic functions and national character data.....	123
17. National group items that are processed with group semantics.....	130
18. Encoding and size of alphanumeric, DBCS, and national data.....	131
19. Summary of file organizations, access modes, and record formats of COBOL files.....	147
20. QSAM file allocation.....	164
21. Maximum record length of QSAM files.....	168
22. Comparison of VSAM, COBOL, and non-VSAM terminology.....	173
23. Comparison of VSAM data-set types.....	174

24. VSAM file organization, access mode, and record format.....	175
25. Definition of VSAM fixed-length records.....	179
26. Definition of VSAM variable-length records.....	180
27. I/O statements for VSAM sequential files.....	181
28. I/O statements for VSAM relative and indexed files.....	181
29. Statements to load records into a VSAM file.....	184
30. Statements to update records in a VSAM file.....	186
31. Methods for improving VSAM performance.....	195
32. Methods for checking for sort errors with NOFASTSORT.....	218
33. Methods for controlling sort behavior.....	219
34. Compiler data sets.....	248
35. Block size of fixed-length compiler data sets.....	251
36. Block size of variable-length compiler data sets.....	251
37. Types of compiler output under z/OS.....	257
38. Severity codes for compiler diagnostic messages.....	263
39. Input files to the cob2 command.....	270
40. Output files from the cob2 command.....	271
41. Commands for compiling and linking a class definition.....	274
42. java command options for customizing the JVM.....	276
43. Compiler options.....	283
44. Mutually exclusive compiler options.....	287
45. EBCDIC multibyte coded character set identifiers.....	296
46. DISPLAY output with the DISPSIGN(COMPAT) option or the DISPSIGN(SEP) option specified:.....	303
47. Values of the LANGUAGE compiler option.....	314
48. Mapping of removed options to new options.....	326

49. Length of record read and file status.....	348
50. Severity levels of compiler messages.....	367
51. Using compiler options to get listings.....	370
52. Terms used in MAP output.....	378
53. Symbols used in LIST and MAP output.....	379
54. Compiler options in the INFO BYTE section.....	382
55. Signature information bytes.....	383
56. Calls between COBOL and assembler under CICS.....	410
57. Compiler options required for the integrated CICS translator.....	411
58. Compiler options required for the separate CICS translator.....	413
59. TRUNC compiler options recommended for the separate CICS translator.....	414
60. Samples with POSIX function calls.....	439
61. Effects of termination statements.....	450
62. Methods for passing data in the CALL statement.....	466
63. Compiler options for DLL applications.....	482
64. Binder options for DLL applications.....	483
65. Special registers used by the XML parser.....	509
66. Results of processing-procedure changes to XML-CODE with XMLPARSE(XMLSS) in effect.....	512
67. Results of processing-procedure changes to XML-CODE with XMLPARSE(COMPAT) in effect.....	513
68. Coded character sets for XML documents.....	522
69. Hexadecimal values of white-space characters.....	524
70. Aliases for XML encoding declarations.....	525
71. Hexadecimal values of special characters for various EBCDIC CCSIDs.....	526
72. XML events and special registers.....	532
73. XML events and special registers.....	537

74. XML events and special registers from parsing XML document with an undeclared namespace prefix.....	539
75. Encoding of generated XML if the ENCODING phrase is omitted.....	550
76. Structure of class definitions.....	564
77. Structure of instance method definitions.....	569
78. Structure of COBOL clients.....	576
79. Conformance of arguments in a COBOL client.....	581
80. Conformance of the returned data item in a COBOL client.....	583
81. Structure of factory definitions.....	590
82. Structure of factory method definitions.....	591
83. JNI services for local and global references.....	604
84. Interoperable data types in COBOL and Java.....	606
85. Interoperable arrays and strings in COBOL and Java.....	606
86. Noninteroperable array types in COBOL and Java.....	607
87. JNI array services.....	608
88. Services that convert between jstring references and national data.....	610
89. Services that convert between jstring references and alphanumeric data.....	611
90. Performance-related compiler options.....	640
91. Performance-tuning worksheet.....	643
92. Language Environment callable services.....	650
93. Comparison of format 1 and format 2 SORT statements.....	652
94. IGZCA2D return codes.....	666
95. IGZCD2A return codes.....	668
96. Reason codes for XML PARSE exceptions that are unique to Enterprise COBOL.....	671
97. XML PARSE exceptions that allow continuation.....	673
98. XML PARSE exceptions that do not allow continuation (for XMLPARSE(COMPAT)).....	676

99. XML GENERATE exceptions.....	679
100. JSON GENERATE exceptions.....	681
101. Layout of the user-exit work area.....	683
102. INEXIT processing.....	684
103. INEXIT parameters.....	684
104. LIBEXIT processing.....	685
105. LIBEXIT processing with nonnested COPY statements.....	686
106. LIBEXIT processing with nested COPY statements.....	687
107. LIBEXIT parameters.....	687
108. PRTEXT processing.....	688
109. PRTEXT parameters.....	689
110. ADEXIT processing.....	690
111. ADEXIT parameters.....	690
112. MSGEXIT processing.....	691
113. MSGEXIT parameters.....	692
114. FIPS (FLAGSTD) message categories.....	694
115. Actions possible in exit modules for CICS, SQL and SQLIMS statements.....	702
116. SYSADATA record types.....	712
117. SYSADATA common header section.....	715
118. SYSADATA job identification record.....	717
119. ADATA identification record.....	718
120. SYSADATA compilation unit start   end record.....	718
121. SYSADATA options record.....	719
122. SYSADATA external symbol record.....	729
123. SYSADATA parse tree record.....	730

124. SYSADATA token record.....	756
125. SYSADATA source error record.....	782
126. SYSADATA source record.....	782
127. SYSADATA COPY REPLACING record.....	783
128. SYSADATA symbol record.....	784
129. SYSADATA symbol cross-reference record.....	796
130. SYSADATA nested program record.....	798
131. SYSADATA library record.....	798
132. SYSADATA statistics record.....	799
133. SYSADATA EVENTS TIMESTAMP record layout.....	800
134. SYSADATA EVENTS PROCESSOR record layout.....	800
135. SYSADATA EVENTS FILE END record layout.....	800
136. SYSADATA EVENTS PROGRAM record layout.....	801
137. SYSADATA EVENTS FILE ID record layout.....	801
138. SYSADATA EVENTS ERROR record layout.....	802

# Preface

---

## About this information

---

This information is for COBOL programmers and system programmers. It helps you understand how to use Enterprise COBOL for z/OS to compile COBOL programs. It also describes the operating system features that you might need to optimize program performance or handle errors.

For information about COBOL language, and for references needed to write a program for an IBM COBOL compiler, see the *Enterprise COBOL for z/OS Language Reference*.

**Important:** Enterprise COBOL for z/OS is referred to as Enterprise COBOL throughout this information.

## How this information will help you

This information will help you write and compile Enterprise COBOL programs. It will also help you define object-oriented classes and methods, invoke methods, and refer to objects in your programs.

This information assumes experience in developing application programs and some knowledge of COBOL. It focuses on using Enterprise COBOL to meet your programming objectives and not on the definition of the COBOL language. For complete information about COBOL syntax, see the *IBM Enterprise COBOL for z/OS Language Reference*.

For information about migrating programs to Enterprise COBOL, see the *IBM Enterprise COBOL for z/OS Migration Guide*.

IBM z/OS Language Environment® provides the runtime environment and runtime services that are required to run Enterprise COBOL programs. You can find information about link-editing and running programs in the *IBM z/OS Language Environment Programming Guide* and *IBM z/OS Language Environment Programming Reference*.

For a comparison of commonly used Enterprise COBOL and Language Environment terms, see [“Comparison of commonly used terms” on page xxvi](#).

## Abbreviated terms

Certain terms are used in a shortened form in this information. Abbreviations for the product names used most frequently are listed alphabetically in the following table.

Term used	Long form
CICS®	CICS Transaction Server
Enterprise COBOL	IBM Enterprise COBOL for z/OS
Language Environment	IBM z/OS Language Environment
MVS™	MVS/ESA
z/OS UNIX	z/OS UNIX System Services

In addition to these abbreviated terms, the term "85 COBOL Standard" is used to refer to the combination of the following standards:

- ISO 1989:1985, Programming languages - COBOL
- ISO/IEC 1989/AMD1:1992, Programming languages - COBOL: Intrinsic function module
- ISO/IEC 1989/AMD2:1994, Programming languages - Correction and clarification amendment for COBOL
- ANSI INCITS 23-1985, Programming Languages - COBOL

- ANSI INCITS 23a-1989, Programming Languages - Intrinsic Function Module for COBOL
- ANSI INCITS 23b-1993, Programming Language - Correction Amendment for COBOL

The ISO standards are identical to the American National standards.

Other terms, if not commonly understood, are shown in *italics* the first time that they appear, and are listed in the glossary.

## Comparison of commonly used terms

To better understand the terms used throughout the IBM z/OS Language Environment and IBM Enterprise COBOL for z/OS information, and to understand which terms are meant to be equivalent, see the following table.

Language Environment term	Enterprise COBOL equivalent
Aggregate	Group item
Array	A table created using the OCCURS clause
Array element	Table element
Enclave	Run unit
External data	WORKING-STORAGE data defined using the EXTERNAL clause
Local data	Any non-EXTERNAL data item
Pass parameters directly, by value	BY VALUE
Pass parameters indirectly, by reference	BY REFERENCE
Pass parameters indirectly, by value	BY CONTENT
Routine	Program
Scalar	Elementary item

## How to read syntax diagrams

Use the following description to read the syntax diagrams in this information.

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The >>--- symbol indicates the beginning of a syntax diagram.

The ---> symbol indicates that the syntax diagram is continued on the next line.

The >--- symbol indicates that the syntax diagram is continued from the previous line.

The --->< symbol indicates the end of a syntax diagram.

Diagrams of syntactical units other than complete statements start with the >--- symbol and end with the ---> symbol.

- Required items appear on the horizontal line (the main path):

▶▶ required\_item ▶▶


- Optional items appear below the main path:

▶▶ required\_item — optional\_item —▶▶

- If you can choose from two or more items, they appear vertically, in a stack. If you must choose one of the items, one item of the stack appears on the main path:



If choosing one of the items is optional, the entire stack appears below the main path:



If one of the items is the default, it appears above the main path and the remaining choices are shown below:



- An arrow returning to the left, above the main line, indicates an item that can be repeated:



If the repeat arrow contains a comma, you must separate repeated items with a comma:



- Keywords appear in uppercase (for example, FROM). They must be spelled exactly as shown. Variables appear in lowercase *italics* (for example, *column-name*). They represent user-supplied names or values.
- If punctuation marks, parentheses, arithmetic operators, or other such symbols are shown, you must enter them as part of the syntax.

## How examples are shown

This information shows numerous examples of sample COBOL statements, program fragments, and small programs to illustrate the coding techniques being described. The examples of program code are written in lowercase, uppercase, or mixed case to demonstrate that you can write your programs in any of these ways.

To more clearly separate some examples from the explanatory text, they are presented in a monospace font.

COBOL keywords and compiler options that appear in text are generally shown in SMALL UPPERCASE. Other terms such as program variable names are sometimes shown in *an italic font* for clarity.

## Additional documentation and support

---

IBM Enterprise COBOL for z/OS provides Portable Document Format (PDF) versions of the entire library for this version and for previous versions on the product site at [www.ibm.com/software/awdtools/cobol/zos/library/](http://www.ibm.com/software/awdtools/cobol/zos/library/).

Support information is also available on the product site at [http://www.ibm.com/support/entry/portal/Overview/Software/Rational/Enterprise\\_COBOL\\_for\\_z~OS](http://www.ibm.com/support/entry/portal/Overview/Software/Rational/Enterprise_COBOL_for_z~OS).

## Summary of changes

---

This section lists the major changes that have been made to this document for Enterprise COBOL Version 6 Release 1 and Version 6 Release 1 with PTFs installed. The latest technical changes are marked within >| and |< in the HTML version, or marked by vertical bars (|) in the left margin in the PDF version.

### Version 6 Release 1 with PTFs installed

#### New, changed, and removed compiler options

- The following compiler options are new:
  - PI68226: INITCHECK (“INITCHECK” on page 311)
  - PI71625: NUMCHECK (“NUMCHECK” on page 320)
  - PI77981: INLINE (“INLINE” on page 312)
  - PI78089: PARMCHECK (“PARMCHECK” on page 327)
  - PI96231: COPYLOC (“COPYLOC” on page 298)
- The following compiler options are modified:
  - PI68023 and PI81838: NOSTGOPT: The default behaviour of the NOSTGOPT compiler option has been changed. (“STGOPT” on page 339)
  - PI74933: SSRANGE: New suboptions MSG and ABD are added to the SSRANGE compiler option to control how the compiler checks reference modification lengths. (“SSRANGE” on page 338)
  - PI98996: NUMCHECK(PAC): For packed decimal (COMP-3) data items that have an even number of digits, the unused bits are checked for zeros. (“NUMCHECK” on page 320)
  - PH01251: NUMCHECK(ZON): New suboptions ALPHNUM | NOALPHNUM are added to the NUMCHECK(ZON) option to control whether the compiler will generate code for an implicit numeric class test for zoned decimal data items that are being compared with an alphanumeric data item, alphanumeric literal or alphanumeric figurative constant. (“NUMCHECK” on page 320)
  - PH13943: NUMCHECK(BIN): NUMCHECK(BIN) will check for binary data items (COMP, COMP-4, and USAGE BINARY) even when TRUNC(BIN) is in effect. (“NUMCHECK” on page 320)
  - PH24414: INITCHECK: New suboptions LAX | STRICT are added to the INITCHECK option to control whether the compiler will issue warning messages for data items unless they are initialized on at least one, or on all, logical paths to a statement. (“INITCHECK” on page 311)
  - Runtime APAR PH20569(V2R2/V2R3/V2R4): The included DWARF diagnostic information when TEST(NOSEPARATE) is in effect can be extracted from the LLA/VLF managed programs. (TEST)
- The following compiler option is removed:
  - PI71625: ZONECHECK is deprecated but is tolerated for compatibility, and it is replaced by NUMCHECK(ZON). (“ZONECHECK” on page 352)

## Statement changes

- PI92944: A new LOC (24 | 31) phrase is added to the ALLOCATE statement to control the location of dynamic storage that is acquired, which overrides the influence of the DATA compiler option. ([“Storage and its addressability” on page 37](#))

## COBOL/JNI interface enhancement

Runtime APAR PH37101(V2R3/V2R4): An enhancement is made to assist COBOL programs running in AMODE 31 to interact with Java™ programs in AMODE 64. ([“COBOL programs in AMODE 31 interacting with Java programs in AMODE 64” on page 443](#))

**Note:** IBM SDK, Java Technology Edition V8.0.6.35 (JVM) is needed for this enhancement.

## Version 6 Release 1

### New, changed, and removed compiler options

- The following compiler options are new:
  - SUPPRESS ([“SUPPRESS” on page 340](#))
  - VSAMOPENFS ([“VSAMOPENFS” on page 349](#))
  - ZONECHECK ([“ZONECHECK” on page 352](#))
- The following compiler options are modified:
  - LANGUAGE: To specify the language of compiler messages, you can use the LANGUAGE compiler option and also set the Language Environment runtime option NATLANG at compile time. ([“LANGUAGE” on page 313](#))
  - SSRANGE: New suboptions ZLEN and NOZLEN are added to the SSRANGE compiler option to control how the compiler checks reference modification lengths. ([“SSRANGE” on page 338](#))

### New statements

- The new JSON GENERATE statement converts data to JSON format. ([Chapter 30, “Producing JSON output,” on page 503](#))

### Listing changes

- Changes are made to the STATIC MAP section of the compilation listing. ([“Example: Static map ” on page 394](#))
- The LVLINFO installation option is removed. The build level information is always included in the listing header.

## How to send your comments

Your feedback is important in helping us to provide accurate, high-quality information. If you have comments about this information or any other Enterprise COBOL documentation, send your comments to: [compinfo@cn.ibm.com](mailto:compinfo@cn.ibm.com).

Be sure to include the name of the document, the publication number, the version of Enterprise COBOL, and, if applicable, the specific location (for example, the page number or section heading) of the text that you are commenting on.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way that IBM believes appropriate without incurring any obligation to you.



---

## Part 1. Coding your program



---

# Chapter 1. Structuring your program

COBOL programs consist of four divisions: IDENTIFICATION DIVISION, ENVIRONMENT DIVISION, DATA DIVISION, and PROCEDURE DIVISION. Each division has a specific logical function.

To define a program, only the IDENTIFICATION DIVISION is required.

To define a COBOL class or method, you need to define some divisions differently than you do for a program.

## related tasks

[“Identifying a program” on page 3](#)

[“Describing the computing environment” on page 5](#)

[“Describing the data” on page 10](#)

[“Processing the data” on page 16](#)

[“Defining a class” on page 564](#)

[“Defining a class instance method” on page 568](#)

[“Structuring OO applications” on page 598](#)

---

## Identifying a program

Use the IDENTIFICATION DIVISION to name a program and optionally provide other identifying information.

You can use the optional AUTHOR, INSTALLATION, DATE-WRITTEN, and DATE-COMPILED paragraphs for descriptive information about a program. The data you enter in the DATE-COMPILED paragraph is replaced with the latest compilation date.

```
IDENTIFICATION DIVISION.  
Program-ID.      Helloprog.  
Author.          A. Programmer.  
Installation.    Computing Laboratories.  
Date-Written.    03/10/2016.  
Date-Compiled.   03/18/2016.
```

Use the PROGRAM-ID paragraph to name your program. The program-name that you assign is used in these ways:

- Other programs use that name to call your program.
- The name appears in the header on each page, except the first, of the program listing that is generated when you compile the program.
- If you use the NAME compiler option, the name is placed on the NAME binder (linkage-editor) control statement to identify the object module that the compilation creates.

**Tip:** Do not use program-names that start with prefixes used by IBM products. If you use program-names that start with any of the following prefixes, your CALL statements might resolve to IBM library or compiler routines rather than to your intended program:

- AFB
- AFH
- CBC
- CEE
- CEH
- CEL
- CEQ
- CEU

- DFH
- DSN
- EDC
- FOR
- IBM
- IFY
- IGY
- IGZ
- ILB

**Tip:** If a program-name is case sensitive, avoid mismatches with the name that the compiler is looking for. Verify that the appropriate setting of the PGMNAME compiler option is in effect.

#### **related tasks**

[“Changing the header of a source listing” on page 5](#)

[“Identifying a program as recursive” on page 4](#)

[“Marking a program as callable by containing programs” on page 4](#)

[“Setting a program to an initial state” on page 4](#)

#### **related references**

Compiler limits (*Enterprise COBOL for z/OS Language Reference*)

Conventions for program-names (*Enterprise COBOL for z/OS Language Reference*)

## **Identifying a program as recursive**

Code the RECURSIVE attribute on the PROGRAM-ID clause to specify that a program can be recursively reentered while a previous invocation is still active.

You can code RECURSIVE only on the outermost program of a compilation unit. Neither nested subprograms nor programs that contain nested subprograms can be recursive. You must code RECURSIVE for programs that you compile with the THREAD option.

Refer to the [“Example: storage sections” on page 14](#), which shows that a recursive program uses both WORKING-STORAGE and LOCAL-STORAGE.

#### **related tasks**

[“Sharing data in recursive or multithreaded programs” on page 15](#)

[“Making recursive calls” on page 461](#)

## **Marking a program as callable by containing programs**

Use the COMMON attribute in the PROGRAM-ID paragraph to specify that a program can be called by the containing program or by any program in the containing program. The COMMON program cannot be called by any program contained in itself.

Only contained programs can have the COMMON attribute.

#### **related concepts**

[“Nested programs” on page 459](#)

## **Setting a program to an initial state**

Use the INITIAL clause in the PROGRAM-ID paragraph to specify that whenever a program is called, that program and any nested programs that it contains are to be placed in their initial state.

When a program is set to its initial state:

- Data items that have VALUE clauses are set to the specified values.

- Changed GO TO statements and PERFORM statements are in their initial states.
- Non-EXTERNAL files are closed.

#### related tasks

[“Ending and reentering main programs or subprograms” on page 450](#)

[“Making static calls” on page 452](#)

[“Making dynamic calls” on page 452](#)

## Changing the header of a source listing

The header on the first page of a source listing contains the identification of the compiler and the current release level, the date and time of compilation, and the page number.

The following example shows these five elements:

```
PP 5655-EC6 IBM Enterprise COBOL for z/OS 6.1.0 P160211    Date 03/18/2016   Time 15:05:19
Page      1
```

The header indicates the compilation platform. You can customize the header on succeeding pages of the listing by using the compiler-directing TITLE statement.

#### related references

TITLE statement (*Enterprise COBOL for z/OS Language Reference*)

## Describing the computing environment

In the ENVIRONMENT DIVISION of a program, you describe the aspects of the program that depend on the computing environment.

Use the CONFIGURATION SECTION to specify the following items:

- Computer for compiling the program (in the SOURCE-COMPUTER paragraph)
- Computer for running the program (in the OBJECT-COMPUTER paragraph)
- Special items such as the currency sign and symbolic characters (in the SPECIAL-NAMES paragraph)
- User-defined classes (in the REPOSITORY paragraph)

Use the FILE-CONTROL and I-O-CONTROL paragraphs of the INPUT-OUTPUT SECTION to:

- Identify and describe the characteristics of the files in the program.
- Associate your files with the external QSAM, VSAM, or z/OS UNIX file system data sets where they physically reside.

The terms *file* in COBOL terminology and *data set* in operating-system terminology have essentially the same meaning and are used interchangeably in this information.

For Customer Information Control System (CICS) and online Information Management System (IMS) message processing programs (MPP), code only the ENVIRONMENT DIVISION header and, optionally, the CONFIGURATION SECTION. Do not code file definitions in your COBOL programs that will run under CICS. IMS allows COBOL definition of files only for batch programs.

- Provide information to control efficient transmission of the data records between your program and the external medium.

[“Example: FILE-CONTROL entries” on page 6](#)

#### related tasks

[“Specifying the collating sequence” on page 6](#)

[“Defining symbolic characters” on page 8](#)

[“Defining a user-defined class” on page 8](#)

[“Defining files to the operating system” on page 8](#)

## related references

Sections and paragraphs (*Enterprise COBOL for z/OS Language Reference*)

## Example: FILE-CONTROL entries

The following table shows example FILE-CONTROL entries for a QSAM sequential file, a VSAM indexed file, and a line-sequential file.

Table 1. <b>FILE-CONTROL</b> entries		
QSAM file	VSAM file	Line-sequential file
SELECT PRINTFILE <sup>1</sup> ASSIGN TO UPDPRINT <sup>2</sup> ORGANIZATION IS SEQUENTIAL <sup>3</sup> ACCESS IS SEQUENTIAL. <sup>4</sup>	SELECT COMMUTER-FILE <sup>1</sup> ASSIGN TO COMMUTER <sup>2</sup> ORGANIZATION IS INDEXED <sup>3</sup> ACCESS IS RANDOM <sup>4</sup> RECORD KEY IS COMMUTER-KEY <sup>5</sup> FILE STATUS IS <sup>5</sup> COMMUTER-FILE- STATUS COMMUTER-VSAM- STATUS.	SELECT PRINTFILE <sup>1</sup> ASSIGN TO UPDPRINT <sup>2</sup> ORGANIZATION IS LINE SEQUENTIAL <sup>3</sup> ACCESS IS SEQUENTIAL. <sup>4</sup>
<ol style="list-style-type: none"><li>1. The SELECT clause chooses a file in the COBOL program to be associated with an external data set.</li><li>2. The ASSIGN clause associates the program's name for the file with the external name for the actual data file. You can define the external name with a DD statement or an environment variable.</li><li>3. The ORGANIZATION clause describes the file's organization. For QSAM files, the ORGANIZATION clause is optional.</li><li>4. The ACCESS MODE clause defines the manner in which the records are made available for processing: sequential, random, or dynamic. For QSAM and line-sequential files, the ACCESS MODE clause is optional. These files always have sequential organization.</li><li>5. For VSAM files, you might have additional statements in the FILE-CONTROL paragraph depending on the type of VSAM file you use.</li></ol>		

## related tasks

Chapter 9, “Processing QSAM files,” on page 151

Chapter 10, “Processing VSAM files,” on page 173

Chapter 11, “Processing line-sequential files,” on page 199

[“Describing the computing environment” on page 5](#)

## Specifying the collating sequence

You can use the PROGRAM COLLATING SEQUENCE clause and the ALPHABET clause of the SPECIAL - NAMES paragraph to establish the collating sequence that is used in several operations on alphanumeric items.

These clauses specify the collating sequence for the following operations on alphanumeric items:

- Comparisons explicitly specified in relation conditions and condition-name conditions
- HIGH-VALUE and LOW-VALUE settings
- SEARCH ALL
- SORT and MERGE unless overridden by a COLLATING SEQUENCE phrase in the SORT or MERGE statement

[“Example: specifying the collating sequence” on page 7](#)

The sequence that you use can be based on one of these alphabets:

- EBCDIC: references the collating sequence associated with the EBCDIC character set
- NATIVE: references the same collating sequence as EBCDIC
- STANDARD-1: references the collating sequence associated with the ASCII character set defined by *ANSI INCITS X3.4, Coded Character Sets - 7-bit American National Standard Code for Information Interchange (7-bit ASCII)*
- STANDARD-2: references the collating sequence associated with the character set defined by *ISO/IEC 646 -- Information technology -- ISO 7-bit coded character set for information interchange, International Reference Version*
- An alteration of the EBCDIC sequence that you define in the SPECIAL - NAMES paragraph

The PROGRAM COLLATING SEQUENCE clause does not affect comparisons that involve national or DBCS operands.

#### **related tasks**

[“Choosing alternate collating sequences” on page 214](#)

[“Comparing national \(UTF-16\) data” on page 140](#)

### **Example: specifying the collating sequence**

The following example shows the ENVIRONMENT DIVISION coding that you can use to specify a collating sequence in which uppercase and lowercase letters are similarly handled in comparisons and in sorting and merging.

When you change the EBCDIC sequence in the SPECIAL - NAMES paragraph, the overall collating sequence is affected, not just the collating sequence of the characters that are included in the SPECIAL - NAMES paragraph.

```
IDENTIFICATION DIVISION.  
.  
ENVIRONMENT DIVISION.  
  CONFIGURATION SECTION.  
    Source-Computer. IBM-390.      Object-Computer. IBM-390  
    Program Collating Sequence Special-Sequence.  
  Special-Names.  
    Alphabet Special-Sequence Is  
      "A" Also "a"  
      "B" Also "b"  
      "C" Also "c"  
      "D" Also "d"  
      "E" Also "e"  
      "F" Also "f"  
      "G" Also "g"  
      "H" Also "h"  
      "I" Also "i"  
      "J" Also "j"  
      "K" Also "k"  
      "L" Also "l"  
      "M" Also "m"  
      "N" Also "n"  
      "O" Also "o"  
      "P" Also "p"  
      "Q" Also "q"  
      "R" Also "r"  
      "S" Also "s"  
      "T" Also "t"  
      "U" Also "u"  
      "V" Also "v"  
      "W" Also "w"  
      "X" Also "x"  
      "Y" Also "y"  
      "Z" Also "z".
```

## related tasks

[“Specifying the collating sequence” on page 6](#)

## Defining symbolic characters

Use the `SYMBOLIC CHARACTERS` clause to give symbolic names to any character of the specified alphabet. Use ordinal position to identify the character, where position 1 corresponds to character `X'00'`.

For example, to give a name to the backspace character (`X'16'` in the EBCDIC alphabet), code:

```
SYMBOLIC CHARACTERS BACKSPACE IS 23
```

## Defining a user-defined class

Use the `CLASS` clause to give a name to a set of characters that you list in the clause.

For example, name the set of digits by coding the following clause:

```
CLASS DIGIT IS "0" THROUGH "9"
```

You can reference the class-name only in a class condition. (This user-defined class is not the same as an object-oriented class.)

## Defining files to the operating system

For all files that you process in your COBOL program, you need to define the files to the operating system with an appropriate system data definition.

Depending on the operating system, this system data definition can take any of the following forms:

- DD statement for MVS JCL.
- `ALLOCATE` command under TSO.
- Environment variable for z/OS or z/OS UNIX. The contents can define either an MVS data set or a file in the z/OS UNIX file system.

The following examples show the relationship of a `FILE-CONTROL` entry to the system data definition and to the `FD` entry in the `FILE SECTION`:

- JCL DD statement:

```
(1)
//OUTFILE DD DSN=MY.OUT171,UNIT=SYSDA,SPACE=(TRK,(50,5))
/*
```

- Environment variable (`export` command):

```
(1)
export OUTFILE=DSN(MY.OUT171),UNIT(SYSDA),SPACE(TRK,(50,5))
```

- COBOL code:

```
ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT CARPOOL
        ASSIGN TO OUTFILE (1)
        ORGANIZATION IS SEQUENTIAL.

DATA DIVISION.
FILE SECTION.
FD CARPOOL (2)
    LABEL RECORD STANDARD
```

```
BLOCK CONTAINS 0 CHARACTERS
RECORD CONTAINS 80 CHARACTERS
```

(1)

The *assignment-name* in the ASSIGN clause points to the *ddname* OUTFILE in the DD statement or the environment variable OUTFILE in the export command:

- `//OUTFILE DD DSN=OUT171 . . .`, or
- `export OUTFILE= . . .`

(2)

When you specify a file *file-name* in a FILE-CONTROL entry, you must describe the file in an FD entry:

```
SELECT CARPOOL
FD CARPOOL
```

### related tasks

[“Optimizing buffer and device space” on page 10](#)

### related references

[“FILE SECTION entries” on page 12](#)

FILE SECTION (*Enterprise COBOL for z/OS Language Reference*)

## Varying the input or output file at run time

The *file-name* that you code in a SELECT clause is used as a constant throughout your COBOL program, but you can associate the name of that file with a different system file at run time.

Changing a file-name within a COBOL program would require changing the input statements and output statements and recompiling the program. Alternatively, you can change the DSN value in the DD statement or the DSN or PATH value in the export command to use a different file at run time.

Environment variable values that are in effect at the time of the OPEN statement are used for associating COBOL file-names to the system file-names (including any path specifications).

The name that you use in the *assignment-name* of the ASSIGN clause must be the same as the *ddname* in the DD statement or the environment variable in the export command.

The *file-name* that you use in the SELECT clause (such as SELECT MASTER) must be the same as in the FD *file-name* entry.

Two files should not use the same *ddname* or environment variable name in their SELECT clauses; otherwise, results could be unpredictable. For example, if DISPLAY output is directed to SYSOUT, do not use SYSOUT as the *ddname* or environment variable name in the SELECT clause for a file.

### Example: using different input files

This example shows that you use the same COBOL program to access different files by coding a DD statement or an export command before the programs runs.

Consider a COBOL program that contains the following SELECT clause:

```
SELECT MASTER ASSIGN TO DA-3330-S-MASTERA
```

Assume the three possible input files are MASTER1, MASTER2, and MASTER3. Before running the program, code one of the following DD statements in the job step that calls for program execution, or issue one of the following export commands from the same shell from which you run the program:

```
//MASTERA DD DSN=MY.MASTER1, . . .
export MASTERA=DSN(MY.MASTER1), . . .

//MASTERA DD DSN=MY.MASTER2, . . .
export MASTERA=DSN(MY.MASTER2), . . .
```

```
//MASTERA      DD  DSN=MY.MASTER3, . . .  
export MASTERA=DSN(MY.MASTER3), . . .
```

Any reference in the program to MASTER will therefore be a reference to the file that is currently assigned to the ddname or environment-variable name MASTERA.

Notice that in this example, you cannot use the PATH (*path*) form of the export command to reference a line-sequential file in the z/OS UNIX file system, because you cannot specify an organization field (S- or AS-) with a line-sequential file.

## Optimizing buffer and device space

Use the APPLY WRITE-ONLY clause to make optimum use of buffer and device space when you create a sequential file with blocked variable-length records.

With APPLY WRITE-ONLY specified, a buffer is truncated only when the next record does not fit in the unused portion of the buffer. Without APPLY WRITE-ONLY specified, a buffer is truncated when it does not have enough space for a maximum-size record.

The APPLY WRITE-ONLY clause has meaning only for sequential files that have variable-length records and are blocked.

The AWO compiler option applies an implicit APPLY WRITE-ONLY clause to all eligible files. The NOAWO compiler option has no effect on files that have the APPLY WRITE-ONLY clause specified. The APPLY WRITE-ONLY clause takes precedence over the NOAWO compiler option.

The APPLY-WRITE ONLY clause can cause input files to use a record area rather than process the data in the buffer. This use might affect the processing of both input files and output files.

### related references

[“AWO” on page 292](#)

## Describing the data

---

Define the characteristics of your data, and group your data definitions into one or more of the sections in the DATA DIVISION.

You can use these sections for defining the following types of data:

- Data used in input-output operations: FILE SECTION
- Data developed for internal processing:
  - To have storage be statically allocated and exist for the life of the *run unit*: WORKING-STORAGE SECTION
  - To have storage be allocated each time a program is entered, and deallocated on return from the program: LOCAL-STORAGE SECTION
- Data from another program: LINKAGE SECTION

The Enterprise COBOL compiler limits the maximum size of DATA DIVISION elements. For details, see the related reference about compiler limits below.

### related concepts

[“Comparison of WORKING-STORAGE and LOCAL-STORAGE” on page 13](#)

### related tasks

[“Using data in input and output operations” on page 11](#)

[“Using data from another program” on page 15](#)

### related references

Compiler limits (*Enterprise COBOL for z/OS Language Reference*)

## Using data in input and output operations

Define the data that you use in input and output operations in the `FILE SECTION`.

Provide the following information about the data:

- Name the input and output files that the program will use. Use the `FD` entry to give names to the files that the input-output statements in the `PROCEDURE DIVISION` can refer to.

Data items defined in the `FILE SECTION` are not available to `PROCEDURE DIVISION` statements until the file has been successfully opened.

- In the record description that follows the `FD` entry, describe the fields of the records in the file:
  - You can code a level-01 description of the entire record, and then in the `WORKING-STORAGE SECTION` code a working copy that describes the fields of the record in more detail. Use the `READ INTO` statement to bring the records into `WORKING-STORAGE`. Processing occurs on the copy of data in `WORKING-STORAGE`. A `WRITE FROM` statement writes processed data into the record area defined in the `FILE SECTION`.
  - The record-name established is the object of `WRITE` and `REWRITE` statements.
  - For `QSAM` files only, you can set the record format in the `RECORDING MODE` clause. If you omit the `RECORDING MODE` clause, the compiler determines the record format based on the `RECORD` clause and on the level-01 record descriptions.
  - For `QSAM` files, you can set a blocking factor for the file in the `BLOCK CONTAINS` clause. If you omit the `BLOCK CONTAINS` clause, the file defaults to unblocked. However, you can override this with `z/OS` data management facilities (including a `DD` file job-control statement).
  - For line-sequential files, you can set a blocking factor for the file in the `BLOCK CONTAINS` clause. When you code `BLOCK CONTAINS 1 RECORDS`, or `BLOCK CONTAINS n CHARACTERS`, where *n* is the length of one logical record in bytes, `WRITE` statements result in the record being transferred immediately to the file rather than being buffered. This technique is useful when you want each record written immediately, such as to an error log.

Programs in the same run unit can share, or have access to, common files. The method for doing this depends on whether the programs are part of a nested (contained) structure or are separately compiled (including programs compiled as part of a batch sequence).

You can use the `EXTERNAL` clause for separately compiled programs. A file that is defined as `EXTERNAL` can be referenced by any program in the run unit that describes the file.

You can use the `GLOBAL` clause for programs in a nested, or contained, structure. If a program contains another program (directly or indirectly), both programs can access a common file by referencing a `GLOBAL` file-name.

### related concepts

[“Nested programs” on page 459](#)

### related tasks

[“Sharing files between programs \(external files\)” on page 475](#)

### related references

[“FILE SECTION entries” on page 12](#)

## FILE SECTION entries

The entries that you can use in the FILE SECTION are summarized in the table below.

Table 2. <b>FILE SECTION entries</b>		
Clause	To define	Notes
FD	The <i>file-name</i> to be referred to in PROCEDURE DIVISION input-output statements (OPEN, CLOSE, READ, also START and DELETE for VSAM)	Must match <i>file-name</i> in the SELECT clause. <i>file-name</i> is associated with a <i>ddname</i> through the <i>assignment-name</i> .
BLOCK CONTAINS	Size of physical records	<p>If the CHARACTERS phrase is specified, size indicates the number of bytes in a record regardless of the USAGE of the data items in the record.</p> <p>QSAM: If provided, must match information on JCL or data-set label. If specified as BLOCK CONTAINS 0, or not provided, the system determines the optimal block size for you.</p> <p>Line sequential: Can be specified to control buffering for WRITE statements.</p> <p>VSAM: Syntax-checked, but has no effect on execution.</p>
RECORD CONTAINS <i>n</i>	Size of logical records (fixed length)	Integer size indicates the number of bytes in a record regardless of the USAGE of the data items in the record. If the clause is provided, it must match information on JCL or data-set label. If <i>n</i> is equal to 0, LRECL must be coded on JCL or data-set label.
RECORD IS VARYING	Size of logical records (variable length)	Integer size or sizes, if specified, indicate the number of bytes in a record regardless of the USAGE of the data items in the record. If the clause is provided, it must match information on JCL or data-set label; compiler checks that record descriptions match.
RECORD CONTAINS <i>n</i> TO <i>m</i>	Size of logical records (variable length)	The integer sizes indicate the number of bytes in a record regardless of the USAGE of the data items in the record. If the clause is provided, it must match information on JCL or data-set label; compiler checks that record descriptions match.
LABEL RECORDS	Labels for QSAM files	VSAM: Handled as comments
STANDARD	Labels exist	QSAM: Handled as comments
OMITTED	Labels do not exist	QSAM: Handled as comments
<i>data-name</i>	Labels defined by the user	QSAM: Allowed for (optional) tape or disk
VALUE OF	An item in the label records associated with file	Comments only
DATA RECORDS	Names of records associated with file	Comments only
LINAGE	Depth of logical page	QSAM only

Table 2. <b>FILE SECTION entries</b> (continued)		
Clause	To define	Notes
CODE-SET	ASCII or EBCDIC files	QSAM only.  When an ASCII file is identified with the CODE-SET clause, the corresponding DD statement might need to have DCB=(OPTCD=Q . . .) or DCB=(RECFM=D . . .) coded if the file was not created using VS COBOL II, COBOL for OS/390® & VM, or IBM Enterprise COBOL for z/OS.
RECORDING MODE	Physical record description	QSAM only

#### related references

FILE SECTION (*Enterprise COBOL for z/OS Language Reference*)

## Comparison of WORKING-STORAGE and LOCAL-STORAGE

How data items are allocated and initialized varies depending on whether the items are in the WORKING-STORAGE SECTION or LOCAL-STORAGE SECTION.

WORKING-STORAGE for programs is allocated when the run unit is started.

Any data items that have VALUE clauses are initialized to the appropriate value at that time. For the duration of the run unit, WORKING-STORAGE items persist in their last-used state. Exceptions are:

- A program with INITIAL specified in the PROGRAM-ID paragraph  
In this case, WORKING-STORAGE data items are reinitialized each time that the program is entered.
- A subprogram that is dynamically called and then canceled  
In this case, WORKING-STORAGE data items are reinitialized on the first reentry into the program following the CANCEL.

WORKING-STORAGE is deallocated at the termination of the run unit.

See the related tasks for information about WORKING-STORAGE in COBOL class definitions.

A separate copy of LOCAL-STORAGE data is allocated for each call of a program or invocation of a method, and is freed on return from the program or method. If you specify a VALUE clause for a LOCAL-STORAGE item, the item is initialized to that value on each call or invocation. If a VALUE clause is not specified, the initial value of the item is undefined.

**Threading:** Each invocation of a program that runs simultaneously on multiple threads shares access to a single copy of WORKING-STORAGE data. Each invocation has a separate copy of LOCAL-STORAGE data.

[“Example: storage sections” on page 14](#)

#### related tasks

[“Ending and reentering main programs or subprograms” on page 450](#)

[Chapter 28, “Preparing COBOL programs for multithreading,” on page 491](#)

[“WORKING-STORAGE SECTION for defining class instance data” on page 567](#)

#### related references

WORKING-STORAGE SECTION (*Enterprise COBOL for z/OS Language Reference*)

LOCAL-STORAGE SECTION (*Enterprise COBOL for z/OS Language Reference*)

## Example: storage sections

The following example is a recursive program that uses both WORKING-STORAGE and LOCAL-STORAGE.

```
CBL pgmn(lu)
*****
* Recursive Program - Factorials
*****
IDENTIFICATION DIVISION.
Program-Id. factorial recursive.
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 numb pic 9(4) value 5.
01 fact pic 9(8) value 0.
LOCAL-STORAGE SECTION.
01 num pic 9(4).
PROCEDURE DIVISION.
    move numb to num.

    if numb = 0
        move 1 to fact
    else
        subtract 1 from numb
        call 'factorial'
        multiply num by fact
    end-if.

    display num '! = ' fact.
    goback.
End Program factorial.
```

The program produces the following output:

```
0000! = 00000001
0001! = 00000001
0002! = 00000002
0003! = 00000006
0004! = 00000024
0005! = 00000120
```

The following tables show the changing values of the data items in LOCAL-STORAGE and WORKING-STORAGE in the successive recursive calls of the program, and in the ensuing gobacks. During the gobacks, fact progressively accumulates the value of 5! (five factorial).

Recursive calls	Value for num in LOCAL-STORAGE	Value for numb in WORKING-STORAGE	Value for fact in WORKING-STORAGE
Main	5	5	0
1	4	4	0
2	3	3	0
3	2	2	0
4	1	1	0
5	0	0	0

Gobacks	Value for num in LOCAL-STORAGE	Value for numb in WORKING-STORAGE	Value for fact in WORKING-STORAGE
5	0	0	1
4	1	0	1

Gobacks	Value for num in LOCAL-STORAGE	Value for numb in WORKING-STORAGE	Value for fact in WORKING-STORAGE
3	2	0	2
2	3	0	6
1	4	0	24
Main	5	0	120

#### **related concepts**

[“Comparison of WORKING-STORAGE and LOCAL-STORAGE” on page 13](#)

## **Using data from another program**

How you share data depends on the type of program. You share data differently in programs that are separately compiled than you do for programs that are nested or for programs that are recursive or multithreaded.

#### **related tasks**

[“Sharing data in separately compiled programs” on page 15](#)

[“Sharing data in nested programs” on page 15](#)

[“Sharing data in recursive or multithreaded programs” on page 15](#)

[“Passing data” on page 465](#)

## **Sharing data in separately compiled programs**

Many applications consist of separately compiled programs that call and pass data to one another. Use the LINKAGE SECTION in the called program to describe the data passed from another program.

In the calling program, code a CALL . . . USING or INVOKE . . . USING statement to pass the data.

#### **related tasks**

[“Passing data” on page 465](#)

[“Coding the LINKAGE SECTION” on page 469](#)

## **Sharing data in nested programs**

Some applications consist of nested programs, that is, programs that are contained in other programs. Level-01 data items can include the GLOBAL attribute. This attribute allows any nested program that includes the declarations to access these data items.

A nested program can also access data items in a sibling program (one at the same nesting level in the same containing program) that is declared with the COMMON attribute.

#### **related concepts**

[“Nested programs” on page 459](#)

## **Sharing data in recursive or multithreaded programs**

If your program has the RECURSIVE attribute or is compiled with the THREAD compiler option, data that is defined in the LINKAGE SECTION is not accessible on subsequent invocations of the program.

To address a record in the LINKAGE SECTION, use either of these techniques:

- Pass an argument to the program and specify the record in an appropriate position in the USING phrase in the program.
- Use the format-5 SET statement.

If your program has the `RECURSIVE` attribute or is compiled with the `THREAD` compiler option, the address of the record is valid for a particular instance of the program invocation. The address of the record in another execution instance of the same program must be reestablished for that execution instance. Unpredictable results will occur if you refer to a data item for which the address has not been established.

#### **related concepts**

[“Multithreading” on page 491](#)

#### **related tasks**

[“Making recursive calls” on page 461](#)

[“Processing files with multithreading” on page 494](#)

#### **related references**

[“THREAD” on page 343](#)

SET statement (*Enterprise COBOL for z/OS Language Reference*)

## Processing the data

---

In the `PROCEDURE DIVISION` of a program, you code the executable statements that process the data that you defined in the other divisions. The `PROCEDURE DIVISION` contains one or two headers and the logic of your program.

The `PROCEDURE DIVISION` begins with the division header and a procedure-name header. The division header for a program can simply be:

```
PROCEDURE DIVISION.
```

You can code the division header to receive parameters by using the `USING` phrase, or to return a value by using the `RETURNING` phrase.

To receive an argument that was passed by reference (the default) or by content, code the division header for a program in either of these ways:

```
PROCEDURE DIVISION USING dataname  
PROCEDURE DIVISION USING BY REFERENCE dataname
```

Be sure to define *dataname* in the `LINKAGE SECTION` of the `DATA DIVISION`.

To receive a parameter that was passed by value, code the division header for a program as follows:

```
PROCEDURE DIVISION USING BY VALUE dataname
```

To return a value as a result, code the division header as follows:

```
PROCEDURE DIVISION RETURNING dataname2
```

You can also combine `USING` and `RETURNING` in a `PROCEDURE DIVISION` header:

```
PROCEDURE DIVISION USING dataname RETURNING dataname2
```

Be sure to define *dataname* and *dataname2* in the `LINKAGE SECTION`.

#### **related concepts**

[“How logic is divided in the PROCEDURE DIVISION” on page 17](#)

#### **related tasks**

[“Coding the LINKAGE SECTION” on page 469](#)

[“Coding the PROCEDURE DIVISION](#)

[for passing arguments” on page 470](#)

[“Using PROCEDURE DIVISION RETURNING . . .” on page 474](#)

[“Eliminating repetitive coding” on page 647](#)

#### **related references**

The procedure division header (*Enterprise COBOL for z/OS Language Reference*)

The USING phrase (*Enterprise COBOL for z/OS Language Reference*)

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

## **How logic is divided in the PROCEDURE DIVISION**

The PROCEDURE DIVISION of a program is divided into sections and paragraphs, which contain sentences, statements, and phrases.

### **Section**

Logical subdivision of your processing logic.

A section has a section header and is optionally followed by one or more paragraphs.

A section can be the subject of a PERFORM statement. One type of section is for declaratives.

### **Paragraph**

Subdivision of a section, procedure, or program.

A paragraph has a name followed by a period and zero or more sentences.

A paragraph can be the subject of a statement.

### **Sentence**

Series of one or more COBOL statements that ends with a period.

### **Statement**

Performs a defined step of COBOL processing, such as adding two numbers.

A statement is a valid combination of words, and begins with a COBOL statement. Statements are imperative (indicating unconditional action), conditional, or compiler-directing. Using explicit scope terminators instead of periods to show the logical end of a statement is preferred.

### **Phrase**

A subdivision of a statement.

#### **related concepts**

[“Compiler-directing statements” on page 19](#)

[“Scope terminators” on page 19](#)

[“Imperative statements” on page 17](#)

[“Conditional statements” on page 18](#)

[“Declaratives” on page 20](#)

#### **related references**

PROCEDURE DIVISION structure

(*Enterprise COBOL for z/OS Language Reference*)

## **Imperative statements**

An imperative statement (such as ADD, MOVE, INVOKE, or CLOSE) indicates an unconditional action to be taken.

You can end an imperative statement with an implicit or explicit scope terminator.

A conditional statement that ends with an explicit scope terminator becomes an imperative statement called a *delimited scope statement*. Only imperative statements (or delimited scope statements) can be nested.

### related concepts

[“Conditional statements” on page 18](#)

[“Scope terminators” on page 19](#)

## Conditional statements

A conditional statement is either a simple conditional statement (IF, EVALUATE, SEARCH) or a conditional statement made up of an imperative statement that includes a conditional phrase or option.

You can end a conditional statement with an implicit or explicit scope terminator. If you end a conditional statement explicitly, it becomes a delimited scope statement (which is an imperative statement).

You can use a delimited scope statement in these ways:

- To delimit the range of operation for a COBOL conditional statement and to explicitly show the levels of nesting

For example, use an END-IF phrase instead of a period to end the scope of an IF statement within a nested IF.

- To code a conditional statement where the COBOL syntax calls for an imperative statement

For example, code a conditional statement as the object of an inline PERFORM:

```
PERFORM UNTIL TRANSACTION-EOF
  PERFORM 200-EDIT-UPDATE-TRANSACTION
  IF NO-ERRORS
    PERFORM 300-UPDATE-COMMUTER-RECORD
  ELSE
    PERFORM 400-PRINT-TRANSACTION-ERRORS
  END-IF
  READ UPDATE-TRANSACTION-FILE INTO WS-TRANSACTION-RECORD
  AT END
    SET TRANSACTION-EOF TO TRUE
  END-READ
END-PERFORM
```

An explicit scope terminator is required for the inline PERFORM statement, but it is not valid for the out-of-line PERFORM statement.

For additional program control, you can use the NOT phrase with conditional statements. For example, you can provide instructions to be performed when a particular exception does not occur, such as NOT ON SIZE ERROR. The NOT phrase cannot be used with the ON OVERFLOW phrase of the CALL statement, but it can be used with the ON EXCEPTION phrase.

Do not nest conditional statements. Nested statements must be imperative statements (or delimited scope statements) and must follow the rules for imperative statements.

The following statements are examples of conditional statements if they are coded without scope terminators:

- Arithmetic statement with ON SIZE ERROR
- Data-manipulation statements with ON OVERFLOW
- CALL statements with ON OVERFLOW
- I/O statements with INVALID KEY, AT END, or AT END-OF-PAGE
- RETURN with AT END

### related concepts

[“Imperative statements” on page 17](#)

[“Scope terminators” on page 19](#)

### related tasks

[“Selecting program actions” on page 89](#)

## related references

Conditional statements (*Enterprise COBOL for z/OS Language Reference*)

## Compiler-directing statements

A compiler-directing statement causes the compiler to take specific action about the program structure, COPY processing, listing control, or control flow.

A compiler-directing statement is not part of the program logic.

## related references

[Chapter 18, “Compiler-directing statements,” on page 357](#)

Compiler-directing statements (*Enterprise COBOL for z/OS Language Reference*)

## Scope terminators

A scope terminator ends a statement. Scope terminators can be explicit or implicit.

Explicit scope terminators end a statement without ending a sentence. They consist of END followed by a hyphen and the name of the statement being terminated, such as END-IF. An implicit scope terminator is a period (.) that ends the scope of all previous statements not yet ended.

Each of the two periods in the following program fragment ends an IF statement, making the code equivalent to the code after it that instead uses explicit scope terminators:

```
IF ITEM = "A"
  DISPLAY "THE VALUE OF ITEM IS " ITEM
  ADD 1 TO TOTAL
  MOVE "C" TO ITEM
  DISPLAY "THE VALUE OF ITEM IS NOW " ITEM.
IF ITEM = "B"
  ADD 2 TO TOTAL.
```

```
IF ITEM = "A"
  DISPLAY "THE VALUE OF ITEM IS " ITEM
  ADD 1 TO TOTAL
  MOVE "C" TO ITEM
  DISPLAY "THE VALUE OF ITEM IS NOW " ITEM
END-IF
IF ITEM = "B"
  ADD 2 TO TOTAL
END-IF
```

If you use implicit terminators, the end of statements can be unclear. As a result, you might end statements unintentionally, changing your program's logic. Explicit scope terminators make a program easier to understand and prevent unintentional ending of statements. For example, in the program fragment below, changing the location of the first period in the first implicit scope example changes the meaning of the code:

```
IF ITEM = "A"
  DISPLAY "VALUE OF ITEM IS " ITEM
  ADD 1 TO TOTAL.
  MOVE "C" TO ITEM
  DISPLAY " VALUE OF ITEM IS NOW " ITEM
IF ITEM = "B"
  ADD 2 TO TOTAL.
```

The MOVE statement and the DISPLAY statement after it are performed regardless of the value of ITEM, despite what the indentation indicates, because the first period terminates the IF statement.

For improved program clarity and to avoid unintentional ending of statements, use explicit scope terminators, especially within paragraphs. Use implicit scope terminators only at the end of a paragraph or the end of a program.

Be careful when coding an explicit scope terminator for an imperative statement that is nested within a conditional statement. Ensure that the scope terminator is paired with the statement for which it was intended. In the following example, the scope terminator will be paired with the second READ statement, though the programmer intended it to be paired with the first.

```
READ FILE1
  AT END
    MOVE A TO B
  READ FILE2
END-READ
```

To ensure that the explicit scope terminator is paired with the intended statement, the preceding example can be recoded in this way:

```
READ FILE1
  AT END
    MOVE A TO B
  READ FILE2
  END-READ
END-READ
```

#### **related concepts**

[“Conditional statements” on page 18](#)

[“Imperative statements” on page 17](#)

## **Declaratives**

Declaratives provide one or more special-purpose sections that are executed when an exception condition occurs.

Start each declarative section with a USE statement that identifies the function of the section. In the procedures, specify the actions to be taken when the condition occurs.

#### **related tasks**

[“Finding and handling input-output errors” on page 362](#)

#### **related references**

Declaratives (*Enterprise COBOL for z/OS Language Reference*)

---

## Chapter 2. Using data

This information is intended to help non-COBOL programmers relate terms for data used in other programming languages to COBOL terms. It introduces COBOL fundamentals for variables, structures, literals, and constants; assigning and displaying values; intrinsic (built-in) functions, and tables (arrays) and pointers.

### related concepts

[“Storage and its addressability” on page 37](#)

### related tasks

[“Using variables, structures, literals, and constants” on page 21](#)

[“Assigning values to data items” on page 25](#)

[“Displaying values on a screen or in a file \(DISPLAY\)” on page 33](#)

[“Using intrinsic functions \(built-in functions\)” on page 36](#)

[“Using tables \(arrays\) and pointers” on page 37](#)

[Chapter 7, “Processing data in an international environment,” on page 119](#)

---

## Using variables, structures, literals, and constants

Most high-level programming languages share the concept of data being represented as variables (data items), structures (group items), literals, or constants.

The data in a COBOL program can be alphabetic, alphanumeric, double-byte character set (DBCS), national, or numeric. You can also define index-names and data items described as `USAGE POINTER`, `USAGE FUNCTION-POINTER`, `USAGE PROCEDURE-POINTER`, or `USAGE OBJECT REFERENCE`. You place all data definitions in the `DATA DIVISION` of your program.

### related tasks

[“Using variables” on page 21](#)

[“Using data items and group items” on page 22](#)

[“Using literals” on page 23](#)

[“Using constants” on page 24](#)

[“Using figurative constants” on page 24](#)

### related references

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Using variables

A *variable* is a data item whose value can change during a program. The value is restricted, however, to the data type that you define when you specify a name and a length for the data item.

For example, if a customer name is an alphanumeric data item in your program, you could define and use the customer name as shown below:

```
Data Division.
01 Customer-Name           Pic X(20).
01 Original-Customer-Name  Pic X(20).
. . .
Procedure Division.
    Move Customer-Name to Original-Customer-Name
. . .
```

You could instead define the customer names above as national data items by specifying their PICTURE clauses as `Pic N(20)` and specifying the `USAGE NATIONAL` clause for the items. National data items are represented in Unicode UTF-16, in which most characters are represented in 2 bytes of storage.

#### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

#### related tasks

[“Using national data \(Unicode\) in COBOL” on page 124](#)

#### related references

[“NSYMBOL” on page 319](#)

[“Storage of character data” on page 131](#)

PICTURE clause (*Enterprise COBOL for z/OS Language Reference*)

## Using data items and group items

Related data items can be parts of a hierarchical data structure. A data item that does not have subordinate data items is called an *elementary item*. A data item that is composed of one or more subordinate data items is called a *group item*.

A record can be either an elementary item or a group item. A group item can be either an *alphanumeric group item* or a *national group item*.

For example, Customer-Record below is an alphanumeric group item that is composed of two subordinate alphanumeric group items (Customer-Name and Part-Order), each of which contains elementary data items. These groups items implicitly have `USAGE DISPLAY`. You can refer to an entire group item or to parts of a group item in `MOVE` statements in the `PROCEDURE DIVISION` as shown below:

```
Data Division.
File Section.
FD  Customer-File
   Record Contains 45 Characters.
01  Customer-Record.
   05  Customer-Name.
      10 Last-Name      Pic x(17).
      10 Filler         Pic x.
      10 Initials       Pic xx.
   05  Part-Order.
      10 Part-Name      Pic x(15).
      10 Part-Color     Pic x(10).
Working-Storage Section.
01  Orig-Customer-Name.
   05 Surname          Pic x(17).
   05 Initials         Pic x(3).
01  Inventory-Part-Name Pic x(15).
.
.
.
Procedure Division.
   Move Customer-Name to Orig-Customer-Name
   Move Part-Name to Inventory-Part-Name
.
.
.
```

You could instead define Customer-Record as a national group item that is composed of two subordinate national group items by changing the declarations in the `DATA DIVISION` as shown below. National group items behave in the same way as elementary category national data items in most operations. The `GROUP-USAGE NATIONAL` clause indicates that a group item and any group items subordinate to it are national groups. Subordinate elementary items in a national group must be explicitly or implicitly described as `USAGE NATIONAL`.

```
Data Division.
File Section.
FD  Customer-File
   Record Contains 90 Characters.
01  Customer-Record      Group-Usage National.
```

```

05 Customer-Name.
   10 Last-Name      Pic n(17).
   10 Filler         Pic n.
   10 Initials       Pic nn.
05 Part-Order.
   10 Part-Name      Pic n(15).
   10 Part-Color     Pic n(10).
Working-Storage Section.
01 Orig-Customer-Name Group-Usage National.
   05 Surname        Pic n(17).
   05 Initials       Pic n(3).
01 Inventory-Part-Name Pic n(15) Usage National.
.
.
.
Procedure Division.
   Move Customer-Name to Orig-Customer-Name
   Move Part-Name to Inventory-Part-Name
.
.
.

```

In the example above, the group items could instead specify the `USAGE NATIONAL` clause at the group level. A `USAGE` clause at the group level applies to each elementary data item in a group (and thus serves as a convenient shorthand notation). However, a group that specifies the `USAGE NATIONAL` clause is *not* a national group despite the representation of the elementary items within the group. Groups that specify the `USAGE` clause are alphanumeric groups and behave in many operations, such as moves and compares, like elementary data items of `USAGE DISPLAY` (except that no editing or conversion of data occurs).

### related concepts

[“Unicode and the encoding of language characters” on page 123](#)  
[“National groups” on page 127](#)

### related tasks

[“Using national data \(Unicode\) in COBOL” on page 124](#)  
[“Using national groups” on page 128](#)

### related references

[“FILE SECTION entries” on page 12](#)  
[“Storage of character data” on page 131](#)  
Classes and categories of group items  
*(Enterprise COBOL for z/OS Language Reference)*  
PICTURE clause *(Enterprise COBOL for z/OS Language Reference)*  
MOVE statement *(Enterprise COBOL for z/OS Language Reference)*  
USAGE clause *(Enterprise COBOL for z/OS Language Reference)*

## Using literals

A *literal* is a character string whose value is given by the characters themselves. If you know the value you want a data item to have, you can use a literal representation of the data value in the `PROCEDURE DIVISION`.

You do not need to define a data item for the value nor refer to it by using a data-name. For example, you can prepare an error message for an output file by moving an alphanumeric literal:

```
Move "Name is not valid" To Customer-Name
```

You can compare a data item to a specific integer value by using a numeric literal. In the example below, `"Name is not valid"` is an alphanumeric literal, and `03519` is a numeric literal:

```

01 Part-number      Pic 9(5).
.
.
.
If Part-number = 03519 then display "Part number was found"

```

You can use the opening delimiter N" or N' to designate a national literal if the NSYMBOL (NATIONAL) compiler option is in effect, or to designate a DBCS literal if the NSYMBOL (DBCS) compiler option is in effect.

You can use the opening delimiter NX" or NX' to designate national literals in hexadecimal notation (regardless of the setting of the NSYMBOL compiler option). Each group of four hexadecimal digits designates a single national character.

#### **related concepts**

[“Unicode and the encoding of language characters” on page 123](#)

#### **related tasks**

[“Using national literals” on page 125](#)

[“Using DBCS literals” on page 143](#)

#### **related references**

[“NSYMBOL” on page 319](#)

Literals (*Enterprise COBOL for z/OS Language Reference*)

## **Using constants**

A *constant* is a data item that has only one value. COBOL does not define a construct for constants. However, you can define a data item with an initial value by coding a VALUE clause in the data description (instead of coding an INITIALIZE statement).

```
Data Division.  
01 Report-Header   pic x(50)  value "Company Sales Report".  
01 Interest        pic 9v9999 value 1.0265.
```

The example above initializes an alphanumeric and a numeric data item. You can likewise use a VALUE clause in defining a national or DBCS constant.

#### **related tasks**

[“Using national data \(Unicode\)](#)

[in COBOL” on page 124](#)

[“Coding for use of DBCS support” on page 142](#)

## **Using figurative constants**

Certain commonly used constants and literals are available as reserved words called *figurative constants*: ZERO, SPACE, HIGH-VALUE, LOW-VALUE, QUOTE, NULL, and ALL *literal*. Because they represent fixed values, figurative constants do not require a data definition.

For example:

```
Move Spaces To Report-Header
```

#### **related tasks**

[“Using national-character](#)

[figurative constants” on page 126](#)

[“Coding for use of DBCS support” on page 142](#)

#### **related references**

Figurative constants (*Enterprise COBOL for z/OS Language Reference*)

## Assigning values to data items

After you have defined a data item, you can assign a value to it at any time. Assignment takes many forms in COBOL, depending on what you want to do.

Table 3. <i>Assignment to data items in a program</i>	
What you want to do	How to do it
Assign values to a data item or large data area.	Use one of these ways: <ul style="list-style-type: none"><li>• INITIALIZE statement</li><li>• MOVE statement</li><li>• STRING or UNSTRING statement</li><li>• VALUE clause (to set data items to the values you want them to have when the program is in initial state)</li></ul>
Assign the results of arithmetic.	Use COMPUTE, ADD, SUBTRACT, MULTIPLY, or DIVIDE statements.
Examine or replace characters or groups of characters in a data item.	Use the INSPECT statement.
Receive values from a file.	Use the READ (or READ INTO) statement.
Receive values from a system input device or a file.	Use the ACCEPT statement.
Establish a constant.	Use the VALUE clause in the definition of the data item, and do not use the data item as a receiver. Such an item is in effect a constant even though the compiler does not enforce read-only constants.
One of these actions: <ul style="list-style-type: none"><li>• Place a value associated with a table element in an index.</li><li>• Set the status of an external switch to ON or OFF.</li><li>• Move data to a condition-name to make the condition true.</li><li>• Set a POINTER, PROCEDURE-POINTER, or FUNCTION-POINTER data item to an address.</li><li>• Associate an OBJECT REFERENCE data item with an object instance.</li></ul>	Use the SET statement.

[“Examples: initializing data items” on page 26](#)

### related tasks

[“Initializing a structure](#)

[\(INITIALIZE\)” on page 29](#)

[“Assigning values to elementary data items \(MOVE\)” on page 30](#)

[“Assigning values to group data items \(MOVE\)” on page 31](#)

[“Assigning input from a screen or file \(ACCEPT\)” on page 33](#)

[“Joining data items \(STRING\)” on page 101](#)

[“Splitting data items \(UNSTRING\)” on page 103](#)

[“Assigning arithmetic results](#)

(MOVE or COMPUTE)” on page 32  
 “Tallying and replacing  
 data items (INSPECT)” on page 110  
 Chapter 7, “Processing data in an international  
 environment,” on page 119

## Examples: initializing data items

The following examples show how you can initialize many kinds of data items, including alphanumeric, national-edited, and numeric-edited data items, by using INITIALIZE statements.

An INITIALIZE statement is functionally equivalent to one or more MOVE statements. The related tasks about initializing show how you can use an INITIALIZE statement on a group item to conveniently initialize all the subordinate data items that are in a given data category.

### Initializing a data item to blanks or zeros:

```
INITIALIZE identifier-1
```

<b>identifier-1 PICTURE</b>	<b>identifier-1 before</b>	<b>identifier-1 after</b>
9(5)	12345	00000
X(5)	AB123	bbbb <sup>1</sup>
N(3)	004100420031 <sup>2</sup>	002000200020 <sup>3</sup>
99XX9	12AB3	bbbb <sup>1</sup>
XXBX/XX	ABbC/DE	bbbb/bb <sup>1</sup>
**99.9CR	1234.5CR	**00.0bb <sup>1</sup>
A(5)	ABCDE	bbbb <sup>1</sup>
+99.99E+99	+12.34E+02	+00.00E+00
1. The symbol <i>b</i> represents a blank space. 2. Hexadecimal representation of the national (UTF-16) characters 'AB1'. The example assumes that <i>identifier-1</i> has Usage <code>National</code> . 3. Hexadecimal representation of the national (UTF-16) characters ' ' (three blank spaces). Note that if <i>identifier-1</i> were not defined as Usage <code>National</code> , and if <code>NSYMBOL (DBCS)</code> were in effect, INITIALIZE would instead store DBCS spaces ('4040') into <i>identifier-1</i> .		

### Initializing an alphanumeric data item:

```
01 ALPHANUMERIC-1 PIC X VALUE "y".
01 ALPHANUMERIC-3 PIC X(1) VALUE "A".
. . .
INITIALIZE ALPHANUMERIC-1
REPLACING ALPHANUMERIC DATA BY ALPHANUMERIC-3
```

<b>ALPHANUMERIC-3</b>	<b>ALPHANUMERIC-1 before</b>	<b>ALPHANUMERIC-1 after</b>
A	y	A

### Initializing an alphanumeric right-justified data item:

```
01 ANJUST PIC X(8) VALUE SPACES JUSTIFIED RIGHT.
01 ALPHABETIC-1 PIC A(4) VALUE "ABCD".
```

```

. . .
INITIALIZE ANJUST
REPLACING ALPHANUMERIC DATA BY ALPHABETIC-1

```

ALPHABETIC-1	ANJUST before	ANJUST after
ABCD	bbbbbb <sup>1</sup>	bbbbABCD <sup>1</sup>
1. The symbol <i>b</i> represents a blank space.		

#### Initializing an alphanumeric-edited data item:

```

01 ALPHANUM-EDIT-1 PIC XXBX/XXX VALUE "ABbC/DEF".
01 ALPHANUM-EDIT-3 PIC X/BB VALUE "M/bb".
. . .
INITIALIZE ALPHANUM-EDIT-1
REPLACING ALPHANUMERIC-EDITED DATA BY ALPHANUM-EDIT-3

```

ALPHANUM-EDIT-3	ALPHANUM-EDIT-1 before	ALPHANUM-EDIT-1 after
M/bb <sup>1</sup>	ABbC/DEF <sup>1</sup>	M/bb/bbb <sup>1</sup>
1. The symbol <i>b</i> represents a blank space.		

#### Initializing a national data item:

```

01 NATIONAL-1 PIC NN USAGE NATIONAL VALUE N"AB".
01 NATIONAL-3 PIC NN USAGE NATIONAL VALUE N"CD".
. . .
INITIALIZE NATIONAL-1
REPLACING NATIONAL DATA BY NATIONAL-3
INITIALIZE NATIONAL-1 NATIONAL TO VALUE

```

NATIONAL-3	NATIONAL-1 before first INITIALIZE	NATIONAL-1 after first INITIALIZE	NATIONAL-1 after second INITIALIZE
00430044 <sup>1</sup>	00410042 <sup>2</sup>	00430044 <sup>1</sup>	00410042 <sup>2</sup>
1. Hexadecimal representation of the national characters 'CD' 2. Hexadecimal representation of the national characters 'AB'			

#### Initializing a national-edited data item:

```

01 NATL-EDIT-1 PIC 0NN USAGE NATIONAL VALUE N"123".
01 NATL-3 PIC NNN USAGE NATIONAL VALUE N"456".
. . .
INITIALIZE NATL-EDIT-1
REPLACING NATIONAL-EDITED DATA BY NATL-3

```

NATL-3	NATL-EDIT-1 before	NATL-EDIT-1 after
003400350036 <sup>1</sup>	003100320033 <sup>2</sup>	003000340035 <sup>3</sup>
1. Hexadecimal representation of the national characters '456' 2. Hexadecimal representation of the national characters '123' 3. Hexadecimal representation of the national characters '045'		

### Initializing a numeric (zoned decimal) data item:

```
01 NUMERIC-1          PIC 9(8)          VALUE 98765432.
01 NUM-INT-CMPT-3     PIC 9(7)    COMP  VALUE 1234567.
. . .
  INITIALIZE NUMERIC-1
    REPLACING NUMERIC DATA BY NUM-INT-CMPT-3
```

NUM-INT-CMPT-3	NUMERIC-1 before	NUMERIC-1 after
1234567	98765432	01234567

### Initializing a numeric (national decimal) data item:

```
01 NAT-DEC-1          PIC 9(3)  USAGE  NATIONAL VALUE 987.
01 NUM-INT-BIN-3      PIC 9(2)  BINARY VALUE 12.
. . .
  INITIALIZE NAT-DEC-1
    REPLACING NUMERIC DATA BY NUM-INT-BIN-3
```

NUM-INT-BIN-3	NAT-DEC-1 before	NAT-DEC-1 after
12	003900380037 <sup>1</sup>	003000310032 <sup>2</sup>
1. Hexadecimal representation of the national characters '987' 2. Hexadecimal representation of the national characters '012'		

### Initializing a numeric-edited (USAGE DISPLAY) data item:

```
01 NUM-EDIT-DISP-1    PIC $$Z9V  VALUE "$127".
01 NUM-DISP-3         PIC 999V   VALUE 12.
. . .
  INITIALIZE NUM-EDIT-DISP-1
    REPLACING NUMERIC-EDITED DATA BY NUM-DISP-3
```

NUM-DISP-3	NUM-EDIT-DISP-1 before	NUM-EDIT-DISP-1 after
012	\$127	\$ 12

### Initializing a numeric-edited (USAGE NATIONAL) data item:

```
01 NUM-EDIT-NATL-1    PIC $$Z9V  NATIONAL VALUE N"$127".
01 NUM-NATL-3         PIC 999V   NATIONAL VALUE 12.
. . .
  INITIALIZE NUM-EDIT-NATL-1
    REPLACING NUMERIC-EDITED DATA BY NUM-NATL-3
```

NUM-NATL-3	NUM-EDIT-NATL-1 before	NUM-EDIT-NATL-1 after
003000310032 <sup>1</sup>	0024003100320037 <sup>2</sup>	0024002000310032 <sup>3</sup>
1. Hexadecimal representation of the national characters '012' 2. Hexadecimal representation of the national characters '\$127' 3. Hexadecimal representation of the national characters '\$ 12'		

### related tasks

[“Initializing a structure](#)

[\(INITIALIZE\)” on page 29](#)

[“Initializing a table \(INITIALIZE\)” on page 71](#)

[“Defining numeric data” on page 41](#)

#### related references

[“NSYMBOL” on page 319](#)

## Initializing a structure (INITIALIZE)

You can reset the values of all subordinate data items in a group item by applying the INITIALIZE statement to that group item. However, it is inefficient to initialize an entire group unless you really need all the items in the group to be initialized.

The following example shows how you can reset fields to spaces and zeros in transaction records that a program produces. The values of the fields are not identical in each record that is produced. (The transaction record is defined as an alphanumeric group item, TRANSACTION-OUT.)

```
01 TRANSACTION-OUT.  
  05 TRANSACTION-CODE      PIC X.  
  05 PART-NUMBER           PIC 9(6).  
  05 TRANSACTION-QUANTITY  PIC 9(5).  
  05 PRICE-FIELDS.  
    10 UNIT-PRICE          PIC 9(5)V9(2).  
    10 DISCOUNT           PIC V9(2).  
    10 SALES-PRICE         PIC 9(5)V9(2).  
  . . .  
  INITIALIZE TRANSACTION-OUT
```

Record	TRANSACTION-OUT before	TRANSACTION-OUT after
1	R001383000240000000000000000000	b000000000000000000000000000000 <sup>1</sup>
2	R001390000480000000000000000000	b000000000000000000000000000000 <sup>1</sup>
3	S001410000120000000000000000000	b000000000000000000000000000000 <sup>1</sup>
4	C001383000000000004250000000000	b000000000000000000000000000000 <sup>1</sup>
5	C002010000000000000000100000000	b000000000000000000000000000000 <sup>1</sup>
1. The symbol <i>b</i> represents a blank space.		

You can likewise reset the values of all the subordinate data items in a national group item by applying the INITIALIZE statement to that group item. The following structure is similar to the preceding structure, but instead uses Unicode UTF-16 data:

```
01 TRANSACTION-OUT GROUP-USAGE NATIONAL.  
  05 TRANSACTION-CODE      PIC N.  
  05 PART-NUMBER           PIC 9(6).  
  05 TRANSACTION-QUANTITY  PIC 9(5).  
  05 PRICE-FIELDS.  
    10 UNIT-PRICE          PIC 9(5)V9(2).  
    10 DISCOUNT           PIC V9(2).  
    10 SALES-PRICE         PIC 9(5)V9(2).  
  . . .  
  INITIALIZE TRANSACTION-OUT
```

Regardless of the previous contents of the transaction record, after the INITIALIZE statement above is executed:

- TRANSACTION-CODE contains NX"0020" (a national space).
- Each of the remaining 27 national character positions of TRANSACTION-OUT contains NX"0030" (a national-decimal zero).

When you use an INITIALIZE statement to initialize an alphanumeric or national group data item, the data item is processed as a group item, that is, with group semantics. The elementary data items within the group are recognized and processed, as shown in the examples above. If you do not code the REPLACING phrase of the INITIALIZE statement:

- SPACE is the implied sending item for alphabetic, alphanumeric, alphanumeric-edited, DBCS, category national, and national-edited receiving items.
- ZERO is the implied sending item for numeric and numeric-edited receiving items.

#### **related concepts**

[“National groups” on page 127](#)

#### **related tasks**

[“Initializing a table \(INITIALIZE\)” on page 71](#)

[“Using national groups” on page 128](#)

#### **related references**

INITIALIZE statement (*Enterprise COBOL for z/OS Language Reference*)

## **Assigning values to elementary data items (MOVE)**

Use a MOVE statement to assign a value to an elementary data item.

The following statement assigns the contents of an elementary data item, Customer-Name, to the elementary data item Orig-Customer-Name:

```
Move Customer-Name to Orig-Customer-Name
```

If Customer-Name is longer than Orig-Customer-Name, truncation occurs on the right. If Customer-Name is shorter, the extra character positions on the right in Orig-Customer-Name are filled with spaces.

For data items that contain numbers, moves can be more complicated than with character data items because there are several ways in which numbers can be represented. In general, the algebraic values of numbers are moved if possible, as opposed to the digit-by-digit moves that are performed with character data. For example, after the MOVE statement below, Item-x contains the value 3.0, represented as 0030:

```
01 Item-x      Pic 999v9.  
  . . .  
  Move 3.06 to Item-x
```

You can move an alphabetic, alphanumeric, alphanumeric-edited, DBCS, integer, or numeric-edited data item to a category national or national-edited data item; the sending item is converted. You can move a national data item to a category national or national-edited data item. If the content of a category national data item has a numeric value, you can move that item to a numeric, numeric-edited, external floating-point, or internal floating-point data item. You can move a national-edited data item only to a category national data item or another national-edited data item. Padding or truncation might occur.

For complete details about elementary moves, see the related reference below about the MOVE statement.

The following example shows an alphanumeric data item in the Greek language that is moved to a national data item:

```
CBL CODEPAGE(00875)  
  . . .  
01 Data-in-Unicode  Pic N(100) usage national.  
01 Data-in-Greek    Pic X(100).  
  . . .  
  Read Greek-file into Data-in-Greek  
  Move Data-in-Greek to Data-in-Unicode
```

**related concepts**

[“Unicode and the encoding of language characters” on page 123](#)

**related tasks**

[“Assigning values to group data items \(MOVE\)” on page 31](#)

[“Converting to or from national \(Unicode\) representation” on page 131](#)

**related references**

[“CODEPAGE” on page 295](#)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

MOVE statement (*Enterprise COBOL for z/OS Language Reference*)

## Assigning values to group data items (MOVE)

Use the MOVE statement to assign values to group data items.

You can move a national group item (a data item that is described with the GROUP-USAGE NATIONAL clause) to another national group item. The compiler processes the move as though each national group item were an elementary item of category national, that is, as if each item were described as PIC N(*m*), where *m* is the length of that item in national character positions.

You can move an alphanumeric group item to an alphanumeric group item or to a national group item. You can also move a national group item to an alphanumeric group item. The compiler performs such moves as group moves, that is, without consideration of the individual elementary items in the sending or receiving group, and without conversion of the sending data item. Be sure that the subordinate data descriptions in the sending and receiving group items are compatible. The moves occur even if a destructive overlap could occur at run time.

You can code the CORRESPONDING phrase in a MOVE statement to move subordinate elementary items from one group item to the identically named corresponding subordinate elementary items in another group item:

```
01 Group-X.
  02 T-Code      Pic X      Value "A".
  02 Month       Pic 99     Value 04.
  02 State       Pic XX     Value "CA".
  02 Filler      PIC X.
01 Group-N      Group-Usage National.
  02 State       Pic NN.
  02 Month       Pic 99.
  02 Filler      Pic N.
  02 Total       Pic 999.
. . .
MOVE CORR Group-X TO Group-N
```

In the example above, State and Month within Group-N receive the values in national representation of State and Month, respectively, from Group-X. The other data items in Group-N are unchanged. (Filler items in a receiving group item are unchanged by a MOVE CORRESPONDING statement.)

In a MOVE CORRESPONDING statement, sending and receiving group items are treated as group items, not as elementary data items; group semantics apply. That is, the elementary data items within each group are recognized, and the results are the same as if each pair of corresponding data items were referenced in a separate MOVE statement. Data conversions are performed according to the rules for the MOVE statement as specified in the related reference below. For details about which types of elementary data items correspond, see the related reference about the CORRESPONDING phrase.

**related concepts**

[“Unicode and the encoding of language characters” on page 123](#)

[“National groups” on page 127](#)

### related tasks

[“Assigning values to elementary data items \(MOVE\)” on page 30](#)

[“Using national groups” on page 128](#)

[“Converting to or from national \(Unicode\) representation” on page 131](#)

### related references

Classes and categories of group items

(*Enterprise COBOL for z/OS Language Reference*)

MOVE statement (*Enterprise COBOL for z/OS Language Reference*)

CORRESPONDING phrase (*Enterprise COBOL for z/OS Language Reference*)

## Assigning arithmetic results (MOVE or COMPUTE)

When assigning a number to a data item, consider using the COMPUTE statement instead of the MOVE statement.

```
Move w to z
Compute z = w
```

In the example above, the two statements in most cases have the same effect. The MOVE statement however carries out the assignment with truncation. You can use the DIAGTRUNC compiler option to request that the compiler issue a warning for MOVE statements that might truncate numeric receivers.

When significant left-order digits would be lost in execution, the COMPUTE statement can detect the condition and allow you to handle it. If you use the ON SIZE ERROR phrase of the COMPUTE statement, the compiler generates code to detect a size-overflow condition. If the condition occurs, the code in the ON SIZE ERROR phrase is performed, and the content of z remains unchanged. If you do not specify the ON SIZE ERROR phrase, the assignment is carried out with truncation. There is no ON SIZE ERROR support for the MOVE statement.

You can also use the COMPUTE statement to assign the result of an arithmetic expression or intrinsic function to a data item. For example:

```
Compute z = y + (x ** 3)
Compute x = Function Max(x y z)
```

You can assign the results of date, time, mathematical, and other calculations to data items by using Language Environment callable services. Language Environment services are available through a standard COBOL CALL statement, and the values they return are passed in the parameters of the CALL statement. For example, you can call the Language Environment service CEESIABS to find the absolute value of a data item by coding the following statement:

```
Call 'CEESIABS' Using Arg, Feedback-code, Result.
```

As a result of this call, data item Result is assigned the absolute value of the value in data item Arg; data item Feedback-code contains the return code that indicates whether the service completed successfully. You have to define all the data items in the DATA DIVISION using the correct descriptions according to the requirements of the particular callable service. For the example above, the data items could be defined as follows:

```
77 Arg           Pic s9(9)  Binary.
77 Feedback-code Pic x(12)  Display.
77 Result        Pic s9(9)  Binary.
```

### related references

[“DIAGTRUNC” on page 302](#)

## Assigning input from a screen or file (ACCEPT)

One way to assign a value to a data item is to read the value from a screen or a file.

To enter data from the screen, first associate the monitor with a mnemonic-name in the SPECIAL-NAMES paragraph. Then use ACCEPT to assign the line of input entered at the screen to a data item. For example:

```
Environment Division.  
Configuration Section.  
Special-Names.  
    Console is Names-Input.  
* * *  
    Accept Customer-Name From Names-Input
```

To read from a file instead of the screen, make the following change:

- Change Console to *device*, where *device* is any valid system device (for example, SYSIN). For example:

```
SYSIN is Names-Input
```

*device* can be a ddname that references a z/OS UNIX file system path. If this ddname is not defined and your program is running in the z/OS UNIX environment, stdin is the input source. If this ddname is not defined and your program is not running in the z/OS UNIX environment, the ACCEPT statement fails.

When you use the ACCEPT statement, you can assign a value to an alphanumeric or national group item, or to an elementary data item that has USAGE DISPLAY, USAGE DISPLAY-1, or USAGE NATIONAL.

When you assign a value to a USAGE NATIONAL data item, input data from the console is converted from the EBCDIC code page specified in the CODEPAGE compiler option to national (Unicode UTF-16) representation. This is the only case where conversion of national data is done when you use the ACCEPT statement. Conversion is done in this case because the input is known to be coming from a screen.

To have conversion done when the input data is from any other device, use the NATIONAL-OF intrinsic function.

### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

### related tasks

[“Converting alphanumeric or DBCS to national \(NATIONAL-OF\)” on page 132](#)

### related references

[“CODEPAGE” on page 295](#)

ACCEPT statement (*Enterprise COBOL for z/OS Language Reference*)

SPECIAL-NAMES paragraph (*Enterprise COBOL for z/OS Language Reference*)

## Displaying values on a screen or in a file (DISPLAY)

You can display the value of a data item on a screen or write it to a file by using the DISPLAY statement.

```
Display "No entry for surname '" Customer-Name "' found in the file."
```

In the example above, if the content of data item *Customer-Name* is JOHNSON, then the statement displays the following message on the system logical output device:

```
No entry for surname 'JOHNSON' found in the file.
```

To write data to a destination other than the system logical output device, use the UPON phrase with a destination other than SYSOUT. For example, the following statement writes to the file that is specified in the SYSPUNCH DD statement:

```
Display "Hello" upon syspunch.
```

You can specify a file in the z/OS UNIX file system by using the SYSPUNCH DD statement. For example, the following definition causes DISPLAY output to be written to the file */u/userid/cobol/demo.lst*:

```
//SYSPUNCH DD PATH='/u/userid/cobol/demo.lst',  
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),PATHMODE=SIRWXU,  
// FILEDATA=TEXT
```

The following statement writes to the job log or console and to the TSO screen if you are running under TSO:

```
Display "Hello" upon console.
```

When you display the value of a USAGE NATIONAL data item to the console, the data item is converted from Unicode (UTF-16) representation to EBCDIC based on the value of the CODEPAGE option. This is the only case in which conversion of national data is done when you use the DISPLAY statement. Conversion is done in this case because the output is known to be directed to a screen.

To have a national data item be converted when you direct output to a different device, use the DISPLAY-OF intrinsic function, as in the following example:

```
01 Data-in-Unicode pic N(10) usage national.  
  . . . Display function Display-of(Data-in-Unicode, 00037)
```

### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

### related tasks

[“Displaying data on the system logical output device” on page 34](#)  
[“Using WITH NO ADVANCING” on page 35](#)  
[“Converting national to alphanumeric \(DISPLAY-OF\)” on page 133](#)  
[“Coding COBOL programs to run under CICS” on page 407](#)

### related references

[“CODEPAGE” on page 295](#)  
DISPLAY statement (*Enterprise COBOL for z/OS Language Reference*)

## Displaying data on the system logical output device

To write data to the system logical output device, either omit the UPON clause or use the UPON clause with destination SYSOUT.

```
Display "Hello" upon sysout.
```

The output is directed to the ddname that you specify in the OUTDD compiler option. You can specify a file in the z/OS UNIX file system with this ddname.

If the OUTDD ddname is not allocated and you are not running in the z/OS UNIX environment, a default DD of SYSOUT=\* is allocated. If the OUTDD ddname is not allocated and you are running in the z/OS UNIX environment, the \_IGZ\_SYSOUT environment variable is used as follows:

**Undefined or set to stdout**

Output is routed to stdout (file descriptor 1).

**Set to stderr**

Output is routed to stderr (file descriptor 2).

**Otherwise (set to something other than stdout or stderr)**

The DISPLAY statement fails; a severity-3 Language Environment condition is raised.

When DISPLAY output is routed to stdout or stderr, the output is not subdivided into records. The output is written as a single stream of characters without line breaks.

If OUTDD and the Language Environment runtime option MSGFILE specify the same ddname, both DISPLAY output and Language Environment runtime diagnostics are routed to the Language Environment message file.

**related tasks**

[“Setting and accessing environment variables” on page 436](#)

**related references**

[“OUTDD” on page 326](#)

DISPLAY statement (*Enterprise COBOL for z/OS Language Reference*)

## Using WITH NO ADVANCING

If you specify the WITH NO ADVANCING phrase, and output is going to a ddname, the printer control character + (plus) is placed into the first output position from the *next* DISPLAY statement. + is the ANSI-defined printer control character that suppresses line spacing before a record is printed.

If you specify the WITH NO ADVANCING phrase and the output is going to stdout or stderr, a newline character is not appended to the end of the stream. A subsequent DISPLAY statement might add additional characters to the end of the stream.

If you do not specify WITH NO ADVANCING, and the output is going to a ddname, the printer control character ' ' (space) is placed into the first output position from the next DISPLAY statement, indicating single-spaced output.

```
DISPLAY "ABC"
DISPLAY "CDEF" WITH NO ADVANCING
DISPLAY "GHIJK" WITH NO ADVANCING
DISPLAY "LMNOPQ"
DISPLAY "RSTUVWX"
```

If you code the statements above, the result sent to the output device is:

```
ABC
CDEF
+GHIJK
+LMNOPQ
RSTUVMX
```

The output that is printed depends on how the output device interprets printer control characters.

If you do not specify the WITH NO ADVANCING phrase and the output is going to stdout or stderr, a newline character is appended to the end of the stream.

**related references**

DISPLAY statement (*Enterprise COBOL for z/OS Language Reference*)

## Using intrinsic functions (built-in functions)

Some high-level programming languages have built-in functions that you can reference in your program as if they were variables that have defined attributes and a predetermined value. In COBOL, these functions are called *intrinsic functions*. They provide capabilities for manipulating strings and numbers.

Because the value of an intrinsic function is derived automatically at the time of reference, you do not need to define functions in the DATA DIVISION. Define only the nonliteral data items that you use as arguments. Figurative constants are not allowed as arguments.

A *function-identifier* is the combination of the COBOL reserved word FUNCTION followed by a function name (such as Max), followed by any arguments to be used in the evaluation of the function (such as x, y, z). For example, the groups of highlighted words below are function-identifiers:

```
Unstring Function Upper-case(Name) Delimited By Space
      Into Fname Lname
Compute A = 1 + Function Log10(x)
Compute M = Function Max(x y z)
```

A function-identifier represents both the invocation of the function and the data value returned by the function. Because it actually represents a data item, you can use a function-identifier in most places in the PROCEDURE DIVISION where a data item that has the attributes of the returned value can be used.

The COBOL word function is a reserved word, but the function-names are not reserved. You can use them in other contexts, such as for the name of a data item. For example, you could use Sqrt to invoke an intrinsic function and to name a data item in your program:

```
Working-Storage Section.
01 x                               Pic 99 value 2.
01 y                               Pic 99 value 4.
01 z                               Pic 99 value 0.
01 Sqrt                           Pic 99 value 0.
. . .
  Compute Sqrt = 16 ** .5
  Compute z = x + Function Sqrt(y)
. . .
```

A function-identifier represents a value that is of one of these types: alphanumeric, national, numeric, or integer. You can include a substring specification (reference modifier) in a function-identifier for alphanumeric or national functions. Numeric intrinsic functions are further classified according to the type of numbers they return.

The functions MAX and MIN can return either type of value depending on the type of arguments you supply.

Functions can reference other functions as arguments provided that the results of the nested functions meet the requirements for the arguments of the outer function. For example, Function Sqrt(5) returns a numeric value. Thus, the three arguments to the MAX function below are all numeric, which is an allowable argument type for this function:

```
Compute x = Function Max((Function Sqrt(5)) 2.5 3.5)
```

### related tasks

[“Processing table items](#)

[using intrinsic functions” on page 85](#)

[“Converting data items \(intrinsic functions\)” on page 111](#)

[“Evaluating data items \(intrinsic functions\)” on page 114](#)

## Using tables (arrays) and pointers

---

In COBOL, arrays are called *tables*. A table is a set of logically consecutive data items that you define in the DATA DIVISION by using the OCCURS clause.

Pointers are data items that contain virtual storage addresses. You define them either explicitly with the USAGE IS POINTER clause in the DATA DIVISION or implicitly as ADDRESS OF special registers.

You can perform the following operations with pointer data items:

- Pass them between programs by using the CALL . . . BY REFERENCE statement.
- Move them to other pointers by using the SET statement.
- Compare them to other pointers for equality by using a relation condition.
- Initialize them to contain an invalid address by using VALUE IS NULL.

Use pointer data items to:

- Accomplish limited base addressing, particularly if you want to pass and receive addresses of a record area that is defined with OCCURS DEPENDING ON and is therefore variably located.
- Handle a chained list.

### related tasks

[“Defining a table \(OCCURS\)” on page 65](#)

[“Using procedure and function pointers” on page 461](#)

## Storage and its addressability

---

When you run COBOL programs, the programs and the data that they use reside in virtual storage. Storage that you use with COBOL can be either below the 16 MB line or above the 16 MB line but below the 2 GB bar. Two modes of addressing are available to address this storage: 24-bit and 31-bit.

You can address storage below (but not above) the 16 MB line with 24-bit addressing. You can address storage either above or below the 16 MB line with 31-bit addressing. *Unrestricted storage* is addressable by 31-bit addressing and therefore encompasses all the storage available to your program, both above and below the 16 MB line.

Enterprise COBOL does not directly exploit the 64-bit virtual addressing capability of z/OS; however, COBOL applications running in 31-bit or 24-bit addressing mode are fully supported on 64-bit z/OS systems.

*Addressing mode* (AMODE) is the attribute that tells which hardware addressing mode is supported by your program: 24-bit addressing, 31-bit addressing, or either 24-bit or 31-bit addressing. These attributes are AMODE 24, AMODE 31, and AMODE ANY, respectively. The program object and the executing program each have an AMODE attribute. Enterprise COBOL V5.1.1 object programs are either AMODE MIN for cases where AMODE 24 is possible, or AMODE 31 in all other cases. See [“Restrictions for AMODE” on page 38](#).

*Residency mode* (RMODE) is the attribute of a program object that identifies where in virtual storage the program will reside: below the 16 MB line, or either below or above. This attribute is RMODE 24 or RMODE ANY.

Enterprise COBOL uses Language Environment services to control the storage used at run time. Thus COBOL compiler options and Language Environment runtime options influence the AMODE and RMODE attributes of your program and data, alone and in combination:

### DATA

Compiler option that influences the location of storage for WORKING-STORAGE data, I-O buffers, and parameter lists for programs compiled with RENT.

### RMODE

Compiler option that influences the residency mode.

## RENT

Compiler option to generate a reentrant program.

## HEAP

Runtime option that controls storage for the runtime heap. For example, COBOL WORKING-STORAGE is allocated from heap storage when the COBOL program is compiled with the RENT option and is in one of the following cases:

- Compiled with Enterprise COBOL V4.2 or earlier releases
- Compiled with the DATA(24) compiler option
- Running in CICS
- A COBOL V5.1.1 or later program in a program object that contains only COBOL programs (except COBOL 5.1.0) and assembler. There are no Language Environment interlanguage calls within the program object and no COBOL V5.1.0 programs.
- A COBOL V5 program in a program object where the main entry point is COBOL V5. In this case, the program object can contain Language Environment interlanguage calls, with COBOL statically linking with C, C++ or PL/I. All COBOL V5 programs within such program objects (even if they are not the main entry point) have their WORKING-STORAGE allocated from heap storage.
- A COBOL V6.1 or later program

## STACK

Runtime option that controls storage for the runtime stack. For example, COBOL LOCAL-STORAGE is allocated from stack storage.

## ALL31

Runtime option that specifies whether an application can run entirely in AMODE 31.

## Restrictions for AMODE

AMODE 24 execution is not supported in the following cases, and the applications must run in AMODE 31. This is the same set of AMODE 24 restrictions as COBOL V3 and V4.

- Programs containing XML PARSE statements
- Programs containing XML GENERATE statements
- Program objects containing COBOL bound together with C, C++, or PL/I programs, and communicating via static CALL
- Programs containing object-oriented language syntax, such as INVOKE statements, or object-oriented class definitions
- Programs compiled with any of the following compiler options:

- DLL
- PGMNAME (LONGUPPER)
- PGMNAME (LONGMIXED)

- Multithreaded applications

**Note:** A program compiled with the THREAD option can run in AMODE 24, but only in an application that does not have multiple threads or PL/I tasks.

- Programs run from the z/OS UNIX file system

**Note:** An AMODE 31 driver program resident in the z/OS UNIX file system can contain a dynamic call to an AMODE 24 program module resident in an MVS PDSE.

- Programs used as COBOL compiler exit modules that are specified on the EXIT compiler option
- Language Environment enclaves that use XPLINK, including either the enclaves that contain non-COBOL programs compiled with the XPLINK compiler option, or run with the XPLINK runtime option

**Note:** To run COBOL programs with addressing mode 24, you must compile all COBOL programs with Enterprise COBOL V5.1.1, or later versions; or Enterprise COBOL V4.2 or earlier versions. If any component of a program object is compiled with Enterprise COBOL V5.1.0, the program object must run

in addressing mode 31. COBOL programs that run with addressing mode 24 must be linked with the binder option RMODE(24).

## Settings for RMODE

The RMODE and RENT options determine the RMODE attribute of your program.

Table 4. <i>Effect of RMODE and RENT compiler options on the RMODE attribute</i>		
RMODE compiler option	RENT compiler option	RMODE attribute
RMODE(AUTO)	RENT	RMODE ANY
RMODE(AUTO)	NORENT	RMODE 24
RMODE(24)	RENT or NORENT	RMODE 24
RMODE(ANY)	RENT	RMODE ANY
RMODE(ANY)	NORENT	Compiler option conflict.  If the NORENT option is specified, the RMODE(24) or RMODE(AUTO) compiler option must be specified.

**Link-edit considerations:** When the object code that COBOL generates has an attribute of RMODE 24, you must link-edit it with RMODE 24. When the object code that COBOL generates has an attribute of RMODE ANY, you can link-edit it with RMODE ANY or RMODE 24.

## Storage restrictions for passing data

Do not pass parameters that are allocated in storage above the 16 MB line to AMODE 24 subprograms. Force the WORKING-STORAGE data and parameter lists below the line for programs that run in 31-bit addressing mode and pass data to programs that run in AMODE 24:

- Compile with the RENT and DATA(24) compiler options, or if the WORKING-STORAGE is on the HEAP (see previous description of the HEAP option), run them with the HEAP( , , BELOW) runtime option.
- Compile with the NORENT compiler option.

## Location of data areas

For reentrant programs, the DATA compiler option, and the HEAP runtime option control whether storage for data areas such as WORKING-STORAGE SECTION and FD record areas is obtained from below the 16 MB line or from unrestricted storage. Compile programs with RENT and RMODE(ANY) or RMODE(AUTO) if they will be run with 31-bit addressing in virtual storage addresses above the 16 MB line. The DATA option does not affect programs that are compiled with NORENT.

## Storage for LOCAL-STORAGE data

The location of LOCAL-STORAGE data items is controlled by the STACK runtime option and the AMODE of the program. LOCAL-STORAGE data items are acquired in unrestricted storage when the STACK( , , ANYWHERE) runtime option is in effect and the program is running in AMODE 31. Otherwise LOCAL-STORAGE is acquired below the 16 MB line. The DATA compiler option does not influence the location of LOCAL-STORAGE data.

## Storage for external data

In addition to affecting how storage is obtained for dynamic data areas (WORKING-STORAGE, FD record areas, and parameter lists), the DATA compiler option can also influence where storage for EXTERNAL

data is obtained. Storage required for EXTERNAL data is obtained from unrestricted storage if the following conditions are met:

- The program is compiled with the DATA(31) and RENT compiler options.
- The HEAP( , , ANYWHERE) runtime option is in effect.
- The ALL31(ON) runtime option is in effect.

In all other cases, the storage for EXTERNAL data is obtained from below the 16 MB line. If you specify the ALL31(ON) runtime option, all the programs in the run unit must be capable of running in 31-bit addressing mode.

## Storage for QSAM input-output buffers

The DATA compiler option can also influence where input-output buffers for QSAM files are obtained. See the related references below for information about allocation of buffers for QSAM files and the DATA compiler option.

## Storage for ALLOCATE statement

The DATA compiler option setting influences how ALLOCATE acquires storage:

- If DATA(24) is in effect and the LOC 31 phrase of the ALLOCATE statement is not specified, ALLOCATE acquires storage from below the 16 MB line.
- If DATA(31) is in effect and the LOC 24 phrase of the ALLOCATE statement is not specified, ALLOCATE will attempt to acquire storage from above the 16 MB line.

### related concepts

[“AMODE switching” on page 454](#)

*Language Environment Programming Guide* (AMODE considerations for heap storage)

### related tasks

[Chapter 25, “Using subprograms,” on page 449](#)

[Chapter 26, “Sharing data,” on page 465](#)

### related references

[“Allocation of buffers for QSAM files” on page 170](#)

[“Allocation of record areas for VSAM files” on page 195](#)

[“DATA” on page 300](#)

[“RENT” on page 330](#)

[“RMODE” on page 331](#)

[“Performance-related compiler options” on page 640](#)

[ALLOCATE statement](#)

*(Enterprise COBOL for z/OS Language Reference)*

*Language Environment Programming Reference* (HEAP, STACK, ALL31)

[MVS Program Management: User's Guide and Reference](#)

---

## Chapter 3. Working with numbers and arithmetic

In general, you can view COBOL numeric data as a series of decimal digit positions. However, numeric items can also have special properties such as an arithmetic sign or a currency sign.

To define, display, and store numeric data so that you can perform arithmetic operations efficiently:

- Use the PICTURE clause and the characters 9, +, -, P, S, and V to define numeric data.
- Use the PICTURE clause and editing characters (such as Z, comma, and period) along with MOVE and DISPLAY statements to display numeric data.
- Use the USAGE clause with various formats to control how numeric data is stored.
- Use the numeric class test to validate that data values are appropriate.
- Use ADD, SUBTRACT, MULTIPLY, DIVIDE, and COMPUTE statements to perform arithmetic.
- Use the CURRENCY SIGN clause and appropriate PICTURE characters to designate the currency you want.

### related tasks

[“Defining numeric data” on page 41](#)

[“Displaying numeric data” on page 43](#)

[“Controlling how numeric data is stored” on page 44](#)

[“Checking for incompatible data \(numeric class test\)” on page 51](#)

[“Performing arithmetic” on page 53](#)

[“Using currency signs” on page 61](#)

---

## Defining numeric data

Define numeric items by using the PICTURE clause with the character 9 in the data description to represent the decimal digits of the number. Do not use an X, which is for alphanumeric data items.

For example, Count-y below is a numeric data item, an external decimal item that has USAGE DISPLAY (a *zoned decimal item*):

```
05 Count-y      Pic 9(4) Value 25.
05 Customer-name Pic X(20) Value "Johnson".
```

You can similarly define numeric data items to hold national characters (UTF-16). For example, Count-n below is an external decimal data item that has USAGE NATIONAL (a *national decimal item*):

```
05 Count-n      Pic 9(4) Value 25 Usage National.
```

You can code up to 18 digits in the PICTURE clause when you compile using the default compiler option ARITH(COMPAT) (referred to as *compatibility mode*). When you compile using ARITH(EXTEND) (referred to as *extended mode*), you can code up to 31 digits in the PICTURE clause.

Other characters of special significance that you can code are:

### P

Indicates leading or trailing zeros

### S

Indicates a sign, positive or negative

### V

Implies a decimal point

The s in the following example means that the value is signed:

```
05 Price Pic s99v99.
```

The field can therefore hold a positive or a negative value. The v indicates the position of an implied decimal point, but does not contribute to the size of the item because it does not require a storage position. An s usually does not contribute to the size of a numeric item, because by default s does not require a storage position.

However, if you plan to port your program or data to a different machine, you might want to code the sign for a zoned decimal data item as a separate position in storage. In the following case, the sign takes 1 byte:

```
05 Price Pic s99V99 Sign Is Leading, Separate.
```

This coding ensures that the convention your machine uses for storing a nonseparate sign will not cause unexpected results on a machine that uses a different convention.

Separate signs are also preferable for zoned decimal data items that will be printed or displayed.

Separate signs are required for national decimal data items that are signed. The sign takes 2 bytes of storage, as in the following example:

```
05 Price Pic s99V99 Usage National Sign Is Leading, Separate.
```

You cannot use the PICTURE clause with internal floating-point data (COMP-1 or COMP-2). However, you can use the VALUE clause to provide an initial value for an internal floating-point literal:

```
05 Compute-result Usage Comp-2 Value 06.23E-24.
```

For information about external floating-point data, see the examples referenced below and the related concept about formats for numeric data.

[“Examples: numeric data and internal representation” on page 48](#)

#### **related concepts**

[“Formats for numeric data” on page 45](#)

[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

#### **related tasks**

[“Displaying numeric data” on page 43](#)

[“Controlling how numeric data is stored” on page 44](#)

[“Performing arithmetic” on page 53](#)

[“Defining national numeric data items” on page 127](#)

#### **related references**

[“Sign representation of zoned and packed-decimal data” on page 51](#)

[“Storage of character data” on page 131](#)

[“ARITH” on page 291](#)

[“NUMPROC” on page 322](#)

SIGN clause (*Enterprise COBOL for z/OS Language Reference*)

## Displaying numeric data

You can define numeric items with certain editing symbols (such as decimal points, commas, dollar signs, and debit or credit signs) to make the items easier to read and understand when you display or print them.

For example, in the code below, Edited-price is a numeric-edited item that has USAGE DISPLAY. (You can specify the clause USAGE IS DISPLAY for numeric-edited items; however, it is implied. It means that the items are stored in character format.)

```
05 Price          Pic      9(5)v99.  
05 Edited-price   Pic  $zz,zz9.99.  
  
.. .  
Move Price To Edited-price  
Display Edited-price
```

If the contents of Price are 0150099 (representing the value 1,500.99), \$ 1,500.99 is displayed when you run the code. The z in the PICTURE clause of Edited-price indicates the suppression of leading zeros.

You can define numeric-edited data items to hold national (UTF-16) characters instead of alphanumeric characters. To do so, define the numeric-edited items as USAGE NATIONAL. The effect of the editing symbols is the same for numeric-edited items that have USAGE NATIONAL as it is for numeric-edited items that have USAGE DISPLAY, except that the editing is done with national characters. For example, if Edited-price is declared as USAGE NATIONAL in the code above, the item is edited and displayed using national characters.

To display numeric or numeric-edited data items that have USAGE NATIONAL in EBCDIC, direct them to CONSOLE. For example, if Edited-price in the code above has USAGE NATIONAL, \$ 1,500.99 is displayed when you run the program if the last statement above is:

```
Display Edited-price Upon Console
```

You can cause an elementary numeric or numeric-edited item to be filled with spaces when a value of zero is stored into it by coding the BLANK WHEN ZERO clause for the item. For example, each of the DISPLAY statements below causes blanks to be displayed instead of zeros:

```
05 Price          Pic      9(5)v99.  
05 Edited-price-D Pic  $99,999.99  
    Blank When Zero.  
05 Edited-price-N Pic  $99,999.99 Usage National  
    Blank When Zero.  
  
.. .  
Move 0 to Price  
Move Price to Edited-price-D  
Move Price to Edited-price-N  
Display Edited-price-D  
Display Edited-price-N upon console
```

You cannot use numeric-edited items as sending operands in arithmetic expressions or in ADD, SUBTRACT, MULTIPLY, DIVIDE, or COMPUTE statements. (Numeric editing takes place when a numeric-edited item is the receiving field for one of these statements, or when a MOVE statement has a numeric-edited receiving field and a numeric-edited or numeric sending field.) You use numeric-edited items primarily for displaying or printing numeric data.

You can move numeric-edited items to numeric or numeric-edited items. In the following example, the value of the numeric-edited item (whether it has USAGE DISPLAY or USAGE NATIONAL) is moved to the numeric item:

```
Move Edited-price to Price  
Display Price
```

If these two statements immediately followed the statements in the first example above, then `Price` would be displayed as `0150099`, representing the value 1,500.99. `Price` would also be displayed as `0150099` if `Edited-price` had `USAGE NATIONAL`.

You can also move numeric-edited items to alphanumeric, alphanumeric-edited, floating-point, and national data items. For a complete list of the valid receiving items for numeric-edited data, see the related reference about the `MOVE` statement.

[“Examples: numeric data and internal representation” on page 48](#)

#### **related tasks**

[“Displaying values on a](#)

[screen or in a file \(DISPLAY\)” on page 33](#)

[“Controlling how numeric data is stored” on page 44](#)

[“Defining numeric data” on page 41](#)

[“Performing arithmetic” on page 53](#)

[“Defining national numeric](#)

[data items” on page 127](#)

[“Converting to or from national \(Unicode\) representation” on page 131](#)

#### **related references**

`MOVE` statement (*Enterprise COBOL for z/OS Language Reference*)

`BLANK WHEN ZERO` clause (*Enterprise COBOL for z/OS Language Reference*)

## **Controlling how numeric data is stored**

---

You can control how the computer stores numeric data items by coding the `USAGE` clause in your data description entries.

You might want to control the format for any of several reasons such as these:

- Arithmetic performed with computational data types is more efficient than with `USAGE DISPLAY` or `USAGE NATIONAL` data types.
- Packed-decimal format requires less storage per digit than `USAGE DISPLAY` or `USAGE NATIONAL` data types.
- Packed-decimal format converts to and from `DISPLAY` or `NATIONAL` format more efficiently than binary format does.
- Floating-point format is well suited for arithmetic operands and results with widely varying scale, while maintaining the maximal number of significant digits.
- You might need to preserve data formats when you move data from one machine to another.

The numeric data you use in your program will have one of the following formats available with COBOL:

- External decimal (`USAGE DISPLAY` or `USAGE NATIONAL`)
- External floating point (`USAGE DISPLAY` or `USAGE NATIONAL`)
- Internal decimal (`USAGE PACKED-DECIMAL`)
- Binary (`USAGE BINARY`)
- Native binary (`USAGE COMP-5`)
- Internal floating point (`USAGE COMP-1` or `USAGE COMP-2`)

`COMP` and `COMP-4` are synonymous with `BINARY`, and `COMP-3` is synonymous with `PACKED-DECIMAL`.

The compiler converts displayable numbers to the internal representation of their numeric values before using them in arithmetic operations. Therefore it is often more efficient if you define data items as `BINARY` or `PACKED-DECIMAL` than as `DISPLAY` or `NATIONAL`. For example:

```
05 Initial-count Pic S9(4) Usage Binary Value 1000.
```

Regardless of which USAGE clause you use to control the internal representation of a value, you use the same PICTURE clause conventions and decimal value in the VALUE clause (except for internal floating-point data, for which you cannot use a PICTURE clause).

[“Examples: numeric data and internal representation” on page 48](#)

#### **related concepts**

[“Formats for numeric data” on page 45](#)

[“Data format conversions” on page 49](#)

[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

#### **related tasks**

[“Defining numeric data” on page 41](#)

[“Displaying numeric data” on page 43](#)

[“Performing arithmetic” on page 53](#)

#### **related references**

[“Conversions and precision” on page 50](#)

[“Sign representation of zoned and packed-decimal data” on page 51](#)

## **Formats for numeric data**

---

Several formats are available for numeric data.

### **External decimal (DISPLAY and NATIONAL) items**

When USAGE DISPLAY is in effect for a category numeric data item (either because you have coded it, or by default), each position (byte) of storage contains one decimal digit. The items are stored in displayable form. External decimal items that have USAGE DISPLAY are referred to as *zoned decimal* data items.

When USAGE NATIONAL is in effect for a category numeric data item, 2 bytes of storage are required for each decimal digit. The items are stored in UTF-16 format. External decimal items that have USAGE NATIONAL must only contain valid UTF-16 digits. If they do not, the data is illegal and the behaviour of the generated code is undefined. External decimal items that have USAGE NATIONAL are referred to as *national decimal* data items.

National decimal data items, if signed, must have the SIGN SEPARATE clause in effect. All other rules for zoned decimal items apply to national decimal items. You can use national decimal items anywhere that other category numeric data items can be used.

External decimal (both zoned decimal and national decimal) data items are primarily intended for receiving and sending numbers between your program and files, terminals, or printers. You can also use external decimal items as operands and receivers in arithmetic processing. However, if your program performs a lot of intensive arithmetic, and efficiency is a high priority, COBOL's computational numeric types might be a better choice for the data items used in the arithmetic.

### **External floating-point (DISPLAY and NATIONAL) items**

When USAGE DISPLAY is in effect for a floating-point data item (either because you have coded it, or by default), each PICTURE character position (except for v, an implied decimal point, if used) takes 1 byte of storage. The items are stored in displayable form. External floating-point items that have USAGE DISPLAY are referred to as *display floating-point* data items in this information when necessary to distinguish them from external floating-point items that have USAGE NATIONAL.

In the following example, Compute-Result is implicitly defined as a display floating-point item:

```
05 Compute-Result Pic -9v9(9)E-99.
```

The minus signs (-) do not mean that the mantissa and exponent must necessarily be negative numbers. Instead, they mean that when the number is displayed, the sign appears as a blank for positive numbers

or a minus sign for negative numbers. If you instead code a plus sign (+), the sign appears as a plus sign for positive numbers or a minus sign for negative numbers.

When `USAGE NATIONAL` is in effect for a floating-point data item, each `PICTURE` character position (except for `v`, if used) takes 2 bytes of storage. The items are stored as national characters (UTF-16). External floating-point items that have `USAGE NATIONAL` are referred to as *national floating-point* data items.

The existing rules for display floating-point items apply to national floating-point items.

In the following example, `Compute-Result-N` is a national floating-point item:

```
05 Compute-Result-N Pic -9v9(9)E-99 Usage National.
```

If `Compute-Result-N` is displayed, the signs appear as described above for `Compute-Result`, but in national characters. To instead display `Compute-Result-N` in EBCDIC characters, direct it to the console:

```
Display Compute-Result-N Upon Console
```

You cannot use the `VALUE` clause for external floating-point items.

As with external decimal numbers, external floating-point numbers have to be converted (by the compiler) to an internal representation of their numeric value before they can be used in arithmetic operations. If you compile with the default option `ARITH (COMPAT)`, external floating-point numbers are converted to long (64-bit) floating-point format. If you compile with `ARITH (EXTEND)`, they are instead converted to extended-precision (128-bit) floating-point format.

## Binary (COMP) items

`BINARY`, `COMP`, and `COMP-4` are synonyms. Binary-format numbers occupy 2, 4, or 8 bytes of storage. If the `PICTURE` clause specifies that an item is signed, the leftmost bit is used as the operational sign.

A binary number with a `PICTURE` description of four or fewer decimal digits occupies 2 bytes; five to nine decimal digits, 4 bytes; and 10 to 18 decimal digits, 8 bytes. Binary items with nine or more digits require more handling by the compiler. Testing them for the `SIZE ERROR` condition and rounding is more cumbersome than with other types.

You can use binary items, for example, for indexes, subscripts, switches, and arithmetic operands or results.

Use the `TRUNC (STD | OPT | BIN)` compiler option to indicate how binary data (`BINARY`, `COMP`, or `COMP-4`) is to be truncated.

## Native binary (COMP-5) items

Data items that you define as `USAGE COMP-5` are represented in storage as binary data. However, unlike `USAGE COMP` items, they can contain values of magnitude up to the capacity of the native binary representation (2, 4, or 8 bytes) rather than being limited to the value implied by the number of 9s in the `PICTURE` clause.

When you move or store numeric data into a `COMP-5` item, truncation occurs at the binary field size rather than at the COBOL `PICTURE` size limit. When you reference a `COMP-5` item, the full binary field size is used in the operation.

`COMP-5` is thus particularly useful for binary data items that originate in non-COBOL programs where the data might not conform to a COBOL `PICTURE` clause.

The table below shows the ranges of possible values for `COMP-5` data items.

<i>Table 5. Ranges in value of COMP-5 data items</i>		
<b>PICTURE</b>	<b>Storage representation</b>	<b>Numeric values</b>
S9(1) through S9(4)	Binary halfword (2 bytes)	-32768 through +32767
S9(5) through S9(9)	Binary fullword (4 bytes)	-2,147,483,648 through +2,147,483,647
S9(10) through S9(18)	Binary doubleword (8 bytes)	-9,223,372,036,854,775,808 through +9,223,372,036,854,775,807
9(1) through 9(4)	Binary halfword (2 bytes)	0 through 65535
9(5) through 9(9)	Binary fullword (4 bytes)	0 through 4,294,967,295
9(10) through 9(18)	Binary doubleword (8 bytes)	0 through 18,446,744,073,709,551,615

You can specify scaling (that is, decimal positions or implied integer positions) in the PICTURE clause of COMP-5 items. If you do so, you must appropriately scale the maximal capacities listed above. For example, a data item you describe as PICTURE S99V99 COMP-5 is represented in storage as a binary halfword, and supports a range of values from -327.68 through +327.67.

**Large literals in VALUE clauses:** Literals specified in VALUE clauses for COMP-5 items can, with a few exceptions, contain values of magnitude up to the capacity of the native binary representation. See *Enterprise COBOL for z/OS Language Reference* for the exceptions.

Regardless of the setting of the TRUNC compiler option, COMP-5 data items behave like binary data does in programs compiled with TRUNC (BIN).

## Packed-decimal (COMP-3) items

PACKED-DECIMAL and COMP-3 are synonyms. Packed-decimal items occupy 1 byte of storage for every two decimal digits you code in the PICTURE description, except that the rightmost byte contains only one digit and the sign. This format is most efficient when you code an odd number of digits in the PICTURE description, so that the leftmost byte is fully used. Packed-decimal items are handled as fixed-point numbers for arithmetic purposes.

## Internal floating-point (COMP-1 and COMP-2) items

COMP-1 refers to short floating-point format and COMP-2 refers to long floating-point format, which occupy 4 and 8 bytes of storage, respectively. The leftmost bit contains the sign and the next 7 bits contain the exponent; the remaining 3 or 7 bytes contain the mantissa.

COMP-1 and COMP-2 data items are stored in System z® hexadecimal format.

### related concepts

[“Unicode and the encoding of language characters” on page 123](#)  
[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

### related tasks

[“Defining numeric data” on page 41](#)  
[“Defining national numeric data items” on page 127](#)

### related references

[“Storage of character data” on page 131](#)  
[“TRUNC” on page 344](#)  
 Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)  
 SIGN clause (*Enterprise COBOL for z/OS Language Reference*)  
 VALUE clause (*Enterprise COBOL for z/OS Language Reference*)

## Examples: numeric data and internal representation

The following table shows the internal representation of numeric items.

<i>Table 6. Internal representation of numeric items</i>			
Numeric type	PICTURE and USAGE and optional SIGN clause	Value	Internal representation
External decimal	PIC S9999 DISPLAY	+ 1234	F1 F2 F3 C4
		- 1234	F1 F2 F3 D4
		1234	F1 F2 F3 C4
	PIC 9999 DISPLAY	1234	F1 F2 F3 F4
	PIC 9999 NATIONAL	1234	00 31 00 32 00 33 00 34
	PIC S9999 DISPLAY SIGN LEADING	+ 1234	C1 F2 F3 F4
		- 1234	D1 F2 F3 F4
	PIC S9999 DISPLAY SIGN LEADING SEPARATE	+ 1234	4E F1 F2 F3 F4
		- 1234	60 F1 F2 F3 F4
	PIC S9999 DISPLAY SIGN TRAILING SEPARATE	+ 1234	F1 F2 F3 F4 4E
		- 1234	F1 F2 F3 F4 60
	PIC S9999 NATIONAL SIGN LEADING SEPARATE	+ 1234	00 2B 00 31 00 32 00 33 00 34
		- 1234	00 2D 00 31 00 32 00 33 00 34
	PIC S9999 NATIONAL SIGN TRAILING SEPARATE	+ 1234	00 31 00 32 00 33 00 34 00 2B
		- 1234	00 31 00 32 00 33 00 34 00 2D
Binary	PIC S9999 BINARY PIC S9999 COMP PIC S9999 COMP-4	+ 1234	04 D2
		- 1234	FB 2E
	PIC S9999 COMP-5	+ 12345 <sup>1</sup>	30 39
		- 12345 <sup>1</sup>	CF C7
	PIC 9999 BINARY PIC 9999 COMP PIC 9999 COMP-4	1234	04 D2
	PIC 9999 COMP-5	60000 <sup>1</sup>	EA 60

Table 6. <i>Internal representation of numeric items</i> (continued)			
Numeric type	PICTURE and USAGE and optional SIGN clause	Value	Internal representation
Internal decimal	PIC S9999 PACKED-DECIMAL PIC S9999 COMP-3	+ 1234	01 23 4C
		- 1234	01 23 4D
	PIC 9999 PACKED-DECIMAL PIC 9999 COMP-3	1234	01 23 4F
Internal floating point	COMP-1	+ 1234	43 4D 20 00
		- 1234	C3 4D 20 00
	COMP-2	+ 1234	43 4D 20 00 00 00 00 00
		- 1234	C3 4D 20 00 00 00 00 00
External floating point	PIC +9(2).9(2)E+99 DISPLAY	+ 12.34E+02	4E F1 F2 4B F3 F4 C5 4E F0 F2
		- 12.34E+02	60 F1 F2 4B F3 F4 C5 4E F0 F2
	PIC +9(2).9(2)E+99 NATIONAL	+ 12.34E+02	00 2B 00 31 00 32 00 2E 00 33 00 34 00 45 00 2B 00 30 00 32
		- 12.34E+02	00 2D 00 31 00 32 00 2E 00 33 00 34 00 45 00 2B 00 30 00 32
1. The example demonstrates that COMP-5 data items can contain values of magnitude up to the capacity of the native binary representation (2, 4, or 8 bytes), rather than being limited to the value implied by the number of 9s in the PICTURE clause.			

## Data format conversions

When the code in your program involves the interaction of items that have different data formats, the compiler converts those items either temporarily, for comparisons and arithmetic operations, or permanently, for assignment to the receiver in a MOVE or COMPUTE statement.

A conversion is actually a move of a value from one data item to another. The compiler performs any conversions that are required during the execution of arithmetic or comparisons by using the same rules that are used for MOVE and COMPUTE statements.

When possible, the compiler performs a move to preserve numeric value instead of a direct digit-for-digit move.

Conversion generally requires additional storage and processing time because data is moved to an internal work area and converted before the operation is performed. The results might also have to be moved back into a work area and converted again.

Conversions between fixed-point data formats (external decimal, packed decimal, or binary) are without loss of precision provided that the target field can contain all the digits of the source operand.

A loss of precision is possible in conversions between fixed-point data formats and floating-point data formats (short floating point, long floating point, or external floating point). These conversions happen during arithmetic evaluations that have a mixture of both fixed-point and floating-point operands.

#### **related references**

[“Conversions and precision” on page 50](#)

[“Sign representation of zoned and packed-decimal data” on page 51](#)

## **Conversions and precision**

In some numeric conversions, a loss of precision is possible; other conversions preserve precision or result in rounding.

Because both fixed-point and external floating-point items have decimal characteristics, references to fixed-point items in the following examples include external floating-point items unless stated otherwise.

When the compiler converts from fixed-point to internal floating-point format, fixed-point numbers in base 10 are converted to the numbering system used internally.

When the compiler converts short form to long form for comparisons, zeros are used for padding the shorter number.

### ***Conversions that lose precision***

When a USAGE COMP-1 data item is moved to a fixed-point data item that has more than nine digits, the fixed-point data item will receive only nine significant digits, and the remaining digits will be zero.

When a USAGE COMP-2 data item is moved to a fixed-point data item that has more than 18 digits, the fixed-point data item will receive only 18 significant digits, and the remaining digits will be zero.

### ***Conversions that preserve precision***

If a fixed-point data item that has six or fewer digits is moved to a USAGE COMP-1 data item and then returned to the fixed-point data item, the original value is recovered.

If a USAGE COMP-1 data item is moved to a fixed-point data item of nine or more digits and then returned to the USAGE COMP-1 data item, the original value is recovered.

If a fixed-point data item that has 15 or fewer digits is moved to a USAGE COMP-2 data item and then returned to the fixed-point data item, the original value is recovered.

If a USAGE COMP-2 data item is moved to a fixed-point (not external floating-point) data item of 18 or more digits and then returned to the USAGE COMP-2 data item, the original value is recovered.

### ***Conversions that result in rounding***

If a USAGE COMP-1 data item, a USAGE COMP-2 data item, an external floating-point data item, or a floating-point literal is moved to a fixed-point data item, rounding occurs in the low-order position of the target data item.

If a USAGE COMP-2 data item is moved to a USAGE COMP-1 data item, rounding occurs in the low-order position of the target data item.

If a fixed-point data item is moved to an external floating-point data item and the PICTURE of the fixed-point data item contains more digit positions than the PICTURE of the external floating-point data item, rounding occurs in the low-order position of the target data item.

## related concepts

Appendix A, “Intermediate results and arithmetic precision,” on page 655

## Sign representation of zoned and packed-decimal data

---

Sign representation affects the processing and interaction of zoned decimal and internal decimal data.

Given  $X'sd'$ , where  $s$  is the sign representation and  $d$  represents the digit, the valid sign representations for zoned decimal (USAGE DISPLAY) data without the SIGN IS SEPARATE clause are:

### Positive:

C, A, E, and F

### Negative:

D and B

The COBOL NUMPROC compiler option affects sign processing for zoned decimal and internal decimal data. NUMPROC has no effect on binary data, national decimal data, or floating-point data.

### NUMPROC(PFD)

Given  $X'sd'$ , where  $s$  is the sign representation and  $d$  represents the digit, when you use NUMPROC (PFD), the compiler assumes that the sign in your data is one of three preferred signs:

#### Signed positive or 0:

$X'C'$

#### Signed negative:

$X'D'$

#### Unsigned or alphanumeric:

$X'F'$

Based on this assumption, the compiler uses whatever sign it is given to process data. The preferred sign is generated only where necessary (for example, when unsigned data is moved to signed data). Using the NUMPROC (PFD) option can save processing time, but you must use preferred signs with your data for correct processing.

### NUMPROC(NOPFD)

When the NUMPROC (NOPFD) compiler option is in effect, the compiler accepts any valid sign configuration. The preferred sign is always generated in the receiver. NUMPROC (NOPFD) is less efficient than NUMPROC (PFD), but you should use it whenever data that does not use preferred signs might exist.

If an unsigned, zoned-decimal sender is moved to an alphanumeric receiver, the sign is unchanged (even with NUMPROC (NOPFD) in effect).

## related references

[“NUMPROC” on page 322](#)

[“ZWB” on page 355](#)

## Checking for incompatible data (numeric class test)

---

The compiler assumes that values you supply for a data item are valid for the PICTURE and USAGE clauses, and does not check their validity. Ensure that the contents of a data item conform to the PICTURE and USAGE clauses before using the item in additional processing.

It can happen that values are passed into your program and assigned to items that have incompatible data descriptions for those values. For example, nonnumeric data might be moved or passed into a field that is defined as numeric, or a signed number might be passed into a field that is defined as unsigned. In either case, the receiving fields contain invalid data. When you give an item a value that is incompatible with its data description, references to that item in the PROCEDURE DIVISION are undefined and your results are unpredictable.

You can use the numeric class test to perform data validation. For example:

```
Linkage Section.  
01 Count-x Pic 999.  
.  
.  
Procedure Division Using Count-x.  
    If Count-x is numeric then display "Data is good"
```

The numeric class test checks the contents of a data item against a set of values that are valid for the PICTURE and USAGE of the data item. For example, a packed-decimal item is checked for hexadecimal values X'0' through X'9' in the digit positions and for a valid sign value in the sign position (whether separate or nonseparate). An external decimal data item that has USAGE DISPLAY is checked for hexadecimal values X'0' through X'9' in the digit positions (the lower 4 bits of each byte), for a valid zone code in the upper 4 bits of each byte and for a valid sign value in the sign position (whether separate or nonseparate). The sign code is in the upper 4 bits of the sign byte or in a separate byte if SIGN IS SEPARATE was specified. If the SIGN IS SEPARATE clause is used, the upper four bits of all bytes must be x'F'.

**Note:** Although the ZONEDATA(MIG|NOPFD) compiler option allows toleration of invalid zone codes in USAGE DISPLAY numeric (zoned decimal) data items in numeric comparisons, invalid zone codes in zoned decimal data items will be treated as nonnumeric by the numeric class test.

For zoned decimal and packed-decimal items, the numeric class test is affected by the NUMPROC compiler option and the NUMCLS option (which is set at installation time). To determine the NUMCLS setting used at your installation, consult your system programmer.

If NUMCLS (PRIM) is in effect at your installation, use the following table to find the values that the compiler considers valid for the sign.

Table 7. <b>NUMCLS(PRIM) and valid signs</b>		
	NUMPROC (NOPFD)	NUMPROC (PFD)
<b>Signed</b>	C, D, F	C, D, +0 (positive zero)
<b>Unsigned</b>	F	F
<b>Separate sign</b>	+, -	+, -, +0 (positive zero)

If NUMCLS (ALT) is in effect at your installation, use the following table to find the values that the compiler considers valid for the sign.

Table 8. <b>NUMCLS(ALT) and valid signs</b>		
	NUMPROC (NOPFD)	NUMPROC (PFD)
<b>Signed</b>	A to F	C, D, +0 (positive zero)
<b>Unsigned</b>	F	F
<b>Separate sign</b>	+, -	+, -, +0 (positive zero)

For more information about numeric class condition, see *Class condition* in the *Enterprise COBOL for z/OS Language Reference*.

You can also use the NUMCHECK (ZON, PAC) option to have the compiler generate implicit numeric class tests for zoned decimal (numeric USAGE DISPLAY) and packed decimal (COMP-3) data items that are used as sending data items. This numeric class test validates data and also validates sign fields against the NUMPROC compiler option to help you decide whether you can use NUMPROC (PFD) or not. For details, see [“NUMCHECK” on page 320](#).

For more information about other invalid data issues, in particular for COBOL migration purposes, see the *FAQ about invalid data* in the *Enterprise COBOL Migration Guide*.

### related references

[“NUMCHECK” on page 320](#)

[“NUMPROC” on page 322](#)

[“ZONECHECK” on page 352](#)

[“ZONEDATA” on page 353](#)

## Performing arithmetic

You can use any of several COBOL language features (including COMPUTE, arithmetic expressions, numeric intrinsic functions, and math and date callable services) to perform arithmetic. Your choice depends on whether a feature meets your particular needs.

For most common arithmetic evaluations, the COMPUTE statement is appropriate. If you need to use numeric literals, numeric data, or arithmetic operators, you might want to use arithmetic expressions. In places where numeric expressions are allowed, you can save time by using numeric intrinsic functions. Language Environment callable services for mathematical functions and for date and time operations also provide a means of assigning arithmetic results to data items.

### related tasks

[“Using COMPUTE and other arithmetic statements” on page 53](#)

[“Using arithmetic expressions” on page 54](#)

[“Using numeric intrinsic functions” on page 54](#)

[“Using math-oriented callable services” on page 56](#)

[“Using date callable services” on page 57](#)

## Using COMPUTE and other arithmetic statements

Use the COMPUTE statement for most arithmetic evaluations rather than ADD, SUBTRACT, MULTIPLY, and DIVIDE statements. Often you can code only one COMPUTE statement instead of several individual arithmetic statements.

The COMPUTE statement assigns the result of an arithmetic expression to one or more data items:

```
Compute z      = a + b / c ** d - e
Compute x y z = a + b / c ** d - e
```

Some arithmetic calculations might be more intuitive using arithmetic statements other than COMPUTE. For example:

COMPUTE	Equivalent arithmetic statements
Compute Increment = Increment + 1	Add 1 to Increment
Compute Balance = Balance - Overdraft	Subtract Overdraft from Balance
Compute IncrementOne = IncrementOne + 1 Compute IncrementTwo = IncrementTwo + 1 Compute IncrementThree = IncrementThree + 1	Add 1 to IncrementOne, IncrementTwo, IncrementThree

You might also prefer to use the DIVIDE statement (with its REMAINDER phrase) for division in which you want to process a remainder. The REM intrinsic function also provides the ability to process a remainder.

When you perform arithmetic calculations, you can use national decimal data items as operands just as you use zoned decimal data items. You can also use national floating-point data items as operands just as you use display floating-point operands.

#### related concepts

[“Fixed-point contrasted with floating-point arithmetic” on page 59](#)

[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

#### related tasks

[“Defining numeric data” on page 41](#)

## Using arithmetic expressions

You can use arithmetic expressions in many (but not all) places in statements where numeric data items are allowed.

For example, you can use arithmetic expressions as comparands in relation conditions:

```
If (a + b) > (c - d + 5) Then. . .
```

Arithmetic expressions can consist of a single numeric literal, a single numeric data item, or a single intrinsic function reference. They can also consist of several of these items connected by arithmetic operators.

Arithmetic operators are evaluated in the following order of precedence:

<i>Table 9. Order of evaluation of arithmetic operators</i>		
Operator	Meaning	Order of evaluation
Unary + or -	Algebraic sign	First
**	Exponentiation	Second
/ or *	Division or multiplication	Third
Binary + or -	Addition or subtraction	Last

Operators at the same level of precedence are evaluated from left to right; however, you can use parentheses to change the order of evaluation. Expressions in parentheses are evaluated before the individual operators are evaluated. Parentheses, whether necessary or not, make your program easier to read.

#### related concepts

[“Fixed-point contrasted with floating-point arithmetic” on page 59](#)

[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

## Using numeric intrinsic functions

You can use numeric intrinsic functions only in places where numeric expressions are allowed. These functions can save you time because you don't have to code the many common types of calculations that they provide.

Numeric intrinsic functions return a signed numeric value, and are treated as temporary numeric data items.

Numeric functions are classified into the following categories:

#### Integer

Those that return an integer

**Floating point**

Those that return a long (64-bit) or extended-precision (128-bit) floating-point value (depending on whether you compile using the default option `ARITH(COMPAT)` or using `ARITH(EXTEND)`)

**Mixed**

Those that return an integer, a floating-point value, or a fixed-point number with decimal places, depending on the arguments

You can use intrinsic functions to perform several different arithmetic operations, as outlined in the following table.

<i>Table 10. Numeric intrinsic functions</i>				
Number handling	Date and time	Finance	Mathematics	Statistics
LENGTH MAX MIN NUMVAL NUMVAL-C ORD-MAX ORD-MIN	CURRENT-DATE DATE-OF-INTEGER DATE-TO-YYYYMMDD DAY-OF-INTEGER DAY-TO-YYYYDDD INTEGER-OF-DATE INTEGER-OF-DAY WHEN-COMPILED YEAR-TO-YYYY	ANNUITY PRESENT-VALUE	ACOS ASIN ATAN COS FACTORIAL INTEGER INTEGER-PART LOG LOG10 MOD REM SIN SQRT SUM TAN	MEAN MEDIAN MIDRANGE RANDOM RANGE STANDARD-DEVIATION VARIANCE

[“Examples: numeric intrinsic functions” on page 57](#)

You can reference one function as the argument of another. A nested function is evaluated independently of the outer function (except when the compiler determines whether a mixed function should be evaluated using fixed-point or floating-point instructions).

You can also nest an arithmetic expression as an argument to a numeric function. For example, in the statement below, there are three function arguments (a, b, and the arithmetic expression (c / d)):

```
Compute x = Function Sum(a b (c / d))
```

You can reference all the elements of a table (or array) as function arguments by using the ALL subscript.

You can also use the integer special registers as arguments wherever integer arguments are allowed.

Many of the capabilities of numeric intrinsic functions are also provided by Language Environment callable services.

**related concepts**

[“Fixed-point contrasted with floating-point arithmetic” on page 59](#)

[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

**related references**

[“ARITH” on page 291](#)

## Using math-oriented callable services

Most COBOL intrinsic functions have corresponding math-oriented callable services that you can use to produce the same results.

When you compile with the default option `ARITH (COMPAT)`, COBOL floating-point intrinsic functions return long (64-bit) results. When you compile with option `ARITH (EXTEND)`, COBOL floating-point intrinsic functions (with the exception of `RANDOM`) return extended-precision (128-bit) results.

For example (considering the first row of the table below), if you compile using `ARITH (COMPAT)`, `CEEDSACS` returns the same result as `ACOS`. If you compile using `ARITH (EXTEND)`, `CEESQACS` returns the same result as `ACOS`.

<i>Table 11. Compatibility of math intrinsic functions and callable services</i>			
<b>COBOL intrinsic function</b>	<b>Corresponding long-precision Language Environment callable service</b>	<b>Corresponding extended-precision Language Environment callable service</b>	<b>Results same for intrinsic function and callable service?</b>
ACOS	CEEDSACS	CEESQACS	Yes
ASIN	CEEDASN	CEESQASN	Yes
ATAN	CEEDATN	CEESQATN	Yes
COS	CEEDCOS	CEESQCOS	Yes
LOG	CEEDLOG	CEESQLOG	Yes
LOG10	CEEDLG1	CEESQLG1	Yes
RANDOM <sup>1</sup>	CEERANO	none	No
REM	CEEDMOD	CEESQMOD	Yes
SIN	CEEDSIN	CEESQSIN	Yes
SQRT	CEEDSQT	CEESQSQT	Yes
TAN	CEEDTAN	CEESQTAN	Yes
1. <code>RANDOM</code> returns a long (64-bit) floating-point result even if you pass it a 31-digit argument and compile with <code>ARITH (EXTEND)</code> .			

Both the `RANDOM` intrinsic function and `CEERANO` service generate random numbers between zero and one. However, because each uses its own algorithm, `RANDOM` and `CEERANO` produce different random numbers from the same seed.

Even for functions that produce the same results, how you use intrinsic functions and Language Environment callable services differs. The rules for the data types required for intrinsic function arguments are less restrictive. For numeric intrinsic functions, you can use arguments that are of any numeric data type. When you invoke a Language Environment callable service with a `CALL` statement, however, you must ensure that the parameters match the numeric data types (generally `COMP-1` or `COMP-2`) required by that service.

The error handling of intrinsic functions and Language Environment callable services sometimes differs. If you pass an explicit feedback token when calling the Language Environment math services, you must check the feedback code after each call and take explicit action to deal with errors. However, if you call with the feedback token explicitly `OMITTED`, you do not need to check the token; Language Environment automatically signals any errors.

### related concepts

[“Fixed-point contrasted with floating-point arithmetic” on page 59](#)

[Appendix A, “Intermediate results and arithmetic precision,” on page 655](#)

#### related tasks

[“Using Language Environment callable services” on page 649](#)

#### related references

[“ARITH” on page 291](#)

## Using date callable services

Both the COBOL date intrinsic functions and the Language Environment date callable services are based on the Gregorian calendar. However, the starting dates can differ depending on the setting of the INTDATE compiler option.

When INTDATE(LILIAN) is in effect, COBOL uses October 15, 1582 as day 1. Language Environment always uses October 15, 1582 as day 1. If you use INTDATE(LILIAN), you get equivalent results from COBOL intrinsic functions and Language Environment date callable services. The following table compares the results when INTDATE(LILIAN) is in effect.

<i>Table 12. INTDATE(LILIAN) and compatibility of date intrinsic functions and callable services</i>		
<b>COBOL intrinsic function</b>	<b>Language Environment callable service</b>	<b>Results</b>
DATE-OF-INTEGER	CEEDATE with picture string YYYYMMDD	Compatible
DAY-OF-INTEGER	CEEDATE with picture string YYYYDDD	Compatible
INTEGER-OF-DATE	CEEDAYS	Compatible
INTEGER-OF-DATE	CEECBLDY	Incompatible

When the default setting of INTDATE(ANSI) is in effect, COBOL uses January 1, 1601 as day 1. The following table compares the results when INTDATE(ANSI) is in effect.

<i>Table 13. INTDATE(ANSI) and compatibility of date intrinsic functions and callable services</i>		
<b>COBOL intrinsic function</b>	<b>Language Environment callable service</b>	<b>Results</b>
INTEGER-OF-DATE	CEECBLDY	Compatible
DATE-OF-INTEGER	CEEDATE with picture string YYYYMMDD	Incompatible
DAY-OF-INTEGER	CEEDATE with picture string YYYYDDD	Incompatible
INTEGER-OF-DATE	CEEDAYS	Incompatible

#### related tasks

[“Using Language Environment callable services” on page 649](#)

#### related references

[“INTDATE” on page 313](#)

## Examples: numeric intrinsic functions

The following examples and accompanying explanations show intrinsic functions in each of several categories.

Where the examples below show zoned decimal data items, national decimal items could instead be used. (Signed national decimal items, however, require that the SIGN SEPARATE clause be in effect.)

## General number handling

Suppose you want to find the maximum value of two prices (represented below as alphanumeric items with dollar signs), put this value into a numeric field in an output record, and determine the length of the output record. You can use NUMVAL - C (a function that returns the numeric value of an alphanumeric or national literal, or an alphanumeric or national data item) and the MAX and LENGTH functions to do so:

```
01 X                      Pic 9(2).
01 Price1                 Pic x(8)  Value "$8000".
01 Price2                 Pic x(8)  Value "$2000".
01 Output-Record.
   05 Product-Name       Pic x(20).
   05 Product-Number    Pic 9(9).
   05 Product-Price     Pic 9(6).
.
.
.
Procedure Division.
   Compute Product-Price =
      Function Max (Function Numval-C(Price1) Function Numval-C(Price2))
   Compute X = Function Length(Output-Record)
```

Additionally, to ensure that the contents in Product-Name are in uppercase letters, you can use the following statement:

```
Move Function Upper-case (Product-Name) to Product-Name
```

## Date and time

The following example shows how to calculate a due date that is 90 days from today. The first eight characters returned by the CURRENT-DATE function represent the date in a four-digit year, two-digit month, and two-digit day format (YYYYMMDD). The date is converted to its integer value; then 90 is added to this value and the integer is converted back to the YYYYMMDD format.

```
01 YYYYMMDD              Pic 9(8).
01 Integer-Form          Pic S9(9).
.
.
.
Move Function Current-Date(1:8) to YYYYMMDD
Compute Integer-Form = Function Integer-of-Date(YYYYMMDD)
Add 90 to Integer-Form
Compute YYYYMMDD = Function Date-of-Integer(Integer-Form)
Display 'Due Date: ' YYYYMMDD
```

## Finance

Business investment decisions frequently require computing the present value of expected future cash inflows to evaluate the profitability of a planned investment. The present value of an amount that you expect to receive at a given time in the future is that amount, which, if invested today at a given interest rate, would accumulate to that future amount.

For example, assume that a proposed investment of \$1,000 produces a payment stream of \$100, \$200, and \$300 over the next three years, one payment per year respectively. The following COBOL statements calculate the present value of those cash inflows at a 10% interest rate:

```
01 Series-Amt1           Pic 9(9)V99      Value 100.
01 Series-Amt2           Pic 9(9)V99      Value 200.
01 Series-Amt3           Pic 9(9)V99      Value 300.
01 Discount-Rate         Pic S9(2)V9(6)   Value .10.
01 Todays-Value          Pic 9(9)V99.
.
.
.
Compute Todays-Value =
   Function
      Present-Value(Discount-Rate Series-Amt1 Series-Amt2 Series-Amt3)
```

You can use the ANNUITY function in business problems that require you to determine the amount of an installment payment (annuity) necessary to repay the principal and interest of a loan. The series of

payments is characterized by an equal amount each period, periods of equal length, and an equal interest rate each period. The following example shows how you can calculate the monthly payment required to repay a \$15,000 loan in three years at a 12% annual interest rate (36 monthly payments, interest per month = .12/12):

```
01 Loan           Pic 9(9)V99.
01 Payment        Pic 9(9)V99.
01 Interest       Pic 9(9)V99.
01 Number-Periods Pic 99.
. . .
Compute Loan = 15000
Compute Interest = .12
Compute Number-Periods = 36
Compute Payment =
    Loan * Function Annuity((Interest / 12) Number-Periods)
```

## Mathematics

The following COBOL statement demonstrates that you can nest intrinsic functions, use arithmetic expressions as arguments, and perform previously complex calculations simply:

```
Compute Z = Function Log(Function Sqrt (2 * X + 1)) + Function Rem(X 2)
```

Here in the addend the intrinsic function REM (instead of a DIVIDE statement with a REMAINDER clause) returns the remainder of dividing X by 2.

## Statistics

Intrinsic functions make calculating statistical information easier. Assume you are analyzing various city taxes and want to calculate the mean, median, and range (the difference between the maximum and minimum taxes):

```
01 Tax-S          Pic 99v999 value .045.
01 Tax-T          Pic 99v999 value .02.
01 Tax-W          Pic 99v999 value .035.
01 Tax-B          Pic 99v999 value .03.
01 Ave-Tax        Pic 99v999.
01 Median-Tax     Pic 99v999.
01 Tax-Range      Pic 99v999.
. . .
Compute Ave-Tax   = Function Mean  (Tax-S Tax-T Tax-W Tax-B)
Compute Median-Tax = Function Median (Tax-S Tax-T Tax-W Tax-B)
Compute Tax-Range = Function Range  (Tax-S Tax-T Tax-W Tax-B)
```

### related tasks

[“Converting to numbers \(NUMVAL, NUMVAL-C\)” on page 113](#)

## Fixed-point contrasted with floating-point arithmetic

How you code arithmetic in a program (whether an arithmetic statement, an intrinsic function, an expression, or some combination of these nested within each other) determines whether the evaluation is done with floating-point or fixed-point arithmetic.

Many statements in a program could involve arithmetic. For example, each of the following types of COBOL statements requires some arithmetic evaluation:

- General arithmetic

```
compute report-matrix-col = (emp-count ** .5) + 1
add report-matrix-min to report-matrix-max giving report-matrix-tot
```

- Expressions and functions

```
compute report-matrix-col = function sqrt(emp-count) + 1
compute whole-hours      = function integer-part((average-hours) + 1)
```

- Arithmetic comparisons

```
if report-matrix-col <      function sqrt(emp-count) + 1
if whole-hours            not = function integer-part((average-hours) + 1)
```

## Floating-point evaluations

In general, if your arithmetic coding has either of the characteristics listed below, it is evaluated in floating-point arithmetic:

- An operand or result field is floating point.

An operand is floating point if you code it as a floating-point literal or if you code it as a data item that is defined as USAGE COMP-1, USAGE COMP-2, or external floating point (USAGE DISPLAY or USAGE NATIONAL with a floating-point PICTURE).

An operand that is a nested arithmetic expression or a reference to a numeric intrinsic function results in floating-point arithmetic when any of the following conditions is true:

- An argument in an arithmetic expression results in floating point.
- The function is a floating-point function.
- The function is a mixed function with one or more floating-point arguments.

- An exponent contains decimal places.

An exponent contains decimal places if you use a literal that contains decimal places, give the item a PICTURE that contains decimal places, or use an arithmetic expression or function whose result has decimal places.

An arithmetic expression or numeric function yields a result that has decimal places if any operand or argument (excluding divisors and exponents) has decimal places.

## Fixed-point evaluations

In general, if an arithmetic operation contains neither of the characteristics listed above for floating point, the compiler causes it to be evaluated in fixed-point arithmetic. In other words, arithmetic evaluations are handled as fixed point only if all the operands are fixed point, the result field is defined to be fixed point, and none of the exponents represent values with decimal places. Nested arithmetic expressions and function references must also represent fixed-point values.

## Arithmetic comparisons (relation conditions)

When you compare numeric expressions using a relational operator, the numeric expressions (whether they are data items, arithmetic expressions, function references, or some combination of these) are comparands in the context of the entire evaluation. That is, the attributes of each can influence the evaluation of the other: both expressions are evaluated in fixed point, or both are evaluated in floating point. This is also true of abbreviated comparisons even though one comparand does not explicitly appear in the comparison. For example:

```
if (a + d) = (b + e) and c
```

This statement has two comparisons:  $(a + d) = (b + e)$ , and  $(a + d) = c$ . Although  $(a + d)$  does not explicitly appear in the second comparison, it is a comparand in that comparison. Therefore, the attributes of  $c$  can influence the evaluation of  $(a + d)$ .

The compiler handles comparisons (and the evaluation of any arithmetic expressions nested in comparisons) in floating-point arithmetic if either comparand is a floating-point value or resolves to a floating-point value.

The compiler handles comparisons (and the evaluation of any arithmetic expressions nested in comparisons) in fixed-point arithmetic if both comparands are fixed-point values or resolve to fixed-point values.

Implicit comparisons (no relational operator used) are not handled as a unit, however; the two comparands are treated separately as to their evaluation in floating-point or fixed-point arithmetic. In the following example, five arithmetic expressions are evaluated independently of one another's attributes, and then are compared to each other.

```
evaluate (a + d)
  when (b + e) thru c
  when (f / g) thru (h * i)
end-evaluate
```

[“Examples: fixed-point and floating-point evaluations” on page 61](#)

#### **related references**

[“Arithmetic expressions in nonarithmetic statements” on page 663](#)

## **Examples: fixed-point and floating-point evaluations**

The following example shows statements that are evaluated using fixed-point arithmetic and using floating-point arithmetic.

Assume that you define the data items for an employee table in the following manner:

```
01 employee-table.
  05 emp-count          pic 9(4).
  05 employee-record occurs 1 to 1000 times
      depending on emp-count.
      10 hours          pic +9(5)ve+99.
. . .
01 report-matrix-col    pic 9(3).
01 report-matrix-min    pic 9(3).
01 report-matrix-max    pic 9(3).
01 report-matrix-tot    pic 9(3).
01 average-hours        pic 9(3)v9.
01 whole-hours          pic 9(4).
```

These statements are evaluated using floating-point arithmetic:

```
compute report-matrix-col = (emp-count ** .5) + 1
compute report-matrix-col = function sqrt(emp-count) + 1
if report-matrix-tot < function sqrt(emp-count) + 1
```

These statements are evaluated using fixed-point arithmetic:

```
add report-matrix-min to report-matrix-max giving report-matrix-tot
compute report-matrix-max =
  function max(report-matrix-max report-matrix-tot)
if whole-hours not = function integer-part((average-hours) + 1)
```

## **Using currency signs**

Many programs need to process financial information and present that information using the appropriate currency signs. With COBOL currency support (and the appropriate code page for your printer or display unit), you can use several currency signs in a program.

You can use one or more of the following signs:

- Symbols such as the dollar sign (\$)
- Currency signs of more than one character (such as USD or EUR)
- Euro sign, established by the Economic and Monetary Union (EMU)

To specify the symbols for displaying financial information, use the CURRENCY SIGN clause (in the SPECIAL-NAMES paragraph in the CONFIGURATION SECTION) with the PICTURE characters that relate to those symbols. In the following example, the PICTURE character \$ indicates that the currency sign \$US is to be used:

```

      Currency Sign is "$US" with Picture Symbol "$".
77  Invoice-Amount      Pic $$,$$9.99.
    ..
      Display "Invoice amount is " Invoice-Amount.

```

In this example, if Invoice-Amount contained 1500.00, the display output would be:

```

Invoice amount is  $US1,500.00

```

By using more than one CURRENCY SIGN clause in your program, you can allow for multiple currency signs to be displayed.

You can use a hexadecimal literal to indicate the currency sign value. Using a hexadecimal literal could be useful if the data-entry method for the source program does not allow the entry of the intended characters easily. The following example shows the hexadecimal value X'9F' used as the currency sign:

```

      Currency Sign X'9F' with Picture Symbol 'U'.
01  Deposit-Amount      Pic UUUUU9.99.

```

If there is no corresponding character for the euro sign on your keyboard, you need to specify it as a hexadecimal value in the CURRENCY SIGN clause. The hexadecimal value for the euro sign is either X'9F' or X'5A' depending on the code page in use, as shown in the following table.

<i>Table 14. Hexadecimal values of the euro sign</i>			
<b>Code page CCSID</b>	<b>Applicable countries</b>	<b>Modified from</b>	<b>Euro sign</b>
1140	USA, Canada, Netherlands, Portugal, Australia, New Zealand	037	X'9F'
1141	Austria, Germany	273	X'9F'
1142	Denmark, Norway	277	X'5A'
1143	Finland, Sweden	278	X'5A'
1144	Italy	280	X'9F'
1145	Spain, Latin America - Spanish	284	X'9F'
1146	UK	285	X'9F'
1147	France	297	X'9F'
1148	Belgium, Canada, Switzerland	500	X'9F'
1149	Iceland	871	X'9F'

## related references

[“CURRENCY” on page 299](#)

CURRENCY SIGN clause (*Enterprise COBOL for z/OS Language Reference*)

## Example: multiple currency signs

The following example shows how you can display values in both euro currency (as EUR) and Swiss francs (as CHF).

```
IDENTIFICATION DIVISION.
PROGRAM-ID. EuroSamp.
Environment Division.
Configuration Section.
Special-Names.
    Currency Sign is "CHF " with Picture Symbol "F"
    Currency Sign is "EUR " with Picture Symbol "U".
Data Division.
WORKING-STORAGE SECTION.
01 Deposit-in-Euro      Pic S9999V99 Value 8000.00.
01 Deposit-in-CHF      Pic S99999V99.
01 Deposit-Report.
    02 Report-in-Franc  Pic -FFFFFF9.99.
    02 Report-in-Euro   Pic -UUUUU9.99.
01 EUR-to-CHF-Conv-Rate Pic 9V99999 Value 1.53893.
. . .
PROCEDURE DIVISION.
Report-Deposit-in-CHF-and-EUR.
    Move Deposit-in-Euro to Report-in-Euro
    Compute Deposit-in-CHF Rounded
        = Deposit-in-Euro * EUR-to-CHF-Conv-Rate
    On Size Error
        Perform Conversion-Error
    Not On Size Error
        Move Deposit-in-CHF to Report-in-Franc
        Display "Deposit in euro = " Report-in-Euro
        Display "Deposit in franc = " Report-in-Franc
    End-Compute
    Goback.
Conversion-Error.
    Display "Conversion error from EUR to CHF"
    Display "Euro value: " Report-in-Euro.
```

The above example produces the following display output:


```
Deposit in euro = EUR 8000.00
Deposit in franc = CHF 12311.44
```

The exchange rate used in this example is for illustrative purposes only.



## Chapter 4. Handling tables

A *table* is a collection of data items that have the same description, such as account totals or monthly averages. A table consists of a table name and subordinate items called *table elements*. A table is the COBOL equivalent of an array.



In the example above, SAMPLE-TABLE-ONE is the group item that contains the table. TABLE-COLUMN names the table element of a one-dimensional table that occurs three times.

Rather than defining repetitious items as separate, consecutive entries in the DATA DIVISION, you use the OCCURS clause in the DATA DIVISION entry to define a table. This practice has these advantages:

- The code clearly shows the unity of the items (the table elements).
- You can use subscripts and indexes to refer to the table elements.
- You can easily repeat data items.

Tables are important for increasing the speed of a program, especially a program that looks up records.

### related concepts

[“Complex OCCURS DEPENDING ON” on page 79](#)

### related tasks

[“Defining a table \(OCCURS\)” on page 65](#)

[“Nesting tables” on page 67](#)

[“Referring to an item in a table” on page 68](#)

[“Putting values into a table” on page 71](#)

[“Creating variable-length tables \(DEPENDENT ON\)” on page 76](#)

[“Searching a table” on page 82](#)

[“Sorting a table” on page 85](#)

[“Processing table items using intrinsic functions” on page 85](#)

[“Working with unbounded tables and groups” on page 86](#)

[“Handling tables efficiently” on page 636](#)

## Defining a table (OCCURS)

To code a table, give the table a group name and define a subordinate item (the table element) to be repeated *n* times.

```
01 table-name.  
  05 element-name OCCURS n TIMES.  
    . . . (subordinate items of the table element)
```

In the example above, table-name is the name of an alphanumeric group item. The table element definition (which includes the OCCURS clause) is subordinate to the group item that contains the table. The OCCURS clause cannot be used in a level-01 description.

If a table is to contain only Unicode (UTF-16) data, and you want the group item that contains the table to behave like an elementary category national item in most operations, code the GROUP-USAGE NATIONAL clause for the group item:

```
01 table-nameN Group-Usage National.  
  05 element-nameN OCCURS m TIMES.  
    10 elementN1 Pic nn.  
    10 elementN2 Pic S99 Sign Is Leading, Separate.  
    . . .
```

Any elementary item that is subordinate to a national group must be explicitly or implicitly described as USAGE NATIONAL, and any subordinate numeric data item that is signed must be implicitly or explicitly described with the SIGN IS SEPARATE clause.

To create tables of two to seven dimensions, use nested OCCURS clauses.

To create a variable-length table, code the DEPENDING ON phrase of the OCCURS clause.

To specify that table elements will be arranged in ascending or descending order based on the values in one or more key fields of the table, code the ASCENDING or DESCENDING KEY phrases of the OCCURS clause, or both. Specify the names of the keys in decreasing order of significance. Keys can be of class alphabetic, alphanumeric, DBCS, national, or numeric. (If it has USAGE NATIONAL, a key can be of category national, or can be a national-edited, numeric-edited, national decimal, or national floating-point item.)

You must code the ASCENDING or DESCENDING KEY phrase of the OCCURS clause to do a binary search (SEARCH ALL) of a table. You can use a format 2 SORT statement to order the table according to its defined keys, thereby making the table searchable by the SEARCH ALL statement. Note that SEARCH ALL will return unpredictable results if the table has not been ordered according to the keys.

[“Example: binary search” on page 84](#)

#### **related concepts**

[“National groups” on page 127](#)

#### **related tasks**

[“Nesting tables” on page 67](#)

[“Referring to an item in a table” on page 68](#)

[“Putting values into a table” on page 71](#)

[“Creating variable-length](#)

[tables \(DEPENDING ON\)” on page 76](#)

[“Using national groups” on page 128](#)

[“Doing a binary search \(SEARCH](#)

[ALL\)” on page 84](#)

[“Defining numeric data” on page 41](#)

#### **related references**

OCCURS clause (*Enterprise COBOL for z/OS Language Reference*)

SIGN clause (*Enterprise COBOL for z/OS Language Reference*)


ASCENDING KEY and DESCENDING KEY phrases

(*Enterprise COBOL for z/OS Language Reference*)

SORT statement (*Enterprise COBOL for z/OS Language Reference*)


## Nesting tables

To create a two-dimensional table, define a one-dimensional table in each occurrence of another one-dimensional table.



For example, in SAMPLE-TABLE-TWO above, TABLE-ROW is an element of a one-dimensional table that occurs two times. TABLE-COLUMN is an element of a two-dimensional table that occurs three times in each occurrence of TABLE-ROW.

To create a three-dimensional table, define a one-dimensional table in each occurrence of another one-dimensional table, which is itself contained in each occurrence of another one-dimensional table. For example:



In SAMPLE-TABLE-THREE, TABLE-DEPTH is an element of a one-dimensional table that occurs two times. TABLE-ROW is an element of a two-dimensional table that occurs two times within each occurrence of TABLE-DEPTH. TABLE-COLUMN is an element of a three-dimensional table that occurs three times within each occurrence of TABLE-ROW.

In a two-dimensional table, the two subscripts correspond to the row and column numbers. In a three-dimensional table, the three subscripts correspond to the depth, row, and column numbers.

[“Example: subscripting” on page 68](#)

[“Example: indexing” on page 68](#)

### related tasks

[“Defining a table \(OCCURS\)” on page 65](#)

[“Referring to an item in a table” on page 68](#)

[“Putting values into a table” on page 71](#)

[“Creating variable-length tables \(DEPENDING ON\)” on page 76](#)

[“Searching a table” on page 82](#)

[“Processing table items using intrinsic functions” on page 85](#)

[“Handling tables efficiently” on page 636](#)

### related references

OCCURS clause (*Enterprise COBOL for z/OS Language Reference*)

## Example: subscripting

The following example shows valid references to SAMPLE-TABLE-THREE that use literal subscripts. The spaces are required in the second example.

```
TABLE-COLUMN (2, 2, 1)
TABLE-COLUMN (2 2 1)
```

In either table reference, the first value (2) refers to the second occurrence within TABLE-DEPTH, the second value (2) refers to the second occurrence within TABLE-ROW, and the third value (1) refers to the first occurrence within TABLE-COLUMN.

The following reference to SAMPLE-TABLE-TWO uses variable subscripts. The reference is valid if SUB1 and SUB2 are data-names that contain positive integer values within the range of the table.

```
TABLE-COLUMN (SUB1 SUB2)
```

### related tasks

[“Subscripting” on page 69](#)

## Example: indexing

The following example shows how displacements to elements that are referenced with indexes are calculated.

Consider the following three-dimensional table, SAMPLE-TABLE-FOUR:

```
01 SAMPLE-TABLE-FOUR
   05 TABLE-DEPTH OCCURS 3 TIMES INDEXED BY INX-A.
      10 TABLE-ROW OCCURS 4 TIMES INDEXED BY INX-B.
         15 TABLE-COLUMN OCCURS 8 TIMES INDEXED BY INX-C PIC X(8).
```

Suppose you code the following relative indexing reference to SAMPLE-TABLE-FOUR:

```
TABLE-COLUMN (INX-A + 1, INX-B + 2, INX-C - 1)
```

This reference causes the following computation of the displacement to the TABLE-COLUMN element:

```
(contents of INX-A) + (256 * 1)
+ (contents of INX-B) + (64 * 2)
+ (contents of INX-C) - (8 * 1)
```

This calculation is based on the following element lengths:

- Each occurrence of TABLE-DEPTH is 256 bytes in length ( $4 * 8 * 8$ ).
- Each occurrence of TABLE-ROW is 64 bytes in length ( $8 * 8$ ).
- Each occurrence of TABLE-COLUMN is 8 bytes in length.

### related tasks

[“Indexing” on page 70](#)

## Referring to an item in a table

A table element has a collective name, but the individual items within it do not have unique data-names.

To refer to an item, you have a choice of three techniques:

- Use the data-name of the table element, along with its occurrence number (called a *subscript*) in parentheses. This technique is called *subscripting*.
- Use the data-name of the table element, along with a value (called an *index*) that is added to the address of the table to locate an item (as a displacement from the beginning of the table). This technique is called *indexing*, or subscripting using index-names.
- Use both subscripts and indexes together.

#### related tasks

[“Subscripting” on page 69](#)

[“Indexing” on page 70](#)

## Subscripting

The lowest possible subscript value is 1, which references the first occurrence of a table element. In a one-dimensional table, the subscript corresponds to the row number.

You can use a literal or a data-name as a subscript. If a data item that has a literal subscript is of fixed length, the compiler resolves the location of the data item.

When you use a data-name as a variable subscript, you must describe the data-name as an elementary numeric integer. The most efficient format is COMPUTATIONAL (COMP) with a PICTURE size that is smaller than five digits. You cannot use a subscript with a data-name that is used as a subscript. The code generated for the application resolves the location of a variable subscript at run time.

You can increment or decrement a literal or variable subscript by a specified integer amount. For example:

```
TABLE-COLUMN (SUB1 - 1, SUB2 + 3)
```

You can change part of a table element rather than the whole element. To do so, refer to the character position and length of the substring to be changed. For example:

```
01 ANY-TABLE.
   05 TABLE-ELEMENT    PIC X(10)
      OCCURS 3 TIMES     VALUE "ABCDEFGHIJ".
   . . .
   MOVE "??" TO TABLE-ELEMENT (1) (3 : 2).
```

The MOVE statement in the example above moves the string '??' into table element number 1, beginning at character position 3, for a length of 2 characters.

ANY-TABLE before the change:	ANY-TABLE after the change:
ABCDEFGHIJ	AB??EFGHIJ
ABCDEFGHIJ	ABCDEFGHIJ
ABCDEFGHIJ	ABCDEFGHIJ

[“Example: subscripting” on page 68](#)

#### related tasks

[“Indexing” on page 70](#)

[“Putting values into a table” on page 71](#)

[“Searching a table” on page 82](#)

[“Handling tables efficiently” on page 636](#)

## Indexing

You create an index by using the INDEXED BY phrase of the OCCURS clause to identify an index-name. For example, INX-A in the following code is an index-name:

```
05 TABLE-ITEM PIC X(8)
   OCCURS 10 INDEXED BY INX-A.
```

The compiler calculates the value contained in the index as the occurrence number (subscript) minus 1, multiplied by the length of the table element. Therefore, for the fifth occurrence of TABLE-ITEM, the binary value contained in INX-A is  $(5 - 1) * 8$ , or 32.

You can use an index-name to reference another table only if both table descriptions have the same number of table elements, and the table elements are of the same length.

You can use the USAGE IS INDEX clause to create an index data item, and can use an index data item with any table. For example, INX-B in the following code is an index data item:

```
77 INX-B  USAGE IS INDEX.
. . .
  SET INX-A TO 10
  SET INX-B TO INX-A.
  PERFORM VARYING INX-A FROM 1 BY 1 UNTIL INX-A > INX-B
    DISPLAY TABLE-ITEM (INX-A)
. . .
END-PERFORM.
```

The index-name INX-A is used to traverse table TABLE-ITEM above. The index data item INX-B is used to hold the index of the last element of the table. The advantage of this type of coding is that calculation of offsets of table elements is minimized, and no conversion is necessary for the UNTIL condition.

You can use the SET statement to assign to an index data item the value that you stored in an index-name, as in the statement SET INX-B TO INX-A above. For example, when you load records into a variable-length table, you can store the index value of the last record into a data item defined as USAGE IS INDEX. Then you can test for the end of the table by comparing the current index value with the index value of the last record. This technique is useful when you look through or process a table.

You can increment or decrement an index-name by an elementary integer data item or a nonzero integer literal, for example:

```
SET INX-A DOWN BY 3
```

The integer represents a number of occurrences. It is converted to an index value before being added to or subtracted from the index.

Initialize the index-name by using a SET, PERFORM VARYING, or SEARCH ALL statement. You can then use the index-name in SEARCH or relational condition statements. To change the value, use a PERFORM, SEARCH, or SET statement.

Because you are comparing a physical displacement, you can directly use index data items only in SEARCH and SET statements or in comparisons with indexes or other index data items. You cannot use index data items as subscripts or indexes.

[“Example: indexing” on page 68](#)

### related tasks

[“Subscripting” on page 69](#)

[“Putting values into a table” on page 71](#)

[“Searching a table” on page 82](#)

[“Processing table items](#)

[using intrinsic functions” on page 85](#)

[“Handling tables efficiently” on page 636](#)

#### related references

INDEXED BY phrase (*Enterprise COBOL for z/OS Language Reference*)

INDEX phrase (*Enterprise COBOL for z/OS Language Reference*)

SET statement (*Enterprise COBOL for z/OS Language Reference*)

## Putting values into a table

You can put values into a table by loading the table dynamically, initializing the table with the INITIALIZE statement, or assigning values with the VALUE clause when you define the table.

#### related tasks

[“Loading a table dynamically” on page 71](#)

[“Loading a variable-length table” on page 78](#)

[“Initializing a table \(INITIALIZE\)” on page 71](#)

[“Assigning values when you define a table \(VALUE\)” on page 72](#)

[“Assigning values to a variable-length table” on page 78](#)

## Loading a table dynamically

If the initial values of a table are different with each execution of your program, you can define the table without initial values. You can instead read the changed values into the table dynamically before the program refers to the table.

To load a table, use the PERFORM statement and either subscripting or indexing.

When reading data to load your table, test to make sure that the data does not exceed the space allocated for the table. Use a named value (rather than a literal) for the maximum item count. Then, if you make the table bigger, you need to change only one value instead of all references to a literal.

[“Example: PERFORM and subscripting” on page 74](#)

[“Example: PERFORM and indexing” on page 75](#)

#### related references

PERFORM statement (*Enterprise COBOL for z/OS Language Reference*)

## Initializing a table (INITIALIZE)

You can load a table by coding one or more INITIALIZE statements.

For example, to move the value 3 into each of the elementary numeric data items in a table called TABLE-ONE, shown below, you can code the following statement:

```
INITIALIZE TABLE-ONE REPLACING NUMERIC DATA BY 3.
```

To move the character 'X' into each of the elementary alphanumeric data items in TABLE-ONE, you can code the following statement:

```
INITIALIZE TABLE-ONE REPLACING ALPHANUMERIC DATA BY "X".
```

When you use the INITIALIZE statement to initialize a table, the table is processed as a group item (that is, with group semantics); elementary data items within the group are recognized and processed. For example, suppose that TABLE-ONE is an alphanumeric group that is defined like this:

```
01 TABLE-ONE.  
  02 Trans-out Occurs 20.  
    05 Trans-code      Pic X      Value "R".  
    05 Part-number     Pic XX     Value "13".  
    05 Trans-quan      Pic 99     Value 10.  
    05 Price-fields.
```

```

10 Unit-price Pic 99V Value 50.
10 Discount Pic 99V Value 25.
10 Sales-Price Pic 999 Value 375.

Initialize TABLE-ONE Replacing Numeric Data By 3
                        Alphanumeric Data By "X"

```

The table below shows the content that each of the twenty 12-byte elements Trans-out(*n*) has before execution and after execution of the INITIALIZE statement shown above:

Trans-out( <i>n</i> ) before	Trans-out( <i>n</i> ) after
R13105025375	XXb030303003 <sup>1</sup>
1. The symbol <i>b</i> represents a blank space.	

You can similarly use an INITIALIZE statement to load a table that is defined as a national group. For example, if TABLE-ONE shown above specified the GROUP-USAGE NATIONAL clause, and Trans-code and Part-number had N instead of X in their PICTURE clauses, the following statement would have the same effect as the INITIALIZE statement above, except that the data in TABLE-ONE would instead be encoded in UTF-16:

```

Initialize TABLE-ONE Replacing Numeric Data By 3
                        National Data By N"X"

```

The REPLACING NUMERIC phrase initializes floating-point data items also.

You can use the REPLACING phrase of the INITIALIZE statement similarly to initialize all of the elementary ALPHABETIC, DBCS, ALPHANUMERIC-EDITED, NATIONAL-EDITED, and NUMERIC-EDITED data items in a table.

The INITIALIZE statement cannot assign values to a variable-length table (that is, a table that was defined using the OCCURS DEPENDING ON clause).

[“Examples: initializing data items” on page 26](#)

#### related tasks

[“Initializing a structure](#)

[\(INITIALIZE\)” on page 29](#)

[“Assigning values when you define a table \(VALUE\)” on page 72](#)

[“Assigning values to a variable-length table” on page 78](#)

[“Looping through a table” on page 98](#)

[“Using data items and group](#)

[items” on page 22](#)

[“Using national groups” on page 128](#)

#### related references

INITIALIZE statement (*Enterprise COBOL for z/OS Language Reference*)

## Assigning values when you define a table (VALUE)

If a table is to contain stable values (such as days and months), you can set the specific values when you define the table.

Set static values in tables in one of these ways:

- Initialize each table item individually.
- Initialize an entire table at the group level.
- Initialize all occurrences of a given table element to the same value.

### related tasks

[“Initializing each table item individually” on page 73](#)  
[“Initializing a table at the group level” on page 74](#)  
[“Initializing all occurrences of a given table element” on page 74](#)  
[“Initializing a structure \(INITIALIZE\)” on page 29](#)

## Initializing each table item individually

If a table is small, you can set the value of each item individually by using a VALUE clause.

Use the following technique, which is shown in the example code below:

1. Define a record (such as Error-Flag-Table below) that contains the items that are to be in the table.
2. Set the initial value of each item in a VALUE clause.
3. Code a REDEFINES entry to make the record into a table.

```
*****  
***          E R R O R   F L A G   T A B L E          ***  
*****  
01 Error-Flag-Table                                Value Spaces.  
  88 No-Errors                                      Value Spaces.  
    05 Type-Error                                  Pic X.  
    05 Shift-Error                                  Pic X.  
    05 Home-Code-Error                             Pic X.  
    05 Work-Code-Error                             Pic X.  
    05 Name-Error                                   Pic X.  
    05 Initials-Error                              Pic X.  
    05 Duplicate-Error                             Pic X.  
    05 Not-Found-Error                             Pic X.  
01 Filler Redefines Error-Flag-Table.  
  05 Error-Flag Occurs 8 Times  
    Indexed By Flag-Index                          Pic X.
```

In the example above, the VALUE clause at the 01 level initializes each of the table items to the same value. Each table item could instead be described with its own VALUE clause to initialize that item to a distinct value.

To initialize larger tables, use MOVE, PERFORM, or INITIALIZE statements.

### related tasks

[“Initializing a structure \(INITIALIZE\)” on page 29](#)  
[“Assigning values to a variable-length table” on page 78](#)

### related references

REDEFINES clause (*Enterprise COBOL for z/OS Language Reference*)  
OCCURS clause (*Enterprise COBOL for z/OS Language Reference*)

## Initializing a table at the group level

Code an alphanumeric or national group data item and assign to it, through the VALUE clause, the contents of the whole table. Then, in a subordinate data item, use an OCCURS clause to define the individual table items.

In the following example, the alphanumeric group data item TABLE-ONE uses a VALUE clause that initializes each of the four elements of TABLE-TWO:

```
01 TABLE-ONE VALUE "1234".
   05 TABLE-TWO OCCURS 4 TIMES PIC X.
```

In the following example, the national group data item Table-OneN uses a VALUE clause that initializes each of the three elements of the subordinate data item Table-TwoN (each of which is implicitly USAGE NATIONAL). Note that you can initialize a national group data item with a VALUE clause that uses an alphanumeric literal, as shown below, or a national literal.

```
01 Table-OneN Group-Usage National Value "AB12CD34EF56".
   05 Table-TwoN Occurs 3 Times Indexed By MyI.
       10 ElementOneN Pic nn.
       10 ElementTwoN Pic 99.
```

After Table-OneN is initialized, ElementOneN(1) contains NX"00410042" (the UTF-16 representation of 'AB'), the national decimal item ElementTwoN(1) contains NX"00310032" (the UTF-16 representation of '12'), and so forth.

### related references

OCCURS clause (*Enterprise COBOL for z/OS Language Reference*)

GROUP-USAGE clause (*Enterprise COBOL for z/OS Language Reference*)

## Initializing all occurrences of a given table element

You can use the VALUE clause in the data description of a table element to initialize all instances of that element to the specified value.

```
01 T2.
   05 T-OBJ PIC 9 VALUE 3.
   05 T OCCURS 5 TIMES
       DEPENDING ON T-OBJ.
       10 X PIC XX VALUE "AA".
       10 Y PIC 99 VALUE 19.
       10 Z PIC XX VALUE "BB".
```

For example, the code above causes all the X elements (1 through 5) to be initialized to AA, all the Y elements (1 through 5) to be initialized to 19, and all the Z elements (1 through 5) to be initialized to BB. T-OBJ is then set to 3.

### related tasks

[“Assigning values to a variable-length table” on page 78](#)

### related references

OCCURS clause (*Enterprise COBOL for z/OS Language Reference*)

## Example: PERFORM and subscripting

This example traverses an error-flag table using subscripting until an error code that has been set is found. If an error code is found, the corresponding error message is moved to a print report field.

```
*****
***      E R R O R   F L A G   T A B L E      ***
```

```

*****
01 Error-Flag-Table          Value Spaces.
  88 No-Errors              Value Spaces.
    05 Type-Error          Pic X.
    05 Shift-Error        Pic X.
    05 Home-Code-Error     Pic X.
    05 Work-Code-Error     Pic X.
    05 Name-Error         Pic X.
    05 Initials-Error     Pic X.
    05 Duplicate-Error     Pic X.
    05 Not-Found-Error     Pic X.
01 Filler Redefines Error-Flag-Table.
  05 Error-Flag Occurs 8 Times
    Indexed By Flag-Index   Pic X.
77 Error-on                  Pic X Value "E".
*****
***      E R R O R   M E S S A G E   T A B L E      ***
*****
01 Error-Message-Table.
  05 Filler                  Pic X(25) Value
    "Transaction Type Invalid".
  05 Filler                  Pic X(25) Value
    "Shift Code Invalid".
  05 Filler                  Pic X(25) Value
    "Home Location Code Inval.".
  05 Filler                  Pic X(25) Value
    "Work Location Code Inval.".
  05 Filler                  Pic X(25) Value
    "Last Name - Blanks".
  05 Filler                  Pic X(25) Value
    "Initials - Blanks".
  05 Filler                  Pic X(25) Value
    "Duplicate Record Found".
  05 Filler                  Pic X(25) Value
    "Commuter Record Not Found".
01 Filler Redefines Error-Message-Table.
  05 Error-Message Occurs 8 Times
    Indexed By Message-Index   Pic X(25).

PROCEDURE DIVISION.
  Perform
    Varying Sub From 1 By 1
    Until No-Errors
    If Error-Flag (Sub) = Error-On
      Move Space To Error-Flag (Sub)
      Move Error-Message (Sub) To Print-Message
      Perform 260-Print-Report
    End-If
  End-Perform
  . . .

```

## Example: PERFORM and indexing

This example traverses an error-flag table using indexing until an error code that has been set is found. If an error code is found, the corresponding error message is moved to a print report field.

```

*****
***      E R R O R   F L A G   T A B L E      ***
*****
01 Error-Flag-Table          Value Spaces.
  88 No-Errors              Value Spaces.
    05 Type-Error          Pic X.
    05 Shift-Error        Pic X.
    05 Home-Code-Error     Pic X.
    05 Work-Code-Error     Pic X.
    05 Name-Error         Pic X.
    05 Initials-Error     Pic X.
    05 Duplicate-Error     Pic X.
    05 Not-Found-Error     Pic X.
01 Filler Redefines Error-Flag-Table.
  05 Error-Flag Occurs 8 Times
    Indexed By Flag-Index   Pic X.
77 Error-on                  Pic X Value "E".
*****
***      E R R O R   M E S S A G E   T A B L E      ***
*****
01 Error-Message-Table.

```

```

05 Filler                                Pic X(25) Value
   "Transaction Type Invalid".
05 Filler                                Pic X(25) Value
   "Shift Code Invalid".
05 Filler                                Pic X(25) Value
   "Home Location Code Inval.".
05 Filler                                Pic X(25) Value
   "Work Location Code Inval.".
05 Filler                                Pic X(25) Value
   "Last Name - Blanks".
05 Filler                                Pic X(25) Value
   "Initials - Blanks".
05 Filler                                Pic X(25) Value
   "Duplicate Record Found".
05 Filler                                Pic X(25) Value
   "Commuter Record Not Found".
01 Filler Redefines Error-Message-Table.
   05 Error-Message Occurs 8 Times
       Indexed By Message-Index          Pic X(25).

PROCEDURE DIVISION.
  . . .
  Set Flag-Index To 1
  Perform Until No-Errors
    Search Error-Flag
      When Error-Flag (Flag-Index) = Error-On
        Move Space To Error-Flag (Flag-Index)
        Set Message-Index To Flag-Index
        Move Error-Message (Message-Index) To
          Print-Message
        Perform 260-Print-Report
      End-Search
    End-Perform
  . . .

```

## Creating variable-length tables (DEPENDING ON)

If you do not know before run time how many times a table element occurs, define a variable-length table. To do so, use the OCCURS DEPENDING ON (ODO) clause.

```
X OCCURS 1 TO 10 TIMES DEPENDING ON Y
```

In the example above, X is called the *ODO subject*, and Y is called the *ODO object*.

You can also specify unbounded tables and groups, see Variable-length tables in the *Enterprise COBOL for z/OS Language Reference* for details.

Two factors affect the successful manipulation of variable-length records:

- Correct calculation of record lengths

The length of the variable portions of a group item is the product of the object of the DEPENDING ON phrase and the length of the subject of the OCCURS clause.

- Conformance of the data in the object of the OCCURS DEPENDING ON clause to its PICTURE clause

If the content of the ODO object does not match its PICTURE clause, the program could terminate abnormally. You must ensure that the ODO object correctly specifies the current number of occurrences of table elements.

The following example shows a group item (REC-1) that contains both the subject and object of the OCCURS DEPENDING ON clause. The way the length of the group item is determined depends on whether it is sending or receiving data.

```

WORKING-STORAGE SECTION.
01 MAIN-AREA.
   03 REC-1.
       05 FIELD-1                                PIC 9.
       05 FIELD-2 OCCURS 1 TO 5 TIMES
           DEPENDING ON FIELD-1                  PIC X(05).

```

```

01 REC-2.
03 REC-2-DATA PIC X(50).

```

If you want to move REC-1 (the sending item in this case) to REC-2, the length of REC-1 is determined immediately before the move, using the current value in FIELD-1. If the content of FIELD-1 conforms to its PICTURE clause (that is, if FIELD-1 contains a zoned decimal item), the move can proceed based on the actual length of REC-1. Otherwise, the result is unpredictable. You must ensure that the ODO object has the correct value before you initiate the move.

When you do a move to REC-1 (the receiving item in this case), the length of REC-1 is determined using the maximum number of occurrences. In this example, five occurrences of FIELD-2, plus FIELD-1, yields a length of 26 bytes. In this case, you do not need to set the ODO object (FIELD-1) before referencing REC-1 as a receiving item. However, the sending field's ODO object (not shown) must be set to a valid numeric value between 1 and 5 for the ODO object of the receiving field to be validly set by the move.

However, if you do a move to REC-1 (again the receiving item) where REC-1 is followed by a variably located group (a type of *complex ODO*), the actual length of REC-1 is calculated immediately before the move, using the current value of the ODO object (FIELD-1). In the following example, REC-1 and REC-2 are in the same record, but REC-2 is not subordinate to REC-1 and is therefore variably located:

```

01 MAIN-AREA
03 REC-1.
05 FIELD-1 PIC 9.
05 FIELD-3 PIC 9.
05 FIELD-2 OCCURS 1 TO 5 TIMES
  DEPENDING ON FIELD-1 PIC X(05).
03 REC-2.
05 FIELD-4 OCCURS 1 TO 5 TIMES
  DEPENDING ON FIELD-3 PIC X(05).

```

The compiler issues a message that lets you know that the actual length was used. This case requires that you set the value of the ODO object before using the group item as a receiving field.

The following example shows how to define a variable-length table when the ODO object (LOCATION-TABLE-LENGTH below) is outside the group:

```

DATA DIVISION.
FILE SECTION.
FD LOCATION-FILE
  RECORDING MODE F
  BLOCK 0 RECORDS
  RECORD 80 CHARACTERS
  LABEL RECORD STANDARD.
01 LOCATION-RECORD.
05 LOC-CODE PIC XX.
05 LOC-DESCRIPTION PIC X(20).
05 FILLER PIC X(58).
WORKING-STORAGE SECTION.
01 FLAGS.
05 LOCATION-EOF-FLAG PIC X(5) VALUE SPACE.
  88 LOCATION-EOF VALUE "FALSE".
01 MISC-VALUES.
05 LOCATION-TABLE-LENGTH PIC 9(3) VALUE ZERO.
05 LOCATION-TABLE-MAX PIC 9(3) VALUE 100.
*****
***          L O C A T I O N   T A B L E          ***
***          FILE CONTAINS LOCATION CODES.        ***
*****
01 LOCATION-TABLE.
05 LOCATION-CODE OCCURS 1 TO 100 TIMES
  DEPENDING ON LOCATION-TABLE-LENGTH PIC X(80).

```

## related concepts

“Complex OCCURS DEPENDING ON” on page 79

## related tasks

[“Assigning values to a variable-length table” on page 78](#)

[“Loading a variable-length table” on page 78](#)

[“Preventing overlay when adding elements to a variable table” on page 81](#)

[“Finding the length of data items” on page 117](#)

## related references

OCCURS DEPENDING ON clause

(*Enterprise COBOL for z/OS Language Reference*)

Variable-length tables (*Enterprise COBOL for z/OS Language Reference*)

## Loading a variable-length table

You can use a *do-until* structure (a TEST AFTER loop) to control the loading of a variable-length table. For example, after the following code runs, LOCATION-TABLE-LENGTH contains the subscript of the last item in the table.

```
DATA DIVISION.
FILE SECTION.
FD LOCATION-FILE
RECORDING MODE F
BLOCK 0 RECORDS
RECORD 80 CHARACTERS
LABEL RECORD STANDARD.
01 LOCATION-RECORD.
05 LOC-CODE PIC XX.
05 LOC-DESCRIPTION PIC X(20).
05 FILLER PIC X(58).

WORKING-STORAGE SECTION.
01 FLAGS.
05 LOCATION-EOF-FLAG PIC X(5) VALUE SPACE.
08 LOCATION-EOF VALUE "YES".
01 MISC-VALUES.
05 LOCATION-TABLE-LENGTH PIC 9(3) VALUE ZERO.
05 LOCATION-TABLE-MAX PIC 9(3) VALUE 100.
*****
*** LOC A T I O N T A B L E ***
*** FILE CONTAINS LOCATION CODES. ***
*****
01 LOCATION-TABLE.
05 LOCATION-CODE OCCURS 1 TO 100 TIMES
DEPENDING ON LOCATION-TABLE-LENGTH PIC X(80).

PROCEDURE DIVISION.
Perform Test After
Varying Location-Table-Length From 1 By 1
Until Location-EOF
Or Location-Table-Length = Location-Table-Max
Move Location-Record To
Location-Code (Location-Table-Length)
Read Location-File
At End Set Location-EOF To True
End-Read
End-Perform
```

## Assigning values to a variable-length table

You can code a VALUE clause for an alphanumeric or national group item that has a subordinate data item that contains the OCCURS clause with the DEPENDING ON phrase. Each subordinate structure that contains the DEPENDING ON phrase is initialized using the maximum number of occurrences.

If you define the entire table by using the DEPENDING ON phrase, all the elements are initialized using the maximum defined value of the ODO (OCCURS DEPENDING ON) object.

If the ODO object is initialized by a VALUE clause, it is logically initialized after the ODO subject has been initialized.

```
01  TABLE-THREE          VALUE "3ABCDE".
   05  X                   PIC 9.
   05  Y OCCURS 5 TIMES
       DEPENDING ON X     PIC X.
```

For example, in the code above, the ODO subject Y(1) is initialized to 'A', Y(2) to 'B', . . . , Y(5) to 'E', and finally the ODO object X is initialized to 3. Any subsequent reference to TABLE-THREE (such as in a DISPLAY statement) refers to X and the first three elements, Y(1) through Y(3), of the table.

#### related tasks

[“Assigning values when you define a table \(VALUE\)” on page 72](#)

#### related references

OCCURS DEPENDING ON clause

(*Enterprise COBOL for z/OS Language Reference*)

## Complex OCCURS DEPENDING ON

Several types of complex OCCURS DEPENDING ON (*complex ODO*) are possible. Complex ODO is supported as an extension to the 85 COBOL Standard.

The basic forms of complex ODO permitted by the compiler are as follows:

- Variably located item or group: A data item described by an OCCURS clause with the DEPENDING ON phrase is followed by a nonsubordinate elementary or group data item.
- Variably located table: A data item described by an OCCURS clause with the DEPENDING ON phrase is followed by a nonsubordinate data item described by an OCCURS clause.
- Table that has variable-length elements: A data item described by an OCCURS clause contains a subordinate data item described by an OCCURS clause with the DEPENDING ON phrase.
- Index name for a table that has variable-length elements.
- Element of a table that has variable-length elements.

[“Example: complex ODO” on page 79](#)

#### related tasks

[“Preventing index errors](#)

[when changing ODO object value” on page 81](#)

[“Preventing overlay when adding elements to a variable table” on page 81](#)

#### related references

[“Effects of change in ODO object value” on page 80](#)

OCCURS DEPENDING ON clause

(*Enterprise COBOL for z/OS Language Reference*)

## Example: complex ODO

The following example illustrates the possible types of occurrence of complex ODO.

```
01  FIELD-A.
   02  COUNTER-1           PIC S99.
   02  COUNTER-2           PIC S99.
   02  TABLE-1.
       03  RECORD-1 OCCURS 1 TO 5 TIMES
           DEPENDING ON COUNTER-1  PIC X(3).
   02  EMPLOYEE-NUMBER     PIC X(5).
   02  TABLE-2 OCCURS 5 TIMES
       INDEXED BY INDX.      (1)
                             (2) (3)
   03  TABLE-ITEM         PIC 99.
                             (4)
   03  RECORD-2 OCCURS 1 TO 3 TIMES
                             (5)
```

```
                                DEPENDING ON COUNTER-2.  
04 DATA-NUM                                PIC S99.
```

**Definition:** In the example, COUNTER-1 is an *ODO object*, that is, it is the object of the DEPENDING ON clause of RECORD-1. RECORD-1 is said to be an *ODO subject*. Similarly, COUNTER-2 is the ODO object of the corresponding ODO subject, RECORD-2.

The types of complex ODO occurrences shown in the example above are as follows:

(1)

A variably located item: EMPLOYEE-NUMBER is a data item that follows, but is not subordinate to, a variable-length table in the same level-01 record.

(2)

A variably located table: TABLE-2 is a table that follows, but is not subordinate to, a variable-length table in the same level-01 record.

(3)

A table with variable-length elements: TABLE-2 is a table that contains a subordinate data item, RECORD-2, whose number of occurrences varies depending on the content of its ODO object.

(4)

An index-name, INDX, for a table that has variable-length elements.

(5)

An element, TABLE-ITEM, of a table that has variable-length elements.

### ***How length is calculated***

The length of the variable portion of each record is the product of its ODO object and the length of its ODO subject. For example, whenever a reference is made to one of the complex ODO items shown above, the actual length, if used, is computed as follows:

- The length of TABLE-1 is calculated by multiplying the contents of COUNTER-1 (the number of occurrences of RECORD-1) by 3 (the length of RECORD-1).
- The length of TABLE-2 is calculated by multiplying the contents of COUNTER-2 (the number of occurrences of RECORD-2) by 2 (the length of RECORD-2), and adding the length of TABLE-ITEM.
- The length of FIELD-A is calculated by adding the lengths of COUNTER-1, COUNTER-2, TABLE-1, EMPLOYEE-NUMBER, and TABLE-2 times 5.

### ***Setting values of ODO objects***

You must set *every* ODO object in a group item before you reference any complex ODO item in the group. For example, before you refer to EMPLOYEE-NUMBER in the code above, you must set COUNTER-1 and COUNTER-2 even though EMPLOYEE-NUMBER does not directly depend on either ODO object for its value.

**Restriction:** An ODO object cannot be variably located.

## **Effects of change in ODO object value**

If a data item that is described by an OCCURS clause with the DEPENDING ON phrase is followed in the same group by one or more nonsubordinate data items (a form of complex ODO), any change in value of the ODO object affects subsequent references to complex ODO items in the record.

For example:

- The size of any group that contains the relevant ODO clause reflects the new value of the ODO object.
- A MOVE to a group that contains the ODO subject is made based on the new value of the ODO object.
- The location of any nonsubordinate items that follow the item described with the ODO clause is affected by the new value of the ODO object. (To preserve the contents of the nonsubordinate items, move them to a work area before the value of the ODO object changes, then move them back.)

The value of an ODO object can change when you move data to the ODO object or to the group in which it is contained. The value can also change if the ODO object is contained in a record that is the target of a READ statement.

#### related tasks

[“Preventing index errors](#)

[when changing ODO object value” on page 81](#)

[“Preventing overlay when adding elements to a variable table” on page 81](#)

## Preventing index errors when changing ODO object value

Be careful if you reference a complex-ODO index-name, that is, an index-name for a table that has variable-length elements, after having changed the value of the ODO object for a subordinate data item in the table.

When you change the value of an ODO object, the byte offset in an associated complex-ODO index is no longer valid because the table length has changed. Unless you take precautions, you will have unexpected results if you then code a reference to the index-name such as:

- A reference to an element of the table
- A SET statement of the form SET *integer-data-item* TO *index-name* (format 1)
- A SET statement of the form SET *index-name* UP | DOWN BY *integer* (format 2)

To avoid this type of error, do these steps:

1. Save the index in an integer data item. (Doing so causes an implicit conversion: the integer item receives the table element occurrence number that corresponds to the offset in the index.)
2. Change the value of the ODO object.
3. Immediately restore the index from the integer data item. (Doing so causes an implicit conversion: the index-name receives the offset that corresponds to the table element occurrence number in the integer item. The offset is computed according to the table length then in effect.)

The following code shows how to save and restore the index-name (shown in [“Example: complex ODO” on page 79](#)) when the ODO object COUNTER-2 changes.

```
77  INTEGER-DATA-ITEM-1      PIC 99.
    . . .
    SET INDX TO 5.
*    INDX is valid at this point.
    SET INTEGER-DATA-ITEM-1 TO INDX.
*    INTEGER-DATA-ITEM-1 now has the
*    occurrence number that corresponds to INDX.
    MOVE NEW-VALUE TO COUNTER-2.
*    INDX is not valid at this point.
    SET INDX TO INTEGER-DATA-ITEM-1.
*    INDX is now valid, containing the offset
*    that corresponds to INTEGER-DATA-ITEM-1, and
*    can be used with the expected results.
```

#### related references

SET statement (*Enterprise COBOL for z/OS Language Reference*)

## Preventing overlay when adding elements to a variable table

Be careful if you increase the number of elements in a variable-occurrence table that is followed by one or more nonsubordinate data items in the same group. When you increment the value of the ODO object and add an element to a table, you can inadvertently overlay the variably located data items that follow the table.

To avoid this type of error, do these steps:


1. Save the variably located data items that follow the table in another data area.
2. Increment the value of the ODO object.

3. Move data into the new table element (if needed).
4. Restore the variably located data items from the data area where you saved them.

In the following example, suppose you want to add an element to the table VARY-FIELD-1, whose number of elements depends on the ODO object CONTROL-1. VARY-FIELD-1 is followed by the nonsubordinate variably located data item GROUP-ITEM-1, whose elements could potentially be overlaid.

```
WORKING-STORAGE SECTION.
01 VARIABLE-REC.
   05 FIELD-1                                PIC X(10).
   05 CONTROL-1                              PIC S99.
   05 CONTROL-2                              PIC S99.
   05 VARY-FIELD-1 OCCURS 1 TO 10 TIMES
      DEPENDING ON CONTROL-1                PIC X(5).
   05 GROUP-ITEM-1.
      10 VARY-FIELD-2
         OCCURS 1 TO 10 TIMES
         DEPENDING ON CONTROL-2            PIC X(9).
01 STORE-VARY-FIELD-2.
   05 GROUP-ITEM-2.
      10 VARY-FLD-2
         OCCURS 1 TO 10 TIMES
         DEPENDING ON CONTROL-2            PIC X(9).
```


Each element of VARY-FIELD-1 has 5 bytes, and each element of VARY-FIELD-2 has 9 bytes. If CONTROL-1 and CONTROL-2 both contain the value 3, you can picture storage for VARY-FIELD-1 and VARY-FIELD-2 as follows:



To add a fourth element to VARY-FIELD-1, code as follows to prevent overlaying the first 5 bytes of VARY-FIELD-2. (GROUP-ITEM-2 serves as temporary storage for the variably located GROUP-ITEM-1.)

```
MOVE GROUP-ITEM-1 TO GROUP-ITEM-2.
ADD 1 TO CONTROL-1.
MOVE five-byte-field TO
   VARY-FIELD-1 (CONTROL-1).
MOVE GROUP-ITEM-2 TO GROUP-ITEM-1.
```

You can picture the updated storage for VARY-FIELD-1 and VARY-FIELD-2 as follows:



Note that the fourth element of VARY-FIELD-1 did not overlay the first element of VARY-FIELD-2.

## Searching a table

COBOL provides two search techniques for tables: *serial* and *binary*.

To do serial searches, use SEARCH and indexing. For variable-length tables, you can use PERFORM with subscripting or indexing.

To do binary searches, use SEARCH ALL and indexing.

A binary search can be considerably more efficient than a serial search. For a serial search, the number of comparisons is of the order of  $n$ , the number of entries in the table. For a binary search, the number of comparisons is of the order of only the logarithm (base 2) of  $n$ . A binary search, however, requires that the table items already be sorted.

#### related tasks

[“Doing a serial search \(SEARCH\)” on page 83](#)

[“Doing a binary search \(SEARCH ALL\)” on page 84](#)

## Doing a serial search (SEARCH)

Use the SEARCH statement to do a serial (sequential) search beginning at the current index setting. To modify the index setting, use the SET statement.

The conditions in the WHEN phrase are evaluated in the order in which they appear:

- If none of the conditions is satisfied, the index is increased to correspond to the next table element, and the WHEN conditions are evaluated again.
- If one of the WHEN conditions is satisfied, the search ends. The index remains pointing to the table element that satisfied the condition.
- If the entire table has been searched and no conditions were met, the AT END imperative statement is executed if there is one. If you did not code AT END, control passes to the next statement in the program.

You can reference only one level of a table (a table element) with each SEARCH statement. To search multiple levels of a table, use nested SEARCH statements. Delimit each nested SEARCH statement with END-SEARCH.

**Performance:** If the found condition comes after some intermediate point in the table, you can speed up the search by using the SET statement to set the index to begin the search after that point. Arranging the table so that the data used most often is at the beginning of the table also enables more efficient serial searching. If the table is large and is presorted, a binary search is more efficient.

[“Example: serial search” on page 83](#)

#### related references

SEARCH statement (*Enterprise COBOL for z/OS Language Reference*)

## Example: serial search

The following example shows how you might find a particular string in the innermost table of a three-dimensional table.

Each dimension of the table has its own index (set to 1, 4, and 1, respectively). The innermost table (TABLE-ENTRY3) has an ascending key.

```
01  TABLE-ONE.
   05  TABLE-ENTRY1 OCCURS 10 TIMES
       INDEXED BY TE1-INDEX.
   10  TABLE-ENTRY2 OCCURS 10 TIMES
       INDEXED BY TE2-INDEX.
   15  TABLE-ENTRY3 OCCURS 5 TIMES
       ASCENDING KEY IS KEY1
       INDEXED BY TE3-INDEX.
       20  KEY1                                PIC X(5).
       20  KEY2                                PIC X(10).

PROCEDURE DIVISION.
    SET TE1-INDEX TO 1
    SET TE2-INDEX TO 4
```

```

SET TE3-INDEX TO 1
MOVE "A1234" TO KEY1 (TE1-INDEX, TE2-INDEX, TE3-INDEX + 2)
MOVE "AAAAAAA00" TO KEY2 (TE1-INDEX, TE2-INDEX, TE3-INDEX + 2)

SEARCH TABLE-ENTRY3
  AT END
    MOVE 4 TO RETURN-CODE
  WHEN TABLE-ENTRY3(TE1-INDEX, TE2-INDEX, TE3-INDEX)
    = "A1234AAAAAAA00"
    MOVE 0 TO RETURN-CODE
END-SEARCH

```

#### Values after execution:

```

TE1-INDEX = 1
TE2-INDEX = 4
TE3-INDEX points to the TABLE-ENTRY3 item
              that equals "A1234AAAAAAA00"
RETURN-CODE = 0

```

## Doing a binary search (SEARCH ALL)

If you use `SEARCH ALL` to do a binary search, you do not need to set the index before you begin. The index is always the one that is associated with the first index-name in the `OCCURS` clause. The index varies during execution to maximize the search efficiency.

To use the `SEARCH ALL` statement to search a table, the table must specify the `ASCENDING` or `DESCENDING KEY` phrases of the `OCCURS` clause, or both, and must already be ordered on the key or keys that are specified in the `ASCENDING` and `DESCENDING KEY` phrases. You can use a `format 2 SORT` statement to order the table according to its defined keys, thereby making the table searchable by the `SEARCH ALL` statement. Note that `SEARCH ALL` will return unpredictable results if the table has not been ordered according to the keys.

In the `WHEN` phrase of the `SEARCH ALL` statement, you can test any key that is named in the `ASCENDING` or `DESCENDING KEY` phrases for the table, but you must test all preceding keys, if any. The test must be an equal-to condition, and the `WHEN` phrase must specify either a key (subscripted by the first index-name associated with the table) or a condition-name that is associated with the key. The `WHEN` condition can be a compound condition that is formed from simple conditions that use `AND` as the only logical connective.

Each key and its object of comparison must be compatible according to the rules for comparison of data items. Note though that if a key is compared to a national literal or identifier, the key must be a national data item.

[“Example: binary search” on page 84](#)

#### related tasks

[“Defining a table \(OCCURS\)” on page 65](#)

#### related references

`SEARCH` statement (*Enterprise COBOL for z/OS Language Reference*)

General relation conditions (*Enterprise COBOL for z/OS Language Reference*)

## Example: binary search

The following example shows how you can code a binary search of a table.

Suppose you define a table that contains 90 elements of 40 bytes each, and three keys. The primary and secondary keys (`KEY-1` and `KEY-2`) are in ascending order, but the least significant key (`KEY-3`) is in descending order:

```

01 TABLE-A.
05 TABLE-ENTRY OCCURS 90 TIMES
   ASCENDING KEY-1, KEY-2
   DESCENDING KEY-3
   INDEXED BY INDX-1.

```

```

10 PART-1      PIC 99.
10 KEY-1       PIC 9(5).
10 PART-2      PIC 9(6).
10 KEY-2       PIC 9(4).
10 PART-3      PIC 9(18).
10 KEY-3       PIC 9(5).

```

You can search this table by using the following statements:

```

SEARCH ALL TABLE-ENTRY
  AT END
    PERFORM NOENTRY
  WHEN KEY-1 (INDX-1) = VALUE-1 AND
        KEY-2 (INDX-1) = VALUE-2 AND
        KEY-3 (INDX-1) = VALUE-3
    MOVE PART-1 (INDX-1) TO OUTPUT-AREA
  END-SEARCH

```

If an entry is found in which each of the three keys is equal to the value to which it is compared (VALUE-1, VALUE-2, and VALUE-3, respectively), PART-1 of that entry is moved to OUTPUT-AREA. If no matching key is found in the entries in TABLE-A, the NOENTRY routine is performed.

## Sorting a table

You can sort a table by using the format 2 SORT statement. It is part of the 2002 COBOL Standard.

The format 2 SORT statement sorts table elements according to the specified table keys, and it is especially useful for tables used with SEARCH ALL. You can specify the keys for sorting as part of the table definition, which can also be used in the SEARCH ALL statement. Alternatively, you can also specify the keys for sorting as part of the SORT statement, either if you want to sort the table using different keys than those specified in the table definition, or if the table has no keys specified.

With the format 2 SORT statement, you don't need to use the input and output procedures as you do with the format 1 SORT statement.

See the following example in which the table is sorted based on specified keys:

```

WORKING-STORAGE SECTION.
01 GROUP-ITEM.
   05 TABL OCCURS 10 TIMES
      10 ELEM-ITEM1 PIC X.
      10 ELEM-ITEM2 PIC X.
      10 ELEM-ITEM3 PIC X.
   ...
PROCEDURE DIVISION.
   ...
   SORT TABL DESCENDING ELEM-ITEM2 ELEM-ITEM3.
   IF TABL (1)...

```

### related references

SORT statement (*Enterprise COBOL for z/OS Language Reference*)  
[“Using the format 2 SORT statement to sort a table” on page 652](#)

## Processing table items using intrinsic functions

You can use intrinsic functions to process alphabetic, alphanumeric, national, or numeric table items. (You can process DBCS data items only with the NATIONAL-OF intrinsic function.) The data descriptions of the table items must be compatible with the requirements for the function arguments.

Use a subscript or index to reference an individual data item as a function argument. For example, assuming that Table-One is a 3 x 3 array of numeric items, you can find the square root of the middle element by using this statement:

```

Compute X = Function Sqrt(Table-One(2,2))

```

You might often need to iteratively process the data in tables. For intrinsic functions that accept multiple arguments, you can use the subscript ALL to reference all the items in the table or in a single dimension of the table. The iteration is handled automatically, which can make your code shorter and simpler.

You can mix scalars and array arguments for functions that accept multiple arguments:

```
Compute Table-Median = Function Median(Arg1 Table-One(ALL))
```

[“Example: processing tables using intrinsic functions” on page 86](#)

#### related tasks

[“Using intrinsic functions \(built-in functions\)” on page 36](#)

[“Converting data items \(intrinsic functions\)” on page 111](#)

[“Evaluating data items \(intrinsic functions\)” on page 114](#)

#### related references

Intrinsic functions (*Enterprise COBOL for z/OS Language Reference*)

## Example: processing tables using intrinsic functions

These examples show how you can apply an intrinsic function to some or all of the elements in a table by using the ALL subscript.

Assuming that Table-Two is a 2 x 3 x 2 array, the following statement adds the values in elements Table-Two(1,3,1), Table-Two(1,3,2), Table-Two(2,3,1), and Table-Two(2,3,2):

```
Compute Table-Sum = FUNCTION SUM (Table-Two(ALL, 3, ALL))
```

The following example computes various salary values for all the employees whose salaries are encoded in Employee-Table:

```
01 Employee-Table.
   05 Emp-Count      Pic s9(4) usage binary.
   05 Emp-Record     Occurs 1 to 500 times
                     depending on Emp-Count.
       10 Emp-Name    Pic x(20).
       10 Emp-Idme    Pic 9(9).
       10 Emp-Salary  Pic 9(7)v99.
..
Procedure Division.
   Compute Max-Salary = Function Max(Emp-Salary(ALL))
   Compute I          = Function Ord-Max(Emp-Salary(ALL))
   Compute Avg-Salary = Function Mean(Emp-Salary(ALL))
   Compute Salary-Range = Function Range(Emp-Salary(ALL))
   Compute Total-Payroll = Function Sum(Emp-Salary(ALL))
```

## Working with unbounded tables and groups

You can process an unbounded group as the input parameter to a called program. The memory for the unbounded group is provided by the calling program. Alternatively, you can define, initialize, and process unbounded groups in a single program.

To work with unbounded tables and groups in a single program, do these steps:

1. In the LINKAGE SECTION, define an unbounded table (with the syntax of OCCURS *n* TO UNBOUNDED), which will be part of an unbounded group.
2. In the WORKING-STORAGE SECTION or LOCAL-STORAGE SECTION, define the OCCURS DEPENDING ON objects.
3. In the PROCEDURE DIVISION, do these steps to process unbounded groups:
  - a. Set the OCCURS DEPENDING ON objects.

- b. Use the LENGTH special register or the LENGTH intrinsic function to compute the total size of the group.
  - c. Use the CALL statement to call a storage allocation service, such as the Language Environment service CEEGTST. Allocate enough memory for the total length of the group. You will need a pointer to this memory (the CEEGTST service returns a pointer).
  - d. Use the SET statement to establish addressability. For example, SET ADDRESS OF *group* TO *pointer*.
4. Use the unbounded table and its containing unbounded group according to the following rules:
- You can reference unbounded tables in COBOL syntax anywhere a table can be referenced.
  - You can reference unbounded groups in COBOL syntax anywhere an alphanumeric or national group can be referenced, with the following exceptions:
    - You cannot specify unbounded groups as a BY CONTENT argument in a CALL statement.
    - You cannot specify unbounded groups as *data-name-2* on the PROCEDURE DIVISION RETURNING phrase.
    - You cannot specify unbounded groups as arguments to intrinsic functions, except as an argument to the LENGTH intrinsic function.

### related references

[“Example: Using unbounded tables for parsing XML documents” on page 87](#)

Example: ALLOCATE and FREE storage for unbounded tables

(*Enterprise COBOL for z/OS Language Reference*)

Variable-length tables (*Enterprise COBOL for z/OS Language Reference*)

OCCURS DEPENDING ON clause

(*Enterprise COBOL for z/OS Language Reference*)

## Example: Using unbounded tables for parsing XML documents

Consider using unbounded tables when parsing an XML document with an unknown number of repetitive elements.

You can use any of the following methods:

- Predetermine the number of elements to expect. One method to determine the number of elements is to parse the XML document twice. During the first parse, count the number of occurrences of each unbounded element in the corresponding OCCURS UNBOUNDED DEPENDING ON object. Then, allocate storage for the data items using these computed values, and parse the XML document a second time to process its payload.
- Pick initial sizes and allow for expansion of the tables. It might be more efficient to set arbitrary limits in the OCCURS UNBOUNDED DEPENDING ON objects based on previous experience, and parse the document directly to process its content. For each unbounded element, check if the current limit is about to be exceeded. If so, allocate more storage for the corresponding array, copy the data from the old array to the expanded array, then free the storage for the old array.

The following examples illustrate the first method. See the *XML schema* example, and note that elements B and C have a maxOccurs value of unbounded, and thus can occur an unlimited number of times in the sequence within element G. In the *XML document* example, element B in fact occurs three times, and element C occurs five times.

In the *XML processing program* example, the processing procedure for the first XML PARSE statement simply computes the number of occurrences of elements B and C. After allocating the required storage, the program executes a second XML PARSE statement to process the XML payload.

### XML schema

```
<?xml version="1.0" encoding="UTF-8"?>
<xsd:schema targetNamespace="http://example.org"
  xmlns:xsd="http://www.w3.org/2001/XMLSchema">
  <xsd:element name="G">
```

```

<xsd:complexType>
<xsd:sequence>
<xsd:element name="A" type="xsd:string" maxOccurs="1" />
<xsd:element name="B" type="xsd:int" maxOccurs="unbounded" />
<xsd:element name="C" type="xsd:int" maxOccurs="unbounded" />
</xsd:sequence>
</xsd:complexType>
</xsd:element>
</xsd:schema>

```

## XML document

```

<?xml version="1.0" encoding="UTF-8"?>
<p:G xmlns:p="http://example.org" >
<A>Hello</A>
<B>1</B>
<B>2</B>
<B>3</B>
<C>1</C>
<C>2</C>
<C>3</C>
<C>4</C>
<C>5</C>
</p:G>

```

## XML processing program

```

Identification division.
Program-id. XMLProc.
Data division.
Working-storage section.
01 NB pic S9(9) binary value zero.
01 NC pic S9(9) binary value zero.
01 Gptr pointer.
01 Gsize pic 9(9) binary.
01 Heap0 pic 9(9) binary value zero.
Linkage section.
01 XML-Doc pic X(500000).
01 G.
    02 A pic x(5).
    02 B pic s9(9) occurs 1 to unbounded depending on NB.
    02 C pic s9(9) occurs 1 to unbounded depending on NC.
Procedure division using XML-Doc.
XML parse XML-Doc processing procedure CountElements
Move length of G to Gsize
Call "CEEGTST" using Heap0 Gsize Gptr omitted
Set address of G to Gptr
XML parse XML-doc processing procedure acquireContent
...
Goback.
CountElements.
If xml-event = 'START-OF-ELEMENT'
    Evaluate xml-text
        When 'B'
            Add 1 to NB
        When 'C'
            Add 1 to NC
        When other
            Continue
    End-evaluate
End-if.
End program XMLProc.

```

## related tasks

[“Working with unbounded tables and groups” on page 86](#)

---

## Chapter 5. Selecting and repeating program actions

Use COBOL control language to choose program actions based on the outcome of logical tests, to iterate over selected parts of your program and data, and to identify statements to be performed as a group.

These controls include the IF, EVALUATE, and PERFORM statements, and the use of switches and flags.

### related tasks

[“Selecting program actions” on page 89](#)

[“Repeating program actions” on page 96](#)

---

## Selecting program actions

You can provide for different program actions depending on the tested value of one or more data items.

The IF and EVALUATE statements in COBOL test one or more data items by means of a conditional expression.

### related tasks

[“Coding a choice of actions” on page 89](#)

[“Coding conditional expressions” on page 93](#)

### related references

IF statement (*Enterprise COBOL for z/OS Language Reference*)

EVALUATE statement (*Enterprise COBOL for z/OS Language Reference*)

## Coding a choice of actions

Use IF . . . ELSE to code a choice between two processing actions. (The word THEN is optional.) Use the EVALUATE statement to code a choice among three or more possible actions.

```
IF condition-p
  statement-1
ELSE
  statement-2
END-IF
```

When one of two processing choices is no action, code the IF statement with or without ELSE. Because the ELSE clause is optional, you can code the IF statement as follows:

```
IF condition-q
  statement-1
END-IF
```

Such coding is suitable for simple cases. For complex logic, you probably need to use the ELSE clause. For example, suppose you have nested IF statements in which there is an action for only one of the processing choices. You could use the ELSE clause and code the null branch of the IF statement with the CONTINUE statement:

```
IF condition-q
  statement-1
ELSE
  CONTINUE
END-IF
```

The EVALUATE statement is an expanded form of the IF statement that allows you to avoid nesting IF statements, a common source of logic errors and debugging problems.

### related tasks

[“Using nested IF statements” on page 90](#)

[“Using the EVALUATE statement” on page 91](#)

[“Coding conditional expressions” on page 93](#)

## Using nested IF statements

If an IF statement contains an IF statement as one of its possible branches, the IF statements are said to be *nested*. Theoretically, there is no limit to the depth of nested IF statements.


However, use nested IF statements sparingly. The logic can be difficult to follow, although explicit scope terminators and indentation can help. If a program has to test a variable for more than two values, EVALUATE is probably a better choice.

The following pseudocode depicts a nested IF statement:

```
IF condition-p
  IF condition-q
    statement-1
  ELSE
    statement-2
  END-IF
statement-3
ELSE
  statement-4
END-IF
```

In the pseudocode above, an IF statement and a sequential structure are nested in one branch of the outer IF. In this structure, the END-IF that closes the nested IF is very important. Use END-IF instead of a period, because a period would end the outer IF structure also.

The following figure shows the logic structure of the pseudocode above.



### related tasks

[“Coding a choice of actions” on page 89](#)

### related references

Explicit scope terminators (*Enterprise COBOL for z/OS Language Reference*)

## Using the EVALUATE statement

You can use the EVALUATE statement instead of a series of nested IF statements to test several conditions and specify a different action for each. Thus you can use the EVALUATE statement to implement a *case structure* or decision table.

You can also use the EVALUATE statement to cause multiple conditions to lead to the same processing, as shown in these examples:

[“Example: EVALUATE using THRU phrase” on page 91](#)

[“Example: EVALUATE using multiple WHEN phrases” on page 92](#)

In an EVALUATE statement, the operands before the WHEN phrase are referred to as *selection subjects*, and the operands in the WHEN phrase are called the *selection objects*. Selection subjects can be identifiers, literals, conditional expressions, or the word TRUE or FALSE. Selection objects can be identifiers, literals, conditional or arithmetic expressions, or the word TRUE, FALSE, or ANY.

You can separate multiple selection subjects with the ALSO phrase. You can separate multiple selection objects with the ALSO phrase. The number of selection objects within each set of selection objects must be equal to the number of selection subjects, as shown in this example:

[“Example: EVALUATE testing several conditions” on page 92](#)

Identifiers, literals, or arithmetic expressions that appear within a selection object must be valid operands for comparison to the corresponding operand in the set of selection subjects. Conditions or the word TRUE or FALSE that appear in a selection object must correspond to a conditional expression or the word TRUE or FALSE in the set of selection subjects. (You can use the word ANY as a selection object to correspond to any type of selection subject.)

The execution of the EVALUATE statement ends when one of the following conditions occurs:

- The statements associated with the selected WHEN phrase are performed.
- The statements associated with the WHEN OTHER phrase are performed.
- No WHEN conditions are satisfied.

WHEN phrases are tested in the order that they appear in the source program. Therefore, you should order these phrases for the best performance. First code the WHEN phrase that contains selection objects that are most likely to be satisfied, then the next most likely, and so on. An exception is the WHEN OTHER phrase, which must come last.

### related tasks

[“Coding a choice of actions” on page 89](#)

### related references

EVALUATE statement (*Enterprise COBOL for z/OS Language Reference*)

General relation conditions (*Enterprise COBOL for z/OS Language Reference*)

### Example: EVALUATE using THRU phrase

This example shows how you can code several conditions in a range of values to lead to the same processing action by coding the THRU phrase. Operands in a THRU phrase must be of the same class.

In this example, CARPOOL-SIZE is the *selection subject*; 1, 2, and 3 THRU 6 are the *selection objects*:

```
EVALUATE CARPOOL-SIZE
  WHEN 1
    MOVE "SINGLE" TO PRINT-CARPOOL-STATUS
  WHEN 2
    MOVE "COUPLE" TO PRINT-CARPOOL-STATUS
  WHEN 3 THRU 6
    MOVE "SMALL GROUP" TO PRINT-CARPOOL STATUS
  WHEN OTHER
    MOVE "BIG GROUP" TO PRINT-CARPOOL STATUS
END-EVALUATE
```

The following nested IF statements represent the same logic:

```
IF CARPOOL-SIZE = 1 THEN
  MOVE "SINGLE" TO PRINT-CARPOOL-STATUS
ELSE
  IF CARPOOL-SIZE = 2 THEN
    MOVE "COUPLE" TO PRINT-CARPOOL-STATUS
  ELSE
    IF CARPOOL-SIZE >= 3 and CARPOOL-SIZE <= 6 THEN
      MOVE "SMALL GROUP" TO PRINT-CARPOOL-STATUS
    ELSE
      MOVE "BIG GROUP" TO PRINT-CARPOOL-STATUS
    END-IF
  END-IF
END-IF
```

### **Example: EVALUATE using multiple WHEN phrases**

The following example shows that you can code multiple WHEN phrases if several conditions should lead to the same action. Doing so gives you more flexibility than using only the THRU phrase, because the conditions do not have to evaluate to values in a range nor have the same class.

```
EVALUATE MARITAL-CODE
  WHEN "M"
    ADD 2 TO PEOPLE-COUNT
  WHEN "S"
  WHEN "D"
  WHEN "W"
    ADD 1 TO PEOPLE-COUNT
END-EVALUATE
```

The following nested IF statements represent the same logic:

```
IF MARITAL-CODE = "M" THEN
  ADD 2 TO PEOPLE-COUNT
ELSE
  IF MARITAL-CODE = "S" OR
    MARITAL-CODE = "D" OR
    MARITAL-CODE = "W" THEN
    ADD 1 TO PEOPLE-COUNT
  END-IF
END-IF
```

### **Example: EVALUATE testing several conditions**

This example shows the use of the ALSO phrase to separate two selection subjects (True ALSO True) and to separate the two corresponding selection objects within each set of selection objects (for example, When A + B < 10 Also C = 10).

Both selection objects in a WHEN phrase must satisfy the TRUE, TRUE condition before the associated action is performed. If both objects do not evaluate to TRUE, the next WHEN phrase is processed.

```
Identification Division.
  Program-ID. MiniEval.
Environment Division.
  Configuration Section.
    Source-Computer. IBM-390. Data Division.
    Working-Storage Section.
      01 Age Pic 999.
      01 Sex Pic X.
      01 Description Pic X(15).
      01 A Pic 999.
      01 B Pic 9999.
      01 C Pic 9999.
      01 D Pic 9999.
      01 E Pic 99999.
      01 F Pic 999999.
  Procedure Division.
    PN01.
      Evaluate True Also True
```

```

When Age < 13 Also Sex = "M"
  Move "Young Boy" To Description
When Age < 13 Also Sex = "F"
  Move "Young Girl" To Description
When Age > 12 And Age < 20 Also Sex = "M"
  Move "Teenage Boy" To Description
When Age > 12 And Age < 20 Also Sex = "F"
  Move "Teenage Girl" To Description
When Age > 19 Also Sex = "M"
  Move "Adult Man" To Description
When Age > 19 Also Sex = "F"
  Move "Adult Woman" To Description
When Other
  Move "Invalid Data" To Description
End-Evaluate
Evaluate True Also True
  When A + B < 10 Also C = 10
    Move "Case 1" To Description
  When A + B > 50 Also C = ( D + E ) / F
    Move "Case 2" To Description
  When Other
    Move "Case Other" To Description
End-Evaluate
Stop Run.

```

## Coding conditional expressions

Using the IF and EVALUATE statements, you can code program actions that will be performed depending on the truth value of a conditional expression.

You can specify the following conditions:

- Relation conditions, such as:
  - Numeric comparisons
  - Alphanumeric comparisons
  - DBCS comparisons
  - National comparisons
- Class conditions; for example, to test whether a data item:
  - IS NUMERIC
  - IS ALPHABETIC
  - IS DBCS
  - IS KANJI
  - IS NOT KANJI
- Condition-name conditions, to test the value of a conditional variable that you define
- Sign conditions, to test whether a numeric operand IS POSITIVE, NEGATIVE, or ZERO
- Switch-status conditions, to test the status of UPSI switches that you name in the SPECIAL - NAMES paragraph
- Complex conditions, such as:
  - Negated conditions; for example, NOT ( A IS EQUAL TO B )
  - Combined conditions (conditions combined with logical operators AND or OR)

### related concepts

[“Switches and flags” on page 94](#)

### related tasks

[“Defining switches and flags” on page 94](#)

[“Resetting switches and flags” on page 95](#)

[“Checking for incompatible data \(numeric class test\)” on page 51](#)

[“Comparing national \(UTF-16\)](#)

[data” on page 140](#)

[“Testing for valid DBCS characters” on page 144](#)

#### **related references**

General relation conditions (*Enterprise COBOL for z/OS Language Reference*)

Class condition (*Enterprise COBOL for z/OS Language Reference*)

Rules for condition-name entries (*Enterprise COBOL for z/OS Language Reference*)

Sign condition (*Enterprise COBOL for z/OS Language Reference*)

Combined conditions (*Enterprise COBOL for z/OS Language Reference*)

## **Switches and flags**

Some program decisions are based on whether the value of a data item is true or false, on or off, yes or no. Control these two-way decisions by using level-88 items with meaningful names (*condition-names*) to act as switches.

Other program decisions depend on the particular value or range of values of a data item. When you use condition-names to give more than just on or off values to a field, the field is generally referred to as a *flag*.

Flags and switches make your code easier to change. If you need to change the values for a condition, you have to change only the value of that level-88 condition-name.

For example, suppose a program uses a condition-name to test a field for a given salary range. If the program must be changed to check for a different salary range, you need to change only the value of the condition-name in the DATA DIVISION. You do not need to make changes in the PROCEDURE DIVISION.

#### **related tasks**

[“Defining switches and flags” on page 94](#)

[“Resetting switches and flags” on page 95](#)

## **Defining switches and flags**

In the DATA DIVISION, define level-88 items that will act as switches or flags, and give them meaningful names.

To test for more than two values with flags, assign more than one condition-name to a field by using multiple level-88 items.

The reader can easily follow your code if you choose meaningful condition-names and if the values assigned to them have some association with logical values.

[“Example: switches” on page 94](#)

[“Example: flags” on page 95](#)

## **Example: switches**

The following examples show how you can use level-88 items to test for various binary-valued (on-off) conditions in your program.

For example, to test for the end-of-file condition for an input file named Transaction-File, you can use the following data definitions:

```
WORKING-STORAGE SECTION.  
01 Switches.  
   05 Transaction-EOF-Switch Pic X value space.  
   88 Transaction-EOF      value "y".
```

The level-88 description says that a condition named Transaction-EOF is in effect when Transaction-EOF-Switch has value 'y'. Referencing Transaction-EOF in the PROCEDURE DIVISION expresses the same condition as testing Transaction-EOF-Switch = "y". For example,

the following statement causes a report to be printed only if Transaction-EOF-Switch has been set to 'y':

```
If Transaction-EOF Then
    Perform Print-Report-Summary-Lines
End-if
```

## Example: flags

The following examples show how you can use several level-88 items together with an EVALUATE statement to determine which of several conditions in a program is true.

Consider for example a program that updates a master file. The updates are read from a transaction file. The records in the file contain a field that indicates which of the three functions is to be performed: add, change, or delete. In the record description of the input file, code a field for the function code using level-88 items:

```
01 Transaction-Input Record
   05 Transaction-Type          Pic X.
      88 Add-Transaction        Value "A".
      88 Change-Transaction     Value "C".
      88 Delete-Transaction     Value "D".
```

The code in the PROCEDURE DIVISION for testing these condition-names to determine which function is to be performed might look like this:

```
Evaluate True
  When Add-Transaction
    Perform Add-Master-Record-Paragraph
  When Change-Transaction
    Perform Update-Existing-Record-Paragraph
  When Delete-Transaction
    Perform Delete-Master-Record-Paragraph
End-Evaluate
```

## Resetting switches and flags

Throughout your program, you might need to reset switches or flags to the original values they had in their data descriptions. To do so, either use a SET statement or define a data item to move to the switch or flag.

When you use the SET *condition-name* TO TRUE statement, the switch or flag is set to the original value that it was assigned in its data description. For a level-88 item that has multiple values, SET *condition-name* TO TRUE assigns the first value (A in the example below):

```
88 Record-is-Active Value "A" "O" "S"
```

Using the SET statement and meaningful condition-names makes it easier for readers to follow your code.

[“Example: set switch on” on page 95](#)

[“Example: set switch off” on page 96](#)

## Example: set switch on

The following examples show how you can set a switch on by coding a SET statement that moves the condition name value to the conditional variable.

For example, the SET statement in the following example has the same effect as coding the statement Move "y" to Transaction-EOF-Switch:

```
01 Switches
```

```

05 Transaction-EOF-Switch Pic X Value space.
88 Transaction-EOF       Value "y".

..
Procedure Division.
000-Do-Main-Logic.
    Perform 100-Initialize-Paragraph
    Read Update-Transaction-File
    At End Set Transaction-EOF to True
    End-Read

```

The following example shows how to assign a value to a field in an output record based on the transaction code of an input record:

```

01 Input-Record.
05 Transaction-Type      Pic X(9).
01 Data-Record-Out.
05 Data-Record-Type      Pic X.
88 Record-Is-Active      Value "A".
88 Record-Is-Suspended   Value "S".
88 Record-Is-Deleted      Value "D".
05 Key-Field             Pic X(5).

..
Procedure Division.
    Evaluate Transaction-Type of Input-Record
        When "ACTIVE"
            Set Record-Is-Active to TRUE
        When "SUSPENDED"
            Set Record-Is-Suspended to TRUE
        When "DELETED"
            Set Record-Is-Deleted to TRUE
    End-Evaluate

```

## Example: set switch off

The following example shows how you can set a switch off by coding a MOVE statement that moves the condition name value to the conditional variable.

For example, you can use a data item called SWITCH-OFF to set an on-off switch to off, as in the following code, which resets a switch to indicate that end-of-file has not been reached:

```

01 Switches
05 Transaction-EOF-Switch Pic X Value space.
88 Transaction-EOF       Value "y".
01 SWITCH-OFF             Pic X Value "n".

..
Procedure Division.
    Move SWITCH-OFF to Transaction-EOF-Switch

```

## Repeating program actions

Use a PERFORM statement to repeat the same code (that is, loop) either a specified number of times or based on the outcome of a decision.

You can also use a PERFORM statement to execute a paragraph and then implicitly return control to the next executable statement. In effect, this PERFORM statement is a way of coding a closed subroutine that you can enter from many different parts of the program.

PERFORM statements can be inline or out-of-line.

### related tasks

[“Choosing inline or out-of-line PERFORM” on page 97](#)

[“Coding a loop” on page 97](#)

[“Looping through a table” on page 98](#)

[“Executing multiple paragraphs or sections” on page 99](#)

### related references

PERFORM statement (*Enterprise COBOL for z/OS Language Reference*)

## Choosing inline or out-of-line PERFORM

An inline PERFORM is an imperative statement that is executed in the normal flow of a program; an out-of-line PERFORM entails a branch to a named paragraph and an implicit return from that paragraph.

To determine whether to code an inline or out-of-line PERFORM statement, answer the following questions:

- Is the PERFORM statement used in several places?

Use an out-of-line PERFORM when you want to use the same portion of code in several places in your program.

- Which placement of the statement will be easier to read?

If the code to be performed is short, an inline PERFORM can be easier to read. But if the code extends over several screens, the logical flow of the program might be clearer if you use an out-of-line PERFORM. (Each paragraph in structured programming should perform one logical function, however.)

- What are the efficiency tradeoffs?

An inline PERFORM avoids the overhead of branching that occurs with an out-of-line PERFORM. But even out-of-line PERFORM coding can improve code optimization, so efficiency gains should not be overemphasized.

In the 1974 COBOL standard, the PERFORM statement is out-of-line and thus requires a branch to a separate paragraph and an implicit return. If the performed paragraph is in the subsequent sequential flow of your program, it is also executed in that logic flow. To avoid this additional execution, place the paragraph outside the normal sequential flow (for example, after the GOBACK) or code a branch around it.

The subject of an inline PERFORM is an imperative statement. Therefore, you must code statements (other than imperative statements) within an inline PERFORM with explicit scope terminators.

[“Example: inline PERFORM statement” on page 97](#)

### Example: inline PERFORM statement

This example shows the structure of an inline PERFORM statement that has the required scope terminators and the required END-PERFORM phrase.

```
Perform 100-Initialize-Paragraph
* The following statement is an inline PERFORM:
Perform Until Transaction-EOF
  Read Update-Transaction-File Into WS-Transaction-Record
  At End
    Set Transaction-EOF To True
  Not At End
    Perform 200-Edit-Update-Transaction
    If No-Errors
      Perform 300-Update-Commuter-Record
    Else
      Perform 400-Print-Transaction-Errors
* End-If is a required scope terminator
  End-If
  Perform 410-Re-Initialize-Fields
* End-Read is a required scope terminator
  End-Read
End-Perform
```

## Coding a loop

Use the PERFORM . . . TIMES statement to execute a paragraph a specified number of times.

```
PERFORM 010-PROCESS-ONE-MONTH 12 TIMES
INSPECT . . .
```

In the example above, when control reaches the PERFORM statement, the code for the paragraph 010-PROCESS-ONE-MONTH is executed 12 times before control is transferred to the INSPECT statement.

Use the `PERFORM . . . UNTIL` statement to execute a paragraph until a condition you choose is satisfied. You can use either of the following forms:

```
PERFORM . . . WITH TEST AFTER . . . UNTIL . . .
PERFORM . . . [WITH TEST BEFORE] . . . UNTIL . . .
```


Use the `PERFORM . . . WITH TEST AFTER . . . UNTIL` statement if you want to execute the paragraph at least once, and test before any subsequent execution. This statement is equivalent to a do-until structure:



In the following example, the implicit `WITH TEST BEFORE` phrase provides a do-while structure:

```
PERFORM 010-PROCESS-ONE-MONTH
UNTIL MONTH GREATER THAN 12
INSPECT . . .
```

When control reaches the `PERFORM` statement, the condition `MONTH GREATER THAN 12` is tested. If the condition is satisfied, control is transferred to the `INSPECT` statement. If the condition is not satisfied, `010-PROCESS-ONE-MONTH` is executed, and the condition is tested again. This cycle continues until the condition tests as true. (To make your program easier to read, you might want to code the `WITH TEST BEFORE` clause.)



## Looping through a table

You can use the `PERFORM . . . VARYING` statement to initialize a table. In this form of the `PERFORM` statement, a variable is increased or decreased and tested until a condition is satisfied.

Thus you use the `PERFORM` statement to control looping through a table. You can use either of these forms:

```
PERFORM . . . WITH TEST AFTER . . . VARYING . . . UNTIL . . .
PERFORM . . . [WITH TEST BEFORE] . . . VARYING . . . UNTIL . . .
```

The following section of code shows an example of looping through a table to check for invalid data:

```
PERFORM TEST AFTER VARYING WS-DATA-IX
FROM 1 BY 1 UNTIL WS-DATA-IX = 12
IF WS-DATA (WS-DATA-IX) EQUALS SPACES
SET SERIOUS-ERROR TO TRUE
DISPLAY ELEMENT-NUM-MSG5
END-IF
END-PERFORM
INSPECT . . .
```

When control reaches the `PERFORM` statement above, `WS-DATA-IX` is set equal to 1 and the `PERFORM` statement is executed. Then the condition `WS-DATA-IX = 12` is tested. If the condition is true, control drops through to the `INSPECT` statement. If the condition is false, `WS-DATA-IX` is increased by 1, the

PERFORM statement is executed, and the condition is tested again. This cycle of execution and testing continues until WS-DATA-IX is equal to 12.

The loop above controls input-checking for the 12 fields of item WS-DATA. Empty fields are not allowed in the application, so the section of code loops and issues error messages as appropriate.

## Executing multiple paragraphs or sections

In structured programming, you usually execute a single paragraph. However, you can execute a group of paragraphs, or a single section or group of sections, by coding the PERFORM . . . THRU statement.

When you use the PERFORM . . . THRU statement, code a paragraph-EXIT statement to clearly indicate the end point of a series of paragraphs.

### **related tasks**

[“Processing table items  
using intrinsic functions” on page 85](#)



---

## Chapter 6. Handling strings

COBOL provides language constructs for performing many different operations on string data items.

For example, you can:

- Join or split data items.
- Manipulate null-terminated strings, such as count or move characters.
- Refer to substrings by their ordinal position and, if needed, length.
- Tally and replace data items, such as count the number of times a specific character occurs in a data item.
- Convert data items, such as change to uppercase or lowercase.
- Evaluate data items, such as determine the length of a data item.

### related tasks

[“Joining data items \(STRING\)” on page 101](#)

[“Splitting data items \(UNSTRING\)” on page 103](#)

[“Manipulating null-terminated strings” on page 106](#)

[“Referring to substrings of data items” on page 107](#)

[“Tallying and replacing data items \(INSPECT\)” on page 110](#)

[“Converting data items \(intrinsic functions\)” on page 111](#)

[“Evaluating data items \(intrinsic functions\)” on page 114](#)

[Chapter 7, “Processing data in an international environment,” on page 119](#)

---

## Joining data items (STRING)

Use the STRING statement to join all or parts of several data items or literals into one data item. One STRING statement can take the place of several MOVE statements.

The STRING statement transfers data into a receiving data item in the order that you indicate. In the STRING statement you also specify:

- A delimiter for each set of sending fields that, if encountered, causes those sending fields to stop being transferred (DELIMITED BY phrase)
- (Optional) Action to be taken if the receiving field is filled before all of the sending data has been processed (ON OVERFLOW phrase)
- (Optional) An integer data item that indicates the leftmost character position within the receiving field into which data should be transferred (WITH POINTER phrase)

The receiving data item must not be an edited item, or a display or national floating-point item. If the receiving data item has:

- USAGE DISPLAY, each identifier in the statement except the POINTER identifier must have USAGE DISPLAY, and each literal in the statement must be alphanumeric
- USAGE NATIONAL, each identifier in the statement except the POINTER identifier must have USAGE NATIONAL, and each literal in the statement must be national
- USAGE DISPLAY-1, each identifier in the statement except the POINTER identifier must have USAGE DISPLAY-1, and each literal in the statement must be DBCS

Only that portion of the receiving field into which data is written by the STRING statement is changed.

[“Example: STRING statement” on page 102](#)

## related tasks

[“Handling errors in joining and splitting strings” on page 224](#)

## related references

STRING statement (*Enterprise COBOL for z/OS Language Reference*)

## Example: STRING statement

The following example shows the STRING statement selecting and formatting information from a record into an output line.

The FILE SECTION defines the following record:

```
01 RCD-01.
   05 CUST-INFO.
      10 CUST-NAME      PIC X(15).
      10 CUST-ADDR      PIC X(35).
   05 BILL-INFO.
      10 INV-NO         PIC X(6).
      10 INV-AMT        PIC $$,$$$.$99.
      10 AMT-PAID       PIC $$,$$$.$99.
      10 DATE-PAID      PIC X(8).
      10 BAL-DUE        PIC $$,$$$.$99.
      10 DATE-DUE       PIC X(8).
```

The WORKING-STORAGE SECTION defines the following fields:

```
77 RPT-LINE            PIC X(120).
77 LINE-POS            PIC S9(3).
77 LINE-NO             PIC 9(5) VALUE 1.
77 DEC-POINT           PIC X VALUE ".".
```

The record RCD-01 contains the following information (the symbol *b* indicates a blank space):

```
J.B.bSMITHbbbbbb
444bSPRINGbST.,bCHICAGO,bILL.bbbbbbb
A14275
$4,736.85
$2,400.00
09/22/76
$2,336.85
10/22/76
```

In the PROCEDURE DIVISION, these settings occur before the STRING statement:

- RPT-LINE is set to SPACES.
- LINE-POS, the data item to be used as the POINTER field, is set to 4.

Here is the STRING statement:

```
STRING
  LINE-NO SPACE CUST-INFO INV-NO SPACE DATE-DUE SPACE
  DELIMITED BY SIZE
  BAL-DUE
  DELIMITED BY DEC-POINT
  INTO RPT-LINE
  WITH POINTER LINE-POS.
```

Because the POINTER field LINE-POS has value 4 before the STRING statement is performed, data is moved into the receiving field RPT-LINE beginning at character position 4. Characters in positions 1 through 3 are unchanged.

The sending items that specify DELIMITED BY SIZE are moved in their entirety to the receiving field. Because BAL-DUE is delimited by DEC-POINT, the moving of BAL-DUE to the receiving field stops when a decimal point (the value of DEC-POINT) is encountered.

## STRING results

When the STRING statement is performed, items are moved into RPT - LINE as shown in the table below.

Item	Positions
LINE - NO	4 - 8
Space	9
CUST - INFO	10 - 59
INV - NO	60 - 65
Space	66
DATE - DUE	67 - 74
Space	75
Portion of BAL - DUE that precedes the decimal point	76 - 81

After the STRING statement is performed, the value of LINE - POS is 82, and RPT - LINE has the values shown below.

---

Column						
4	10			60	67	76
↓	↓			↓	↓	↓
00001	J.B. SMITH	444 SPRING ST., CHICAGO, ILL.		A14275	10/22/76	\$2,336

---

## Splitting data items (UNSTRING)

Use the UNSTRING statement to split a sending field into several receiving fields. One UNSTRING statement can take the place of several MOVE statements.

In the UNSTRING statement you can specify:

- Delimiters that, when one of them is encountered in the sending field, cause the current receiving field to stop receiving and the next, if any, to begin receiving (DELIMITED BY phrase)
- A field for the delimiter that, when encountered in the sending field, causes the current receiving field to stop receiving (DELIMITER IN phrase)
- An integer data item that stores the number of characters placed in the current receiving field (COUNT IN phrase)
- An integer data item that indicates the leftmost character position within the sending field at which UNSTRING processing should begin (WITH POINTER phrase)
- An integer data item that stores a tally of the number of receiving fields that are acted on (TALLYING IN phrase)
- Action to be taken if all of the receiving fields are filled before the end of the sending data item is reached (ON OVERFLOW phrase)

The sending data item and the delimiters in the DELIMITED BY phrase must be of category alphabetic, alphanumeric, alphanumeric-edited, DBCS, national, or national-edited.

Receiving data items can be of category alphabetic, alphanumeric, numeric, DBCS, or national. If numeric, a receiving data item must be zoned decimal or national decimal. If a receiving data item has:

- USAGE DISPLAY, the sending item and each delimiter item in the statement must have USAGE DISPLAY, and each literal in the statement must be alphanumeric
- USAGE NATIONAL, the sending item and each delimiter item in the statement must have USAGE NATIONAL, and each literal in the statement must be national

- USAGE DISPLAY-1, the sending item and each delimiter item in the statement must have USAGE DISPLAY-1, and each literal in the statement must be DBCS

[“Example: UNSTRING statement” on page 104](#)

#### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

#### related tasks

[“Handling errors in joining and splitting strings” on page 224](#)

#### related references

UNSTRING statement (*Enterprise COBOL for z/OS Language Reference*)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Example: UNSTRING statement

The following example shows the UNSTRING statement transferring selected information from an input record. Some information is organized for printing and some for further processing.

The FILE SECTION defines the following records:

```
* Record to be acted on by the UNSTRING statement:
01 INV-RCD.
   05 CONTROL-CHARS          PIC XX.
   05 ITEM-INDENT            PIC X(20).
   05 FILLER                  PIC X.
   05 INV-CODE                PIC X(10).
   05 FILLER                  PIC X.
   05 NO-UNITS                PIC 9(6).
   05 FILLER                  PIC X.
   05 PRICE-PER-M            PIC 99999.
   05 FILLER                  PIC X.
   05 RTL-AMT                 PIC 9(6).99.

*
* UNSTRING receiving field for printed output:
01 DISPLAY-REC.
   05 INV-NO                  PIC X(6).
   05 FILLER                  PIC X VALUE SPACE.
   05 ITEM-NAME               PIC X(20).
   05 FILLER                  PIC X VALUE SPACE.
   05 DISPLAY-DOLS            PIC 9(6).

*
* UNSTRING receiving field for further processing:
01 WORK-REC.
   05 M-UNITS                  PIC 9(6).
   05 FIELD-A                  PIC 9(6).
   05 WK-PRICE REDEFINES FIELD-A PIC 9999V99.
   05 INV-CLASS                PIC X(3).

*
* UNSTRING statement control fields:
77 DBY-1                      PIC X.
77 CTR-1                      PIC S9(3).
77 CTR-2                      PIC S9(3).
77 CTR-3                      PIC S9(3).
77 CTR-4                      PIC S9(3).
77 DLTR-1                     PIC X.
77 DLTR-2                     PIC X.
77 CHAR-CT                    PIC S9(3).
77 FLDS-FILLED                PIC S9(3).
```

In the PROCEDURE DIVISION, these settings occur before the UNSTRING statement:

- A period (.) is placed in DBY-1 for use as a delimiter.
- CHAR-CT (the POINTER field) is set to 3.
- The value zero (0) is placed in FLDS-FILLED (the TALLYING field).
- Data is read into record INV-RCD, whose format is as shown below.

Column						
1	10	20	30	40	50	60
↓	↓	↓	↓	↓	↓	↓
ZY	FOUR-PENNY-NAILS		707890/8BA	475120	00122	000379.50

Here is the UNSTRING statement:

```
* Move subfields of INV-RCD to the subfields of DISPLAY-REC
* and WORK-REC:
  UNSTRING INV-RCD
    DELIMITED BY ALL SPACES OR "/" OR DBY-1
    INTO ITEM-NAME      COUNT IN CTR-1
      INV-NO            DELIMITER IN DLTR-1  COUNT IN CTR-2
      INV-CLASS
      M-UNITS           COUNT IN CTR-3
      FIELD-A
      DISPLAY-DOLS DELIMITER IN DLTR-2  COUNT IN CTR-4
    WITH POINTER CHAR-CT
    TALLYING IN FLDS-FILLED
    ON OVERFLOW GO TO UNSTRING-COMPLETE.
```

Because the POINTER field CHAR-CT has value 3 before the UNSTRING statement is performed, the two character positions of the CONTROL-CHARS field in INV-RCD are ignored.

### UNSTRING results

When the UNSTRING statement is performed, the following steps take place:

- Positions 3 through 18 (FOUR-PENNY-NAILS) of INV-RCD are placed in ITEM-NAME, left justified in the area, and the four unused character positions are padded with spaces. The value 16 is placed in CTR-1.
- Because ALL SPACES is coded as a delimiter, the five contiguous space characters in positions 19 through 23 are considered to be one occurrence of the delimiter.
- Positions 24 through 29 (707890) are placed in INV-NO. The delimiter character slash (/) is placed in DLTR-1, and the value 6 is placed in CTR-2.
- Positions 31 through 33 (BBA) are placed in INV-CLASS. The delimiter is SPACE, but because no field has been defined as a receiving area for delimiters, the space in position 34 is bypassed.
- Positions 35 through 40 (475120) are placed in M-UNITS. The value 6 is placed in CTR-3. The delimiter is SPACE, but because no field has been defined as a receiving area for delimiters, the space in position 41 is bypassed.
- Positions 42 through 46 (00122) are placed in FIELD-A and right justified in the area. The high-order digit position is filled with a zero (0). The delimiter is SPACE, but because no field was defined as a receiving area for delimiters, the space in position 47 is bypassed.
- Positions 48 through 53 (000379) are placed in DISPLAY-DOLS. The period (.) delimiter in DBY-1 is placed in DLTR-2, and the value 6 is placed in CTR-4.
- Because all receiving fields have been acted on and two characters in INV-RCD have not been examined, the ON OVERFLOW statement is executed. Execution of the UNSTRING statement is completed.

After the UNSTRING statement is performed, the fields contain the values shown below.

Field	Value
DISPLAY-REC	707890 FOUR-PENNY-NAILS 000379
WORK-REC	4751200000122BBA
CHAR-CT (the POINTER field)	55
FLDS-FILLED (the TALLYING field)	6

## Manipulating null-terminated strings

You can construct and manipulate null-terminated strings (for example, strings that are passed to or from a C program) by various mechanisms.

For example, you can:

- Use null-terminated literal constants (Z" . . . ").
- Use an INSPECT statement to count the number of characters in a null-terminated string:

```
MOVE 0 TO char-count
INSPECT source-field TALLYING char-count
                     FOR CHARACTERS
                     BEFORE X"00"
```

- Use an UNSTRING statement to move characters in a null-terminated string to a target field, and get the character count:

```
WORKING-STORAGE SECTION.
01 source-field          PIC X(1001).
01 char-count            COMP-5 PIC 9(4).
01 target-area.
   02 individual-char OCCURS 1 TO 1000 TIMES DEPENDING ON char-count
                     PIC X.

PROCEDURE DIVISION.
  UNSTRING source-field DELIMITED BY X"00"
                      INTO target-area
                      COUNT IN char-count

  ON OVERFLOW
    DISPLAY "source not null terminated or target too short"
  END-UNSTRING
```

- Use a SEARCH statement to locate trailing null or space characters. Define the string being examined as a table of single characters.
- Check each character in a field in a loop (PERFORM). You can examine each character in a field by using a reference modifier such as source-field (I:1).

[“Example: null-terminated strings” on page 106](#)

### related tasks

[“Handling null-terminated strings” on page 471](#)

### related references

Alphanumeric literals (*Enterprise COBOL for z/OS Language Reference*)

## Example: null-terminated strings

The following example shows several ways in which you can process null-terminated strings.

```
01 L pic X(20) value z'ab'.
01 M pic X(20) value z'cd'.
01 N pic X(20).
01 N-Length pic 99 value zero.
01 Y pic X(13) value 'Hello, World!'.

* Display null-terminated string:
  Inspect N tallying N-length
           for characters before initial x'00'
  Display 'N: ' N(1:N-Length) ' Length: ' N-Length

* Move null-terminated string to alphanumeric, strip null:
  Unstring N delimited by X'00' into X

* Create null-terminated string:
  String Y      delimited by size
           X'00' delimited by size
```

```

        into N.
    * Concatenate two null-terminated strings to produce another:
      String L      delimited by x'00'
        M          delimited by x'00'
      X'00' delimited by size
        into N.

```

## Referring to substrings of data items

Refer to a substring of a data item that has USAGE DISPLAY, DISPLAY-1, or NATIONAL by using a reference modifier. You can also refer to a substring of an alphanumeric or national character string that is returned by an intrinsic function by using a reference modifier.

**Note:** To get a substring of a character string argument that is encoded in UTF-8, use the USUBSTR function as described in “Using intrinsic functions to process UTF-8 encoded data” on page 135.

The following example shows how to use a reference modifier to refer to a twenty-character substring of a data item called Customer-Record:

```
Move Customer-Record(1:20) to Orig-Customer-Name
```

You code a reference modifier in parentheses immediately after the data item. As the example shows, a reference modifier can contain two values that are separated by a colon, in this order:

1. Ordinal position (from the left) of the character that you want the substring to start with
2. (Optional) Length of the required substring in *character positions*

The reference-modifier position and length for an item that has USAGE DISPLAY are expressed in terms of single-byte characters. The reference-modifier position and length for items that have USAGE DISPLAY-1 or NATIONAL are expressed in terms of DBCS character positions and national character positions, respectively.

If you omit the length in a reference modifier (coding only the ordinal position of the first character, followed by a colon), the substring extends to the end of the item. Omit the length where possible as a simpler and less error-prone coding technique.

You can refer to substrings of USAGE DISPLAY data items, including alphanumeric groups, alphanumeric-edited data items, numeric-edited data items, display floating-point data items, and zoned decimal data items, by using reference modifiers. When you reference-modify any of these data items, the result is of category alphanumeric. When you reference-modify an alphabetic data item, the result is of category alphabetic.

You can refer to substrings of USAGE NATIONAL data items, including national groups, national-edited data items, numeric-edited data items, national floating-point data items, and national decimal data items, by using reference modifiers. When you reference-modify any of these data items, the result is of category national. For example, suppose that you define a national decimal data item as follows:

```
01 NATL-DEC-ITEM Usage National Pic 999 Value 123.
```

You can use NATL-DEC-ITEM in an arithmetic expression because NATL-DEC-ITEM is of category numeric. But you cannot use NATL-DEC-ITEM(2:1) (the national character 2, which in hexadecimal notation is NX"0032") in an arithmetic expression, because it is of category national.

You can refer to substrings of table entries, including variable-length entries, by using reference modifiers. To refer to a substring of a table entry, code the subscript expression before the reference modifier. For example, assume that PRODUCT-TABLE is a properly coded table of character strings. To move D to the fourth character in the second string in the table, you can code this statement:

```
MOVE 'D' to PRODUCT-TABLE (2), (4:1)
```

You can code either or both of the two values in a reference modifier as a variable or as an arithmetic expression.

[“Example: arithmetic expressions as reference modifiers” on page 109](#)

Because numeric function identifiers can be used anywhere that arithmetic expressions can be used, you can code a numeric function identifier in a reference modifier as the leftmost character position or as the length, or both.

[“Example: intrinsic functions as reference modifiers” on page 109](#)

Each number in the reference modifier must have a value of at least 1. The sum of the two numbers must not exceed the total length of the data item by more than 1 character position so that you do not reference beyond the end of the substring.

If the leftmost character position or the length value is a fixed-point noninteger, truncation occurs to create an integer. If either is a floating-point noninteger, rounding occurs to create an integer.

The SSRANGE compiler option detects out-of-range reference modifiers, and flags violations with a runtime message.

#### **related concepts**

[“Reference modifiers” on page 108](#)

[“Unicode and the encoding of language characters” on page 123](#)

#### **related tasks**

[“Referring to an item in a table” on page 68](#)

#### **related references**

[“SSRANGE” on page 338](#)

Reference modification (*Enterprise COBOL for z/OS Language Reference*)

Function definitions (*Enterprise COBOL for z/OS Language Reference*)

## **Reference modifiers**

Reference modifiers let you easily refer to a substring of a data item.

For example, assume that you want to retrieve the current time from the system and display its value in an expanded format. You can retrieve the current time with the ACCEPT statement, which returns the hours, minutes, seconds, and hundredths of seconds in this format:

```
HHMMSSss
```

However, you might prefer to view the current time in this format:

```
HH:MM:SS
```

Without reference modifiers, you would have to define data items for both formats. You would also have to write code to convert from one format to the other.

With reference modifiers, you do not need to provide names for the subfields that describe the TIME elements. The only data definition you need is for the time as returned by the system. For example:

```
01  REFMOD-TIME-ITEM    PIC X(8).
```

The following code retrieves and expands the time value:

```
ACCEPT REFMOD-TIME-ITEM FROM TIME.
DISPLAY "CURRENT TIME IS: "
* Retrieve the portion of the time value that corresponds to
```

```

*   the number of hours:
      REFMOD-TIME-ITEM (1:2)
      ":"
* Retrieve the portion of the time value that corresponds to
*   the number of minutes:
      REFMOD-TIME-ITEM (3:2)
      ":"
* Retrieve the portion of the time value that corresponds to
*   the number of seconds:
      REFMOD-TIME-ITEM (5:2)

```

[“Example: arithmetic expressions as reference modifiers” on page 109](#)

[“Example: intrinsic](#)

[functions as reference modifiers” on page 109](#)

### related tasks

[“Assigning input from a screen or file \(ACCEPT\)” on page 33](#)

[“Referring to substrings of data items” on page 107](#)

[“Using national data \(Unicode\) in COBOL” on page 124](#)

### related references

Reference modification (*Enterprise COBOL for z/OS Language Reference*)

## Example: arithmetic expressions as reference modifiers

Suppose that a field contains some right-justified characters, and you want to move those characters to another field where they will be left justified. You can do so by using reference modifiers and an INSPECT statement.

Suppose a program has the following data:

```

01 LEFTY      PIC X(30).
01 RIGHTY     PIC X(30) JUSTIFIED RIGHT.
01 I          PIC 9(9)  USAGE BINARY.

```

The program counts the number of leading spaces and, using arithmetic expressions in a reference modifier, moves the right-justified characters into another field, justified to the left:

```

MOVE SPACES TO LEFTY
MOVE ZERO TO I
INSPECT RIGHTY
  TALLYING I FOR LEADING SPACE.
IF I IS LESS THAN LENGTH OF RIGHTY THEN
  MOVE RIGHTY ( I + 1 : LENGTH OF RIGHTY - I ) TO LEFTY
END-IF

```

The MOVE statement transfers characters from RIGHTY, beginning at the position computed as I + 1 for a length that is computed as LENGTH OF RIGHTY - I, into the field LEFTY.

## Example: intrinsic functions as reference modifiers

You can use intrinsic functions in reference modifiers if you do not know the leftmost position or length of a substring at compile time.

For example, the following code fragment causes a substring of Customer-Record to be moved into the data item WS-name. The substring is determined at run time.

```

05 WS-name      Pic x(20).
05 Left-posn    Pic 99.

```

```
05 I Pic 99.  
Move Customer-Record(Function Min(Left-posn I):Function Length(WS-name)) to WS-name
```

If you want to use a noninteger function in a position that requires an integer function, you can use the `INTEGER` or `INTEGER-PART` function to convert the result to an integer. For example:

```
Move Customer-Record(Function Integer(Function Sqrt(I)): ) to WS-name
```

#### related references

`INTEGER` (*Enterprise COBOL for z/OS Language Reference*)

`INTEGER-PART` (*Enterprise COBOL for z/OS Language Reference*)

## Tallying and replacing data items (INSPECT)

Use the `INSPECT` statement to inspect characters or groups of characters in a data item and to optionally replace them.

Use the `INSPECT` statement to do the following tasks:

- Count the number of times a specific character occurs in a data item (`TALLYING` phrase).
- Fill a data item or selected portions of a data item with specified characters such as spaces, asterisks, or zeros (`REPLACING` phrase).
- Convert all occurrences of a specific character or string of characters in a data item to replacement characters that you specify (`CONVERTING` phrase).

You can specify one of the following data items as the item to be inspected:

- An elementary item described explicitly or implicitly as `USAGE DISPLAY`, `USAGE DISPLAY-1`, or `USAGE NATIONAL`
- An alphanumeric group item or national group item

If the inspected item has:

- `USAGE DISPLAY`, each identifier in the statement (except the `TALLYING` count field) must have `USAGE DISPLAY`, and each literal in the statement must be alphanumeric
- `USAGE NATIONAL`, each identifier in the statement (except the `TALLYING` count field) must have `USAGE NATIONAL`, and each literal in the statement must be national
- `USAGE DISPLAY-1`, each identifier in the statement (except the `TALLYING` count field) must have `USAGE DISPLAY-1`, and each literal in the statement must be a DBCS literal

[“Examples: INSPECT statement” on page 110](#)

#### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

#### related references

`INSPECT` statement (*Enterprise COBOL for z/OS Language Reference*)

## Examples: INSPECT statement

The following examples show some uses of the `INSPECT` statement to examine and replace characters.

In the following example, the `INSPECT` statement examines and replaces characters in data item `DATA-2`. The number of times a leading zero (0) occurs in the data item is accumulated in `COUNTR`. The first instance of the character A that follows the first instance of the character C is replaced by the character 2.

```
77 COUNTR PIC 9 VALUE ZERO.  
01 DATA-2 PIC X(11).
```

```

. . .
INSPECT DATA-2
  TALLYING COUNTR FOR LEADING "0"
  REPLACING FIRST "A" BY "2" AFTER INITIAL "C"

```

DATA-2 before	COUNTR after	DATA-2 after
00ACADEMY00	2	00AC2DEMY00
0000ALABAMA	4	0000ALABAMA
CHATHAM0000	0	CH2THAM0000

In the following example, the INSPECT statement examines and replaces characters in data item DATA-3. Each character that precedes the first instance of a quotation mark (") is replaced by the character 0.

```

77 COUNTR          PIC 9   VALUE ZERO.
01 DATA-3         PIC X(8).
. . .
INSPECT DATA-3
  REPLACING CHARACTERS BY ZEROS BEFORE INITIAL QUOTE

```

DATA-3 before	COUNTR after	DATA-3 after
456"ABEL	0	000"ABEL
ANDES"12	0	00000"12
"Twas BR	0	"Twas BR

The following example shows the use of INSPECT CONVERTING with AFTER and BEFORE phrases to examine and replace characters in data item DATA-4. All characters that follow the first instance of the character / but that precede the first instance of the character ? (if any) are translated from lowercase to uppercase.

```

01 DATA-4         PIC X(11).
. . .
INSPECT DATA-4
  CONVERTING
    "abcdefghijklmnopqrstuvwxyz" TO
    "ABCDEFGHIJKLMNOPQRSTUVWXYZ"
  AFTER INITIAL "/"
  BEFORE INITIAL "?"

```

DATA-4 before	DATA-4 after
a/five/?six	a/FIVE/?six
r/Rexx/RRRr	r/REXX/RRRR
zfour?inspe	zfour?inspe

## Converting data items (intrinsic functions)

You can use intrinsic functions to convert character-string data items to several other formats, for example, to uppercase or lowercase, to reverse order, to numbers, or to one code page from another.

You can use the NATIONAL-OF and DISPLAY-OF intrinsic functions to convert to and from national (Unicode) strings.

You can also use the INSPECT statement to convert characters.

[“Examples: INSPECT statement” on page 110](#)

#### related tasks

[“Changing case \(UPPER-CASE, LOWER-CASE\)” on page 112](#)

[“Transforming to reverse order \(REVERSE\)” on page 112](#)

[“Converting to numbers \(NUMVAL, NUMVAL-C\)” on page 113](#)

[“Converting from one code page to another” on page 114](#)

## Changing case (UPPER-CASE, LOWER-CASE)

You can use the UPPER-CASE and LOWER-CASE intrinsic functions to easily change the case of alphanumeric, alphabetic, or national strings.

```
01 Item-1 Pic x(30) Value "Hello World!".
01 Item-2 Pic x(30).
. . .
  Display Item-1
  Display Function Upper-case(Item-1)
  Display Function Lower-case(Item-1)
  Move Function Upper-case(Item-1) to Item-2
  Display Item-2
```

The code above displays the following messages on the system logical output device:

```
Hello World!
HELLO WORLD!
hello world!
HELLO WORLD!
```

The DISPLAY statements do not change the actual contents of Item-1, but affect only how the letters are displayed. However, the MOVE statement causes uppercase letters to replace the contents of Item-2.

**Note:** The UPPER-CASE and LOWER-CASE intrinsic functions do not support alphanumeric arguments that contain UTF-8 encoded data.

#### related tasks

[“Assigning input from a screen or file \(ACCEPT\)” on page 33](#)

[“Displaying values on a screen or in a file \(DISPLAY\)” on page 33](#)

## Transforming to reverse order (REVERSE)

You can reverse the order of the characters in a string by using the REVERSE intrinsic function.

```
Move Function Reverse(Orig-cust-name) To Orig-cust-name
```

For example, the statement above reverses the order of the characters in Orig-cust-name. If the starting value is JOHNSONbbb, the value after the statement is performed is bbbNOSNHOJ, where *b* represents a blank space.

#### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

## Converting to numbers (NUMVAL, NUMVAL-C)

The NUMVAL and NUMVAL - C functions convert character strings (alphanumeric or national literals, or class alphanumeric or class national data items) to numbers. Use these functions to convert free-format character-representation numbers to numeric form so that you can process them numerically.

```
01 R      Pic x(20) Value "- 1234.5678".
01 S      Pic x(20) Value " $12,345.67CR".
01 Total  Usage is Comp-1.
. . .
Compute Total = Function Numval(R) + Function Numval-C(S)
```

Use NUMVAL - C when the argument includes a currency symbol or comma or both, as shown in the example above. You can also place an algebraic sign before or after the character string, and the sign will be processed. The arguments must not exceed 18 digits when you compile with the default option ARITH (COMPAT) (*compatibility mode*) nor 31 digits when you compile with ARITH (EXTEND) (*extended mode*), not including the editing symbols.

NUMVAL and NUMVAL - C return long (64-bit) floating-point values in compatibility mode, and return extended-precision (128-bit) floating-point values in extended mode. A reference to either of these functions represents a reference to a numeric data item.

At most 15 decimal digits can be converted accurately to long-precision floating point (as described in the related reference below about conversions and precision). Internally NUMVAL uses long-precision floating calculations to convert the given number to the output, so if the argument to NUMVAL or NUMVAL - C has more than 15 digits, it is recommended that you specify the ARITH (EXTEND) compiler option so that an extended-precision function result that can accurately represent the value of the argument is returned. Otherwise, the result may lose precision in an unexpected manner.

When you use NUMVAL or NUMVAL - C, you do not need to statically define numeric data in a fixed format nor input data in a precise manner. For example, suppose you define numbers to be entered as follows:

```
01 X      Pic S999V99 leading sign is separate.
. . .
Accept X from Console
```

The user of the application must enter the numbers exactly as defined by the PICTURE clause. For example:

```
+001.23
-300.00
```

However, using the NUMVAL function, you could code:

```
01 A      Pic x(10).
01 B      Pic S999V99.
. . .
Accept A from Console
Compute B = Function Numval(A)
```

The input could then be:

```
1.23
-300
```

### related concepts

[“Formats for numeric data” on page 45](#)

[“Data format conversions” on page 49](#)

[“Unicode and the encoding of language characters” on page 123](#)

**related tasks**

[“Converting to or from national \(Unicode\) representation” on page 131](#)

**related references**

[“Conversions and precision” on page 50](#)

[“ARITH” on page 291](#)

## Converting from one code page to another

You can nest the DISPLAY-OF and NATIONAL-OF intrinsic functions to easily convert from any code page to any other code page.

For example, the following code converts an EBCDIC string to an ASCII string:

```
77 EBCDIC-CCSID PIC 9(4) BINARY VALUE 1140.  
77 ASCII-CCSID PIC 9(4) BINARY VALUE 819.  
77 Input-EBCDIC PIC X(80).  
77 ASCII-Output PIC X(80).  
  
* Convert EBCDIC to ASCII  
  Move Function Display-of  
    (Function National-of (Input-EBCDIC EBCDIC-CCSID),  
      ASCII-CCSID)  
  to ASCII-output
```

**related concepts**

[“Unicode and the encoding of language characters” on page 123](#)

**related tasks**

[“Converting to or from national \(Unicode\) representation” on page 131](#)

## Evaluating data items (intrinsic functions)

You can use intrinsic functions to determine the ordinal position of a character in the collating sequence, to find the largest or smallest item in a series, to find the length of data item, or to determine when a program was compiled.

Use these intrinsic functions:

- CHAR and ORD to evaluate integers and single alphabetic or alphanumeric characters with respect to the collating sequence used in a program
- MAX, MIN, ORD-MAX, and ORD-MIN to find the largest and smallest items in a series of data items, including USAGE NATIONAL data items
- LENGTH to find the length of data items, including USAGE NATIONAL data items
- WHEN-COMPILED to find the date and time when a program was compiled

**related concepts**

[“Unicode and the encoding of language characters” on page 123](#)

**related tasks**

[“Evaluating single characters for collating sequence” on page 115](#)

[“Finding the largest or smallest data item” on page 115](#)

[“Finding the length of data items” on page 117](#)

[“Finding the date of compilation” on page 118](#)

## Evaluating single characters for collating sequence

To find out the ordinal position of a given alphabetic or alphanumeric character in the collating sequence, use the ORD function with the character as the argument. ORD returns an integer that represents that ordinal position.

You can use a one-character substring of a data item as the argument to ORD:

```
IF Function Ord(Customer-record(1:1)) IS > 194 THEN . . .
```

If you know the ordinal position in the collating sequence of a character, and want to find the character that it corresponds to, use the CHAR function with the integer ordinal position as the argument. CHAR returns the required character. For example:

```
INITIALIZE Customer-Name REPLACING ALPHABETIC BY Function Char(65)
```

### related references

CHAR (*Enterprise COBOL for z/OS Language Reference*)

ORD (*Enterprise COBOL for z/OS Language Reference*)

## Finding the largest or smallest data item

To determine which of two or more alphanumeric, alphabetic, or national data items has the largest value, use the MAX or ORD-MAX intrinsic function. To determine which item has the smallest value, use MIN or ORD-MIN. These functions evaluate according to the collating sequence.

To compare numeric items, including those that have USAGE NATIONAL, you can use MAX, ORD-MAX, MIN, or ORD-MIN. With these intrinsic functions, the algebraic values of the arguments are compared.

The MAX and MIN functions return the content of one of the arguments that you supply. For example, suppose that your program has the following data definitions:

```
05 Arg1 Pic x(10) Value "THOMASSON ".
05 Arg2 Pic x(10) Value "THOMAS ".
05 Arg3 Pic x(10) Value "VALLEJO ".
```

The following statement assigns VALLEJObbbb to the first 10 character positions of Customer-record, where *b* represents a blank space:

```
Move Function Max(Arg1 Arg2 Arg3) To Customer-record(1:10)
```

If you used MIN instead, then THOMASbbbb would be assigned.

The functions ORD-MAX and ORD-MIN return an integer that represents the ordinal position (counting from the left) of the argument that has the largest or smallest value in the list of arguments that you supply. If you used the ORD-MAX function in the previous example, the compiler would issue an error message because the reference to a numeric function is not in a valid place. Using the same arguments as in the previous example, ORD-MAX can be used as follows:

```
Compute x = Function Ord-max(Arg1 Arg2 Arg3)
```

The statement above assigns the integer 3 to *x* if the same arguments are used as in the previous example. If you used ORD-MIN instead, the integer 2 would be returned. The examples above might be more realistic if Arg1, Arg2, and Arg3 were successive elements of an array (table).

If you specify a national item for any argument, you must specify all arguments as class national.

### related tasks

[“Performing arithmetic” on page 53](#)

[“Processing table items  
using intrinsic functions” on page 85](#)  
[“Returning variable results  
with alphanumeric or national functions” on page 116](#)

#### related references

MAX (*Enterprise COBOL for z/OS Language Reference*)  
MIN (*Enterprise COBOL for z/OS Language Reference*)  
ORD-MAX (*Enterprise COBOL for z/OS Language Reference*)  
ORD-MIN (*Enterprise COBOL for z/OS Language Reference*)

## Returning variable results with alphanumeric or national functions

The results of alphanumeric or national functions could be of varying lengths and values depending on the function arguments.

In the following example, the amount of data moved to R3 and the results of the COMPUTE statement depend on the values and sizes of R1 and R2:

```
01 R1    Pic x(10) value "e".
01 R2    Pic x(05) value "f".
01 R3    Pic x(20) value spaces.
01 L     Pic 99.
. . .
. . . Move Function Max(R1 R2) to R3
. . . Compute L = Function Length(Function Max(R1 R2))
```

This code has the following results:

- R2 is evaluated to be larger than R1.
- The string 'fbbbb' is moved to R3, where *b* represents a blank space. (The unfilled character positions in R3 are padded with spaces.)
- L evaluates to the value 5.

If R1 contained 'g' instead of 'e', the code would have the following results:

- R1 would evaluate as larger than R2.
- The string 'gbbbbbbbbb' would be moved to R3. (The unfilled character positions in R3 would be padded with spaces.)
- The value 10 would be assigned to L.

If a program uses national data for function arguments, the lengths and values of the function results could likewise vary. For example, the following code is identical to the fragment above, but uses national data instead of alphanumeric data.

```
01 R1    Pic n(10) national value "e".
01 R2    Pic n(05) national value "f".
01 R3    Pic n(20) national value spaces.
01 L     Pic 99    national.
. . .
. . . Move Function Max(R1 R2) to R3
. . . Compute L = Function Length(Function Max(R1 R2))
```

This code has the following results, which are similar to the first set of results except that these are for national characters:

- R2 is evaluated to be larger than R1.
- The string NX"0066 0020 0020 0020 0020" (the equivalent in national characters of 'fbbbb', where *b* represents a blank space), shown here in hexadecimal notation with added spaces for readability, is moved to R3. The unfilled character positions in R3 are padded with national spaces.
- L evaluates to the value 5, the length in national character positions of R2.

You might be dealing with variable-length output from alphanumeric or national functions. Plan your program accordingly. For example, you might need to think about using variable-length files when the records that you are writing could be of different lengths:

```
File Section.
FD  Output-File Recording Mode V.
01  Short-Customer-Record  Pic X(50).
01  Long-Customer-Record   Pic X(70).
Working-Storage Section.
01  R1      Pic x(50).
01  R2      Pic x(70).
. . .
If R1 > R2
  Write Short-Customer-Record from R1
Else
  Write Long-Customer-Record from R2
End-if
```

#### related tasks

[“Finding the largest or](#)

[smallest data item” on page 115](#)

[“Performing arithmetic” on page 53](#)

#### related references

MAX (*Enterprise COBOL for z/OS Language Reference*)

## Finding the length of data items

You can use the LENGTH function in many contexts (including tables and numeric data) to determine the length of an item. For example, you can use the LENGTH function to determine the length of an alphanumeric or national literal, or a data item of any type except DBCS.

The LENGTH function returns the length of a national item (a literal, or any item that has USAGE NATIONAL, including national group items) as an integer equal to the length of the argument in national character positions. It returns the length of any other data item as an integer equal to the length of the argument in alphanumeric character positions.

The following COBOL statement demonstrates moving a data item into the field in a record that holds customer names:

```
Move Customer-name To Customer-record(1:Function Length(Customer-name))
```

You can also use the LENGTH OF special register, which returns the length in bytes even for national data. Coding either Function Length(Customer-name) or LENGTH OF Customer-name returns the same result for alphanumeric items: the length of Customer-name in bytes.

You can use the LENGTH function only where arithmetic expressions are allowed. However, you can use the LENGTH OF special register in a greater variety of contexts. For example, you can use the LENGTH OF special register as an argument to an intrinsic function that accepts integer arguments. (You cannot use an intrinsic function as an operand to the LENGTH OF special register.) You can also use the LENGTH OF special register as a parameter in a CALL statement.

#### related tasks

[“Performing arithmetic” on page 53](#)

[“Creating variable-length tables \(DEPENDING ON\)” on page 76](#)

[“Processing table items using intrinsic functions” on page 85](#)

#### related references

LENGTH (*Enterprise COBOL for z/OS Language Reference*)

LENGTH OF (*Enterprise COBOL for z/OS Language Reference*)

## Finding the date of compilation

You can use the `WHEN-COMPILED` intrinsic function to determine when a program was compiled. The 21-character result indicates the four-digit year, month, day, and time (in hours, minutes, seconds, and hundredths of seconds) of compilation, and the difference in hours and minutes from Greenwich mean time.

The first 16 positions are in the following format:

```
YYYYMMDDhhmmsshh
```

You can instead use the `WHEN-COMPILED` special register to determine the date and time of compilation in the following format:

```
MM/DD/YYhh.mm.ss
```

The `WHEN-COMPILED` special register supports only a two-digit year, and does not carry fractions of a second. You can use this special register only as the sending field in a `MOVE` statement.

### related references

`WHEN-COMPILED` (*Enterprise COBOL for z/OS Language Reference*)

---

## Chapter 7. Processing data in an international environment

Enterprise COBOL supports Unicode UTF-16 as national character data at run time. UTF-16 provides a consistent and efficient way to encode plain text. Using UTF-16, you can develop software that will work with various national languages.

Use these COBOL facilities to code and compile programs that process national data:

- Data types and literals:
  - Character data types, defined with the `USAGE NATIONAL` clause and a `PICTURE` clause that defines data of category national, national-edited, or numeric-edited
  - Numeric data types, defined with the `USAGE NATIONAL` clause and a `PICTURE` clause that defines a numeric data item (a *national decimal item*) or an external floating-point data item (a *national floating-point item*)
  - National literals, specified with literal prefix `N` or `NX`
  - Figurative constant `ALL national-literal`
  - Figurative constants `QUOTE`, `SPACE`, `HIGH-VALUE`, `LOW-VALUE`, or `ZERO`, which have national character (UTF-16) values when used in national-character contexts
- The COBOL statements shown in the related reference below about COBOL statements and national data
- Intrinsic functions:
  - `NATIONAL-OF` to convert an alphanumeric or double-byte character set (DBCS) character string to `USAGE NATIONAL` (UTF-16)
  - `DISPLAY-OF` to convert a national character string to `USAGE DISPLAY` in a selected code page (EBCDIC, ASCII, EUC, or UTF-8)
  - The other intrinsic functions shown in the related reference below about intrinsic functions and national data
- The `GROUP-USAGE NATIONAL` clause to define groups that contain only `USAGE NATIONAL` data items and that behave like elementary category national items in most operations
- Compiler options:
  - `CODEPAGE` to specify the code page to use for alphanumeric and DBCS data in your program
  - `NSYMBOL` to control whether national or DBCS processing is used for the `N` symbol in literals and `PICTURE` clauses

You can also take advantage of implicit conversions of alphanumeric or DBCS data items to national representation. The compiler performs such conversions (in most cases) when you move these items to national data items, or compare these items with national data items.

### related concepts

[“Unicode and the encoding of language characters” on page 123](#)  
[“National groups” on page 127](#)

### related tasks

[“Using national data \(Unicode\) in COBOL” on page 124](#)  
[“Converting to or from national \(Unicode\) representation” on page 131](#)  
[“Processing UTF-8 data” on page 134](#)  
[“Processing Chinese GB 18030 data” on page 139](#)

[“Comparing national \(UTF-16\) data” on page 140](#)

[“Coding for use of DBCS support” on page 142](#)

[Appendix B, “Converting double-byte character set \(DBCS\) data,” on page 665](#)

#### related references

[“COBOL statements and national data” on page 120](#)

[“Intrinsic functions and national data” on page 123](#)

[“CODEPAGE” on page 295](#)

[“NSYMBOL” on page 319](#)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

Data categories and PICTURE rules

(*Enterprise COBOL for z/OS Language Reference*)

MOVE statement (*Enterprise COBOL for z/OS Language Reference*)

General relation conditions (*Enterprise COBOL for z/OS Language Reference*)

## COBOL statements and national data

You can use national data with the PROCEDURE DIVISION and compiler-directing statements shown in the table below.

Table 15. COBOL statements and national data			
COBOL statement	Can be national	Comment	For more information
ACCEPT	<i>identifier-1, identifier-2</i>	<i>identifier-1</i> is converted from the native code page specified in the CODEPAGE compiler option only if input is from CONSOLE.	<a href="#">“Assigning input from a screen or file (ACCEPT)” on page 33</a>
ADD	All identifiers can be numeric items that have USAGE NATIONAL. <i>identifier-3</i> (GIVING) can be numeric-edited with USAGE NATIONAL.		<a href="#">“Using COMPUTE and other arithmetic statements” on page 53</a>
CALL	<i>identifier-2, identifier-3, identifier-4, identifier-5; literal-2, literal-3</i>		<a href="#">“Passing data” on page 465</a>
COMPUTE	<i>identifier-1</i> can be numeric or numeric-edited with USAGE NATIONAL. <i>arithmetic-expression</i> can contain numeric items that have USAGE NATIONAL.		<a href="#">“Using COMPUTE and other arithmetic statements” on page 53</a>
COPY . . . REPLACING	<i>operand-1, operand-2</i> of the REPLACING phrase		<a href="#">Chapter 18, “Compiler-directing statements,” on page 357</a>
DISPLAY	<i>identifier-1</i>	<i>identifier-1</i> is converted to EBCDIC only if the CONSOLE mnemonic-name is specified directly or indirectly.	<a href="#">“Displaying values on a screen or in a file (DISPLAY)” on page 33</a>

Table 15. **COBOL statements and national data** (continued)

COBOL statement	Can be national	Comment	For more information
DIVIDE	All identifiers can be numeric items that have USAGE NATIONAL. <i>identifier-3</i> (GIVING) and <i>identifier-4</i> (REMAINDER) can be numeric-edited with USAGE NATIONAL.		<a href="#">“Using COMPUTE and other arithmetic statements” on page 53</a>
INITIALIZE	<i>identifier-1</i> ; <i>identifier-2</i> or <i>literal-1</i> of the REPLACING phrase	If you specify REPLACING NATIONAL or REPLACING NATIONAL - EDITED, <i>identifier-2</i> or <i>literal-1</i> must be valid as a sending operand in a move to <i>identifier-1</i> .	<a href="#">“Examples: initializing data items” on page 26</a>
INSPECT	All identifiers and literals. ( <i>identifier-2</i> , the TALLYING integer data item, can have USAGE NATIONAL.)	If any of these (other than <i>identifier-2</i> , the TALLYING identifier) have USAGE NATIONAL, all must be national.	<a href="#">“Tallying and replacing data items (INSPECT)” on page 110</a>
INVOKE	Method-name as <i>identifier-2</i> or <i>literal-1</i> ; <i>identifier-3</i> or <i>literal-2</i> in the BY VALUE phrase		<a href="#">“Invoking methods (INVOKE)” on page 580</a>
MERGE	Merge keys	The COLLATING SEQUENCE phrase does not apply.	<a href="#">“Setting sort or merge criteria” on page 213</a>
MOVE	Both the sender and receiver, or only the receiver	Implicit conversions are performed for valid MOVE operands.	<a href="#">“Assigning values to elementary data items (MOVE)” on page 30</a> <a href="#">“Assigning values to group data items (MOVE)” on page 31</a>
MULTIPLY	All identifiers can be numeric items that have USAGE NATIONAL. <i>identifier-3</i> (GIVING) can be numeric-edited with USAGE NATIONAL.		<a href="#">“Using COMPUTE and other arithmetic statements” on page 53</a>
SEARCH ALL (binary search)	Both the key data item and its object of comparison	The key data item and its object of comparison must be compatible according to the rules of comparison. If the object of comparison is of class national, the key must be also.	<a href="#">“Doing a binary search (SEARCH ALL)” on page 84</a>
SORT	Sort keys	The COLLATING SEQUENCE phrase does not apply.	<a href="#">“Setting sort or merge criteria” on page 213</a>

Table 15. **COBOL statements and national data** (continued)

COBOL statement	Can be national	Comment	For more information
STRING	All identifiers and literals. ( <i>identifier-4</i> , the POINTER integer data item, can have USAGE NATIONAL.)	If <i>identifier-3</i> , the receiving data item, is national, all identifiers and literals (other than <i>identifier-4</i> , the POINTER identifier) must be national.	<a href="#">“Joining data items (STRING)” on page 101</a>
SUBTRACT	All identifiers can be numeric items that have USAGE NATIONAL. <i>identifier-3</i> (GIVING) can be numeric-edited with USAGE NATIONAL.		<a href="#">“Using COMPUTE and other arithmetic statements” on page 53</a>
UNSTRING	All identifiers and literals. ( <i>identifier-6</i> and <i>identifier-7</i> , the COUNT and TALLYING integer data items, respectively, can have USAGE NATIONAL.)	If <i>identifier-4</i> , a receiving data item, has USAGE NATIONAL, the sending data item and each delimiter must have USAGE NATIONAL, and each literal must be national.	<a href="#">“Splitting data items (UNSTRING)” on page 103</a>
XML GENERATE	<i>identifier-1</i> (the generated XML document); <i>identifier-2</i> (the source field or fields); <i>identifier-4</i> or <i>literal-4</i> (the namespace identifier); <i>identifier-5</i> or <i>literal-5</i> (the namespace prefix)		<a href="#">Chapter 32, “Producing XML output,” on page 545</a>
XML PARSE	<i>identifier-1</i> (the XML document)	The XML -NTEXT special register contains national character document fragments during parsing. XML -NNAMESPACE and XML -NNAMESPACE -PREFIX special registers contain the associated namespace identifier and namespace prefix, if any, in national characters.	<a href="#">Chapter 31, “Processing XML input,” on page 505</a>

#### related tasks

[“Defining numeric data” on page 41](#)  
[“Displaying numeric data” on page 43](#)  
[“Using national data \(Unicode\) in COBOL” on page 124](#)  
[“Comparing national \(UTF-16\) data” on page 140](#)

#### related references

[“CODEPAGE” on page 295](#)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Intrinsic functions and national data

You can use arguments of class national with the intrinsic functions shown in the table below.

Table 16. <i>Intrinsic functions and national character data</i>		
Intrinsic function	Function type	For more information
DISPLAY-OF	Alphanumeric	<a href="#">“Converting national to alphanumeric (DISPLAY-OF)” on page 133</a>
LENGTH	Integer	<a href="#">“Finding the length of data items” on page 117</a>
LOWER-CASE, UPPER-CASE	National	<a href="#">“Changing case (UPPER-CASE, LOWER-CASE)” on page 112</a>
NUMVAL, NUMVAL-C	Numeric	<a href="#">“Converting to numbers (NUMVAL, NUMVAL-C)” on page 113</a>
MAX, MIN	National	<a href="#">“Finding the largest or smallest data item” on page 115</a>
ORD-MAX, ORD-MIN	Integer	<a href="#">“Finding the largest or smallest data item” on page 115</a>
REVERSE	National	<a href="#">“Transforming to reverse order (REVERSE)” on page 112</a>

You can use national decimal arguments wherever zoned decimal arguments are allowed. You can use national floating-point arguments wherever display floating-point arguments are allowed. (See the related reference below about arguments for a complete list of intrinsic functions that can take integer or numeric arguments.)

#### related tasks

[“Defining numeric data” on page 41](#)

[“Using national data \(Unicode\)](#)

[in COBOL” on page 124](#)

#### related references

Arguments (*Enterprise COBOL for z/OS Language Reference*)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Unicode and the encoding of language characters

Enterprise COBOL provides basic runtime support for Unicode, which can handle tens of thousands of characters that cover all commonly used characters and symbols in the world.

A *character set* is a defined set of characters, but is not associated with a coded representation. A *coded character set* (also referred to in this documentation as a *code page*) is a set of unambiguous rules that relate the characters of the set to their coded representation. Each code page has a name and is like a table that sets up the symbols for representing a character set; each symbol is associated with a unique bit pattern, or *code point*. Each code page also has a *coded character set identifier (CCSID)*, which is a value from 1 to 65,536.

Unicode has several encoding schemes, called *Unicode Transformation Format (UTF)*, such as UTF-8, UTF-16, and UTF-32. Enterprise COBOL uses UTF-16 (CCSID 1200) in big-endian format as the representation for national literals and data items that have USAGE NATIONAL.

UTF-8 represents ASCII invariant characters a-z, A-Z, 0-9, and certain special characters such as ' @ , . + - = / \* ( ) the same way that they are represented in ASCII. UTF-16 represents these characters as NX'00nn', where X'nn' is the representation of the character in ASCII.

For example, the string 'ABC' is represented in UTF-16 as NX'004100420043'. In UTF-8, 'ABC' is represented as X'414243'.

One or more *encoding units* are used to represent a character from a coded character set. For UTF-16, an encoding unit takes 2 bytes of storage. Any character defined in any EBCDIC, ASCII, or EUC code page is represented in one UTF-16 encoding unit when the character is converted to the national data representation.

**Cross-platform considerations:** Enterprise COBOL and COBOL for AIX® support UTF-16 in big-endian format in national data. COBOL for Windows supports UTF-16 in little-endian format (UTF-16LE) in national data. If you are porting Unicode data that is encoded in UTF-16LE representation to Enterprise COBOL from another platform, you must convert that data to UTF-16 in big-endian format to process the data as national data.

#### **related tasks**

[“Converting to or from national \(Unicode\) representation” on page 131](#)

#### **related references**

[“Storage of character data” on page 131](#)

Character sets and code pages (*Enterprise COBOL for z/OS Language Reference*)

## **Using national data (Unicode) in COBOL**

---

In Enterprise COBOL, you can specify national (UTF-16) data in any of several ways.

These types of national data are available:

- National data items (categories national, national-edited, and numeric-edited)
- National literals
- Figurative constants as national characters
- Numeric data items (national decimal and national floating-point)

In addition, you can define national groups that contain only data items that explicitly or implicitly have USAGE NATIONAL, and that behave in the same way as elementary category national data items in most operations.

These declarations affect the amount of storage that is needed.

#### **related concepts**

[“Unicode and the encoding of language characters” on page 123](#)

[“National groups” on page 127](#)

#### **related tasks**

[“Defining national data items” on page 125](#)

[“Using national literals” on page 125](#)

[“Using national-character figurative constants” on page 126](#)

[“Defining national numeric data items” on page 127](#)

[“Using national groups” on page 128](#)

[“Converting to or from national \(Unicode\) representation” on page 131](#)

[“Comparing national \(UTF-16\) data” on page 140](#)

#### **related references**

[“Storage of character data” on page 131](#)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Defining national data items

Define national data items with the `USAGE NATIONAL` clause to hold national (UTF-16) character strings.

You can define national data items of the following categories:

- National
- National-edited
- Numeric-edited

To define a category national data item, code a `PICTURE` clause that contains only one or more `PICTURE` symbols `N`.

To define a national-edited data item, code a `PICTURE` clause that contains at least one of each of the following symbols:

- Symbol `N`
- Simple insertion editing symbol `B`, `0`, or `/`

To define a numeric-edited data item of class national, code a `PICTURE` clause that defines a numeric-edited item (for example, `-$999.99`) and code a `USAGE NATIONAL` clause. You can use a numeric-edited data item that has `USAGE NATIONAL` in the same way that you use a numeric-edited item that has `USAGE DISPLAY`.

You can also define a data item as numeric-edited by coding the `BLANK WHEN ZERO` clause for an elementary item that is defined as numeric by its `PICTURE` clause.

If you code a `PICTURE` clause but do not code a `USAGE` clause for data items that contain only one or more `PICTURE` symbols `N`, you can use the compiler option `NSYMBOL(NATIONAL)` to ensure that such items are treated as national data items instead of as DBCS items.

### related tasks

[“Displaying numeric data” on page 43](#)

### related references

[“NSYMBOL” on page 319](#)

`BLANK WHEN ZERO` clause (*Enterprise COBOL for z/OS Language Reference*)

## Using national literals

To specify national literals, use the prefix character `N` and compile with the option `NSYMBOL(NATIONAL)`.

You can use either of these notations:

- `N"character-data"`
- `N'character-data'`

If you compile with the option `NSYMBOL(DBCS)`, the literal prefix character `N` specifies a DBCS literal, not a national literal.

To specify a national literal as a hexadecimal value, use the prefix `NX`. You can use either of these notations:

- `NX"hexadecimal-digits"`
- `NX'hexadecimal-digits'`

Each of the following `MOVE` statements sets the national data item `Y` to the UTF-16 value of the characters `'AB'`:

```
01 Y pic NN usage national.  
  . . Move NX"00410042" to Y
```

```
Move N"AB"      to Y
Move "AB"       to Y
```

Do not use alphanumeric hexadecimal literals in contexts that call for national literals, because such usage is easily misunderstood. For example, the following statement also results in moving the UTF-16 characters 'AB' (not the hexadecimal bit pattern C1C2) to Y, where Y is defined as `USAGE NATIONAL`:

```
Move X"C1C2" to Y
```

You cannot use national literals in the `SPECIAL-NAMES` paragraph or as program-names. You can use a national literal to name an object-oriented method in the `METHOD-ID` paragraph or to specify a method-name in an `INVOKE` statement.

#### related tasks

[“Using literals” on page 23](#)

#### related references

[“NSYMBOL” on page 319](#)

National literals (*Enterprise COBOL for z/OS Language Reference*)

## Using national-character figurative constants

You can use the figurative constant `ALL national-literal` in a context that requires national characters. `ALL national-literal` represents all or part of the string that is generated by successive concatenations of the encoding units that make up the national literal.

You can use the figurative constants `QUOTE`, `SPACE`, `HIGH-VALUE`, `LOW-VALUE`, or `ZERO` in a context that requires national characters, such as a `MOVE` statement, an implicit move, or a relation condition that has national operands. In these contexts, the figurative constant represents a national-character (UTF-16) value.

When you use the figurative constant `HIGH-VALUE` in a context that requires national characters, its value is `NX'FFFF'`. When you use `LOW-VALUE` in a context that requires national characters, its value is `NX'0000'`.

**Restrictions:** You must not use `HIGH-VALUE` or the value assigned from `HIGH-VALUE` in a way that results in conversion of the value from one data representation to another (for example, between `USAGE DISPLAY` and `USAGE NATIONAL`). `X'FF'` (the value of `HIGH-VALUE` in an alphanumeric context when the EBCDIC collating sequence is being used) does not represent a valid EBCDIC character, and `NX'FFFF'` does not represent a valid national character. Conversion of such a value to another representation results in a *substitution character* being used (not `X'FF'` or `NX'FFFF'`). Consider the following example:

```
01 natl-data PIC NN Usage National.
01 alph-data PIC XX.
. . .
MOVE HIGH-VALUE TO natl-data, alph-data
IF natl-data = alph-data. . .
```

The `IF` statement above evaluates as false even though each of its operands was set to `HIGH-VALUE`. Before an elementary alphanumeric operand is compared to a national operand, the alphanumeric operand is treated as though it were moved to a temporary national data item, and the alphanumeric characters are converted to the corresponding national characters. When `X'FF'` is converted to UTF-16, however, the UTF-16 item gets a substitution character value and so does not compare equally to `NX'FFFF'`.

#### related tasks

[“Converting to or from national \(Unicode\) representation” on page 131](#)

[“Comparing national \(UTF-16\) data” on page 140](#)

### related references

Figurative constants (*Enterprise COBOL for z/OS Language Reference*)

DISPLAY-OF (*Enterprise COBOL for z/OS Language Reference*)

Support for Unicode: Using Unicode Services

## Defining national numeric data items

Define data items with the `USAGE NATIONAL` clause to hold numeric data that is represented in national characters (UTF-16). You can define national decimal items and national floating-point items.

To define a national decimal item, code a `PICTURE` clause that contains only the symbols 9, P, S, and V. If the `PICTURE` clause contains S, the `SIGN IS SEPARATE` clause must be in effect for that item.

To define a national floating-point item, code a `PICTURE` clause that defines a floating-point item (for example, `+99999.9E-99`).

You can use national decimal items in the same way that you use zoned decimal items. You can use national floating-point items in the same way that you use display floating-point items.

### related tasks

[“Defining numeric data” on page 41](#)

[“Displaying numeric data” on page 43](#)

### related references

`SIGN` clause (*Enterprise COBOL for z/OS Language Reference*)

## National groups

National groups, which are specified either explicitly or implicitly with the `GROUP-USAGE NATIONAL` clause, contain only data items that have `USAGE NATIONAL`. In most cases, a national group item is processed as though it were redefined as an elementary category national item described as `PIC N(m)`, where  $m$  is the number of national (UTF-16) characters in the group.

For some operations on national groups, however (just as for some operations on alphanumeric groups), group semantics apply. Such operations (for example, `MOVE CORRESPONDING` and `INITIALIZE`) recognize or process the elementary items within the national group.

Where possible, use national groups instead of alphanumeric groups that contain `USAGE NATIONAL` items. National groups provide several advantages for the processing of national data compared to the processing of national data within alphanumeric groups:

- When you move a national group to a longer data item that has `USAGE NATIONAL`, the receiving item is padded with national characters. By contrast, if you move an alphanumeric group that contains national characters to a longer alphanumeric group that contains national characters, alphanumeric spaces are used for padding. As a result, mishandling of data items could occur.
- When you move a national group to a shorter data item that has `USAGE NATIONAL`, the national group is truncated at national-character boundaries. By contrast, if you move an alphanumeric group that contains national characters to a shorter alphanumeric group that contains national characters, truncation might occur between the 2 bytes of a national character.
- When you move a national group to a national-edited or numeric-edited item, the content of the group is edited. By contrast, if you move an alphanumeric group to an edited item, no editing takes place.
- When you use a national group as an operand in a `STRING`, `UNSTRING`, or `INSPECT` statement:
  - The group content is processed as national characters rather than as single-byte characters.
  - `TALLYING` and `POINTER` operands operate at the logical level of national characters.
  - The national group operand is supported with a mixture of other national operand types.

By contrast, if you use an alphanumeric group that contains national characters in these contexts, the characters are processed byte by byte. As a result, invalid handling or corruption of data could occur.

**USAGE NATIONAL groups:** A group item can specify the `USAGE NATIONAL` clause at the group level as a convenient shorthand for the `USAGE` of each of the elementary data items within the group. Such a group is *not* a national group, however, but an alphanumeric group, and behaves in many operations, such as moves and compares, like an elementary data item of `USAGE DISPLAY` (except that no editing or conversion of data occurs).

#### related tasks

[“Assigning values to group](#)

[data items \(MOVE\)” on page 31](#)

[“Joining data items \(STRING\)” on page 101](#)

[“Splitting data items \(UNSTRING\)” on page 103](#)

[“Tallying and replacing](#)

[data items \(INSPECT\)” on page 110](#)

[“Using national groups” on page 128](#)

#### related references

`GROUP-USAGE` clause (*Enterprise COBOL for z/OS Language Reference*)

## Using national groups

To define a group data item as a national group, code a `GROUP-USAGE NATIONAL` clause at the group level for the item. The group can contain only data items that explicitly or implicitly have `USAGE NATIONAL`.

The following data description entry specifies that a level-01 group and its subordinate groups are national group items:

```
01 Nat-Group-1    GROUP-USAGE NATIONAL.
   02 Group-1.
       04 Month    PIC 99.
       04 DayOf    PIC 99.
       04 Year     PIC 9999.
   02 Group-2     GROUP-USAGE NATIONAL.
       04 Amount   PIC 9(4).99 USAGE NATIONAL.
```

In the example above, `Nat-Group-1` is a national group, and its subordinate groups `Group-1` and `Group-2` are also national groups. A `GROUP-USAGE NATIONAL` clause is implied for `Group-1`, and `USAGE NATIONAL` is implied for the subordinate items in `Group-1`. `Month`, `DayOf`, and `Year` are national decimal items, and `Amount` is a numeric-edited item that has `USAGE NATIONAL`.

You can subordinate national groups within alphanumeric groups as in the following example:

```
01 Alpha-Group-1.
   02 Group-1.
       04 Month    PIC 99.
       04 DayOf    PIC 99.
       04 Year     PIC 9999.
   02 Group-2     GROUP-USAGE NATIONAL.
       04 Amount   PIC 9(4).99.
```

In the example above, `Alpha-Group-1` and `Group-1` are alphanumeric groups; `USAGE DISPLAY` is implied for the subordinate items in `Group-1`. (If `Alpha-Group-1` specified `USAGE NATIONAL` at the group level, `USAGE NATIONAL` would be implied for each of the subordinate items in `Group-1`. However, `Alpha-Group-1` and `Group-1` would be alphanumeric groups, not national groups, and would behave like alphanumeric groups during operations such as moves and compares.) `Group-2` is a national group, and `USAGE NATIONAL` is implied for the numeric-edited item `Amount`.

You cannot subordinate alphanumeric groups within national groups. All elementary items within a national group must be explicitly or implicitly described as `USAGE NATIONAL`, and all group items within a national group must be explicitly or implicitly described as `GROUP-USAGE NATIONAL`.

#### **related concepts**

[“National groups” on page 127](#)

#### **related tasks**

[“Using national groups as elementary items” on page 129](#)

[“Using national groups as group items” on page 129](#)

#### **related references**

`GROUP-USAGE` clause (*Enterprise COBOL for z/OS Language Reference*)

## **Using national groups as elementary items**

In most cases, you can use a national group as though it were an elementary data item.

In the following example, a national group item, `Group-1`, is moved to a national-edited item, `Edited-date`. Because `Group-1` is treated as an elementary data item during the move, editing takes place in the receiving data item. The value in `Edited-date` after the move is `06/23/2010` in national characters.

```
01 Edited-date PIC NN/NN/NNNN USAGE NATIONAL.
01 Group-1     GROUP-USAGE NATIONAL.
   02 Month    PIC 99 VALUE 06.
   02 DayOf    PIC 99 VALUE 23.
   02 Year     PIC 9999 VALUE 2010.

MOVE Group-1 to Edited-date.
```

If `Group-1` were instead an alphanumeric group in which each of its subordinate items had `USAGE NATIONAL` (specified either explicitly with a `USAGE NATIONAL` clause on each elementary item, or implicitly with a `USAGE NATIONAL` clause at the group level), a group move, rather than an elementary move, would occur. Neither editing nor conversion would take place during the move. The value in the first eight character positions of `Edited-date` after the move would be `06232010` in national characters, and the value in the remaining two character positions would be 4 bytes of alphanumeric spaces.

#### **related tasks**

[“Assigning values to group data items \(MOVE\)” on page 31](#)

[“Comparing national data and alphanumeric-group operands” on page 142](#)

[“Using national groups as group items” on page 129](#)

#### **related references**

`MOVE` statement (*Enterprise COBOL for z/OS Language Reference*)

## **Using national groups as group items**

In some cases when you use a national group, it is handled with group semantics; that is, the elementary items in the group are recognized or processed.

In the following example, an `INITIALIZE` statement that acts upon national group item `Group-OneN` causes the value 15 in national characters to be moved to only the numeric items in the group:

```
01 Group-OneN Group-Usage National.
   05 Trans-codeN Pic N Value "A".
   05 Part-numberN Pic NN Value "XX".
```

```

05 Trans-quant Pic 99 Value 10.
Initialize Group-OneN Replacing Numeric Data By 15

```

Because only Trans-quant in Group-OneN above is numeric, only Trans-quant receives the value 15. The other subordinate items are unchanged.

The table below summarizes the cases where national groups are processed with group semantics.

<i>Table 17. National group items that are processed with group semantics</i>		
Language feature	Uses of national group items	Comment
CORRESPONDING phrase of the ADD, SUBTRACT, or MOVE statement	Specify a national group item for processing as a group in accordance with the rules of the CORRESPONDING phrase.	Elementary items within the national group are processed like elementary items that have USAGE NATIONAL within an alphanumeric group.
Host variable in EXEC SQL statement	Specify a national group item as a host variable.	The national group item is in effect shorthand for the set of host variables that are subordinate to the group item.
INITIALIZE statement	Specify a national group for processing as a group in accordance with the rules of the INITIALIZE statement.	Elementary items within the national group are initialized like elementary items that have USAGE NATIONAL within an alphanumeric group.
Name qualification	Use the name of a national group item to qualify the names of elementary data items and of subordinate group items in the national group.	Follow the same rules for qualification as for an alphanumeric group.
THROUGH phrase of the RENAME clause	To specify a national group item in the THROUGH phrase, use the same rules as for an alphanumeric group item.	The result is an alphanumeric group item.
FROM phrase of the XML GENERATE statement	Specify a national group item in the FROM phrase for processing as a group in accordance with the rules of the XML GENERATE statement.	Elementary items within the national group are processed like elementary items that have USAGE NATIONAL within an alphanumeric group.

#### related tasks

[“Initializing a structure \(INITIALIZE\)” on page 29](#)  
[“Initializing a table \(INITIALIZE\)” on page 71](#)  
[“Assigning values to elementary data items \(MOVE\)” on page 30](#)  
[“Assigning values to group data items \(MOVE\)” on page 31](#)  
[“Finding the length of data items” on page 117](#)  
[“Generating XML output” on page 545](#)  
[“Using national group items in SQL statements” on page 420](#)

#### related references

Qualification (*Enterprise COBOL for z/OS Language Reference*)  
 RENAME clause (*Enterprise COBOL for z/OS Language Reference*)

## Storage of character data

Use the table below to compare alphanumeric (DISPLAY), DBCS (DISPLAY-1), and Unicode (NATIONAL) encoding and to plan storage usage.

<i>Table 18. Encoding and size of alphanumeric, DBCS, and national data</i>			
Characteristic	DISPLAY	DISPLAY-1	NATIONAL
Character encoding unit	1 byte	2 bytes	2 bytes
Code page	EBCDIC	EBCDIC DBCS	UTF-16BE <sup>1</sup>
Encoding units per graphic character	1	1	1 or 2 <sup>2</sup>
Bytes per graphic character	1 byte	2 bytes	2 or 4 bytes
<div><div>1. Use the CODEPAGE compiler option to specify the EBCDIC code page that is applicable to alphanumeric or DBCS data.</div><div>2. Most characters are represented in UTF-16 using one encoding unit. In particular, the following characters are represented using a single UTF-16 encoding unit per character:<ul style="list-style-type: none"><li>• COBOL characters A-Z, a-z, 0-9, space, + - * / = \$ , ; . " ( ) &gt; &lt; : '</li><li>• All characters that are converted from an EBCDIC or ASCII code page</li></ul></div></div>			

### related concepts

[“Unicode and the encoding of language characters” on page 123](#)

## Converting to or from national (Unicode) representation

You can implicitly or explicitly convert data items to national (UTF-16) representation.

You can implicitly convert alphabetic, alphanumeric, DBCS, or integer data to national data by using the MOVE statement. Implicit conversions also take place in other COBOL statements, such as IF statements that compare an alphanumeric data item with a data item that has USAGE NATIONAL.

You can explicitly convert to and from national data items by using the intrinsic functions NATIONAL-OF and DISPLAY-OF, respectively. By using these intrinsic functions, you can specify a code page for the conversion that is different from the code page that is in effect with the CODEPAGE compiler option.

### related tasks

[“Converting alphanumeric, DBCS, and integer to national \(MOVE\)” on page 131](#)

[“Converting alphanumeric or DBCS to national \(NATIONAL-OF\)” on page 132](#)

[“Converting national to alphanumeric \(DISPLAY-OF\)” on page 133](#)

[“Overriding the default code page” on page 133](#)

[“Comparing national \(UTF-16\) data” on page 140](#)

### related references

[“CODEPAGE” on page 295](#)

[“Conversion exceptions” on page 133](#)

## Converting alphanumeric, DBCS, and integer to national (MOVE)

You can use a MOVE statement to implicitly convert data to national representation.

You can move the following kinds of data to category national or national-edited data items, and thus convert the data to national representation:

- Alphabetic
- Alphanumeric
- Alphanumeric-edited
- DBCS
- Integer of USAGE DISPLAY
- Numeric-edited of USAGE DISPLAY

You can likewise move the following kinds of data to numeric-edited data items that have USAGE NATIONAL:

- Alphanumeric
- Display floating-point (floating-point of USAGE DISPLAY)
- Numeric-edited of USAGE DISPLAY
- Integer of USAGE DISPLAY

For complete rules about moves to national data, see the related reference about the MOVE statement.

For example, the MOVE statement below moves the alphanumeric literal "AB" to the national data item UTF16-Data:

```
01 UTF16-Data Pic N(2) Usage National.  
  Move "AB" to UTF16-Data
```

After the MOVE statement above, UTF16-Data contains NX '00410042', the national representation of the alphanumeric characters 'AB'.

If padding is required in a receiving data item that has USAGE NATIONAL, the default UTF-16 space character (NX '0020') is used. If truncation is required, it occurs at the boundary of a national-character position.

#### **related tasks**

[“Assigning values to elementary data items \(MOVE\)” on page 30](#)

[“Assigning values to group data items \(MOVE\)” on page 31](#)

[“Displaying numeric data” on page 43](#)

[“Coding for use of DBCS support” on page 142](#)

#### **related references**

MOVE statement (*Enterprise COBOL for z/OS Language Reference*)

## **Converting alphanumeric or DBCS to national (NATIONAL-OF)**

Use the NATIONAL-OF intrinsic function to convert alphabetic, alphanumeric, or DBCS data to a national data item. Specify the source code page as the second argument if the source is encoded in a different code page than is in effect with the CODEPAGE compiler option.

[“Example: converting to and from national data” on page 133](#)

#### **related tasks**

[“Processing UTF-8 data” on page 134](#)

[“Processing Chinese GB 18030 data” on page 139](#)

[“Processing alphanumeric data items that contain DBCS data” on page 144](#)

#### **related references**

[“CODEPAGE” on page 295](#)

NATIONAL-OF (*Enterprise COBOL for z/OS Language Reference*)

## **Converting national to alphanumeric (DISPLAY-OF)**

Use the DISPLAY-OF intrinsic function to convert national data to an alphanumeric (USAGE DISPLAY) character string that is represented in a code page that you specify as the second argument.

If you omit the second argument, the output code page is the one that was in effect with the CODEPAGE compiler option when the source was compiled.

If you specify an EBCDIC or ASCII code page that combines single-byte character set (SBCS) and DBCS characters, the returned string might contain a mixture of SBCS and DBCS characters. The DBCS substrings are delimited by shift-in and shift-out characters if the code page in effect for the function is an EBCDIC code page.

[“Example: converting to and from national data” on page 133](#)

#### **related tasks**

[“Processing UTF-8 data” on page 134](#)

[“Processing Chinese GB 18030 data” on page 139](#)

#### **related references**

DISPLAY-OF (*Enterprise COBOL for z/OS Language Reference*)

## **Overriding the default code page**

In some cases, you might need to convert data to or from a code page that differs from the CCSID that is specified as the CODEPAGE option value. To do so, convert the item by using a conversion function in which you explicitly specify the code page.

If you specify a code page as an argument to the DISPLAY-OF intrinsic function, and the code page differs from the code page that is in effect with the CODEPAGE compiler option, do not use the function result in any operations that involve implicit conversion (such as an assignment to, or comparison with, a national data item). Such operations assume the EBCDIC code page that is specified with the CODEPAGE compiler option.

#### **related references**

[“CODEPAGE” on page 295](#)

## **Conversion exceptions**

Implicit or explicit conversion between national data and alphanumeric data can fail and generate a severity-3 Language Environment condition.

Failure can occur if the code page that you specified implicitly or explicitly is not a valid code page.

A character that does not have a counterpart in the target CCSID does not result in a conversion exception. Such a character is converted to a *substitution character* in the target code page.

#### **related references**

[“CODEPAGE” on page 295](#)

## **Example: converting to and from national data**

The following example shows the NATIONAL-OF and DISPLAY-OF intrinsic functions and the MOVE statement for converting to and from national (UTF-16) data items. It also demonstrates the need for explicit conversions when you operate on strings that are encoded in multiple code pages.

```
CBL CODEPAGE(00037)
```

```

* . . .
01 Data-in-Unicode      pic N(100) usage national.
01 Data-in-Greek       pic X(100).
01 other-data-in-US-English pic X(12) value "PRICE in $ =".
* . . .
    Read Greek-file into Data-in-Greek
    Move function National-of(Data-in-Greek, 00875)
      to Data-in-Unicode
* . . . process Data-in-Unicode here . . .
    Move function Display-of(Data-in-Unicode, 00875)
      to Data-in-Greek
    Write Greek-record from Data-in-Greek

```

The example above works correctly because the input code page is specified. Data-in-Greek is converted as data represented in CCSID 00875 (Greek). However, the following statement results in an incorrect conversion unless all the characters in the item happen to be among those that have a common representation in both the Greek and the English code pages:

```
Move Data-in-Greek to Data-in-Unicode
```

The MOVE statement above converts Data-in-Greek to Unicode representation based on the CCSID 00037 (U.S. English) to UTF-16 conversion. This conversion does not produce the expected results because Data-in-Greek is encoded in CCSID 00875.

If you can correctly set the CODEPAGE compiler option to CCSID 00875 (that is, the rest of your program also handles EBCDIC data in Greek), you can code the same example correctly as follows:

```

CBL CODEPAGE(00875)
* . . .
01 Data-in-Unicode pic N(100) usage national.
01 Data-in-Greek   pic X(100).
* . . .
    Read Greek-file into Data-in-Greek
* . . . process Data-in-Greek here ...
* . . . or do the following (if need to process data in Unicode):
    Move Data-in-Greek to Data-in-Unicode
* . . . process Data-in-Unicode
    Move function Display-of(Data-in-Unicode) to Data-in-Greek
    Write Greek-record from Data-in-Greek

```

## Processing UTF-8 data

To process UTF-8 data, first convert the UTF-8 data to UTF-16 in a national data item. After processing the national data, convert it back to UTF-8 for output. For the conversions, use the intrinsic functions NATIONAL-OF and DISPLAY-OF, respectively. Use code page 1208 for UTF-8 data.

National data is encoded in UTF-16, which uses one encoding unit for almost all commonly encountered characters. With this property, you can use string operations such as reference modification on the national data. If it is more convenient to retain the UTF-8 encoding, use the Unicode intrinsic functions to assist with processing the data. For details, see [“Using intrinsic functions to process UTF-8 encoded data”](#) on page 135.

Take the following steps to convert ASCII or EBCDIC data to UTF-8:

1. Use the function NATIONAL-OF to convert the ASCII or EBCDIC string to a national (UTF-16) string.
2. Use the function DISPLAY-OF to convert the national string to UTF-8.

The following example converts Greek EBCDIC data to UTF-8:

```

01 Greek-EBCDIC pic X(10) value "αβγδεζηθ".
01 UnicodeString pic N(10).
01 UTF-8-String pic X(20).
    Move function National-of(Greek-EBCDIC, 00875) to UnicodeString
    Move function Display-of(UnicodeString, 01208) to UTF-8-String

```

**Usage note:** Use care if you use reference modification to refer to data encoded in UTF-8. UTF-8 characters are encoded with a varying number of bytes per character. Avoid operations that might split a multibyte character.

#### **related tasks**

[“Referring to substrings](#)

[of data items” on page 107](#)

[“Converting to or from national \(Unicode\) representation” on page 131](#)

[“Parsing XML documents](#)

[encoded in UTF-8” on page 526](#)

[“Using intrinsic functions to process UTF-8 encoded data” on page 135](#)

## **Using intrinsic functions to process UTF-8 encoded data**

If it is more convenient to keep your data encoded in UTF-8, use the Unicode intrinsic functions to facilitate testing and processing the UTF-8 data.

You can use the following intrinsic functions:

### **UVALID**

To verify that the UTF-8 character data is well-formed

### **USUPPLEMENTARY**

If the data is to be converted to national, and it is important that every character can be represented by a single 16-bit encoding unit, use the USUPPLEMENTARY function to determine whether a valid UTF-8 character string contains a Unicode supplementary code point; that is, a code point with a Unicode scalar value above U+FFFF, requiring a 4-byte representation in UTF-8.

### **USUBSTR**

It provides a convenient alternative to reference modification for referring to substrings of the UTF-8 character string. USUBSTR expects character position and length arguments versus the computed byte locations and counts required by reference modification.

Auxiliary functions can provide additional information about a valid UTF-8 character string:

### **ULENGTH**

To determine the total number of Unicode code points in the string

### **UPOS**

To determine the byte position in the string of the *n*th Unicode code point

### **UWIDTH**

To determine the width in bytes of the *n*th Unicode code point in the string

The following code fragment illustrates UTF-8 validity checking, and the use of the auxiliary functions:

```
checkUTF-8-validity.  
  Compute u = function UVALID(UTF-8-testStr)  
  If u not = 0  
    Display 'checkUTF-8-validity failure:'  
    Display '  The UTF-8 representation is not valid,'  
      'starting at byte ' u '.'  
    Compute v = function ULENGTH(UTF-8-testStr(1:u - 1))  
    Compute u = function UPOS(UTF-8-testStr v)  
    Compute w = function UWIDTH(UTF-8-testStr v)  
    Display '  The ' v 'th and last valid code point starts '  
      'at byte ' u ' for ' w ' bytes.'  
  End-if.
```

In the following string, the sequence that starts with x'F5' is not valid UTF-8 because no byte can have a value in the range x'F5' to x'FF':

```
x'6162D0B0E4BA8CF5646364'
```

The output from checkUTF-8-validity for this string is as follows:

```
checkUTF-8-validity failure:
  The UTF-8 representation is not valid, starting at byte 08.
  The 04th and last valid code point starts at byte 05 for 03 bytes.
```

The following code fragment illustrates checking for the presence of a Unicode supplementary code point, requiring a 4-byte representation in UTF-8:

```
checkUTF-8-suppl.
  Compute u = function USUPPLEMENTARY(UTF-8-testStr)
  If u not = 0
    Display ' checkUTF-8-suppl hit:'
    Compute v = function ULENGTH(UTF-8-testStr(1:u - 1))
    Compute w = function UWIDTH(UTF-8-testStr v + 1)
    Display ' The ' v 'th code point of the string'
      ', starting at byte ' u ', '
    Display ' is a Unicode supplementary code point, '
      'width ' w ' bytes.'
  End-if.
```

In the following string, the sequence x'F0908C82' is a supplementary character (as is any valid UTF-8 sequence beginning with a byte in the range x'F0' to x'F4'):

```
x'6162D0B0E4BA8CF0908C826364'
```

The output from checkUTF-8-suppl for this string is as follows:

```
checkUTF-8-suppl hit:
  The 04th code point of the string, starting at byte 08,
  is a Unicode supplementary code point, width 04 bytes.
```

#### related references

[“CODEPAGE” on page 295](#)

### Example: deriving initials from UTF-8 names

The following program uses the Unicode functions to derive composers' initials from a table of names in Czech. It is intended to illustrate these functions, and is not necessarily the most efficient way of doing the task. Although the program processes the composer names in UTF-8, the data begins and ends in EBCDIC in order to permit a meaningful display of the program source and output. The compiler option CODEPAGE (1153) ensures that the names are interpreted correctly when translated to and from Unicode.

## Program initials

```
Process codepage(1153)
*-----*
* For a table of Czech composer names represented in UTF-8,      *
* determine and print out the initials of each name.             *
*-----*
Identification division.
  Program-id. initials.
Data division.
  Working-storage section.
    1 utilityVariables.
      2 UTF-8-space pic x value x'20'.
      2 UTF-8-hyphen pic x value x'2D'.
      2 UTF-8-ch pic xxx.
      2 i comp pic 9.
      2 j comp pic 99.
      2 hex pic x(160).
    1 EBCDICNameData.
      2 pic x(40) value 'Antonín Leopold Dvořák'.
      2 pic x(40) value 'Leoš Janáček'.
      2 pic x(40) value 'Rafael Jeroným Kubelík'.
      2 pic x(40) value 'Pavel Křížkovský'.
      2 pic x(40) value 'Jan Václav Hugo Voříšek'.
    1 redefines EBCDICNameData.
      2 EBCDICName pic x(40) occurs 5 times.
    1 UTF-8-nameData.
      2 composer pic x(40) occurs 5 times.
    1 composerInitials.
      2 occurs 5.
        3 cInitSize comp pic 99.
        3 cInit pic x(8).
    1 state pic 9.
      88 seekingInitial value 0.  *> Skip space and hyphen
      88 seekingSeparator value 1. *> Skip all but space and hyphen
```

## Program initials, continued

```
Procedure division.
  main.
    Display 'Compute composer initials...'
    Initialize composerInitials
    Perform test before varying i from 1 by 1 until i > 5
  * Start by translating each composer name from EBCDIC to UTF-8.
    Move function display-of
      (function national-of(EBCDICname(i)) 1208)
    to composer(i)
  * Test each character of the name; skip leading spaces, etc.
    Set seekingInitial to true
    Move 1 to cInitSize(i)
    Perform varying j from 1 by 1
      until j > function ULENGTH(composer(i))
    Move function USUBSTR(composer(i) j 1) to UTF-8-ch
  * Initial found. Save in buffer, then skip to next space/hyphen.
    If seekingInitial and
      UTF-8-ch not = UTF-8-Space and UTF-8-Hyphen
    String function USUBSTR(composer(i) j 1)
      delimited by size
      into cInit(i) with pointer cInitSize(i)
    Set seekingSeparator to true
    End-if
  * Space/hyphen found; skip spaces or hyphens to next initial.
    If seekingSeparator and
      (UTF-8-ch = UTF-8-Space or UTF-8-Hyphen)
    Set seekingInitial to true
    End-if
  End-perform
  * Adjust string pointer to number of initials found.
    Subtract 1 from cInitSize(i)
  End-perform
  * Print out the UTF-8 initials, translated to EBCDIC, and
  * also in hexadecimal, using program ToHex (listed later).
    Perform test before varying i from 1 by 1 until i > 5
    Call 'toHex' using hex cInit(i) value cInitSize(i)
    Display '  #' i ': ' function display-of(
      function national-of(cInit(i) (1:cInitSize(i)) 1208))
      ' (x''' hex(1:2 * cInitSize(i)) ''')'
    End-perform.
  Goback.
End program initials.
```

## Output from program initials

```
Compute composer initials...
#1: ALD (x'414C44')
#2: LJ (x'4C4A')
#3: RJK (x'524A4B')
#4: PK (x'504B')
#5: JVHV (x'4A564856')
```

## Program toHex

```
Identification division.
  Program-id. toHex.
Data division.
  Working-storage section.
    1 hexv.
      2 pic x(32) value '000102030405060708090A0B0C0D0E0F'.
      2 pic x(32) value '101112131415161718191A1B1C1D1E1F'.
      2 pic x(32) value '202122232425262728292A2B2C2D2E2F'.
      2 pic x(32) value '303132333435363738393A3B3C3D3E3F'.
      2 pic x(32) value '404142434445464748494A4B4C4D4E4F'.
      2 pic x(32) value '505152535455565758595A5B5C5D5E5F'.
      2 pic x(32) value '606162636465666768696A6B6C6D6E6F'.
```

```

2 pic x(32) value '707172737475767778797A7B7C7D7E7F'.
2 pic x(32) value '808182838485868788898A8B8C8D8E8F'.
2 pic x(32) value '909192939495969798999A9B9C9D9E9F'.
2 pic x(32) value 'A0A1A2A3A4A5A6A7A8A9AAABACADAEAF'.
2 pic x(32) value 'B0B1B2B3B4B5B6B7B8B9BABBBBCBDBEBF'.
2 pic x(32) value 'C0C1C2C3C4C5C6C7C8C9CACBCCCDCECF'.
2 pic x(32) value 'D0D1D2D3D4D5D6D7D8D9DADBDCDDDEDF'.
2 pic x(32) value 'E0E1E2E3E4E5E6E7E8E9EAEBECEDEEEF'.
2 pic x(32) value 'F0F1F2F3F4F5F6F7F8F9FAFBFCFDFEFF'.
1 redefines hexv.
2 hex pic xx occurs 256 times.
Local-storage section.
1 i pic 9(4) binary.
1 j pic 9(4) binary value 0.
1 jx redefines j.
2 pic x.
2 jxd pic x.
Linkage section.
1 ostr.
2 ostrv pic xx occurs 1024 times.
1 istr.
2 istrv pic x occurs 1024 times.
1 len pic 9(9) binary.
Procedure division using ostr istr value len.
  If len > 1024
    Display '>> Error: length ' len ' greater than toHex '
      'supported maximum of 1024.'
    Stop run
  End-if
  Perform with test before varying i from 1 by 1 until i > len
    Move 0 to j
    Move istrv(i) to jxd
    Add 1 to j
    Move hex(j) to ostrv(i)
  End-perform
  Goback
.
End program toHex.

```

## Processing Chinese GB 18030 data

GB 18030 is a national-character standard specified by the government of the People's Republic of China.

GB 18030 characters can be encoded in either UTF-16 or in code page CCSID 1392. Code page 1392 is an ASCII multibyte code page that uses 1, 2, or 4 bytes per character. A subset of the GB 18030 characters can be encoded in the Chinese ASCII code page, CCSID 1386, or in the Chinese EBCDIC code page, CCSID 1388.

Enterprise COBOL does not have explicit support for GB 18030, but does support the processing of GB 18030 characters in several ways. You can:

- Use DBCS data items to process GB 18030 characters that are represented in CCSID 1388.
- Use national data items to define and process GB 18030 characters that are represented in UTF-16, CCSID 01200.
- Process data in any code page (including CCSID 1388 or 1392) by converting the data to UTF-16, processing the UTF-16 data, and then converting the data back to the original code-page representation.

When you need to process Chinese GB 18030 data that requires conversion, first convert the input data to UTF-16 in a national data item. After you process the national data item, convert it back to Chinese GB 18030 for output. For the conversions, use the intrinsic functions `NATIONAL-OF` and `DISPLAY-OF`, respectively, and specify code page 1388 or 1392 as the second argument of each function.

The following example illustrates these conversions:

```

01 Chinese-EBCDIC pic X(16) value "奥林匹克运动会".
01 Chinese-GB18030-String pic X(16).
01 UnicodeString pic N(14).
* * *
* Move function National-of(Chinese-EBCDIC, 1388) to UnicodeString
* Process data in Unicode
* Move function Display-of(UnicodeString, 1388) to Chinese-GB18030-String

```

#### related tasks

[“Converting to or from national \(Unicode\) representation” on page 131](#)  
[“Coding for use of DBCS support” on page 142](#)

#### related references

[“Storage of character data” on page 131](#)

## Comparing national (UTF-16) data

---

You can compare national (UTF-16) data, that is, national literals and data items that have USAGE NATIONAL (whether of class national or class numeric), explicitly or implicitly with other kinds of data in relation conditions.

You can code conditional expressions that use national data in the following statements:

- EVALUATE
- IF
- INSPECT
- PERFORM
- SEARCH
- STRING
- UNSTRING

For full details about comparing national data items to other data items, see the related references.

#### related tasks

[“Comparing two class national operands” on page 140](#)  
[“Comparing class national and class numeric operands” on page 141](#)  
[“Comparing national numeric and other numeric operands” on page 141](#)  
[“Comparing national and other character-string operands” on page 142](#)  
[“Comparing national data and alphanumeric-group operands” on page 142](#)

#### related references

Relation conditions (*Enterprise COBOL for z/OS Language Reference*)  
 General relation conditions (*Enterprise COBOL for z/OS Language Reference*)  
 National comparisons (*Enterprise COBOL for z/OS Language Reference*)  
 Group comparisons (*Enterprise COBOL for z/OS Language Reference*)

## Comparing two class national operands

You can compare the character values of two operands of class national.

Either operand (or both) can be any of the following types of items:

- A national group
- An elementary category national or national-edited data item

- A numeric-edited data item that has USAGE NATIONAL

One of the operands can instead be a national literal or a national intrinsic function.

When you compare two class national operands that have the same length, they are determined to be equal if all pairs of the corresponding characters are equal. Otherwise, comparison of the binary values of the first pair of unequal characters determines the operand with the larger binary value.

When you compare operands that have unequal lengths, the shorter operand is treated as if it were padded on the right with default UTF-16 space characters (NX '0020 ') to the length of the longer operand.

The PROGRAM COLLATING SEQUENCE clause does not affect the comparison of two class national operands.

**related concepts**

[“National groups” on page 127](#)

**related tasks**

[“Using national groups” on page 128](#)

**related references**

National comparisons (*Enterprise COBOL for z/OS Language Reference*)

## Comparing class national and class numeric operands

You can compare national literals or class national data items to integer literals or numeric data items that are defined as integer (that is, national decimal items or zoned decimal items). At most one of the operands can be a literal.

You can also compare national literals or class national data items to floating-point data items (that is, display floating-point or national floating-point items).

Numeric operands are converted to national (UTF-16) representation if they are not already in national representation. A comparison is made of the national character values of the operands.

**related references**

General relation conditions (*Enterprise COBOL for z/OS Language Reference*)

## Comparing national numeric and other numeric operands

National numeric operands (national decimal and national floating-point operands) are data items of class numeric that have USAGE NATIONAL.

You can compare the algebraic values of numeric operands regardless of their USAGE. Thus you can compare a national decimal item or a national floating-point item with a binary item, an internal-decimal item, a zoned decimal item, a display floating-point item, or any other numeric item.

**related tasks**

[“Defining national numeric data items” on page 127](#)

**related references**

General relation conditions (*Enterprise COBOL for z/OS Language Reference*)

## Comparing national and other character-string operands

You can compare the character value of a national literal or class national data item with the character value of any of the following other character-string operands: alphabetic, alphanumeric, alphanumeric-edited, DBCS, or numeric-edited of USAGE DISPLAY.

These operands are treated as if they were moved to an elementary national data item. The characters are converted to national (UTF-16) representation, and the comparison proceeds with two national character operands.

### related tasks

[“Using national-character figurative constants” on page 126](#)

### related references

National comparisons (*Enterprise COBOL for z/OS Language Reference*)

## Comparing national data and alphanumeric-group operands

You can compare a national literal, a national group item, or any elementary data item that has USAGE NATIONAL to an alphanumeric group.

Neither operand is converted. The national operand is treated as if it were moved to an alphanumeric group item of the same size in bytes as the national operand, and the two groups are compared. An alphanumeric comparison is done regardless of the representation of the subordinate items in the alphanumeric group operand.

For example, Group-XN is an alphanumeric group that consists of two subordinate items that have USAGE NATIONAL:

```
01 Group-XN.  
  02 TransCode PIC NN   Value "AB"   Usage National.  
  02 Quantity  PIC 999   Value 123    Usage National.  
  
  If N"AB123" = Group-XN Then Display "EQUAL"  
  Else Display "NOT EQUAL".
```

When the IF statement above is executed, the 10 bytes of the national literal N"AB123" are compared byte by byte to the content of Group-XN. The items compare equally, and "EQUAL" is displayed.

### related references

Group comparisons (*Enterprise COBOL for z/OS Language Reference*)

## Coding for use of DBCS support

IBM Enterprise COBOL for z/OS supports using applications in any of many national languages, including languages that use double-byte character sets (DBCS).

The following list summarizes the support for DBCS:

- DBCS characters in user-defined words (DBCS names)
- DBCS characters in comments
- DBCS data items (defined with PICTURE N, G, or G and B)
- DBCS literals
- DBCS compiler option

#### **related tasks**

[“Defining DBCS data” on page 143](#)

[“Using DBCS literals” on page 143](#)

[“Testing for valid DBCS characters” on page 144](#)

[“Processing alphanumeric data items that contain DBCS data” on page 144](#)

[Appendix B, “Converting double-byte character set \(DBCS\) data,” on page 665](#)

#### **related references**

[“DBCS” on page 301](#)

## **Defining DBCS data**

Use the PICTURE and USAGE clauses to define DBCS data items. DBCS data items can use PICTURE symbols G, G and B, or N. Each DBCS character position is 2 bytes in length.

You can specify a DBCS data item by using the USAGE DISPLAY-1 clause. When you use PICTURE symbol G, you must specify USAGE DISPLAY-1. When you use PICTURE symbol N but omit the USAGE clause, USAGE DISPLAY-1 or USAGE NATIONAL is implied depending on the setting of the NSYMBOL compiler option.

If you use a VALUE clause with the USAGE clause in the definition of a DBCS item, you must specify a DBCS literal or the figurative constant SPACE or SPACES.

For the purpose of handling reference modifications, each character in a DBCS data item is considered to occupy the number of bytes that corresponds to the code-page width (that is, 2).

#### **related references**

[“NSYMBOL” on page 319](#)

## **Using DBCS literals**

You can use the prefix N or G to represent a DBCS literal.

That is, you can specify a DBCS literal in either of these ways:

- N ' *dbcs characters* ' (provided that the compiler option NSYMBOL (DBCS) is in effect)
- G ' *dbcs characters* '

You can use quotation marks (") or apostrophes (') as the delimiters of a DBCS literal irrespective of the setting of the APOST or QUOTE compiler option. You must code the same opening and closing delimiter for a DBCS literal.

The shift-out (SO) control character X'0E' must immediately follow the opening delimiter, and the shift-in (SI) control character X'0F' must immediately precede the closing delimiter.

In addition to DBCS literals, you can use alphanumeric literals to specify any character in one of the supported code pages. However, any string of DBCS characters that is within an alphanumeric literal must be delimited by the SO and SI characters, and the DBCS compiler option must be in effect for the SO and SI characters to be recognized as shift codes.

You cannot continue an alphanumeric literal that contains DBCS characters. The length of a DBCS literal is likewise limited by the available space in Area B on a single source line. The maximum length of a DBCS literal is thus 28 double-byte characters.

An alphanumeric literal that contains DBCS characters is processed byte by byte, that is, with semantics appropriate for single-byte characters, except when it is converted explicitly or implicitly to national data representation, as for example in an assignment to or comparison with a national data item.

#### **related tasks**

[“Using figurative constants” on page 24](#)

**related references**

[“DBCS” on page 301](#)

[“NSYMBOL” on page 319](#)

[“APOST/QUOTE” on page 289](#)

DBCS literals (*Enterprise COBOL for z/OS Language Reference*)

## Testing for valid DBCS characters

The Kanji class test tests for valid Japanese graphic characters. This testing includes Katakana, Hiragana, Roman, and Kanji character sets.

The Kanji class test is done by checking characters for the range X'41' through X'7E' in the first byte and X'41' through X'FE' in the second byte, plus the space character X'4040'.

The DBCS class test tests for valid graphic characters for the code page.

The DBCS class test is done by checking characters for the range X'41' through X'FE' in both the first and second byte of each character, plus the space character X'4040'.

**related tasks**

[“Coding conditional expressions” on page 93](#)

**related references**

Class condition (*Enterprise COBOL for z/OS Language Reference*)

## Processing alphanumeric data items that contain DBCS data

If you use byte-oriented operations (for example, STRING, UNSTRING, or reference modification) on an alphanumeric data item that contains DBCS characters, results are unpredictable. You should instead convert the item to a national data item before you process it.

That is, do these steps:

1. Convert the item to UTF-16 in a national data item by using a MOVE statement or the NATIONAL-OF intrinsic function.
2. Process the national data item as needed.
3. Convert the result back to an alphanumeric data item by using the DISPLAY-OF intrinsic function.

**related tasks**

[“Joining data items \(STRING\)” on page 101](#)

[“Splitting data items \(UNSTRING\)” on page 103](#)

[“Referring to substrings](#)

[of data items” on page 107](#)

[“Converting to or from national \(Unicode\) representation” on page 131](#)

---

## Chapter 8. Processing files

Reading and writing data is an essential part of every program. Your program retrieves information, processes it as you request, and then produces the results.

The source of the information and the target for the results can be one or more of the following items:

- Another program
- Direct-access storage device
- Magnetic tape
- Printer
- Terminal
- Card reader or punch

The information as it exists on an external device is in a physical record or block, a collection of information that is handled as a unit by the system during input or output operations.

Your COBOL program does not directly handle physical records. It processes logical records. A logical record can correspond to a complete physical record, part of a physical record, or to parts or all of one or more physical records. Your COBOL program handles logical records exactly as you have defined them.

In COBOL, a collection of logical records is a file, a sequence of pieces of information that your program can process.

### **related concepts**

[“File organization and input-output devices” on page 145](#)

### **related tasks**

[“Choosing file organization and access mode” on page 146](#)

[“Allocating files” on page 148](#)

[“Checking for input or output errors” on page 149](#)

---

## File organization and input-output devices

Depending on the input-output devices, your file organization can be sequential, line sequential, indexed, or relative. Decide on the file types and devices to be used when you design your program.

You have the following choices of file organization:

### **Sequential file organization**

The chronological order in which records are entered when a file is created establishes the arrangement of the records. Each record except the first has a unique predecessor record, and each record except the last has a unique successor record. Once established, these relationships do not change.

The access (record transmission) mode allowed for sequential files is sequential only.

### **Line-sequential file organization**

Line-sequential files are sequential files that reside in the z/OS UNIX file system and that contain only characters as data. Each record ends with a newline character.

The only access (record transmission) mode allowed for line-sequential files is sequential.

### **Indexed file organization**

Each record in the file contains a special field whose contents form the record key. The position of the key is the same in each record. The index component of the file establishes the logical arrangement of the file, an ordering by record key. The actual physical arrangement of the records in the file is not significant to your COBOL program.

An indexed file can also use alternate indexes in addition to the record key. These keys let you access the file using a different logical ordering of the records.

The access (record transmission) modes allowed for indexed files are sequential, random, or dynamic. When you read or write indexed files sequentially, the sequence is that of the key values.

### **Relative file organization**

Records in the file are identified by their location relative to the beginning of the file. The first record in the file has a relative record number of 1, the tenth record has a relative record number of 10, and so on.

The access (record transmission) modes allowed for relative files are sequential, random, or dynamic. When relative files are read or written sequentially, the sequence is that of the relative record number.

With IBM Enterprise COBOL for z/OS, requests to the operating system for the storage and retrieval of records from input-output devices are handled by the two access methods QSAM and VSAM, and the z/OS UNIX file system.

The device type upon which you elect to store your data could affect the choices of file organization available to you. Direct-access storage devices provide greater flexibility in the file organization options. Sequential-only devices limit organization options but have other characteristics, such as the portability of tapes, that might be useful.

### **Sequential-only devices**

Terminals, printers, card readers, and punches are called *unit-record devices* because they process one line at a time. Therefore, you must also process records one at a time sequentially in your program when it reads from or writes to unit-record devices.

On tape, records are ordered sequentially, so your program must process them sequentially. Use QSAM physical sequential files when processing tape files. The records on tape can be fixed length or variable length.

### **Direct-access storage devices**

Direct-access storage devices hold many records. The record arrangement of files stored on these devices determines the ways that your program can process the data. When using direct-access devices, you have greater flexibility within your program, because you can use several types of file organization:

- Sequential (VSAM or QSAM)
- Line sequential (z/OS UNIX)
- Indexed (VSAM)
- Relative (VSAM)

### **related tasks**

[“Allocating files” on page 148](#)

[Chapter 9, “Processing QSAM files,” on page 151](#)

[Chapter 10, “Processing VSAM files,” on page 173](#)

[Chapter 11, “Processing line-sequential files,” on page 199](#)

[“Choosing file organization and access mode” on page 146](#)

## **Choosing file organization and access mode**

---

There are several guidelines you can use to determine which file organization and access mode to use in an application.

Consider the following guidelines when choosing file organization:

- If an application accesses records (whether fixed-length or variable-length) only sequentially and does not insert records between existing records, a QSAM or VSAM sequential file is the simplest type.
- If you are developing an application for z/OS UNIX file system that sequentially accesses records that contain only printable characters and certain control characters, line-sequential files work best.

- If an application requires both sequential and random access (whether records are fixed length or variable length), a VSAM indexed file is the most flexible type.
- If an application inserts and deletes records randomly, a relative file works well.

Consider the following guidelines when choosing access mode:

- If a large percentage of a file is referenced or updated in an application, sequential access is faster than random or dynamic access.
- If a small percentage of records is processed during each run of an application, use random or dynamic access.

<b>Table 19. Summary of file organizations, access modes, and record formats of COBOL files</b>					
<b>File organization</b>	<b>Sequential access</b>	<b>Random access</b>	<b>Dynamic access</b>	<b>Fixed length</b>	<b>Variable length</b>
QSAM (physical sequential)	X			X	X
Line sequential	X			X <sup>1</sup>	X
VSAM sequential (ESDS)	X			X	X
VSAM indexed (KSDS)	X	X	X	X	X
VSAM relative (RRDS)	X	X	X	X	X
1. The data itself is in variable format but can be read into and written from COBOL fixed-length records.					

#### related references

“Format for coding input and output” on page 147

“Control characters in line-sequential files” on page 200

## Format for coding input and output

The following example shows the general format of input-output coding. Explanations of the user-supplied information are shown after the code.

```
IDENTIFICATION DIVISION.
ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT filename ASSIGN TO assignment-name (1) (2)
    ORGANIZATION IS org ACCESS MODE IS access (3) (4)
    FILE STATUS IS file-status (5)
DATA DIVISION.
FILE SECTION.
FD filename
01 recordname (6)
   nn . . . fieldlength & type (7) (8)
   nn . . . fieldlength & type
WORKING-STORAGE SECTION
01 file-status PICTURE 99.
PROCEDURE DIVISION.
    OPEN iomode filename (9)
    READ filename
    WRITE recordname
    CLOSE filename
STOP RUN.
```

The user-supplied information in the code above is described below:

**(1) *filename***

Any legal COBOL name. You must use the same file-name in the SELECT clause and in the FD entry, and in the READ, OPEN, and CLOSE statements. In addition, the file-name is required if you use the START or DELETE statements. This name is not necessarily the actual name of the data set as known to the system. Each file requires its own SELECT clause, FD entry, and input-output statements.

**(2) *assignment-name***

Any name you choose, provided that it follows COBOL and system naming rules. The name can be 1 - 30 characters long if it is a user-defined word, or 1 - 160 characters long if it is a literal. You code the *name* part of the *assignment-name* in a DD statement, in an ALLOCATE command (TSO), or as an environment variable (for example, in an export command) (z/OS UNIX).

**(3) *org***

The organization can be SEQUENTIAL, LINE SEQUENTIAL, INDEXED, or RELATIVE. This clause is optional for QSAM files.

**(4) *access***

The access mode can be SEQUENTIAL, RANDOM, or DYNAMIC. For sequential file processing, including line-sequential, you can omit this clause.

**(5) *file-status***

The COBOL file status key. You can specify the file status key as a two-character category alphanumeric or category national item, or as a two-digit zoned decimal (USAGE DISPLAY) or national decimal (USAGE NATIONAL) item.

**(6) *recordname***

The name of the record used in the WRITE or REWRITE statements.

**(7) *fieldlength***

The logical length of the field.

**(8) *type***

The record format of the file. If you break the record entry beyond the level-01 description, map each element accurately against the fields in the record.

**(9) *iomode***

The INPUT or OUTPUT mode. If you are only reading from a file, code INPUT. If you are only writing to a file, code OUTPUT or EXTEND. If you are both reading and writing, code I-O, except for organization LINE SEQUENTIAL.

**related tasks**

[Chapter 9, "Processing QSAM files," on page 151](#)

[Chapter 10, "Processing VSAM files," on page 173](#)

[Chapter 11, "Processing line-sequential files," on page 199](#)

## Allocating files

---

For any type of file (sequential, line sequential, indexed, or relative) in your z/OS or z/OS UNIX applications, you can define the external name with either a ddname or an environment-variable name. The external name is the name in the *assignment-name* of the ASSIGN clause.

If the file is in the z/OS UNIX file system, you can use either a DD definition or an environment variable to define the file by specifying its path name with the PATH keyword.

The environment-variable name must be uppercase. The allowable attributes for its value depend on the organization of the file being defined.

Because you can define the external name in either of two ways, the COBOL run time goes through the following steps to find the definition of the file:

1. If the ddname is explicitly allocated, it is used. The definition can be from a DD statement in JCL, an ALLOCATE command from TSO/E, or a user-initiated dynamic allocation.

2. If the ddname is not explicitly allocated and an environment variable of the same name is set, the value of the environment variable is used.

The file is dynamically allocated using the attributes specified by the environment variable. At a minimum, you must specify either the `PATH()` or `DSN()` option. All options and attributes must be in uppercase, except for the *path-name* suboption of the `PATH` option, which is case sensitive. You cannot specify a temporary data-set name in the `DSN()` option.

File status code 98 results from any of the following cases:

- The contents (including a value of null or all blanks) of the environment variable are not valid.
- The dynamic allocation of the file fails.
- The dynamic deallocation of the file fails.

The COBOL run time checks the contents of the environment variable at each `OPEN` statement. If a file with the same external name was dynamically allocated by a previous `OPEN` statement, and the contents of the environment variable have changed since that `OPEN`, the run time dynamically deallocates the previous allocation and reallocates the file using the options currently set in the environment variable. If the contents of the environment variable have not changed, the run time uses the current allocation.

3. If neither a ddname nor an environment variable is defined, the following steps occur:
  - a) If the allocation is for a QSAM file and the `CBLQDA` runtime option is in effect, `CBLQDA` dynamic allocation processing takes place for those eligible files. This type of "implicit" dynamic allocation persists for the life of the run unit and cannot be reallocated.
  - b) Otherwise, the allocation fails.

The COBOL run time deallocates all dynamic allocations at run unit termination, except for implicit `CBLQDA` allocations.

#### **related tasks**

[“Setting and accessing environment variables” on page 436](#)

[“Defining and allocating QSAM files” on page 164](#)

[“Dynamically creating QSAM files” on page 161](#)

[“Allocating VSAM files” on page 192](#)

## **Checking for input or output errors**

---

After each input or output statement is performed, the file status key is updated with a value that indicates the success or failure of the operation.

Using a `FILE STATUS` clause, test the file status key after each input or output statement, and call an error-handling procedure if a nonzero file status code is returned. With VSAM files, you can use a second data item in the `FILE STATUS` clause to get additional VSAM status code information.

Another way of handling errors in input and output operations is to code `ERROR` (synonymous with `EXCEPTION`) declaratives.

#### **related tasks**

[“Handling errors in input](#)

[and output operations” on page 225](#)

[“Coding ERROR declaratives” on page 228](#)

[“Using file status keys” on page 229](#)



---

## Chapter 9. Processing QSAM files

Queued sequential access method (QSAM) files are unkeyed files in which the records are placed one after another, according to entry order.

Your program can process these files only sequentially, retrieving (with the READ statement) records in the same order as they are in the file. Each record is placed after the preceding record. To process QSAM files in your program, use COBOL language statements that:

- Identify and describe the QSAM files in the ENVIRONMENT DIVISION and the DATA DIVISION.
- Process the records in these files in the PROCEDURE DIVISION.

After you have created a record, you cannot change its length or its position in the file, and you cannot delete it. You can, however, update QSAM files on direct-access storage devices (using REWRITE), though not in the z/OS UNIX file system.

QSAM files can be on tape, direct-access storage devices (DASDs), unit-record devices, and terminals. QSAM processing is best for tables and intermediate storage.

You can also access byte-stream files in the z/OS UNIX file system using QSAM. These files are binary byte-oriented sequential files with no record structure. The record definitions that you code in your COBOL program and the length of the variables that you read into and write from determine the amount of data transferred.

### related concepts

*z/OS DFSMS: Using Data Sets* (Access methods)

### related tasks

[“Defining QSAM files and records in COBOL” on page 151](#)

[“Coding input and output](#)

[statements for QSAM files” on page 160](#)

[“Handling errors in QSAM files” on page 163](#)

[“Working with QSAM files” on page 163](#)

[“Accessing z/OS UNIX files](#)

[using QSAM” on page 170](#)

[“Processing QSAM ASCII files on tape” on page 171](#)

---

## Defining QSAM files and records in COBOL

Use the FILE-CONTROL entry to define the files in a COBOL program as QSAM files, and to associate the files with their external file-names.

An *external file-name* (a ddname or environment variable name) is the name by which a file is known to the operating system. In the following example, COMMUTER-FILE-MST is your program's name for the file; COMMUTR is the external name:

```
FILE-CONTROL.  
  SELECT COMMUTER-FILE-MST  
  ASSIGN TO S-COMMUTR  
  ORGANIZATION IS SEQUENTIAL  
  ACCESS MODE IS SEQUENTIAL.
```

The ASSIGN clause *name* can include an S- before the external name to document that the file is a QSAM file. Both the ORGANIZATION and ACCESS MODE clauses are optional.

### related tasks

[“Establishing record formats” on page 152](#)

[“Setting block sizes” on page 158](#)

## Establishing record formats

In the FD entry in the DATA DIVISION, code the record format and indication of whether the records are blocked. In the associated record description entry or entries, specify the *record-name* and record length.

You can code a record format of F, V, S, or U in the RECORDING MODE clause. COBOL determines the record format from the RECORD clause or from the record descriptions associated with the FD entry for the file. If you want the records to be blocked, code the BLOCK CONTAINS clause in the FD entry.

The following example shows how the FD entry might look for a file that has fixed-length records:

```
FILE SECTION.  
FD  COMMUTER-FILE-MST  
   RECORDING MODE IS F  
   BLOCK CONTAINS 0 RECORDS  
   RECORD CONTAINS 80 CHARACTERS.  
01  COMMUTER-RECORD-MST.  
    05  COMMUTER-NUMBER      PIC  X(16).  
    05  COMMUTER-DESCRIPTION PIC  X(64).
```

A recording mode of S is not supported for files in the z/OS UNIX file system. The above example is appropriate for such a file.

### related concepts

[“Logical records” on page 152](#)

### related tasks

[“Requesting fixed-length format” on page 152](#)

[“Requesting variable-length format” on page 153](#)

[“Requesting spanned format” on page 155](#)

[“Requesting undefined format” on page 157](#)

[“Defining QSAM files and records in COBOL” on page 151](#)

### related references

[“FILE SECTION entries” on page 12](#)

## Logical records

COBOL uses the term *logical record* in a slightly different way than z/OS QSAM.

For format-V and format-S files, a QSAM logical record includes a 4-byte prefix in front of the user data portion of the record that is not included in the definition of a COBOL logical record.

For format-F and format-U files, and for byte-stream files in the z/OS UNIX file system, the definitions of QSAM logical record and COBOL logical record are identical.

In this information, *QSAM logical record* refers to the QSAM definition, and *logical record* refers to the COBOL definition.

### related references

[“Layout of format-F records” on page 153](#)

[“Layout of format-V records” on page 154](#)

[“Layout of format-S records” on page 156](#)

[“Layout of format-U records” on page 157](#)

## Requesting fixed-length format

Fixed-length records are in format F. Use RECORDING MODE F to explicitly request this format.

You can omit the RECORDING MODE clause. The compiler determines the recording mode to be F if the length of the largest level-01 record associated with the file is not greater than the block size coded in the BLOCK CONTAINS clause, and you take one of the following actions:

- Use the RECORD CONTAINS *integer* clause (format-1 RECORD clause) to indicate the length of the record in bytes.

When you use this clause, the file is always fixed format with record length *integer* even if there are multiple level-01 record description entries with different lengths associated with the file.

- Omit the `RECORD CONTAINS integer` clause, but code the same fixed size and no `OCCURS DEPENDING ON` clause for all level-01 record description entries associated with the file. This fixed size is the record length.

In an unblocked format-F file, the logical record is the same as the block.

In a blocked format-F file, the number of logical records in a block (the *blocking factor*) is constant for every block in the file except the last block, which might be shorter.

Files in the z/OS UNIX file system are never blocked.

#### **related concepts**

[“Logical records” on page 152](#)

#### **related tasks**

[“Requesting variable-length format” on page 153](#)

[“Requesting spanned format” on page 155](#)

[“Requesting undefined format” on page 157](#)


[“Establishing record formats” on page 152](#)

#### **related references**

[“Layout of format-F records” on page 153](#)

### ***Layout of format-F records***

The layout of format-F QSAM records is shown below.



#### **related concepts**

[“Logical records” on page 152](#)

#### **related tasks**

[“Requesting fixed-length format” on page 152](#)

*z/OS DFSMS: Using Data Sets* (Fixed-length record formats)

#### **related references**

[“Layout of format-V records” on page 154](#)

[“Layout of format-S records” on page 156](#)

[“Layout of format-U records” on page 157](#)

## **Requesting variable-length format**

Variable-length records can be in format V or format D. Format-D records are variable-length records on ASCII tape files. Format-D records are processed in the same way as format-V records.

Use `RECORDING MODE V` for both. You can omit the `RECORDING MODE` clause. The compiler determines the recording mode to be V if the largest level-01 record associated with the file is not greater than the block size set in the `BLOCK CONTAINS` clause, and you take one of the following actions:

- Use the `RECORD IS VARYING` clause (format-3 `RECORD` clause).

If you provide values for *integer-1* and *integer-2* (RECORD IS VARYING FROM *integer-1* TO *integer-2*), the maximum record length is the value coded for *integer-2* regardless of the lengths coded in the level-01 record description entries associated with the file. The integer sizes indicate the minimum and maximum record lengths in numbers of bytes regardless of the USAGE of the data items in the record.

If you omit *integer-1* and *integer-2*, the maximum record length is determined to be the size of the largest level-01 record description entry associated with the file.

- Use the RECORD CONTAINS *integer-1* TO *integer-2* clause (format-2 RECORD clause). Make *integer-1* and *integer-2* match the minimum length and the maximum length in bytes of the level-01 record description entries associated with the file. The maximum record length is the *integer-2* value.
- Omit the RECORD clause, but code multiple level-01 records (associated with the file) that are of different sizes or contain an OCCURS DEPENDING ON clause.

The maximum record length is determined to be the size of the largest level-01 record description entry associated with the file.

When you specify a READ INTO statement for a format-V file, the record size read for that file is used in the MOVE statement generated by the compiler. Consequently, you might not get the result you expect if the record just read does not correspond to the level-01 record description. All other rules of the MOVE statement apply. For example, when you specify a MOVE statement for a format-V record read in by the READ statement, the size of the record moved corresponds to its level-01 record description.

When you specify a READ statement for a format-V file followed by a MOVE of the level-01 record, the actual record length is not used. The program will attempt to move the number of bytes described by the level-01 record description. If this number exceeds the actual record length and extends outside the area addressable by the program, results are unpredictable. If the number of bytes described by the level-01 record description is shorter than the physical record read, truncation of bytes beyond the level-01 description occurs. To find the actual length of a variable-length record, specify *data-name-1* in format 3 of the RECORD clause of the File Definition (FD).

### related tasks

[“Requesting fixed-length format” on page 152](#)

[“Requesting spanned format” on page 155](#)

[“Requesting undefined format” on page 157](#)

[“Establishing record formats” on page 152](#)

### related references


[“FILE SECTION entries” on page 12](#)

[“Layout of format-V records” on page 154](#)

*Enterprise COBOL Migration Guide* (Moving from the VS COBOL II run time)

## Layout of format-V records

Format-V QSAM records have control fields that precede the data. The QSAM logical record length is determined by adding 4 bytes (for the control fields) to the record length defined in your program. However, you must not include these 4 bytes in the description of the record and record length.



### CC

The first 4 bytes of each block contain control information.

**LL** Represents 2 bytes designating the length of the block (including the **CC** field).

**BB** Represents 2 bytes reserved for system use.

**cc**

The first 4 bytes of each logical record contain control information.

**11** Represents 2 bytes designating the logical record length (including the **cc** field).

**bb** Represents 2 bytes reserved for system use.

The block length is determined as follows:

- Unblocked format-V records: CC + cc + the data portion
- Blocked format-V records: CC + the cc of each record + the data portion of each record

The operating system provides the control bytes when the file is written; the control byte fields do not appear in the description of the logical record in the DATA DIVISION of your program. COBOL allocates input and output buffers that are large enough to accommodate the control bytes. These control fields in the buffer are not available for you to use in your program. When variable-length records are written on unit record devices, control bytes are neither printed nor punched. They appear however on other external storage devices, as well as in buffer areas of storage. If you move V-mode records from an input buffer to a WORKING-STORAGE area, the records will be moved without the control bytes.

Files in the z/OS UNIX file system are never blocked.

**related concepts**

[“Logical records” on page 152](#)

**related tasks**

[“Requesting variable-length format” on page 153](#)

**related references**

[“Layout of format-F records” on page 153](#)

[“Layout of format-S records” on page 156](#)

[“Layout of format-U records” on page 157](#)

## Requesting spanned format

Spanned records are in format S. A *spanned record* is a QSAM logical record that can be contained in one or more physical blocks.

You can code RECORDING MODE S for spanned records in QSAM files that are assigned to magnetic tape or to direct access devices. Do not request spanned records for files in the z/OS UNIX file system. You can omit the RECORDING MODE clause. The compiler determines the recording mode to be S if the maximum record length (in bytes) plus 4 is greater than the block size set in the BLOCK CONTAINS clause.

For files with format S in your program, the compiler determines the maximum record length with the same rules as are used for format V. The length is based on your usage of the RECORD clause.

When creating files that contain format-S records and a record is larger than the remaining space in a block, COBOL writes a segment of the record to fill the block. The rest of the record is stored in the next block or blocks depending on its length. COBOL supports QSAM spanned records up to 32,760 bytes in length.

When retrieving files that have format-S records, a program can retrieve only complete records.

**Benefits of format-S files:** You can efficiently use external storage and still organize your files with logical record lengths by defining files with format-S records:

- You can set block lengths to efficiently use track capacities on direct access devices.
- You are not required to adjust the logical record lengths to device-dependent physical block lengths. One logical record can span two or more physical blocks.
- You have greater flexibility when you want to transfer logical records between direct access storage types.

You will, however, have additional overhead in processing format-S files.

**Format-S files and READ INTO:** When you specify a READ INTO statement for a format-S file, the compiler generates a MOVE statement that uses the size of the record that it just read for that file. If the record just read does not correspond to the level-01 record description, you might not get the result that you expect. All other rules of the MOVE statement apply.

#### **related concepts**

[“Logical records” on page 152](#)

[“Spanned blocked and unblocked files” on page 156](#)

#### **related tasks**

[“Requesting fixed-length format” on page 152](#)

[“Requesting variable-length format” on page 153](#)

[“Requesting undefined format” on page 157](#)

[“Establishing record formats” on page 152](#)

#### **related references**

[“FILE SECTION entries” on page 12](#)

[“Layout of format-S records” on page 156](#)

### ***Spanned blocked and unblocked files***

A spanned blocked QSAM file is made up of blocks, each containing one or more logical records or segments of logical records. A spanned unblocked file is made up of physical blocks, each containing one logical record or one segment of a logical record.

In a spanned blocked file, a logical record can be either fixed or variable in length, and its size can be smaller than, equal to, or larger than the physical block size. There are no required relationships between logical records and physical block sizes.

In a spanned unblocked file, the logical records can be either fixed or variable in length. When the physical block contains one logical record, the block length is determined by the logical record size. When a logical record has to be segmented, the system always writes the largest physical block possible. The system segments the logical record when the entire logical record cannot fit on a track.

#### **related concepts**

[“Logical records” on page 152](#)

#### **related tasks**

[“Requesting spanned format” on page 155](#)

### ***Layout of format-S records***

Spanned records are preceded by control fields, as explained below.



Each block is preceded by a 4-byte block descriptor field ('BDF' in the image above). There is only one block descriptor field at the beginning of each physical block.

Each segment of a record in a block is preceded by a 4-byte segment descriptor field ('SDF' in the image) even if the segment is the entire record. There is one segment descriptor field for each record segment in the block. The segment descriptor field also indicates whether the segment is the first, the last, or an intermediate segment.

You do not describe these fields in the DATA DIVISION, and the fields are not available for you to use in your COBOL program.

#### **related tasks**

[“Requesting spanned format” on page 155](#)

#### **related references**

[“Layout of format-F records” on page 153](#)

[“Layout of format-V records” on page 154](#)

[“Layout of format-U records” on page 157](#)

## Requesting undefined format

Format-U records have undefined or unspecified characteristics. With format U, you can process blocks that do not meet format-F or format-V specifications.

When you use format-U files, each block of storage is one logical record. A read of a format-U file returns the entire block as a record. A write to a format-U file writes a record out as a block. The compiler determines the recording mode to be U only if you code `RECORDING MODE U`.

It is recommended that you not use format U to update or extend a file that was written with a different record format. If you use format U to update a file that was written with a different format, the RECFM value in the data-set label could be changed or the data set could contain records written in different formats.

The record length is determined in your program based on how you use the RECORD clause:

- If you use the `RECORD CONTAINS integer` clause (format-1 RECORD clause), the record length is the *integer* value regardless of the lengths of the level-01 record description entries associated with the file. The integer size indicates the number of bytes in a record regardless of the USAGE of its data items.
- If you use the `RECORD IS VARYING` clause (format-3 RECORD clause), the record length is determined based on whether you code *integer-1* and *integer-2*.

If you code *integer-1* and *integer-2* (`RECORD IS VARYING FROM integer-1 TO integer-2`), the maximum record length is the *integer-2* value regardless of the lengths of the level-01 record description entries associated with the file. The integer sizes indicate the minimum and maximum record lengths in numbers of bytes regardless of the USAGE of the data items in the record.

If you omit *integer-1* and *integer-2*, the maximum record length is determined to be the size of the largest level-01 record description entry associated with the file.

- If you use the `RECORD CONTAINS integer-1 TO integer-2` clause (format-2 RECORD clause), with *integer-1* and *integer-2* matching the minimum length and the maximum length in bytes of the level-01 record description entries associated with the file, the maximum record length is the *integer-2* value.
- If you omit the RECORD clause, the maximum record length is determined to be the size of the largest level-01 record description entry associated with the file.

**Format-U files and READ INTO:** When you specify a `READ INTO` statement for a format-U file, the compiler generates a `MOVE` statement that uses the size of the record that it just read for that file. If the record just read does not correspond to the level-01 record description, you might not get the result that you expect. All other rules of the `MOVE` statement apply.

### related tasks

[“Requesting fixed-length format” on page 152](#)

[“Requesting variable-length format” on page 153](#)

[“Requesting spanned format” on page 155](#)

[“Establishing record formats” on page 152](#)


### related references

[“FILE SECTION entries” on page 12](#)

[“Layout of format-U records” on page 157](#)

## Layout of format-U records

With format-U, each block of external storage is handled as a logical record. There are no record-length or block-length fields.



**related concepts**

[“Logical records” on page 152](#)

**related tasks**

[“Requesting undefined format” on page 157](#)

**related references**

[“Layout of format-F records” on page 153](#)

[“Layout of format-V records” on page 154](#)

[“Layout of format-S records” on page 156](#)

## Setting block sizes

In COBOL, you establish the size of a physical record by using the `BLOCK CONTAINS` clause. If you omit this clause, the compiler assumes that the records are not blocked.

Blocking QSAM files on tape and disk can enhance processing speed and minimize storage requirements. You can block files in the z/OS UNIX file system, PDSE members, and spooled data sets, but doing so has no effect on how the system stores the data.

If you set the block size explicitly in the `BLOCK CONTAINS` clause, the size must not be greater than the maximum block size for the device. If you specify the `CHARACTERS` phrase of the `BLOCK CONTAINS` clause, size must indicate the number of bytes in a record regardless of the `USAGE` of the data items in the record. The block size that is set for a format-F file must be an integral multiple of the record length.

If your program uses QSAM files on tape, use a physical block size of at least 12 to 18 bytes. Otherwise, the block will be skipped over when a parity check occurs during one of the following actions:

- Reading a block of records of fewer than 12 bytes
- Writing a block of records of fewer than 18 bytes

Larger blocks generally give you better performance. Blocks of only a few kilobytes are particularly inefficient; you should choose a block size of at least tens of kilobytes. If you specify record blocking and omit the block size, the system will pick a block size that is optimal for device utilization and for data transfer speed.

**Letting z/OS determine block size:** To maximize performance, do not explicitly set the block size for a blocked file in your COBOL source program. For new blocked data sets, it is simpler to allow z/OS to supply a system-determined block size. To use this feature, follow these guidelines:

- Code `BLOCK CONTAINS 0` in your source program or compile with the `BLOCK0` option. For details about `BLOCK0`, see [“BLOCK0” on page 293](#).
- Do not code `RECORD CONTAINS 0` in your source program.
- Do not code a `BLKSIZE` value in the JCL DD statement.

**Setting block size explicitly:** If you prefer to set a block size explicitly, your program will be most flexible if you follow these guidelines:

- Code `BLOCK CONTAINS 0` in your source program.
- Code a `BLKSIZE` value in the ddname definition (the JCL DD statement).

For extended-format data sets on z/OS, z/OS DFSMS adds a 32-byte block suffix to the physical record. If you specify a block size explicitly (using JCL or ISPF), do not include the size of this block suffix in the block size. This block suffix is not available for you to use in your program. z/OS DFSMS allocates the space used to read in the block suffix. However, when you calculate how many blocks of an extended-format data set will fit on a track of a direct-access device, you need to include the size of the block suffix in the block size.

If you specify a block size that is larger than 32760 directly in the `BLOCK CONTAINS` clause or indirectly with the use of `BLOCK CONTAINS n RECORDS`, the `OPEN` of the data set fails with file status code 90 unless you define the data set to be on tape.

For existing blocked data sets, it is simplest to:

- Code `BLOCK CONTAINS 0` in your source program.
- Not code a `BLKSIZE` value in the `ddname` definition.

When you omit the `BLKSIZE` from the `ddname` definition, the block size is automatically obtained by the system from the data-set label.

**Taking advantage of LBI:** You can improve the performance of tape data sets by using the large block interface (LBI) for large block sizes. When the LBI is available, the COBOL run time automatically uses this facility for those tape files for which you use system-determined block size. LBI is also used for those files for which you explicitly define a block size in JCL or a `BLOCK CONTAINS` clause. Use of the LBI allows block sizes to exceed 32760 if the tape device supports it.

The LBI is not used in all cases. An attempt to use a block size greater than 32760 in the following cases is diagnosed at compile time or results in a failure at `OPEN`:

- Spanned records
- `OPEN I-O`

Using a block size that exceeds 32760 might result in your not being able to read the tape on another system. A tape that you create with a block size greater than 32760 can be read only on a system that has a tape device that supports block sizes greater than 32760. If you specify a block size that is too large for the file, the device, or the operating system level, a runtime message is issued.

To limit a system-determined block size to 32760, do not specify `BLKSIZE` anywhere, and set one of the following items to 32760:

- The `BLKSZLIM` keyword on the `DD` statement for the data set
- `BLKSZLIM` for the data class by using the `BLKSZLIM` keyword (must be set by your systems programmer)
- A block-size limit for the system in the `DEVSUPxx` member of `SYS1.PARMLIB` by using the keyword `TAPEBLKSZLIM` (must be set by your systems programmer)

The block-size limit is the first nonzero value that the compiler finds by checking these items.

If no `BLKSIZE` or `BLKSZLIM` value is available from any source, the system limits `BLKSIZE` to 32760. You can then enable block sizes larger than 32760 in one of two ways:

- Specify a `BLKSZLIM` value greater than 32760 in the `DD` statement for the file and use `BLOCK CONTAINS 0` in your COBOL source.
- Specify a value greater than 32760 for the `BLKSIZE` in the `DD` statement or in the `BLOCK CONTAINS` clause in your COBOL source.

`BLKSZLIM` is device-independent.

**Block size and the DCB RECFM subparameter:** Under z/OS, you can code the S or T option in the DCB `RECFM` subparameter:

- Use the S (standard) option in the DCB `RECFM` subparameter for a format-F record with only standard blocks (ones that have no truncated blocks or unfilled tracks in the file, except for the last block of the file). S is also supported for records on tape. It is ignored if the records are not on DASD or tape.

Using this standard block option might improve input-output performance, especially for direct-access devices.

- The T (track overflow) option for QSAM files is no longer useful.

#### related tasks

[“Defining QSAM files and records in COBOL” on page 151](#)  
[z/OS DFSMS: Using Data Sets](#)

#### related references

[“FILE SECTION entries” on page 12](#)  
[“BLOCK0” on page 293](#)  
[BLOCK CONTAINS clause \(Enterprise COBOL for z/OS Language Reference\)](#)

## Coding input and output statements for QSAM files

---

You can code the following input and output statements to process a QSAM file or a byte-stream file in the z/OS UNIX file system using QSAM: OPEN, READ, WRITE, REWRITE, and CLOSE.

### OPEN

Initiates the processing of files. You can open all QSAM files as INPUT, OUTPUT, or EXTEND (depending on device capabilities).

You can also open QSAM files on direct access storage devices as I-O. You cannot open z/OS UNIX files as I-O; a file status of 37 results if you attempt to do so.

### READ

Reads a record from the file. With sequential processing, your program reads one record after another in the same order in which they were entered when the file was created.

### WRITE

Creates a record in the file. Your program writes new records to the end of the file.

### REWRITE

Updates a record. You cannot update a file in the z/OS UNIX file system using REWRITE.

### CLOSE

Releases the connection between the file and your program.

### related tasks

[“Opening QSAM files” on page 160](#)

[“Dynamically creating QSAM files” on page 161](#)

[“Adding records to QSAM files” on page 161](#)

[“Updating QSAM files” on page 161](#)

[“Writing QSAM files to a printer or spooled data set” on page 162](#)

[“Closing QSAM files” on page 162](#)

### related references

OPEN statement (*Enterprise COBOL for z/OS Language Reference*)

READ statement (*Enterprise COBOL for z/OS Language Reference*)

WRITE statement (*Enterprise COBOL for z/OS Language Reference*)

REWRITE statement (*Enterprise COBOL for z/OS Language Reference*)

CLOSE statement (*Enterprise COBOL for z/OS Language Reference*)

File status key (*Enterprise COBOL for z/OS Language Reference*)

## Opening QSAM files

Before a program can use any READ, WRITE, or REWRITE statements to process records in a file, it must first open the file by using an OPEN statement.

An OPEN statement works if both of the following conditions are true:

- The file is available or has been dynamically allocated.
- The *fixed file attributes* coded in the ddname definition or the data-set label for the file match the attributes coded for that file in the SELECT clause and FD entry.

Mismatches in the file-organization attributes, code set, maximum record size, or record format (fixed or variable) result in file status code 39, and the failure of the OPEN statement. Mismatches in maximum record size and record format are not errors when opening files in the z/OS UNIX file system.

For fixed-length QSAM files, if you code RECORD CONTAINS 0 in the FD entry, the record size attributes are not in conflict. The record size is taken from the DD statement or the data-set label, and the OPEN statement is successful.

Code CLOSE WITH LOCK so that the file cannot be opened again while the program is running.

Use the REVERSED option of the OPEN statement to process tape files in reverse order. The file is positioned at the end, and READ statements read the data records in reverse order, starting with the last record. The REVERSED option is supported only for files that have fixed-length records.

#### **related tasks**

[“Dynamically creating QSAM files” on page 161](#)

[“Ensuring that file attributes match your program” on page 167](#)

#### **related references**

OPEN statement (*Enterprise COBOL for z/OS Language Reference*)

## **Dynamically creating QSAM files**

Sometimes a QSAM file is unavailable on the operating system, but a COBOL program specifies that the file be created. Under certain circumstances, the file is created for you dynamically.

A QSAM file is considered to be *available* on z/OS when it has been identified to the operating system using a valid DD statement, an export command for an environment variable, or a TSO ALLOCATE command. Otherwise the file is *unavailable*.

Note that a DD statement with a misspelled ddname is equivalent to a missing DD statement, and an environment variable with a value that is not valid is equivalent to an unset variable.

The QSAM file is implicitly created if you use the runtime option CBLQDA and one of the following circumstances exists:

- An optional file is being opened as EXTEND or I-O.

*Optional files* are files that are not necessarily available each time the program is run. You define a file that is being opened in INPUT, I-O, or EXTEND mode as optional by coding the SELECT OPTIONAL clause in the FILE-CONTROL paragraph.

- The file is being opened for OUTPUT, regardless of the OPTIONAL phrase.

The file is allocated with the system default attributes established at your installation and the attributes coded in the SELECT clause and FD entry in your program.

Do not confuse this implicit allocation mechanism with the explicit dynamic allocation of files by means of environment variables. Explicit dynamic allocation requires that a valid environment variable be set. CBLQDA support is used only when the QSAM file is unavailable as defined above, which includes no valid environment variable being set.

Under z/OS, files created using the CBLQDA option are temporary data sets and do not exist after the program has run.

#### **related tasks**

[“Opening QSAM files” on page 160](#)

## **Adding records to QSAM files**

To add to a QSAM file, open the file as EXTEND and use the WRITE statement to add records immediately after the last record in the file.

To add records to a file opened as I-O, you must first close the file and open it as EXTEND.

#### **related references**

READ statement (*Enterprise COBOL for z/OS Language Reference*)

WRITE statement (*Enterprise COBOL for z/OS Language Reference*)

## **Updating QSAM files**

You can update QSAM files only if they reside on direct access storage devices. You cannot update files in the z/OS UNIX file system.

Replace an existing record with another record of the same length by doing these steps:

1. Open the file as I-O.
2. Use REWRITE to update an existing record. (The last file processing statement before REWRITE must have been a successful READ statement.)

You cannot open as I-O an extended format data set that you allocate in compressed format.

#### related references

REWRITE statement (*Enterprise COBOL for z/OS Language Reference*)

## Writing QSAM files to a printer or spooled data set

COBOL provides language statements to control the size of a printed page and control the vertical positioning of records.

**Controlling the page size:** Use the LINAGE clause of the FD entry to control the size of your printed page: the number of lines in the top and bottom margins and in the footing area of the page. When you use the LINAGE clause, COBOL handles the file as if you had also requested the ADV compiler option.

If you use the LINAGE clause in combination with WRITE BEFORE|AFTER ADVANCING *nn* LINES, be careful about the values you set. With the ADVANCING *nn* LINES phrase, COBOL first calculates the sum of LINAGE-COUNTER plus *nn*. Subsequent actions depend on the size of *nn*. The END-OF-PAGE imperative phrase is performed after the LINAGE-COUNTER is increased. Consequently, the LINAGE-COUNTER could be pointing to the next logical page instead of to the current footing area when the END-OF-PAGE phrase is performed.

AT END-OF-PAGE or NOT AT END-OF-PAGE imperative phrases are performed only if the write operation completes successfully. If the write operation is unsuccessful, control is passed to the end of the WRITE statement, and all conditional phrases are omitted.

**Controlling the vertical positioning of records:** Use the WRITE ADVANCING statement to control the vertical positioning of each record you write on a printed page.

BEFORE ADVANCING prints the record before the page is advanced. AFTER ADVANCING prints the record after the page is advanced.

Specify the number of lines the page is advanced with an integer (or an *identifier* with a *mnemonic-name*) following ADVANCING. If you omit the ADVANCING phrase from a WRITE statement, the effect is as if you had coded:

```
AFTER ADVANCING 1 LINE
```

#### related references

WRITE statement (*Enterprise COBOL for z/OS Language Reference*)

## Closing QSAM files

Use the CLOSE statement to disconnect your program from a QSAM file. If you try to close a file that is already closed, you will get a logic error.

If you do not close a QSAM file, the file is automatically closed for you under the following conditions:

- When the run unit ends normally, the run time closes all open files that are defined in any COBOL programs in the run unit.
- If the run unit ends abnormally and the TRAP(ON) runtime option is in effect, the run time closes all open files that are defined in any COBOL programs in the run unit.
- When Language Environment condition handling has completed and the application resumes in a routine other than where the condition occurred, the run time closes all open files that are defined in any COBOL programs in the run unit that might be called again and reentered.

You can change the location where the program resumes running (after a condition is handled) by moving the resume cursor with the Language Environment CEEMRCR callable service or by using language constructs such as a C longjmp.

- When you use CANCEL for a COBOL subprogram, the run time closes any open nonexternal files that are defined in that program.
- When a COBOL subprogram with the INITIAL attribute returns control, the run time closes any open nonexternal files that are defined in that program.
- When a thread of a multithreaded application ends, both external and nonexternal files that you opened from within that same thread are closed.

File status key data items in the DATA DIVISION are set when these implicit CLOSE operations are performed, but your EXCEPTION/ERROR declarative is not invoked.

**Errors:** If you open a QSAM file in a multithreaded application, you must close it from the same thread of execution from which the file was opened. Attempting to close the file from a different thread results in a close failure with file-status condition 90.

#### **related references**

CLOSE statement (*Enterprise COBOL for z/OS Language Reference*)

## Handling errors in QSAM files

---

When an input statement or output statement fails, COBOL does not take corrective action for you. You choose whether your program should continue running after a less-than-severe input or output error occurs.

COBOL provides these ways for you to intercept and handle certain QSAM input and output errors:

- End-of-file phrase (AT END)
- EXCEPTION/ERROR declarative
- FILE STATUS clause
- INVALID KEY phrase

If you do not code a FILE STATUS key or a declarative, serious QSAM processing errors will cause a message to be issued and a Language Environment condition to be signaled, which will cause an abend if you specify the runtime option ABTERMENC (ABEND).

If you use the FILE STATUS clause or the EXCEPTION/ERROR declarative, code EROPT=ACC in the DCB of the DD statement for that file. Otherwise, your COBOL program will not be able to continue processing after some error conditions.

If you use the FILE STATUS clause, be sure to check the key and take appropriate action based on its value. If you do not check the key, your program might continue, but the results will probably not be what you expected.

#### **related tasks**

[“Handling errors in input and output operations” on page 225](#)

## Working with QSAM files

---

To work with QSAM files in a COBOL program, you define and allocate the files, retrieve them, and ensure that their file attributes match those in the program. You can also use striped extended-format QSAM data sets to help improve performance.

#### **related tasks**

[“Defining and allocating QSAM files” on page 164](#)  
[“Retrieving QSAM files” on page 166](#)

[“Ensuring that file attributes match your program” on page 167](#)

[“Using striped extended-format QSAM data sets” on page 169](#)

#### related references

[“Allocation of buffers for QSAM files” on page 170](#)

## Defining and allocating QSAM files

You can define a QSAM file or a byte-stream file in the z/OS UNIX file system by using either a DD statement or an environment variable. Allocation of these files follows the general rules for the allocation of COBOL files.

When you use an environment variable, the name must be in uppercase. Specify the MVS data set in one of these ways:

- DSN(*data-set-name*)
- DSN(*data-set-name(member-name)*)

*data-set-name* must be fully qualified and cannot be a temporary data set (that is, it must not start with &).

**Restriction:** You cannot create a PDS or PDSE by using an environment variable.

You can optionally specify the following attributes in any order after DSN:

- A disposition value, one of: NEW, OLD, SHR, or MOD
- TRACKS or CYL
- SPACE(*nnn,mmm*)
- VOL(*volume-serial*)
- UNIT(*type*)
- KEEP, DELETE, CATALOG, or UNCATALOG
- STORCLAS(*storage-class*)
- MGMTCLAS(*management-class*)
- DATACLAS(*data-class*)

You can use either an environment variable or a DD definition to define a file in the z/OS UNIX file system. To do so, define one of the following items with a name that matches the external name in the ASSIGN clause:

- A DD allocation that uses PATH= '*absolute-path-name*' and FILEDATA=BINARY
- An environment variable with a value PATH(*pathname*), where *pathname* is an absolute path name (starting with /)

For compatibility with releases of COBOL before COBOL for OS/390 & VM Version 2 Release 2, you can also specify FILEDATA=TEXT when using a DD allocation for z/OS UNIX files, but this use is not recommended. To process text files in the z/OS UNIX file system, use LINE SEQUENTIAL organization. If you do use QSAM to process text files in the z/OS UNIX file system, you cannot use environment variables to define the files.

When you define a QSAM file, use the parameters as shown below.

Table 20. <b>QSAM file allocation</b>		
What you want to do	DD parameter to use	EV keyword to use
Name the file.	DSNAME (data-set name)	DSN
Select the type and quantity of input-output devices to be allocated for the file.	UNIT	UNIT for type only

Table 20. <b>QSAM file allocation</b> (continued)		
What you want to do	DD parameter to use	EV keyword to use
Give instructions for the volume in which the file will reside and for volume mounting.	VOLUME (or let the system choose an output volume)	VOL
Allocate the type and amount of space the file needs. (Only for direct-access storage devices.)	SPACE	SPACE for the amount of space (primary and secondary only); TRACKS or CYL for the type of space
Specify the type and some of the contents of the label associated with the file.	LABEL	n/a
Indicate whether you want to catalog, pass, or keep the file after the job step is completed.	DISP	NEW, OLD, SHR, MOD plus KEEP, DELETE, CATALOG, or UNCATALOG
Complete any data control block information that you want to add.	DCB subparameters	n/a

Some of the information about the QSAM file must always be coded in the FILE - CONTROL paragraph, the FD entry, and other COBOL clauses. Other information must be coded in the DD statement or environment variable for output files. For input files, the system can obtain information from the file label (for standard label files). If DCB information is provided in the DD statement for input files, it overrides information on the data-set label. For example, the amount of space allocated for a new direct-access device file can be set in the DD statement by the SPACE parameter.

You cannot express certain characteristics of QSAM files in the COBOL language, but you can code them in the DD statement for the file by using the DCB parameter. Use the subparameters of the DCB parameter to provide information that the system needs for completing the data set definition, including the following items:

- Block size (BLKSIZE=), if BLOCK CONTAINS 0 RECORDS was coded at compile time (recommended)
- Options to be executed if an error occurs in reading or writing a record
- TRACK OVERFLOW or standard blocks
- Mode of operation for a card reader or punch

DCB attributes coded for a DD DUMMY do not override those coded in the FD entry of your COBOL program.

[“Example: setting and accessing environment variables” on page 438](#)

#### **related tasks**

[“Setting block sizes” on page 158](#)

[“Defining QSAM files and records in COBOL” on page 151](#)

[“Allocating files” on page 148](#)

#### **related references**

[“Parameters for creating QSAM files” on page 166](#)

[MVS Program Management: User's Guide and Reference](#)

## Parameters for creating QSAM files

The following DD statement parameters are frequently used to create QSAM files.

---

```
DSNAME= [ dataset-name  
DSN=    dataset-name(member-name)  
        &&name  
        &&name(member-name) ]  
  
UNIT=   ( name[,unitcount] )  
  
VOLUME= ( [PRIVATE] [,RETAIN] [,vol-sequence-num] [,volume-count] ...  
VOL=    ... [ ,SER=(volume-serial[,volume-serial]...) ]  
        [ ,REF=[ dsname  
                *,ddname  
                *.stepname.ddname  
                *.stepname.proclist.ddname ] ] )  
  
SPACE=  ( [TRK  
          CYL  
          average-record-length ] , (primary-quantity[,secondary-quantity][,directory-quantity]))  
  
LABEL=  ( [Data-set-sequence-number,] [ NL  
                                       SL  
                                       SUL ] [ ,EXPDT= [ yyddd  
                                                         yyyy/ddd ] ] )  
        [ ,RETPD=xxxx ] )  
  
DISP=   ( [ NEW  
          MOD ] [ ,DELETE  
                ,KEEP  
                ,PASS  
                ,CATLG ] [ ,DELETE  
                          ,KEEP  
                          ,CATLG ] )  
  
DCB=    ( subparameter-list )
```

---

### related tasks

[“Defining and allocating QSAM files” on page 164](#)

## Retrieving QSAM files

You retrieve QSAM files, cataloged or not, by using job control statements or environment variables.

### Cataloged files

All data set information, such as volume and space, is stored in the catalog and file label. All you have to code are the data set name and a disposition. When you use a DD statement, this is the DSNAME parameter and the DISP parameter. When you use an environment variable, this is the DSN parameter and one of the parameters OLD, SHR, or MOD.

### Noncataloged files

Some information is stored in the file label, but you must code the unit and volume information, and the *dsname* and disposition.

If you are using JCL, and you created the file in the current job step or in a previous job step in the current job, you can refer to the previous DD statement for most of the data set information. You do, however, need to code DSNAME and DISP.

### related references

[“Parameters for retrieving QSAM files” on page 167](#)

## Parameters for retrieving QSAM files

The following DD statement parameters are used to retrieve previously created files.

---

```
DSNAME= [ dataset-name  
DSN=    dataset-name(member-name)  
        *.ddname  
        *.stepname.ddname  
        &&name  
        &&name(member-name) ]  
  
UNIT=   ( name[,unitcount] )  
  
VOLUME= ( subparameter-list )  
VOL=  
  
LABEL=  ( subparameter-list )  
  
DISP=   ( [ OLD  
           SHR  
           MOD ] [ ,DELETE  
                 ,KEEP  
                 ,PASS  
                 ,CATLG  
                 ,UNCATLG ] [ ,DELETE  
                               ,KEEP  
                               ,CATLG  
                               ,UNCATLG ] )  
  
DCB=    ( subparameter-list )
```

---

### related tasks

[“Retrieving QSAM files” on page 166](#)

## Ensuring that file attributes match your program

When the fixed file attributes in the DD statement or the data-set label and the attributes that are coded for that file in the SELECT clause and FD entry are not consistent, an OPEN statement in your program might not work.

Mismatches in the attributes for file organization, record format (fixed or variable), record length, or the code set result in file status code 39 and the failure of the OPEN statement. An exception exists for files in the z/OS UNIX file system: mismatches in record format and record length do not cause an error.

To prevent common file status 39 problems, follow the guidelines for processing existing or new files.

If you have not made a file available with a DD statement or a TSO ALLOCATE command, and your COBOL program specifies that the file be created, Enterprise COBOL dynamically allocates the file. When the file is opened, the file attributes that are coded in your program are used. You do not have to worry about file attribute conflicts.

Remember that information in the JCL or environment variable overrides information in the data-set label.

### related tasks

[“Processing existing files” on page 168](#)

[“Processing new files” on page 169](#)

[“Opening QSAM files” on page 160](#)

### related references

[“FILE SECTION entries” on page 12](#)

## Processing existing files

When your program processes an existing file, code the description of the file in your COBOL program to be consistent with the file attributes of the data set. Use the guidelines below to define the maximum record length.

*Table 21. Maximum record length of QSAM files*

For this format:	Specify this:
V or S	Exactly 4 bytes less than the length attribute of the data set
F	Same value as the length attribute of the data set
U	Same value as the length attribute of the data set

The easiest way to define variable-length (format-V) records in a program is to use the `RECORD IS VARYING FROM integer-1 TO integer-2` clause in the FD entry and set an appropriate value for *integer-2*. Express the integer sizes in bytes regardless of the underlying USAGE of the data items in the record. For example, assume that you determine that the length attribute of the data set is 104 bytes (LRECL=104). Remembering that the maximum record length is determined from the `RECORD IS VARYING` clause and not from the level-01 record descriptions, you could define a format-V file in your program with this code:

```
FILE SECTION.  
FD  COMMUTER-FILE-MST  
   RECORDING MODE IS V  
   RECORD IS VARYING FROM 4 TO 100 CHARACTERS.  
01  COMMUTER-RECORD-A   PIC X(4).  
01  COMMUTER-RECORD-B   PIC X(75).
```

Assume that the existing file in the previous example was format-U instead of format-V. If the 104 bytes are all user data, you could define the file in your program with this code:

```
FILE SECTION.  
FD  COMMUTER-FILE-MST  
   RECORDING MODE IS U  
   RECORD IS VARYING FROM 4 TO 104 CHARACTERS.  
01  COMMUTER-RECORD-A   PIC X(4).  
01  COMMUTER-RECORD-B   PIC X(75).
```

To define fixed-length records in your program, either code the `RECORD CONTAINS integer` clause, or omit this clause and code all level-01 record descriptions to be the same fixed size. In either case, use a value that equals the value of the length attribute of the data set. If you intend to use the same program to process different files at run time, and those files have differing fixed lengths, avoid record-length conflicts by coding `RECORD CONTAINS 0`.

If the existing file is an ASCII data set (DCB=(OPTCD=Q)), you must use the `CODE-SET` clause in the FD entry for the file.

### related tasks

- [“Processing new files” on page 169](#)
- [“Requesting fixed-length format” on page 152](#)
- [“Requesting variable-length format” on page 153](#)
- [“Requesting undefined format” on page 157](#)
- [“Opening QSAM files” on page 160](#)

### related references

- [“FILE SECTION entries” on page 12](#)

## Processing new files

If your COBOL program writes records to a new file that will be made available before the program runs, ensure that the file attributes in the DD statement, the environment variable, or the allocation do not conflict with the attributes in the program.

Usually you need to code only a minimum of parameters when predefining files. But if you need to explicitly set a length attribute for the data set (for example, you are using an ISPF allocation panel, or your DD statement is for a batch job in which the program uses `RECORD CONTAINS 0`), follow these guidelines:

- For format-V and format-S files, set a length attribute that is 4 bytes larger than that defined in the program.
- For format-F and format-U files, set a length attribute that is the same as that defined in the program.
- If you open the file as OUTPUT and write it to a printer, the compiler might add 1 byte to the record length to account for the carriage-control character, depending on the ADV compiler option and the language used in your program. In such a case, take the added byte into account when coding the LRECL value.

For example, if your program contains the following code for a file that has variable-length records, the LRECL value in the DD statement or allocation should be 54.

```
FILE SECTION.  
FD  COMMUTER-FILE-MST  
   RECORDING MODE IS V  
   RECORD CONTAINS 10 TO 50 CHARACTERS.  
01  COMMUTER-RECORD-A   PIC X(10).  
01  COMMUTER-RECORD-B   PIC X(50).
```

### related tasks

[“Processing existing files” on page 168](#)

[“Requesting fixed-length format” on page 152](#)

[“Requesting variable-length format” on page 153](#)

[“Requesting undefined format” on page 157](#)

[“Opening QSAM files” on page 160](#)

[“Dynamically creating QSAM files” on page 161](#)

### related references

[“FILE SECTION entries” on page 12](#)

## Using striped extended-format QSAM data sets

Striped extended-format QSAM data sets can benefit applications that process files that have large amounts of data or in which the time needed for I/O operations significantly affects overall performance.

*A striped extended-format QSAM data set* is an extended-format QSAM data set that is spread over multiple volumes, thus allowing parallel data access.

For you to gain the maximum benefit from using QSAM striped data sets, z/OS DFSMS needs to be able to allocate the required number of buffers above the 16 MB line. When you develop applications that contain files allocated to QSAM striped data sets, follow these guidelines:

- Avoid using a QSAM striped data set for a file that cannot have buffers allocated above the 16 MB line.
- Omit the RESERVE clause in the FILE-CONTROL entry for the file. Doing so lets z/OS DFSMS determine the optimum number of buffers for the data set.
- Compile your program with the DATA(31) and RENT compiler options, and make the program object AMODE 31.
- Specify the ALL31(ON) runtime option if the file is an EXTERNAL file with format-F, format-V, or format-U records.

Note that all striped data sets are extended-format data sets, but not all extended-format data sets are striped.

#### **related tasks**

*z/OS DFSMS: Using Data Sets*

## **Allocation of buffers for QSAM files**

z/OS DFSMS automatically allocates buffers for storing input and output for a QSAM file above or below the 16 MB line as appropriate for the file.

Most QSAM files have buffers allocated above the 16 MB line. Exceptions are:

- Programs running in AMODE 24.
- Programs compiled with the DATA(24) and RENT options.
- Programs compiled with the NORENT option.
- EXTERNAL files when the ALL31(OFF) runtime option is specified. To specify the ALL31(ON) runtime option, all programs in the run unit must be capable of running in 31-bit addressing mode.
- Files allocated to the TSO terminal.
- A file with format-S (spanned) records, if the file is any of the following ones:
  - An EXTERNAL file (even if ALL31(ON) is specified)
  - A file specified in a SAME RECORD AREA clause of the I-O-CONTROL paragraph
  - A blocked file that is opened I-O and updated using the REWRITE statement

#### **related concepts**

[“Storage and its addressability” on page 37](#)

#### **related tasks**

[“Using striped extended-format QSAM data sets” on page 169](#)

## **Accessing z/OS UNIX files using QSAM**

---

You can process byte-stream files in the z/OS UNIX file system as ORGANIZATION SEQUENTIAL files using QSAM. To do this, specify as the *assignment-name* in the ASSIGN clause either a ddname or an environment-variable name.

#### **ddname**

A DD allocation that identifies the file with the keywords PATH= and FILEDATA=BINARY

#### **Environment-variable name**

An environment variable that holds the runtime value of the z/OS UNIX file system path for the file

Observe the following restrictions:

- Spanned record format is not supported.
- OPEN I-O and REWRITE are not supported. If you attempt one of these operations, one of the following file-status conditions results:
  - 37 from OPEN I-O
  - 47 from REWRITE (because you could not have successfully opened the file as I-O)

#### **Usage notes**

- File status 39 (fixed file attribute conflict) is not enforced for either of the following types of conflicts:
  - Record-length conflict
  - Record-type conflict (fixed as opposed to variable)
- A READ returns the number of bytes of the maximum logical record size for the file except for the last record, which might be shorter.

For example, suppose that a file definition has level-01 record descriptions of 3, 5, and 10 bytes long, and you write the following three records: 'abc', 'defgh', and 'ijklmnopqr', in that order. The first READ of this file returns 'abcdefghij', the second READ returns 'klmnopqr', and the third READ results in the AT END condition.

For compatibility with releases of IBM COBOL before COBOL for OS/390 & VM Version 2 Release 2, you can also specify FILEDATA=TEXT when using a DD allocation for z/OS UNIX files, but this use is not recommended. To process text files in the z/OS UNIX file system, use LINE SEQUENTIAL organization. If you use QSAM to process text files in the z/OS UNIX file system, you cannot use environment variables to define the files.

#### related tasks

“Allocating files” on page 148

“Defining and allocating QSAM files” on page 164

*z/OS DFSMS: Using Data Sets* (Using HFS data sets)

## Processing QSAM ASCII files on tape

If your program processes a QSAM ASCII file, you must request the ASCII alphabet, define the record formats, and define the ddname (with JCL).

In addition, if your program processes signed numeric data items from ASCII files, define the numeric data as zoned decimal items with separate signs, that is, as USAGE DISPLAY and with the SEPARATE phrase of the SIGN clause.

The CODEPAGE compiler option has no effect on the code page used for conversions between ASCII and EBCDIC for ASCII tape support. For information about how CCSIDs used for the ASCII tape support are selected and what the default CCSIDs are, see the z/OS DFSMS documentation.

**Requesting the ASCII alphabet:** In the SPECIAL -NAMES paragraph, code STANDARD-1 for ASCII:

```
ALPHABET-NAME IS STANDARD-1
```

In the FD entry for the file, code:

```
CODE-SET IS ALPHABET-NAME
```

**Defining the record formats:** Process QSAM ASCII tape files with any of these record formats:

- Fixed length (format F)
- Undefined (format U)
- Variable length (format V)

If you use variable-length records, you cannot explicitly code format D; instead, code RECORDING MODE V. The format information is internally converted to D mode. D-mode records have a 4-byte record descriptor for each record.

**Defining the ddname:** Under z/OS, processing ASCII files requires special JCL coding. Code these subparameters of the DCB parameter in the DD statement:

**BUFOFF=[L|n]**

**L**

A 4-byte block prefix that contains the block length (including the block prefix)

**n**

The length of the block prefix:

- For input, from 0 through 99
- For output, either 0 or 4

Use this value if you coded BLOCK CONTAINS 0.

**BLKSIZE=*n***

***n***

The size of the block, including the length of the block prefix

**LABEL=[AL|AUL|NL]**

**AL**

American National Standard (ANS) labels

**AUL**

ANS and user labels

**NL**

No labels

**OPTCD=Q**

**Q**

This value is required for ASCII files and is the default if the file is created using Enterprise COBOL.

**related references**

*z/OS DFSMS: Using Data Sets* (Character data conversion)

## Chapter 10. Processing VSAM files

Virtual storage access method (VSAM) is an access method for files on direct-access storage devices. With VSAM you can load files, retrieve records from files, update files, and add, replace, and delete records in files.

VSAM processing has these advantages over QSAM:

- Protection of data against unauthorized access
- Compatibility across systems
- Independence of devices (no need to be concerned with block size and other control information)
- Simpler JCL (information needed by the system is provided in integrated catalogs)
- Ability to use indexed file organization or relative file organization

The following table shows how VSAM terms differ from COBOL terms and other terms that you might be familiar with.

<i>Table 22. Comparison of VSAM, COBOL, and non-VSAM terminology</i>		
<b>VSAM term</b>	<b>COBOL term</b>	<b>Similar non-VSAM term</b>
Data set	File	Data set
Entry-sequenced data set (ESDS)	Sequential file	QSAM data set
Key-sequenced data set (KSDS)	Indexed file	ISAM data set
Relative-record data set (RRDS)	Relative file	BDAM data set
Control interval		Block
Control interval size (CISZ)		Block size
Buffers (BUFNI/BUFND)		BUFNO
Access method control block (ACB)		Data control block (DCB)
Cluster (CL)		Data set
Cluster definition		Data-set allocation
AMP parameter of JCL DD statement		DCB parameter of JCL DD statement
Record size		Record length

The term *file* in this VSAM documentation refers to either a COBOL file or a VSAM data set.

If you have complex requirements or frequently use VSAM, see the VSAM publications for your operating system.

### **related concepts**

[“VSAM files” on page 174](#)

### **related tasks**

[“Defining VSAM file organization and records” on page 175](#)

[“Coding input and output](#)

[statements for VSAM files” on page 180](#)

[“Handling errors in VSAM files” on page 188](#)

[“Protecting VSAM files with a password” on page 188](#)

[“Working with VSAM data sets under z/OS and z/OS UNIX” on page 189](#)

[“Improving VSAM performance” on page 195](#)

## related references

*z/OS DFSMS: Using Data Sets*

*z/OS DFSMS Macro Instructions for Data Sets*

*z/OS DFSMS: Access Method Services for Catalogs*

[“Allocation of record areas for VSAM files” on page 195](#)

[“Extended addressability support” on page 196](#)

## VSAM files

The physical organization of VSAM data sets differs considerably from the organizations used by other access methods.

VSAM data sets are held in control intervals (CI) and control areas (CA). The size of the CI and CA is normally determined by the access method; and the way in which they are used is not visible to you.

You can use three types of file organization with VSAM:

### VSAM sequential file organization

(Also referred to as VSAM *ESDS* (*entry-sequenced data set*) organization.) In VSAM sequential file organization, the records are stored in the order in which they were entered.

VSAM entry-sequenced data sets are equivalent to QSAM sequential files. The order of the records is fixed.

### VSAM indexed file organization

(Also referred to as VSAM *KSDS* (*key-sequenced data set*) organization.) In a VSAM indexed file (KSDS), the records are ordered according to the collating sequence of an embedded prime key field, which you define. The prime key consists of one or more consecutive characters in the records. The prime key uniquely identifies the record and determines the sequence in which it is accessed with respect to other records. A prime key for a record might be, for example, an employee number or an invoice number.

### VSAM relative file organization

(Also referred to as VSAM fixed-length or variable-length *RRDS* (*relative-record data set*) organization.) A VSAM relative-record data set (RRDS) contains records ordered by their relative key. The *relative key* is the relative record number, which represents the location of the record relative to where the file begins. The relative record number identifies the fixed- or variable-length record.

In a VSAM fixed-length RRDS, records are placed in a series of fixed-length slots in storage. Each slot is associated with a relative record number. For example, in a fixed-length RRDS that contains 10 slots, the first slot has a relative record number of 1, and the tenth slot has a relative record number of 10.

In a VSAM variable-length RRDS, the records are ordered according to their relative record number. Records are stored and retrieved according to the relative record number that you set.

Throughout this information, the term *VSAM relative-record data set* (or *RRDS*) is used to mean both relative-record data sets with fixed-length records and with variable-length records, unless they need to be differentiated.

The following table compares the characteristics of the different types of VSAM data sets.

Table 23. Comparison of VSAM data-set types			
Characteristic	Entry-sequenced data set (ESDS)	Key-sequenced data set (KSDS)	Relative-record data set (RRDS)
Order of records	Order in which they are written	Collating sequence by key field	Order of relative record number
Access	Sequential	By key through an index	By relative record number, which is handled like a key

<i>Table 23. Comparison of VSAM data-set types (continued)</i>			
Characteristic	Entry-sequenced data set (ESDS)	Key-sequenced data set (KSDS)	Relative-record data set (RRDS)
Alternate indexes	Can have one or more alternate indexes, although not supported in COBOL	Can have one or more alternate indexes	Cannot have alternate indexes
Relative byte address (RBA) and relative record number (RRN) of a record	RBA cannot change.	RBA can change.	RRN cannot change.
Space for adding records	Uses space at the end of the data set	Uses distributed free space for inserting records and changing their lengths in place	For fixed-length RRDS, uses empty slots in the data set  For variable-length RRDS, uses distributed free space and changes the lengths of added records in place
Space from deleting records	You cannot delete a record, but you can reuse its space for a record of the same length.	Space from a deleted or shortened record is automatically reclaimed in a control interval.	Space from a deleted record can be reused.
Spanned records	Can have spanned records	Can have spanned records	Cannot have spanned records
Reuse as work file	Can be reused unless it has an alternate index, is associated with key ranges, or exceeds 123 extents per volume	Can be reused unless it has an alternate index, is associated with key ranges, or exceeds 123 extents per volume	Can be reused

#### related tasks

[“Specifying sequential organization for VSAM files” on page 176](#)

[“Specifying indexed organization for VSAM files” on page 176](#)

[“Specifying relative organization for VSAM files” on page 177](#)

[“Defining VSAM files” on page 190](#)

## Defining VSAM file organization and records

Use an entry in the FILE-CONTROL paragraph in the ENVIRONMENT DIVISION to define the file organization and access modes for the VSAM files in your COBOL program.

In the FILE SECTION of the DATA DIVISION, code a file description (FD) entry for the file. In the associated record description entry or entries, define the *record-name* and record length. Code the logical size of the records by using the RECORD clause.

**Important:** You can process VSAM data sets in Enterprise COBOL programs only after you define them by using access method services.

<i>Table 24. VSAM file organization, access mode, and record format</i>					
File organization	Sequential access	Random access	Dynamic access	Fixed length	Variable length
VSAM sequential (ESDS)	Yes	No	No	Yes	Yes

Table 24. **VSAM file organization, access mode, and record format** (continued)

File organization	Sequential access	Random access	Dynamic access	Fixed length	Variable length
VSAM indexed (KSDS)	Yes	Yes	Yes	Yes	Yes
VSAM relative (RRDS)	Yes	Yes	Yes	Yes	Yes

#### related tasks

[“Specifying sequential organization for VSAM files” on page 176](#)

[“Specifying indexed organization for VSAM files” on page 176](#)

[“Specifying relative organization for VSAM files” on page 177](#)

[“Specifying access modes for VSAM files” on page 178](#)

[“Defining record lengths for VSAM files” on page 179](#)

[“Using file status keys” on page 229](#)

[“Using VSAM status codes \(VSAM files only\)” on page 230](#)

[“Defining VSAM files” on page 190](#)

## Specifying sequential organization for VSAM files

Identify VSAM ESDS files in a COBOL program with the `ORGANIZATION IS SEQUENTIAL` clause. You can access (read or write) records in sequential files only sequentially.

After you place a record in the file, you cannot shorten, lengthen, or delete it. However, you can update (REWRITE) a record if the length does not change. New records are added at the end of the file.

The following example shows typical `FILE-CONTROL` entries for a VSAM sequential file (ESDS):

```
SELECT S-FILE
  ASSIGN TO SEQUENTIAL-AS-FILE
  ORGANIZATION IS SEQUENTIAL
  ACCESS IS SEQUENTIAL
  FILE STATUS IS FSTAT-CODE VSAM-CODE.
```

#### related concepts

[“VSAM files” on page 174](#)

## Specifying indexed organization for VSAM files

Identify a VSAM KSDS file in a COBOL program by using the `ORGANIZATION IS INDEXED` clause. Code a prime key for the record by using the `RECORD KEY` clause. You can also use alternate keys and an alternate index.

```
RECORD KEY IS data-name
```

In the example above, *data-name* is the name of the prime key field as you define it in the record description entry in the `DATA DIVISION`. The prime key data item can be class alphabetic, alphanumeric, DBCS, numeric, or national. If it has `USAGE NATIONAL`, the prime key can be category national, or can be a national-edited, numeric-edited, national decimal, or national floating-point data item. The collation of record keys is based on the binary value of the keys regardless of the class or category of the keys.

The following example shows the statements for a VSAM indexed file (KSDS) that is accessed dynamically. In addition to the primary key, `COMMUTER-NO`, an alternate key, `LOCATION-NO`, is specified:

```
SELECT I-FILE
  ASSIGN TO INDEXED-FILE
  ORGANIZATION IS INDEXED
  ACCESS IS DYNAMIC
```

```
RECORD KEY IS IFILE-RECORD-KEY
ALTERNATE RECORD KEY IS IFILE-ALTREC-KEY
FILE STATUS IS FSTAT-CODE VSAM-CODE.
```

### related concepts

[“VSAM files” on page 174](#)

### related tasks

[“Using alternate keys” on page 177](#)

[“Using an alternate index” on page 177](#)

### related references

RECORD KEY clause (*Enterprise COBOL for z/OS Language Reference*)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Using alternate keys

In addition to the primary key, you can code one or more alternate keys for a VSAM KSDS file. By using alternate keys, you can access an indexed file to read records in some sequence other than the prime-key sequence.

Alternate keys do not need to be unique. More than one record could be accessed if alternate keys are coded to allow duplicates. For example, you could access the file through employee department rather than through employee number.

You define the alternate key in your COBOL program with the `ALTERNATE RECORD KEY` clause:

```
ALTERNATE RECORD KEY IS data-name
```

In the example above, *data-name* is the name of the alternate key field as you define it in the record description entry in the `DATA DIVISION`. Alternate key data items, like prime key data items, can be class alphabetic, alphanumeric, DBCS, numeric, or national. The collation of alternate keys is based on the binary value of the keys regardless of the class or category of the keys.

## Using an alternate index

To use an alternate index for a VSAM KSDS file, you need to define a data set called the *alternate index* (AIX) by using access method services.

The AIX contains one record for each value of a given alternate key. The records are in sequential order by alternate-key value. Each record contains the corresponding primary keys of all records in the associated indexed files that contain the alternate-key value.

### related tasks

[“Creating alternate indexes” on page 190](#)

## Specifying relative organization for VSAM files

Identify VSAM RRDS files in a COBOL program by using the `ORGANIZATION IS RELATIVE` clause. Use the `RELATIVE KEY IS` clause to associate each logical record with its relative record number.

The following example shows a relative-record data set (RRDS) that is accessed randomly by the value in the relative key:

```
SELECT R-FILE
  ASSIGN TO RELATIVE-FILE
  ORGANIZATION IS RELATIVE
  ACCESS IS RANDOM
  RELATIVE KEY IS RFILE-RELATIVE-KEY
  FILE STATUS IS FSTAT-CODE VSAM-CODE.
```

You can use a randomizing routine to associate a key value in each record with the relative record number for that record. Although there are many techniques to convert a record key to a relative record number,

the most commonly used is the division/remainder technique. With this technique, you divide the key by a value equal to the number of slots in the data set to produce a quotient and remainder. When you add one to the remainder, the result is a valid relative record number.

Alternate indexes are not supported for VSAM RRDS.

#### **related concepts**

[“VSAM files” on page 174](#)

[“Fixed-length and variable-length RRDS” on page 178](#)

#### **related tasks**

[“Using variable-length RRDS” on page 178](#)

[“Defining VSAM files” on page 190](#)

## **Fixed-length and variable-length RRDS**

In an RRDS that has fixed-length records, each record occupies one slot. You store and retrieve records according to the relative record number of the slot. A variable-length RRDS does not have slots; instead, the free space that you define allows for more efficient record insertions.

When you load an RRDS that has fixed-length records, you have the option of skipping over slots and leaving them empty. When you load an RRDS that has variable-length records, you can skip over relative record numbers.

## **Using variable-length RRDS**

To use relative-record data sets (RRDS) that have variable-length records, you must use VSAM variable-length RRDS support.

Do these steps:

1. Define the file with the `ORGANIZATION IS RELATIVE` clause.
2. Use FD entries to describe the records with variable-length sizes.
3. Use the `NOSIMVRD` runtime option.
4. Define the VSAM file through access-method services as an RRDS.

#### **related tasks**

[“Defining VSAM files” on page 190](#)

#### **related references**

*z/OS DFSMS: Access Method Services for Catalogs*

## **Specifying access modes for VSAM files**

You can access records in VSAM sequential files only sequentially. You can access records in VSAM indexed and relative files in three ways: sequentially, randomly, or dynamically.

For sequential access, code `ACCESS IS SEQUENTIAL` in the `FILE-CONTROL` entry. Records in indexed files are then accessed in the order of the key field selected (either primary or alternate). Records in relative files are accessed in the order of the relative record numbers.

For random access, code `ACCESS IS RANDOM` in the `FILE-CONTROL` entry. Records in indexed files are then accessed according to the value you place in a key field. Records in relative files are accessed according to the value you place in the relative key.

For dynamic access, code `ACCESS IS DYNAMIC` in the `FILE-CONTROL` entry. Dynamic access is a mixed sequential-random access in the same program. Using dynamic access, you can write one program to perform both sequential and random processing, accessing some records in sequential order and others by their keys.

[“Example: using dynamic access with VSAM files” on page 179](#)

### related tasks

[“Reading records from a VSAM file” on page 185](#)

## Example: using dynamic access with VSAM files

Suppose that you have an indexed file of employee records, and the employee's hourly wage forms the record key.

If your program processes those employees who earn between \$15.00 and \$20.00 per hour and those who earn \$25.00 per hour and above, using dynamic access of VSAM files, the program would:

1. Retrieve the first record randomly (with a random-retrieval READ) based on the key of 1500.
2. Read sequentially (using READ NEXT) until the salary field exceeds 2000.
3. Retrieve the next record randomly, based on a key of 2500.
4. Read sequentially until the end of the file.

### related tasks

[“Reading records from a VSAM file” on page 185](#)

## Defining record lengths for VSAM files

You can define VSAM records to be fixed or variable in length. COBOL determines the record format from the RECORD clause and the record descriptions that are associated with the FD entry for a file.

Because the concept of blocking has no meaning for VSAM files, you can omit the BLOCK CONTAINS clause. The clause is syntax-checked, but it has no effect on how the program runs.

### related tasks

[“Defining fixed-length records” on page 179](#)

[“Defining variable-length records” on page 180](#)

*Enterprise COBOL Migration Guide*

### related references

[“FILE SECTION entries” on page 12](#)

## Defining fixed-length records

To define VSAM records as fixed length, use one of these coding options.

Table 25. <i>Definition of VSAM fixed-length records</i>			
RECORD clause	Clause format	Record length	Comments
Code RECORD CONTAINS <i>integer</i> .	1	Fixed in size with a length of <i>integer-3</i> bytes	The lengths of the level-01 record description entries associated with the file do not matter.
Omit the RECORD clause, but code all level-01 records that are associated with the file as the same size; and code none with an OCCURS DEPENDING ON clause.		The fixed size that you coded	

### related references

RECORD clause (*Enterprise COBOL for z/OS Language Reference*)

## Defining variable-length records

To define VSAM records as variable length, use one of these coding options.

Table 26. <i>Definition of VSAM variable-length records</i>			
RECORD clause	Clause format	Maximum record length	Comments
Code RECORD IS VARYING FROM <i>integer-6</i> TO <i>integer-7</i> .	3	<i>integer-7</i> bytes	The lengths of the level-01 record description entries associated with the file do not matter.
Code RECORD IS VARYING.	3	Size of the largest level-01 record description entry associated with the file	The compiler determines the maximum record length.
Code RECORD CONTAINS <i>integer-4</i> TO <i>integer-5</i> .	2	<i>integer-5</i> bytes	The minimum record length is <i>integer-4</i> bytes.
Omit the RECORD clause, but code multiple level-01 records that are associated with the file and are of different sizes or contain an OCCURS DEPENDING ON clause.		Size of the largest level-01 record description entry associated with the file	The compiler determines the maximum record length.

When you specify a READ INTO statement for a format-V file, the record size that is read for that file is used in the MOVE statement generated by the compiler. Consequently, you might not get the result you expect if the record read in does not correspond to the level-01 record description. All other rules of the MOVE statement apply. For example, when you specify a MOVE statement for a format-V record read in by the READ statement, the size of the record corresponds to its level-01 record description.

### related references

RECORD clause (*Enterprise COBOL for z/OS Language Reference*)

## Coding input and output statements for VSAM files

Use the COBOL statements shown below to process VSAM files.

### OPEN

To connect the VSAM data set to your COBOL program for processing.

### WRITE

To add records to a file or load a file.

### START

To establish the current location in the cluster for a READ NEXT statement.

START does not retrieve a record; it only sets the current record pointer.

### READ and READ NEXT

To retrieve records from a file.

### REWRITE

To update records.

### DELETE

To logically remove records from indexed and relative files only.

### CLOSE

To disconnect the VSAM data set from your program.

All of the following factors determine which input and output statements you can use for a given VSAM data set:

- Access mode (sequential, random, or dynamic)
- File organization (ESDS, KSDS, or RRDS)
- Mode of OPEN statement (INPUT, OUTPUT, I-O, or EXTEND)

The following table shows the possible combinations of statements and open modes for sequential files (ESDS). The X indicates that you can use a statement with the open mode shown at the top of the column.

<i>Table 27. I/O statements for VSAM sequential files</i>					
Access mode	COBOL statement	OPEN INPUT	OPEN OUTPUT	OPEN I-O	OPEN EXTEND
Sequential	OPEN	X	X	X	X
	WRITE		X		X
	START				
	READ	X		X	
	REWRITE			X	
	DELETE				
	CLOSE	X	X	X	X

The following table shows the possible combinations of statements and open modes that you can use with indexed (KSDS) files and relative (RRDS) files. The X indicates that you can use the statement with the open mode shown at the top of the column.

<i>Table 28. I/O statements for VSAM relative and indexed files</i>					
Access mode	COBOL statement	OPEN INPUT	OPEN OUTPUT	OPEN I-O	OPEN EXTEND
Sequential	OPEN	X	X	X	X
	WRITE		X		X
	START	X		X	
	READ	X		X	
	REWRITE			X	
	DELETE			X	
	CLOSE	X	X	X	X
Random	OPEN	X	X	X	
	WRITE		X	X	
	START				
	READ	X		X	
	REWRITE			X	
	DELETE			X	
	CLOSE	X	X	X	

Table 28. I/O statements for VSAM relative and indexed files (continued)

Access mode	COBOL statement	OPEN INPUT	OPEN OUTPUT	OPEN I - O	OPEN EXTEND
Dynamic	OPEN	X	X	X	
	WRITE		X	X	
	START	X		X	
	READ	X		X	
	REWRITE			X	
	DELETE			X	
	CLOSE	X	X	X	

The fields that you code in the FILE STATUS clause are updated by VSAM after each input-output statement to indicate the success or failure of the operation.

#### related concepts

[“File position indicator” on page 182](#)

#### related tasks

[“Opening a file \(ESDS, KSDS, or RRDS\)” on page 182](#)

[“Reading records from a VSAM file” on page 185](#)

[“Updating records in a VSAM file” on page 185](#)

[“Adding records to a VSAM file” on page 186](#)

[“Replacing records in a VSAM file” on page 187](#)

[“Deleting records from a VSAM file” on page 187](#)

[“Closing VSAM files” on page 187](#)

#### related references

File status key (*Enterprise COBOL for z/OS Language Reference*)

## File position indicator

The file position indicator marks the next record to be accessed for sequential COBOL requests. You do not set the file position indicator in your program. It is set by successful OPEN, START, READ, and READ NEXT statements.

Subsequent READ or READ NEXT requests use the established file position indicator location and update it.

The file position indicator is not used or affected by the output statements WRITE, REWRITE, or DELETE. The file position indicator has no meaning for random processing.

#### related tasks

[“Reading records from a VSAM file” on page 185](#)

## Opening a file (ESDS, KSDS, or RRDS)

Before you can use WRITE, START, READ, REWRITE, or DELETE statements to process records in a file, you must first open the file with an OPEN statement.

Whether a file is available or optional affects OPEN processing, file creation, and the resulting file status key. For example, if you open in EXTEND, I - O, or INPUT mode a nonexistent non-OPTIONAL file, the result is an OPEN error, and file status 35 is returned. If the file is OPTIONAL, however, the same OPEN statement returns file status 05, and, for open modes EXTEND and I - O, creates the file.

An OPEN operation works successfully only if you set fixed file attributes in the DD statement or data-set label for a file, and specify consistent attributes for the file in the SELECT clause and FD entries of your

COBOL program. Mismatches in the following items result in a file status key 39 and the failure of the OPEN statement:

- Attributes for file organization (sequential, relative, or indexed)
- Prime record key
- Alternate record keys
- Maximum record size
- Record type (fixed or variable)

How you code the OPEN statement for a VSAM file depends on whether the file is empty (a file that has never contained records) or loaded. For either type of file, your program should check the file status key after each OPEN statement.

#### **related tasks**

[“Opening an empty file” on page 183](#)

[“Opening a loaded file \(a file with records\)” on page 184](#)

#### **related references**

[“Statements to load records into a VSAM file” on page 184](#)

## **Opening an empty file**

To open a file that has never contained records (an empty file), use a form of the OPEN statement.

Depending on the type of file that you are opening, use one of the following statements:

- OPEN OUTPUT for ESDS files.
- OPEN OUTPUT or OPEN EXTEND for KSDS and RRDS files. (Either coding has the same effect.) If you coded the file for random or dynamic access and the file is optional, you can use OPEN I-O.

*Optional files* are files that are not necessarily available each time a program is run. You can define files opened in INPUT, I-O, or OUTPUT mode as optional by defining them with the SELECT OPTIONAL clause in the FILE-CONTROL paragraph.

**Initially loading a file sequentially:** Initially loading a file means writing records into the file for the first time. Doing so is not the same as writing records into a file from which all previous records have been deleted. To initially load a VSAM file:

1. Open the file.
2. Use sequential processing (ACCESS IS SEQUENTIAL). (Sequential processing is faster than random or dynamic processing.)
3. Use WRITE to add a record to the file.

Using OPEN OUTPUT to load a VSAM file significantly improves the performance of your program. Using OPEN I-O or OPEN EXTEND has a negative effect on the performance of your program.

When you load VSAM indexed files sequentially, you optimize both loading performance and subsequent processing performance, because sequential processing maintains user-defined free space. Future insertions will be more efficient.

With ACCESS IS SEQUENTIAL, you must write the records in ascending RECORD KEY order.

When you load VSAM relative files sequentially, the records are placed in the file in the ascending order of relative record numbers.

**Initially loading a file randomly or dynamically:** You can use random or dynamic processing to load a file, but they are not as efficient as sequential processing. Because VSAM does not support random or dynamic processing, COBOL has to perform some extra processing to enable you to use ACCESS IS RANDOM or ACCESS IS DYNAMIC with OPEN OUTPUT or OPEN I-O. These steps prepare the file for use and give it the status of a loaded file because it has been used at least once.

In addition to extra overhead for preparing files for use, random processing does not consider any user-defined free space. As a result, any future insertions might be inefficient. Sequential processing maintains user-defined free space.

When you are loading an extended-format VSAM data set, file status 30 will occur for the OPEN if z/OS DFSMS system-managed buffering sets the buffering to local shared resources (LSR). To successfully load the VSAM data set in this case, specify ACCBIAS=USER in the DD AMP parameter for the VSAM data set to bypass system-managed buffering.

**Loading a VSAM data set with access method services:** You can load or update a VSAM data set by using the access method services REPRO command. Use REPRO whenever possible.

#### related tasks

[“Opening a loaded file \(a file with records\)” on page 184](#)

#### related references

[“Statements to load records into a VSAM file” on page 184](#)

*z/OS DFSMS: Access Method Services for Catalogs (REPRO)*

## Statements to load records into a VSAM file

Use the statements shown below to load records into a VSAM file.

<i>Table 29. Statements to load records into a VSAM file</i>			
Division	ESDS	KSDS	RRDS
ENVIRONMENT DIVISION	SELECT ASSIGN FILE STATUS PASSWORD ACCESS MODE	SELECT ASSIGN ORGANIZATION IS INDEXED RECORD KEY ALTERNATE RECORD KEY FILE STATUS PASSWORD ACCESS MODE	SELECT ASSIGN ORGANIZATION IS RELATIVE RELATIVE KEY FILE STATUS PASSWORD ACCESS MODE
DATA DIVISION	FD entry	FD entry	FD entry
PROCEDURE DIVISION	OPEN OUTPUT OPEN EXTEND WRITE CLOSE	OPEN OUTPUT OPEN EXTEND WRITE CLOSE	OPEN OUTPUT OPEN EXTEND WRITE CLOSE

#### related tasks

[“Opening an empty file” on page 183](#)

[“Updating records in a VSAM file” on page 185](#)

## Opening a loaded file (a file with records)

To open a file that already contains records, use OPEN INPUT, OPEN I-O, or OPEN EXTEND.

If you open a VSAM entry-sequenced or relative-record file as EXTEND, the added records are placed after the last existing records in the file.

If you open a VSAM key-sequenced file as EXTEND, each record you add must have a record key higher than the highest record in the file.

**related tasks**

[“Opening an empty file” on page 183](#)

[“Working with VSAM data sets under z/OS and z/OS UNIX” on page 189](#)

**related references**

[“Statements to load records into a VSAM file” on page 184](#)

[z/OS DFSMS: Access Method Services for Catalogs](#)

## Reading records from a VSAM file

Use the READ statement to retrieve (READ) records from a file. To read a record, you must have opened the file INPUT or I-O. Your program should check the file status key after each READ.

You can retrieve records in VSAM sequential files only in the sequence in which they were written.

You can retrieve records in VSAM indexed and relative record files in any of the following ways:

**Sequentially**

According to the ascending order of the key you are using, the RECORD KEY or the ALTERNATE RECORD KEY, beginning at the current position of the file position indicator for indexed files, or according to ascending relative record locations for relative files

**Randomly**

In any order, depending on how you set the RECORD KEY or ALTERNATE RECORD KEY or the RELATIVE KEY before your READ request

**Dynamically**

Mixed sequential and random

With dynamic access, you can switch between reading a specific record directly and reading records sequentially, by using READ NEXT for sequential retrieval and READ for random retrieval (by key).

When you want to read sequentially, beginning at a specific record, use START before the READ NEXT statement to set the file position indicator to point to a particular record. When you code START followed by READ NEXT, the next record is read and the file position indicator is reset to the next record. You can move the file position indicator randomly by using START, but all reading is done sequentially from that point.

```
START file-name KEY IS EQUAL TO ALTERNATE-RECORD-KEY
```

When a direct READ is performed for a VSAM indexed file, based on an alternate index for which duplicates exist, only the first record in the data set (base cluster) with that alternate key value is retrieved. You need a series of READ NEXT statements to retrieve each of the data set records with the same alternate key. A file status code of 02 is returned if there are more records with the same alternate key value to be read; a code of 00 is returned when the last record with that key value has been read.

**related concepts**

[“File position indicator” on page 182](#)

**related tasks**

[“Specifying access modes for VSAM files” on page 178](#)

## Updating records in a VSAM file

To update a VSAM file, use these PROCEDURE DIVISION statements.

*Table 30. Statements to update records in a VSAM file*

Access method	ESDS	KSDS	RRDS
ACCESS IS SEQUENTIAL	OPEN EXTEND WRITE CLOSE  or  OPEN I-O READ REWRITE CLOSE	OPEN EXTEND WRITE CLOSE  or  OPEN I-O READ REWRITE DELETE CLOSE	OPEN EXTEND WRITE CLOSE  or  OPEN I-O READ REWRITE DELETE CLOSE
ACCESS IS RANDOM	Not applicable	OPEN I-O READ WRITE REWRITE DELETE CLOSE	OPEN I-O READ WRITE REWRITE DELETE CLOSE
ACCESS IS DYNAMIC (sequential processing)	Not applicable	OPEN I-O READ NEXT WRITE REWRITE START DELETE CLOSE	OPEN I-O READ NEXT WRITE REWRITE START DELETE CLOSE
ACCESS IS DYNAMIC (random processing)	Not applicable	OPEN I-O READ WRITE REWRITE DELETE CLOSE	OPEN I-O READ WRITE REWRITE DELETE CLOSE

#### related references

[“Statements to load records into a VSAM file” on page 184](#)

## Adding records to a VSAM file

Use the COBOL WRITE statement to add a record to a file without replacing any existing records. The record to be added must not be larger than the maximum record size that you set when you defined the file. Your program should check the file status key after each WRITE statement.

**Adding records sequentially:** Use ACCESS IS SEQUENTIAL and code the WRITE statement to add records sequentially to the end of a VSAM file that has been opened with either OUTPUT or EXTEND.

Sequential files are always written sequentially.

For indexed files, you must write new records in ascending key sequence. If you open the file `EXTEND`, the record keys of the records to be added must be higher than the highest primary record key on the file when you opened the file.

For relative files, the records must be in sequence. If you include a `RELATIVE KEY` data item in the `SELECT` clause, the relative record number of the record to be written is placed in that data item.

**Adding records randomly or dynamically:** When you write records to an indexed data set and `ACCESS IS RANDOM` or `ACCESS IS DYNAMIC`, you can write the records in any order.

## Replacing records in a VSAM file

To replace a record in a VSAM file, use `REWRITE` on a file that you opened as `I-O`. If the file was not opened as `I-O`, the record is not rewritten and the status key is set to 49. Check the file status key after each `REWRITE` statement.

For sequential files, the length of the replacement record must be the same as the length of the original record. For indexed files or variable-length relative files, you can change the length of the record you replace.

To replace a record randomly or dynamically, you do not have to first `READ` the record. Instead, locate the record you want to replace as follows:

- For indexed files, move the record key to the `RECORD KEY` data item, and then issue the `REWRITE`.
- For relative files, move the relative record number to the `RELATIVE KEY` data item, and then issue the `REWRITE`.

## Deleting records from a VSAM file

To remove an existing record from an indexed or relative file, open the file `I-O` and use the `DELETE` statement. You cannot use `DELETE` on a sequential file.

When you use `ACCESS IS SEQUENTIAL` or the file contains spanned records, your program must first read the record to be deleted. The `DELETE` then removes the record that was read. If the `DELETE` is not preceded by a successful `READ`, the deletion is not done and the status key value is set to 92.

When you use `ACCESS IS RANDOM` or `ACCESS IS DYNAMIC`, your program does not have to first read the record to be deleted. To delete a record, move the key of the record to be deleted to the `RECORD KEY` data item, and then issue the `DELETE`. Your program should check the file status key after each `DELETE` statement.

## Closing VSAM files

Use the `CLOSE` statement to disconnect your program from a VSAM file. If you try to close a file that is already closed, you will get a logic error. Check the file status key after each `CLOSE` statement.

If you do not close a VSAM file, the file is automatically closed for you under the following conditions:

- When the run unit ends normally, all open files defined in any COBOL programs in the run unit are closed.
- When the run unit ends abnormally, if the `TRAP(ON)` runtime option has been set, all open files defined in any COBOL programs in the run unit are closed.
- When Language Environment condition handling has completed and the application resumes in a routine other than where the condition occurred, open files defined in any COBOL programs in the run unit that might be called again and reentered are closed.

You can change the location where a program resumes after a condition is handled. To make this change, you can, for example, move the resume cursor with the `CEEMRCR` callable service or use language constructs such as a `C longjmp` statement.

- When you issue `CANCEL` for a COBOL subprogram, any open nonexternal files defined in that program are closed.

- When a COBOL subprogram with the INITIAL attribute returns control, any open nonexternal files defined in that program are closed.
- When a thread of a multithreaded application ends, both external and nonexternal files that were opened from within that same thread are closed.

File status key data items in the DATA DIVISION are set when these implicit CLOSE operations are performed, but your EXCEPTION/ERROR declarative is not invoked.

**Errors:** If you open a VSAM file in a multithreaded application, you must close it from the same thread of execution. Attempting to close the file from a different thread results in a close failure with file-status condition 90.

## Handling errors in VSAM files

---

When an input or output statement operation fails, COBOL does not perform corrective action for you.

All OPEN and CLOSE errors with a VSAM file, whether logical errors in your program or input/output errors on the external storage media, return control to your COBOL program even if you coded no DECLARATIVE and no FILE STATUS clause.

If any other input or output statement operation fails, you choose whether your program will continue running after a less-than-severe error.

COBOL provides these ways for you to intercept and handle certain VSAM input and output errors:

- End-of-file phrase (AT END)
- EXCEPTION/ERROR declarative
- FILE STATUS clause (file status key and VSAM status code)
- INVALID KEY phrase

You should define a status key for each VSAM file that you define in your program. Check the status key value after each input or output request, especially OPEN and CLOSE.

If you do not code a file status key or a declarative, serious VSAM processing errors will cause a message to be issued and a Language Environment condition to be signaled, which will cause an abend if you specify the runtime option ABTERMENC (ABEND).

### related tasks

[“Handling errors in input and output operations” on page 225](#)

[“Using VSAM status codes \(VSAM files only\)” on page 230](#)

### related references

*z/OS DFSMS Macro Instructions for Data Sets* (VSAM macro return and reason codes)

## Protecting VSAM files with a password

---

Although the preferred security mechanism on a z/OS system is RACF, Enterprise COBOL also supports using explicit passwords on VSAM files to prevent unauthorized access and update.

To use explicit passwords, code the PASSWORD clause in the FILE-CONTROL paragraph. Use this clause only if the catalog entry for the files includes a read or an update password:

- If the catalog entry includes a read password, you cannot open and access the file in a COBOL program unless you use the PASSWORD clause in the FILE-CONTROL paragraph and describe it in the DATA DIVISION. The *data-name* referred to must contain a valid password when the file is opened.
- If the catalog entry includes an update password, you can open and access it, but not update it, unless you code the PASSWORD clause in the FILE-CONTROL paragraph and describe it in the DATA DIVISION.

- If the catalog entry includes both a read password and an update password, specify the update password to both read and update the file in your program.

If your program only retrieves records and does not update them, you need only the read password. If your program loads files or updates them, you need to specify the update password that was cataloged.

For indexed files, the PASSWORD data item for the RECORD KEY must contain the valid password before the file can be successfully opened.

If you password-protect a VSAM indexed file, you must also password-protect each alternate index in order to be fully password protected. Where you place the PASSWORD clause is important because each alternate index has its own password. The PASSWORD clause must directly follow the key clause to which it applies.

## Example: password protection for a VSAM indexed file

The following example shows the COBOL code used for a VSAM indexed file that has password protection.

```

INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT LIBFILE
    ASSIGN TO PAYMAST
    ORGANIZATION IS INDEXED
    RECORD KEY IS EMPL-NUM
    PASSWORD IS BASE-PASS
    ALTERNATE RECORD KEY IS EMPL-PHONE
    PASSWORD IS PATH1-PASS

WORKING-STORAGE SECTION.
01 BASE-PASS          PIC X(8) VALUE "25BSREAD".
01 PATH1-PASS         PIC X(8) VALUE "25ATREAD".

```

## Working with VSAM data sets under z/OS and z/OS UNIX

Be aware of special coding considerations for VSAM files under z/OS and z/OS UNIX for access method services (IDCAMS) commands, environment variables, and JCL.

A VSAM file is *available* if all of the following conditions are true:

- You define it using access method services.
- You define it for your program by providing a DD statement, an environment variable, or an ALLOCATE command.
- It has previously contained a record.

A VSAM file is *unavailable* if it has never contained a record, even if you have defined the file.

You always get a return code of zero on completion of the OPEN statement for a VSAM sequential file.

Use the access method services REPRO command to empty a file. Deleting records in this manner resets the high-use relative byte address (RBA) of the file to zero. The file is effectively empty and appears to COBOL as if it never contained a record.

### related tasks

[“Defining files to the operating system” on page 8](#)

[“Defining VSAM files” on page 190](#)

[“Creating alternate indexes” on page 190](#)

[“Allocating VSAM files” on page 192](#)

[“Sharing VSAM files through RLS” on page 193](#)

## Defining VSAM files

You can process VSAM entry-sequenced, key-sequenced, and relative-record data sets in Enterprise COBOL only after you define them through access method services (IDCAMS).

A VSAM *cluster* is a logical definition for a VSAM data set and has one or two components:

- The data component of a VSAM cluster contains the data records.
- The index component of a VSAM key-sequenced cluster consists of the index records.

Use the `DEFINE CLUSTER` access-method services command to define VSAM data sets (clusters). This process includes creating an entry in an integrated catalog without any data transfer. Define the following information about the cluster:

- Name of the entry
- Name of the catalog to contain this definition and its password (can use default name)
- Organization (sequential, indexed, or relative)
- Device and volumes that the data set will occupy
- Space required for the data set
- Record size and control interval sizes (CISIZE)
- Passwords (if any) required for future access

Depending on what kind of data set is in the cluster, also define the following information for each cluster:

- For VSAM indexed data sets (KSDS), specify length and position of the prime key in the records.
- For VSAM fixed-length relative-record data sets (RRDS), specify the record size as greater than or equal to the maximum size COBOL record:

```
DEFINE CLUSTER NUMBERED  
RECORDSIZE(n,n)
```

If you define a data set in this way, all records are padded to the fixed slot size *n*. If you use the `RECORD IS VARYING ON data-name` form of the `RECORD` clause, a `WRITE` or `REWRITE` uses the length specified in `DEPENDING ON data-name` as the length of the record to be transferred by VSAM. This data is then padded to the fixed slot size. `READ` statements always return the fixed slot size in the `DEPENDING ON data-name`.

- For VSAM variable-length relative-record data sets (RRDS), specify the average size COBOL record expected and the maximum size COBOL record expected:

```
DEFINE CLUSTER NUMBERED  
RECORDSIZE(avg,m)
```

The average size COBOL record expected must be less than the maximum size COBOL record expected.

### related tasks

[“Creating alternate indexes” on page 190](#)

[“Allocating VSAM files” on page 192](#)

[“Specifying relative organization for VSAM files” on page 177](#)

### related references

*z/OS DFSMS: Access Method Services for Catalogs*

## Creating alternate indexes

An alternate index provides access to the records in a data set that uses more than one key. It accesses records in the same way as the prime index key of an indexed data set (KSDS).

When planning to use an alternate index, you must know:

- The type of data set (base cluster) with which the index will be associated
- Whether the keys will be unique or not unique
- Whether the index is to be password protected
- Some of the performance aspects of using alternate indexes

Because an alternate index is, in practice, a VSAM data set that contains pointers to the keys of a VSAM data set, you must define the alternate index and the alternate index path (the entity that establishes the relationship between the alternate index and the prime index). After you define an alternate index, make a catalog entry to establish the relationship (or path) between the alternate index and its base cluster. This path allows you to access the records of the base cluster through the alternate keys.

To use an alternate index, do these steps:

1. Define the alternate index by using the `DEFINE ALTERNATEINDEX` command. In it, specify these items:

- Name of the alternate index
- Name of its related VSAM indexed data set
- Location in the record of any alternate indexes and whether they are unique
- Whether alternate indexes are to be updated when the data set is changed
- Name of the catalog to contain this definition and its password (can use default name)

In your COBOL program, the alternate index is identified solely by the `ALTERNATE RECORD KEY` clause in the `FILE-CONTROL` paragraph. The `ALTERNATE RECORD KEY` definitions must match the definitions in the catalog entry. Any password entries that you cataloged should be coded directly after the `ALTERNATE RECORD KEY` phrase.

2. Relate the alternate index to the base cluster (the data set to which the alternate index gives you access) by using the `DEFINE PATH` command. In it, specify these items:

- Name of the path
- Alternate index to which the path is related
- Name of the catalog that contains the alternate index

The base cluster and alternate index are described by entries in the same catalog.

3. Load the VSAM indexed data set.
4. Build the alternate index by using (typically) the `BLDINDEX` command. Identify the input file as the indexed data set (base cluster) and the output file as the alternate index or its path. `BLDINDEX` reads all the records in the VSAM indexed data set (or base cluster) and extracts the data needed to build the alternate index.

Alternatively, you can use the runtime option `AIXBLD` to build the alternate index at run time. However, this option might adversely affect performance.

[“Example: entries for alternate indexes” on page 191](#)

#### **related tasks**

[“Using an alternate index” on page 177](#)

#### **related references**

*Language Environment Programming Reference* (AIXBLD (COBOL only))

## **Example: entries for alternate indexes**

The following example maps the relationships between the COBOL `FILE-CONTROL` entry and the `DD` statements or environment variables for a VSAM indexed file that has two alternate indexes.

Using JCL:

```
//MASTERA DD DSN=clustername,DISP=OLD (1)
```

```
//MASTERA1 DD DSN=DSNAME=path1,DISP=OLD (2)
//MASTERA2 DD DSN=DSNAME=path2,DISP=OLD (3)
```

Using environment variables:

```
export MASTERA=DSN(clustername),OLD (1)
export MASTERA=DSN(path1),OLD (2)
export MASTERA=DSN(path2),OLD (3)
FILE-CONTROL.
  SELECT MASTER-FILE ASSIGN TO MASTERA (4)
    RECORD KEY IS EM-NAME
    PASSWORD IS PW-BASE (5)
    ALTERNATE RECORD KEY IS EM-PHONE (6)
      PASSWORD IS PW-PATH1
    ALTERNATE RECORD KEY IS EM-CITY (7)
      PASSWORD IS PW-PATH2.
```

- (1) The base cluster name is *clustername*.
- (2) The name of the first alternate index path is *path1*.
- (3) The name of the second alternate index path is *path2*.
- (4) The ddname or environment variable name for the base cluster is specified with the ASSIGN clause.
- (5) Passwords immediately follow their indexes.
- (6) The key EM- PHONE relates to the first alternate index.
- (7) The key EM-CITY relates to the second alternate index.

#### related tasks

[“Creating alternate indexes” on page 190](#)

## Allocating VSAM files

You must predefine and catalog all VSAM data sets through the access method services DEFINE command. Most of the information about a VSAM data set is in the catalog, so you need to specify only minimal DD or environment variable information.

Allocation of VSAM files (indexed, relative, and sequential) follows the general rules for the allocation of COBOL files.

When you use an environment variable to allocate a VSAM file, the variable name must be in uppercase. Usually the input and data buffers are the only variables that you are concerned about. You must specify these options in the order shown, but no others:

1. DSN(*dsname*), where *dsname* is the name of the base cluster
2. OLD or SHR

The basic DD statement that you need for VSAM files and the corresponding export command are these:

```
//ddname DD DSN=dsname,DISP=SHR,AMP=AMORG
export evname="DSN(dsname),SHR"
```

In either case, *dsname* must be the same as the name used in the access method services DEFINE CLUSTER or DEFINE PATH command. DISP must be OLD or SHR because the data set is already cataloged. If you specify MOD when using JCL, the data set is treated as OLD.

AMP is a VSAM JCL parameter that supplements the information that the program supplies about the data set. AMP takes effect when your program opens the VSAM file. Any information that you set through the AMP parameter takes precedence over the information that is in the catalog or that the program supplies. The AMP parameter is required only under the following circumstances:

- You use a dummy VSAM data set. For example,

```
//ddname DD DUMMY,AMP=AMORG
```

- You request additional index or data buffers. For example,

```
//ddname DD DSN=VSAM.dsname,DISP=SHR,  
// AMP=('BUFNI=4,BUFND=8')
```

You cannot specify AMP if you allocate a VSAM data set with an environment variable.

For a VSAM base cluster, specify the same system-name (ddname or environment variable name) that you specify in the ASSIGN clause after the SELECT clause.

When you use alternate indexes in your COBOL program, you must specify not only a system-name (using a DD statement or environment variable) for the base cluster, but also a system-name for each alternate index path. No language mechanism exists to explicitly declare system-names for alternate index paths within the program. Therefore, you must adhere to the following guidelines for forming the system-name (ddname or environment variable name) for each alternate index path:

- Concatenate the base cluster name with an integer.
- Begin with 1 for the path associated with the first alternate record defined for the file in your program (ALTERNATE RECORD KEY clause of the FILE-CONTROL paragraph).
- Increment by 1 for the path associated with each successive alternate record definition for that file.

For example, if the system-name of a base cluster is ABCD, the system-name for the first alternate index path defined for the file in your program is ABCD1, the system-name for the second alternate index path is ABCD2, and so on.

If the length of the base cluster system-name together with the sequence number exceeds eight characters, the base cluster portion of the system-name is truncated on the right to reduce the concatenated result to eight characters. For example, if the system-name of a base cluster is ABCDEFGH, the system name of the first alternate index path is ABCDEFG1, the tenth is ABCDEF10, and so on.

#### **related tasks**

[“Allocating files” on page 148](#)

#### **related references**

[MVS Program Management: User's Guide and Reference](#)

## **Sharing VSAM files through RLS**

By using the VSAM JCL parameter RLS, you can specify record-level sharing with VSAM. Specifying RLS is the only way to request the RLS mode when running COBOL programs.

Use RLS=CR when consistent read protocols are required, and RLS=NRI when no read integrity protocols are required. You cannot specify RLS if you allocate your VSAM data set with an environment variable

#### **related tasks**

[“Preventing update problems with VSAM files in RLS mode” on page 194](#)

[“Handling errors in VSAM files in RLS mode” on page 194](#)

#### **related references**

[“Restrictions when using RLS” on page 194](#)

## Preventing update problems with VSAM files in RLS mode

When you open a VSAM data set in RLS mode for I-O (updates), the first READ causes an exclusive lock of the record regardless of the value of RLS (RLS=CR or RLS=NRI) that you specify.

If the COBOL file is defined as ACCESS RANDOM, VSAM releases the exclusive lock on the record after a WRITE or REWRITE statement is executed or a READ statement is executed for another record. When a WRITE or REWRITE is done, VSAM writes the record immediately.

However, if the COBOL file is defined as ACCESS DYNAMIC, VSAM does not release the exclusive lock on the record after a WRITE or REWRITE statement, nor after a READ statement, unless the I-O statement causes VSAM to move to another control interval (CI). As a result, if a WRITE or REWRITE was done, VSAM does not write the record until processing is moved to another CI and the lock is released. When you use ACCESS DYNAMIC, one way to cause the record to be written immediately, to release the exclusive lock immediately, or both, is to define the VSAM data set to allow only one record per CI.

Specifying RLS=CR locks a record and prevents an update to it until another READ is requested for another record. While a lock on the record being read is in effect, other users can request a READ for the same record, but they cannot update the record until the read lock is released. When you specify RLS=NRI, no lock will be in effect when a READ for input is executed. Another user might update the record.

The locking rules for RLS=CR can cause the application to wait for availability of a record lock. This wait might slow down the READ for input. You might need to modify your application logic to use RLS=CR. Do not use the RLS parameter for batch jobs that update nonrecoverable spheres until you are sure that the application functions correctly in a multiple-updater environment.

When you open a VSAM data set in RLS mode for INPUT or I-O processing, it is good to issue an OPEN or START *immediately* before a READ. If there is a delay between the OPEN or START and the READ, another user might add records before the record on which the application is positioned after the OPEN or START. The COBOL run time points explicitly to the beginning of the VSAM data set at the time when OPEN was requested, but another user might add records that would alter the true beginning of the VSAM data set if the READ is delayed.

## Restrictions when using RLS

When you use RLS mode, several restrictions apply to VSAM cluster attributes and to runtime options.

Be aware of these restrictions:

- The VSAM cluster attributes KEYRANGE and IMBED are not supported when you open a VSAM file.
- The VSAM cluster attribute REPLICATE is not recommended because the benefits are negated by the system-wide buffer pool and potentially large CF cache structure in the storage hierarchy.
- The AIXBLD runtime option is not supported when you open a VSAM file because VSAM does not allow an empty path to be opened. If you need the AIXBLD runtime option to build the alternate index data set, open the VSAM data set in non-RLS mode.
- The SIMVRD runtime option is not supported for VSAM files.
- Temporary data sets are not allowed.

## Handling errors in VSAM files in RLS mode

If your application accesses a VSAM data set in RLS mode, be sure to check the file status and VSAM feedback codes after *each* request.

If your application encounters "SMSVSAM server not available" while processing input or output, explicitly close the VSAM file before you try to open it again. VSAM generates return code 16 for such failures, and there is no feedback code. You can have COBOL programs check the first 2 bytes of the second file status area for VSAM return code 16. The COBOL run time generates message IGZ0205W and automatically closes the file if the error occurs during OPEN processing.

All other RLS mode errors return a VSAM return code of 4, 8, or 12.

### related tasks

“Using VSAM status codes  
(VSAM files only)” on page 230

## Allocation of record areas for VSAM files

For reentrant COBOL programs, the record areas for VSAM files are allocated above the 16 MB line by default.

If you specify the DATA(24) compiler option, the VSAM record areas and other dynamic storage areas are allocated in storage below 16 MB.

Programs that pass data in VSAM file records as CALL . . . USING parameters to AMODE 24 subprograms are impacted. You can recompile such programs with the DATA(24) compiler option, or use the Language Environment HEAP runtime option, to ensure that the records are addressable by the AMODE 24 programs.

## Improving VSAM performance

Your system programmer is most likely responsible for tuning the performance of COBOL and VSAM. As an application programmer, you can control the aspects of VSAM that are listed in the following table.

<i>Table 31. Methods for improving VSAM performance</i>		
Aspect of VSAM	What you can do	Rationale and comments
Invoking access methods service	Build your alternate indexes in advance, using IDCAMS.	
Buffering	For sequential access, request more data buffers; for random access, request more index buffers. Specify both BUFND and BUFNI if ACCESS IS DYNAMIC.  Avoid coding additional buffers unless your application will run interactively; then code buffers only when response-time problems arise that might be caused by delays in input and output.	The default is one index (BUFNI) and two data buffers (BUFND).
Loading records, using access methods services	Use the access methods service REPRO command when: <ul style="list-style-type: none"><li>• The target indexed data set already contains records.</li><li>• The input sequential data set contains records to be updated or inserted into the indexed data set.</li></ul> If you use a COBOL program to load the file, use OPEN OUTPUT and ACCESS SEQUENTIAL.	The REPRO command can update an indexed data set as fast or faster than any COBOL program under these conditions.
File access modes	For best performance, access records sequentially.	Dynamic access is less efficient than sequential access, but more efficient than random access. Random access results in increased EXCPs because VSAM must access the index for each request.

*Table 31. Methods for improving VSAM performance (continued)*

Aspect of VSAM	What you can do	Rationale and comments
Key design	Design the key in the records so that the high-order portion is relatively constant and the low-order portion changes often.	This method compresses the key best.
Multiple alternate indexes	Avoid using multiple alternate indexes.	Updates must be applied through the primary paths and are reflected through multiple alternate paths, perhaps slowing performance.
Relative file organization	Use VSAM fixed-length relative data sets rather than VSAM variable-length relative data sets.	Although not as space efficient, VSAM fixed-length relative data sets are more run time efficient than VSAM variable-length relative data sets.
Control interval sizes (CISZ)	<p>Provide your system programmer with information about the data access and future growth of your VSAM data sets. From this information, your system programmer can determine the best control interval size (CISZ) and FREESPACE size (FSPC).</p> <p>Choose proper values for CISZ and FSPC to minimize control area (CA) splits. You can diagnose the current number of CA splits by issuing the LISTCAT ALL command on the cluster, and then compress (using EXPORT, IMPORT, or REPRO) the cluster to omit all CA splits periodically.</p>	<p>VSAM calculates CISZ to best fit the direct-access storage device (DASD) usage algorithm, which might not, however, be efficient for your application.</p> <p>An average CISZ of 4K is suitable for most applications. A smaller CISZ means faster retrieval for random processing at the expense of inserts (that is, more CISZ splits and therefore more space in the data set). A larger CISZ results in the transfer of more data across the channel for each READ. This is more efficient for sequential processing, similar to a large OS BLKSIZE.</p> <p>Many control area (CA) splits are unfavorable for VSAM performance. The FREESPACE value can affect CA splits, depending on how the file is used.</p>

#### related tasks

“Specifying access modes for VSAM files” on page 178

*z/OS DFSMS: Using Data Sets* (Building a resource pool, Selecting the optimal percentage of free space)

#### related references

*z/OS DFSMS: Access Method Services for Catalogs*

## Extended addressability support

You can access VSAM data sets that are defined with the extended addressability attribute, use those VSAM data sets in COBOL programs without COBOL source changes, and maintain compatibility with previous versions of COBOL.

With extended addressability support, you can define larger VSAM data sets outside of COBOL. The 4 GB VSAM architectural limit for data set size imposed by using the 4-byte field for the relative byte address (RBA) is eliminated.

To use the extended addressability, the VSAM data set must be Storage Management Subsystem (SMS)-managed and be defined as extended format. The size limit for a VSAM data set is determined in either of the following ways:

- Control Interval (CI) size multiplied by 4 GB

- Volume size multiplied by 59

For example, a 4 KB CI size yields a maximum data set size of 16 TB, and a 32 KB CI size yields a maximum data set size of 128 TB. A 4 KB CI size is preferred by many applications for performance reasons. For extended-format data sets that grow beyond 4 GB, the processing time does not increase.

Extended addressability is also supported for programs compiled with earlier versions: VS COBOL II programs compiled with RES and any later compilers.

Extended addressability and extended format are not the same concept. Extended format is a prerequisite for extended addressability. Extended format is a technique that affects the way of storing count key data (CKD) in a 3390/3380 logical track. Extended format implements data striping and increases the performance and the reliability of an I/O operation. If a data set is allocated as an extended-format data set, 32 bytes are added to each physical block.

**Restriction:** Extended addressability was introduced for KSDS data sets in DFSMS/MVS V1.3. Since DFSMS/MVS V1.4, extended addressability is supported in record level sharing (RLS). With DFSMS/MVS V1.5, support for extended addressability is extended to all other VSAM record organizations.

#### **related tasks**

*z/OS DFSMS: Using Data Sets*



---

## Chapter 11. Processing line-sequential files

Line-sequential files reside in the z/OS UNIX file system and can contain both printable characters and control characters as data. Each record ends with an EBCDIC newline character (X'15'), which is not included in the record length.

Because line-sequential files are sequential, records are placed one after another according to entry order. Your program can process these files only sequentially, retrieving (with the READ statement) records in the same order as they are in the file. A new record is placed after the preceding record.

To process line-sequential files in a program, code COBOL language statements that:

- Identify and describe the files in the ENVIRONMENT DIVISION and the DATA DIVISION
- Process the records in the files in the PROCEDURE DIVISION

After you have created a record, you cannot change its length or its position in the file, and you cannot delete it.

### related tasks

[“Defining line-sequential files and records in COBOL” on page 199](#)

[“Allocating line-sequential files” on page 200](#)

[“Coding input-output statements for line-sequential files” on page 201](#)

[“Handling errors in line-sequential files” on page 204](#)

*UNIX System Services User's Guide*

---

## Defining line-sequential files and records in COBOL

Use the FILE-CONTROL paragraph in the ENVIRONMENT DIVISION to define the files in a COBOL program as line-sequential files, and to associate the files with the corresponding external file-names (ddnames or environment variable names).

An external file-name is the name by which a file is known to the operating system. In the following example, COMMUTER-FILE is the name that your program uses for the file; COMMUTR is the external name:

```
FILE-CONTROL.  
  SELECT COMMUTER-FILE  
  ASSIGN TO COMMUTR  
  ORGANIZATION IS LINE SEQUENTIAL  
  ACCESS MODE IS SEQUENTIAL  
  FILE STATUS IS ECODE.
```

The ASSIGN *assignment-name* clause must not include an organization field (S- or AS-) before the external name. The ACCESS phrase and the FILE STATUS clause are optional.

### related tasks

[“Describing the structure of a line-sequential file” on page 200](#)

[“Allocating line-sequential files” on page 200](#)

[“Coding input-output statements for line-sequential files” on page 201](#)

### related references

[“Control characters in line-sequential files” on page 200](#)

## Describing the structure of a line-sequential file

In the FILE SECTION, code a file description (FD) entry for the file. In the associated record description entry or entries, define the *record-name* and record length.

Code the logical size in bytes of the records by using the RECORD clause. Line-sequential files are stream files. Because of their character-oriented nature, the physical records are of variable length.

The following examples show how the FD entry might look for a line-sequential file:

### With fixed-length records:

```
FILE SECTION.  
FD  COMMUTER-FILE  
   RECORD CONTAINS 80 CHARACTERS.  
01  COMMUTER-RECORD.  
    05  COMMUTER-NUMBER          PIC  X(16).  
    05  COMMUTER-DESCRIPTION     PIC  X(64).
```

### With variable-length records:

```
FILE SECTION.  
FD  COMMUTER-FILE  
   RECORD VARYING FROM 16 TO 80 CHARACTERS.  
01  COMMUTER-RECORD.  
    05  COMMUTER-NUMBER          PIC  X(16).  
    05  COMMUTER-DESCRIPTION     PIC  X(64).
```

If you code the same fixed size and no OCCURS DEPENDING ON clause for any level-01 record description entries associated with the file, that fixed size is the logical record length. However, because blanks at the end of a record are not written to the file, the physical records might be of varying lengths.

### related tasks

[“Allocating line-sequential files” on page 200](#)

[“Coding input-output statements](#)

[for line-sequential files” on page 201](#)

### related references

Data division--file description entries

(*Enterprise COBOL for z/OS Language Reference*)

## Control characters in line-sequential files

A line-sequential file can contain control characters. Be aware though that if a line-sequential file contains a newline character (X'15'), the newline character will function as a record delimiter.

Control characters other than newline are treated as data and are part of the record.

## Allocating line-sequential files

You can allocate a line-sequential file in the z/OS UNIX file system by using either a DD statement or an environment variable. Allocation of line-sequential files follows the general rules for allocating COBOL files.

To allocate a line-sequential file, code a DD allocation or an environment variable that has a name that matches the external name in the ASSIGN clause:

- A DD allocation:
  - A DD statement that specifies PATH= '*absolute-path-name*'
  - A TSO allocation that specifies PATH( '*absolute-path-name*' )

You can optionally also specify these options:

- PATHOPTS

- PATHMODE
- PATHDISP
- An environment variable that has a value of PATH(*absolute-path-name*). No other values can be specified.

For example, to have your program use z/OS UNIX file /u/myfiles/commuterfile for a COBOL file that has an *assignment-name* of COMMUTR, you can use the following command:

```
export COMMUTR="PATH(/u/myfiles/commuterfile) "
```

#### related tasks

[“Allocating files” on page 148](#)

[“Defining line-sequential files and records in COBOL” on page 199](#)

#### related references

*MVS Program Management: User's Guide and Reference*

## Coding input-output statements for line-sequential files

---

Code the input and output statements shown below to process a line-sequential file.

### OPEN

To initiate the processing of a file.

You can open a line-sequential file as INPUT, OUTPUT, or EXTEND. You cannot open a line-sequential file as I-O.

### READ

To read a record from a file.

With sequential processing, a program reads one record after another in the same order in which the records were entered when the file was created.

### WRITE

To create a record in a file.

A program writes new records to the end of the file.

### CLOSE

To release the connection between a file and the program.

#### related tasks

[“Defining line-sequential files and records in COBOL” on page 199](#)

[“Describing the structure of a line-sequential file” on page 200](#)

[“Opening line-sequential files” on page 202](#)

[“Reading records from line-sequential files” on page 202](#)

[“Adding records to line-sequential files” on page 203](#)

[“Closing line-sequential files” on page 203](#)

[“Handling errors in line-sequential files” on page 204](#)

#### related references

OPEN statement (*Enterprise COBOL for z/OS Language Reference*)

READ statement (*Enterprise COBOL for z/OS Language Reference*)

WRITE statement (*Enterprise COBOL for z/OS Language Reference*)

CLOSE statement (*Enterprise COBOL for z/OS Language Reference*)

## Opening line-sequential files

Before your program can use any READ or WRITE statements to process records in a file, it must first open the file with an OPEN statement. An OPEN statement works if the file is available or has been dynamically allocated.

Code CLOSE WITH LOCK so that the file cannot be opened again while the program is running.

### related tasks

[“Reading records from line-sequential files” on page 202](#)

[“Adding records to line-sequential files” on page 203](#)

[“Closing line-sequential files” on page 203](#)

[“Allocating line-sequential files” on page 200](#)

### related references

OPEN statement (*Enterprise COBOL for z/OS Language Reference*)

CLOSE statement (*Enterprise COBOL for z/OS Language Reference*)

## Reading records from line-sequential files

To read from a line-sequential file, open the file and use the READ statement. Your program reads one record after another in the same order in which the records were entered when the file was created.

Characters in the file record are read one at a time into the record area until one of the following conditions occurs:

- The record delimiter (the EBCDIC newline character) is encountered.

The delimiter is discarded and the remainder of the record area is filled with spaces. (Record area is longer than the file record.)

- The entire record area is filled with characters.

If the next unread character is the record delimiter, it is discarded. The next READ reads from the first character of the next record. (Record area is the same length as the file record.)

Otherwise the next unread character is the first character to be read by the next READ. (Record area is shorter than the file record.)

- End-of-file is encountered.

The remainder of the record area is filled with spaces. (Record area is longer than the file record.)

### related tasks

[“Opening line-sequential files” on page 202](#)

[“Adding records to line-sequential files” on page 203](#)

[“Closing line-sequential files” on page 203](#)

[“Allocating line-sequential files” on page 200](#)

### related references

OPEN statement (*Enterprise COBOL for z/OS Language Reference*)

WRITE statement (*Enterprise COBOL for z/OS Language Reference*)

## Adding records to line-sequential files

To add to a line-sequential file, open the file as EXTEND and use the WRITE statement to add records immediately after the last record in the file.

Blanks at the end of the record area are removed, and the record delimiter is added. The characters in the record area from the first character up to and including the added record delimiter are written to the file as one record.

Records written to line-sequential files must contain only USAGE DISPLAY and DISPLAY-1 items. Zoned decimal data items must be unsigned or declared with the SEPARATE phrase of the SIGN clause if signed.

### related tasks

[“Opening line-sequential files” on page 202](#)

[“Reading records from line-sequential files” on page 202](#)

[“Closing line-sequential files” on page 203](#)

[“Allocating line-sequential files” on page 200](#)

### related references

OPEN statement (*Enterprise COBOL for z/OS Language Reference*)

WRITE statement (*Enterprise COBOL for z/OS Language Reference*)

## Closing line-sequential files

Use the CLOSE statement to disconnect your program from a line-sequential file. If you try to close a file that is already closed, you will get a logic error.

If you do not close a line-sequential file, the file is automatically closed for you under the following conditions:

- When the run unit ends normally.
- When the run unit ends abnormally, if the TRAP (ON) runtime option is set.
- When Language Environment condition handling is completed and the application resumes in a routine other than where the condition occurred, open files defined in any COBOL programs in the run unit that might be called again and reentered are closed.

You can change the location where the program resumes (after a condition is handled) by moving the resume cursor with the Language Environment CEEMRCR callable service or using HLL language constructs such as a C longjmp call.

File status codes are set when these implicit CLOSE operations are performed, but EXCEPTION/ERROR declaratives are not invoked.

### related tasks

[“Opening line-sequential files” on page 202](#)

[“Reading records from line-sequential files” on page 202](#)

[“Adding records to line-sequential files” on page 203](#)

[“Allocating line-sequential files” on page 200](#)

### related references

CLOSE statement (*Enterprise COBOL for z/OS Language Reference*)

## Handling errors in line-sequential files

---

When an input or output statement fails, COBOL does not take corrective action for you. You choose whether your program should continue running after an input or output statement fails.

COBOL provides these language elements for intercepting and handling certain line-sequential input and output errors:

- End-of-file phrase (AT END)
- EXCEPTION/ERROR declarative
- FILE STATUS clause

If you do not use one of these techniques, an error in processing input or output raises a Language Environment condition.

If you use the FILE STATUS clause, be sure to check the key and take appropriate action based on its value. If you do not check the key, your program might continue, but the results will probably not be what you expected.

### **related tasks**

[“Coding input-output statements for line-sequential files” on page 201](#)

[“Handling errors in input and output operations” on page 225](#)

---

## Chapter 12. Sorting and merging files

You can arrange records in a particular sequence by using a SORT or MERGE statement. You can mix SORT and MERGE statements in the same COBOL program.

**Note:** The SORT statement, sort processes, and sort restrictions that are described in this topic relate to the format 1 SORT statement only. For more information about sorting a table by using the format 2 SORT statement, see [“Sorting a table” on page 85](#).

### **SORT statement**

Accepts input (from a file or an internal procedure) that is not in sequence, and produces output (to a file or an internal procedure) in a requested sequence. You can add, delete, or change records before or after they are sorted.

### **MERGE statement**

Compares records from two or more sequenced files and combines them in order. You can add, delete, or change records after they are merged.

A program can contain any number of sort and merge operations. They can be the same operation performed many times or different operations. However, one operation must finish before another begins.

With Enterprise COBOL, your IBM licensed program for sorting and merging must be DFSORT or an equivalent. Where DFSORT is mentioned, you can use any equivalent sort or merge product.

COBOL programs that contain SORT or MERGE statements can reside above or below the 16 MB line.

The steps you take to sort or merge are generally as follows:

1. Describe the sort or merge file to be used for sorting or merging.
2. Describe the input to be sorted or merged. If you want to process the records before you sort them, code an input procedure.
3. Describe the output from sorting or merging. If you want to process the records after you sort or merge them, code an output procedure.
4. Request the sort or merge.
5. Determine whether the sort or merge operation was successful.

### **Restrictions:**

- You cannot run a COBOL program that contains SORT or MERGE statements under z/OS UNIX. This restriction includes BPXBATCH.
- You cannot use SORT or MERGE statements in programs compiled with the THREAD option. This includes programs that use object-oriented syntax and multithreaded applications, both of which require the THREAD option. In addition, the COBOL program that uses SORT or MERGE statements cannot call directly or indirectly other applications that require z/OS Unix System Services or applications that use multithreading. For example, the JVM uses both of them.
- You cannot use the DFSORT conventional technique. The conventional technique is used in the following cases:
  - The NOBLKSET option is specified. BLKSET is the default when invoking DFSORT.
  - Tape device is used for intermediate work storage.
  - L5 is used in the RECORD statement of DFSORT OPTION control. L5 specifies the average record length. Instead of using L5, the same can be specified by using the AVGLEN=n statement.

To assist migration of legacy COBOL programs, toleration runtime APARs PH20569(V2R2) and PH21261(V2R3/V2R4) are provided for programs running in AMODE 31. There is no toleration for AMODE 64. For details, see Using DFSORT option NOBLKSET (*Enterprise COBOL Migration Guide*).

**related concepts**

[“Sort and merge process” on page 206](#)

**related tasks**

[“Sorting](#)

[a table” on page 85](#)

[“Describing the sort or merge file” on page 206](#)

[“Describing the input to sorting or merging” on page 207](#)

[“Describing the output from sorting or merging” on page 209](#)

[“Requesting the sort or](#)

[merge” on page 212](#)

[“Determining whether the sort or merge was successful” on page 215](#)

[“Stopping a sort or merge operation prematurely” on page 216](#)

[“Improving sort performance with FASTSORT” on page 216](#)

[“Controlling sort behavior” on page 219](#)

*DFSORT Application Programming Guide*

**related references**

[“CICS SORT application](#)

[restrictions” on page 222](#)

[SORT statement \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

[MERGE statement \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## Sort and merge process

---

During the sorting of a file, all of the records in the file are ordered according to the contents of one or more fields (*keys*) in each record. You can sort the records in either ascending or descending order of each key.

If there are multiple keys, the records are first sorted according to the content of the first (or primary) key, then according to the content of the second key, and so on.

To sort a file, use the format 1 SORT statement.

During the merging of two or more files (which must already be sorted), the records are combined and ordered according to the contents of one or more keys in each record. You can order the records in either ascending or descending order of each key. As with sorting, the records are first ordered according to the content of the primary key, then according to the content of the second key, and so on.

Use MERGE . . . USING to name the files that you want to combine into one sequenced file. The merge operation compares keys in the records of the input files, and passes the sequenced records one by one to the RETURN statement of an output procedure or to the file that you name in the GIVING phrase.

**related tasks**

[“Setting sort or merge](#)

[criteria” on page 213](#)

**related references**

[SORT statement \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

[MERGE statement \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## Describing the sort or merge file

---

Describe the sort file to be used for sorting or merging. You need SELECT clauses and SD entries even if you are sorting or merging data items only from WORKING-STORAGE or LOCAL-STORAGE.

Code as follows:

1. Write one or more SELECT clauses in the FILE-CONTROL paragraph of the ENVIRONMENT DIVISION to name a sort file. For example:

```

ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT Sort-Work-1 ASSIGN TO SortFile.

```

*Sort-Work-1* is the name of the file in your program. Use this name to refer to the file.

2. Describe the sort file in an SD entry in the FILE SECTION of the DATA DIVISION. Every SD entry must contain a record description. For example:

```

DATA DIVISION.
FILE SECTION.
SD Sort-Work-1
    RECORD CONTAINS 100 CHARACTERS.
01 SORT-WORK-1-AREA.
    05 SORT-KEY-1    PIC X(10).
    05 SORT-KEY-2    PIC X(10).
    05 FILLER        PIC X(80).

```

The file described in an SD entry is the working file used for a sort or merge operation. You cannot perform any input or output operations on this file and you do not need to provide a ddname definition for it.

#### related references

[“FILE SECTION entries” on page 12](#)

## Describing the input to sorting or merging

Describe the input file or files for sorting or merging by following the procedure below.

1. Write one or more SELECT clauses in the FILE-CONTROL paragraph of the ENVIRONMENT DIVISION to name the input files. For example:

```

ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
    SELECT Input-File ASSIGN TO InFile.

```

*Input-File* is the name of the file in your program. Use this name to refer to the file.

2. Describe the input file (or files when merging) in an FD entry in the FILE SECTION of the DATA DIVISION. For example:

```

DATA DIVISION.
FILE SECTION.
FD Input-File
    LABEL RECORDS ARE STANDARD
    BLOCK CONTAINS 0 CHARACTERS
    RECORDING MODE IS F
    RECORD CONTAINS 100 CHARACTERS.
01 Input-Record    PIC X(100).

```

#### related tasks

[“Coding the input procedure” on page 208](#)

[“Requesting the sort or merge” on page 212](#)

#### related references

[“FILE SECTION entries” on page 12](#)

## Example: describing sort and input files for SORT

The following example shows the ENVIRONMENT DIVISION and DATA DIVISION entries needed to describe sort work files and an input file.

```
ID Division.
Program-ID. Smp1Sort.
Environment Division.
Input-Output Section.
File-Control.
*
* Assign name for a working file is treated as documentation.
*
    Select Sort-Work-1 Assign To SortFile.
    Select Sort-Work-2 Assign To SortFile.
    Select Input-File Assign To InFile.
. . .
Data Division.
File Section.
SD Sort-Work-1
  Record Contains 100 Characters.
01 Sort-Work-1-Area.
  05 Sort-Key-1 Pic X(10).
  05 Sort-Key-2 Pic X(10).
  05 Filler Pic X(80).
SD Sort-Work-2
  Record Contains 30 Characters.
01 Sort-Work-2-Area.
  05 Sort-Key Pic X(5).
  05 Filler Pic X(25).
FD Input-File
  Label Records Are Standard
  Block Contains 0 Characters
  Recording Mode is F
  Record Contains 100 Characters.
01 Input-Record Pic X(100).
. . .
Working-Storage Section.
01 EOS-Sw Pic X.
01 Filler.
  05 Table-Entry Occurs 100 Times
    Indexed By X1 Pic X(30).
. . .
```

### related tasks

[“Requesting the sort or merge” on page 212](#)

## Coding the input procedure

To process the records in an input file before they are released to the sort program, use the INPUT PROCEDURE phrase of the format 1 SORT statement.

You can use an input procedure to:

- Release data items to the sort file from WORKING-STORAGE or LOCAL-STORAGE.
- Release records that have already been read elsewhere in the program.
- Read records from an input file, select or process them, and release them to the sort file.

Each input procedure must be contained in either paragraphs or sections. For example, to release records from a table in WORKING-STORAGE or LOCAL-STORAGE to the sort file SORT-WORK-2, you could code as follows:

```
SORT SORT-WORK-2
  ON ASCENDING KEY SORT-KEY
  INPUT PROCEDURE 600-SORT3-INPUT-PROC
. . .
600-SORT3-INPUT-PROC SECTION.
  PERFORM WITH TEST AFTER
    VARYING X1 FROM 1 BY 1 UNTIL X1 = 100
```

```
RELEASE SORT-WORK-2-AREA FROM TABLE-ENTRY (X1)
END-PERFORM.
```

To transfer records to the sort program, all input procedures must contain at least one `RELEASE` or `RELEASE FROM` statement. To release A from X, for example, you can code:

```
MOVE X TO A.
RELEASE A.
```

Alternatively, you can code:

```
RELEASE A FROM X.
```

The following table compares the `RELEASE` and `RELEASE FROM` statements.

RELEASE	RELEASE FROM
<pre>MOVE SORT-EXT-RECORD   TO SORT-RECORD PERFORM RELEASE-SORT-RECORD . . RELEASE-SORT-RECORD.   RELEASE SORT-RECORD</pre>	<pre>PERFORM RELEASE-SORT-RECORD . RELEASE-SORT-RECORD.   RELEASE SORT-RECORD   FROM SORT-EXT-RECORD</pre>

#### related references

[“Restrictions on input and output procedures” on page 211](#)

`RELEASE` statement (*Enterprise COBOL for z/OS Language Reference*)

## Describing the output from sorting or merging

If the output from sorting or merging is a file, describe the file by following the procedure below.

1. Write a `SELECT` clause in the `FILE-CONTROL` paragraph of the `ENVIRONMENT DIVISION` to name the output file. For example:

```
ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
  SELECT Output-File ASSIGN TO OutFile.
```

*Output-File* is the name of the file in your program. Use this name to refer to the file.

2. Describe the output file (or files when merging) in an `FD` entry in the `FILE SECTION` of the `DATA DIVISION`. For example:

```
DATA DIVISION.
FILE SECTION.
FD Output-File
  LABEL RECORDS ARE STANDARD
  BLOCK CONTAINS 0 CHARACTERS
  RECORDING MODE IS F
  RECORD CONTAINS 100 CHARACTERS.
01 Output-Record PIC X(100).
```

#### related tasks

[“Coding the output procedure” on page 210](#)

[“Requesting the sort or merge” on page 212](#)

#### related references

[“FILE SECTION entries” on page 12](#)

## Coding the output procedure

To select, edit, or otherwise change sorted records before writing them from the sort work file into another file, use the `OUTPUT PROCEDURE` phrase of the `format 1 SORT` statement.

Each output procedure must be contained in either a section or a paragraph. An output procedure must include both of the following elements:

- At least one `RETURN` statement or one `RETURN` statement with the `INTO` phrase
- Any statements necessary to process the records that are made available, one at a time, by the `RETURN` statement

The `RETURN` statement makes each sorted record available to the output procedure. (The `RETURN` statement for a sort file is similar to a `READ` statement for an input file.)

You can use the `AT END` and `END-RETURN` phrases with the `RETURN` statement. The imperative statements in the `AT END` phrase are performed after all the records have been returned from the sort file. The `END-RETURN` explicit scope terminator delimits the scope of the `RETURN` statement.

If you use `RETURN INTO` instead of `RETURN`, the records will be returned to `WORKING-STORAGE`, `LOCAL-STORAGE`, or to an output area.

**DFSORT coding:** If you use DFSORT and a `RETURN` statement does not encounter an `AT END` condition before a COBOL program finishes running, the `format 1 SORT` statement could end abnormally with DFSORT message IEC025A. To avoid this situation, be sure to code the `RETURN` statement with the `AT END` phrase. In addition, ensure that the `RETURN` statement is executed until the `AT END` condition is encountered. The `AT END` condition occurs after the last record is returned to the program from the sort work file and a subsequent `RETURN` statement is executed.

[“Example: coding the output procedure when using DFSORT” on page 210](#)

### related references

[“Restrictions on input and output procedures” on page 211](#)

`RETURN` statement (*Enterprise COBOL for z/OS Language Reference*)

## Example: coding the output procedure when using DFSORT

The following example shows a coding technique that ensures that the `RETURN` statement encounters the `AT END` condition before the program finishes running. The `RETURN` statement, coded with the `AT END` phrase, is executed until the `AT END` condition occurs.

```
IDENTIFICATION DIVISION.
DATA DIVISION.
FILE SECTION.
SD OUR-FILE.
01 OUR-SORT-REC.
   03 SORT-KEY          PIC X(10).
   03 FILLER            PIC X(70).
.
.
.
WORKING-STORAGE SECTION.
01 WS-SORT-REC          PIC X(80).
01 END-OF-SORT-FILE-INDICATOR PIC X VALUE 'N'.
   88 NO-MORE-SORT-RECORDS      VALUE 'Y'.
.
.
.
PROCEDURE DIVISION.
A-CONTROL SECTION.
    SORT OUR-FILE ON ASCENDING KEY SORT-KEY
        INPUT PROCEDURE IS B-INPUT
        OUTPUT PROCEDURE IS C-OUTPUT.
.
.
.
B-INPUT SECTION.
    MOVE . . . . . TO WS-SORT-REC.
    RELEASE OUR-SORT-REC FROM WS-SORT-REC.
.
.
.
C-OUTPUT SECTION.
    DISPLAY 'STARTING READS OF SORTED RECORDS: '.
    RETURN OUR-FILE
    AT END
```

```

        SET NO-MORE-SORT-RECORDS TO TRUE.
    PERFORM WITH TEST BEFORE UNTIL NO-MORE-SORT-RECORDS
    IF SORT-RETURN = 0 THEN
        DISPLAY 'OUR-SORT-REC = ' OUR-SORT-REC
        RETURN OUR-FILE
    AT END
        SET NO-MORE-SORT-RECORDS TO TRUE
    END-IF
END-PERFORM.

```

## Restrictions on input and output procedures

Several restrictions apply to each input or output procedure called by SORT and to each output procedure called by MERGE.

Observe these restrictions:

- The procedure must not contain any SORT or MERGE statements.
- You can use ALTER, GO TO, and PERFORM statements in the procedure to refer to procedure-names outside the input or output procedure. However, control must return to the input or output procedure after a GO TO or PERFORM statement.
- The remainder of the PROCEDURE DIVISION must not contain any transfers of control to points inside the input or output procedure (with the exception of the return of control from a declarative section).
- In an input or output procedure, you can call a program that follows standard linkage conventions. However, the called program cannot issue a SORT or MERGE statement.
- During a SORT or MERGE operation, the SD data item is used. You must not use it in the output procedure before the first RETURN executes. If you move data into this record area before the first RETURN statement, the first record to be returned will be overwritten.
- Language Environment condition handling does not let user-written condition handlers be established in an input or output procedure.

### related tasks

[“Coding the input procedure” on page 208](#)

[“Coding the output procedure” on page 210](#)

*Language Environment Programming Guide* (Preparing to link-edit and run)

## Defining sort and merge data sets

To use DFSORT under z/OS, code DD statements in the runtime JCL to describe the necessary data sets that are listed below.

### Sort or merge work

Define a minimum of three data sets: SORTWK01, SORTWK02, SORTWK03, . . . , SORTWKnn (where nn is 99 or less). These data sets cannot be in the z/OS UNIX file system.

### SYSOUT

Define for sort diagnostic messages, unless you change the data-set name. (Change the name using either the MSGDDN keyword of the OPTION control statement in the SORT-CONTROL data set, or using the SORT-MESSAGE special register.)

### SORTCKPT

Define if the sort or merge is to take checkpoints.

### Input and output

Define input and output data sets, if any.

### SORTLIB (DFSORT library)

Define the library that contains the sort modules, for example, SYS1.SORTLIB.

### related tasks

[“Controlling sort behavior” on page 219](#)

[“Using checkpoint/restart with DFSORT” on page 221](#)

## Sorting variable-length records

---

Your sort work file will be variable length only if you define it to be variable length, even if the input file to the sort contains variable-length records.

The compiler determines that the sort work file is variable length if you code one of the following elements in the SD entry:

- A RECORD IS VARYING clause
- Two or more record descriptions that define records that have different sizes, or records that contain an OCCURS DEPENDING ON clause

You cannot use RECORDING MODE V for the sort work file because the SD entry does not allow the RECORDING MODE clause.

**Performance consideration:** To improve sort performance of variable-length files, specify the most frequently occurring record length of the input file (the modal length) on the SMS= control card or in the SORT-MODE-SIZE special register.

### related tasks

[“Changing DFSORT defaults with control statements” on page 220](#)

[“Controlling sort behavior” on page 219](#)

## Requesting the sort or merge

---

To read records from an input file (files for MERGE) without preliminary processing, use SORT . . . USING or MERGE . . . USING and the name of the input file (files) that you declared in a SELECT clause.

To transfer sorted or merged records from the sort or merge program to another file without any further processing, use SORT . . . GIVING or MERGE . . . GIVING and the name of the output file that you declared in a SELECT clause. For example:

```
SORT Sort-Work-1
  ON ASCENDING KEY Sort-Key-1
  USING Input-File
  GIVING Output-File.
```

For SORT . . . USING or MERGE . . . USING, the compiler generates an input procedure to open the file (files), read the records, release the records to the sort or merge program, and close the file (files). The file (files) must not be open when the SORT or MERGE statement begins execution. For SORT . . . GIVING or MERGE . . . GIVING, the compiler generates an output procedure to open the file, return the records, write the records, and close the file. The file must not be open when the SORT or MERGE statement begins execution.

The USING or GIVING files in a SORT or MERGE statement can be sequential files residing in the z/OS UNIX file system.

[“Example: describing sort and input files for SORT” on page 208](#)

If you want an input procedure to be performed on the sort records before they are sorted, use SORT . . . INPUT PROCEDURE. If you want an output procedure to be performed on the sorted records, use SORT . . . OUTPUT PROCEDURE. For example:

```
SORT Sort-Work-1
  ON ASCENDING KEY Sort-Key-1
  INPUT PROCEDURE EditInputRecords
  OUTPUT PROCEDURE FormatData.
```

[“Example: sorting with input and output procedures” on page 214](#)

**Restriction:** You cannot use an input procedure with the MERGE statement. The source of input to the merge operation must be a collection of already sorted files. However, if you want an output procedure to be performed on the merged records, use MERGE . . . OUTPUT PROCEDURE. For example:

```
MERGE Merge-Work
  ON ASCENDING KEY Merge-Key
  USING Input-File-1 Input-File-2 Input-File-3
  OUTPUT PROCEDURE ProcessOutput.
```

In the FILE SECTION, you must define *Merge-Work* in an SD entry, and the input files in FD entries.

#### related tasks

[“Defining sort and merge data sets” on page 211](#)

#### related references

SORT statement (*Enterprise COBOL for z/OS Language Reference*)

MERGE statement (*Enterprise COBOL for z/OS Language Reference*)

## Setting sort or merge criteria

To set sort or merge criteria, define the keys on which the operation is to be performed.

**Note:** The process of setting sort criteria that is described in this topic relates to the format 1 SORT statement only. For more information about sorting a table by using the format 2 SORT statement, see [“Sorting a table” on page 85](#).

Do these steps:

1. In the record description of the files to be sorted or merged, define the key or keys.

There is no maximum number of keys, but the keys must be located in the first 4092 bytes of the record description. The total length of the keys cannot exceed 4092 bytes unless the EQUALS keyword is coded in the DFSORT OPTION control statement, in which case the total length of the keys must not exceed 4088 bytes.

**Restriction:** A key cannot be variably located.

2. In the SORT or MERGE statement, specify the key fields to be used for sequencing by coding the ASCENDING or DESCENDING KEY phrase, or both. When you code more than one key, some can be ascending, and some descending.

Specify the names of the keys in decreasing order of significance. The leftmost key is the primary key. The next key is the secondary key, and so on.

SORT and MERGE keys can be of class alphabetic, alphanumeric, national, or numeric (but not numeric of USAGE NATIONAL). If it has USAGE NATIONAL, a key can be of category national or can be a national-edited or numeric-edited data item. A key cannot be a national decimal data item or a national floating-point data item.

The collation order for national keys is determined by the binary order of the keys. If you specify a national data item as a key, any COLLATING SEQUENCE phrase in the SORT or MERGE statement does not apply to that key.

You can mix SORT and MERGE statements in the same COBOL program. A program can perform any number of sort or merge operations. However, one operation must end before another can begin.

#### related tasks

[“Sorting a table” on page 85](#)

#### related references

*DFSORT Application Programming Guide* (SORT control statement)

SORT statement (*Enterprise COBOL for z/OS Language Reference*)  
MERGE statement (*Enterprise COBOL for z/OS Language Reference*)

## Example: sorting with input and output procedures

The following example shows the use of an input and an output procedure in a format 1 SORT statement. The example also shows how you can define a primary key (SORT-GRID-LOCATION) and a secondary key (SORT-SHIFT) before using them in the format 1 SORT statement.

```
DATA DIVISION.
SD  SORT-FILE
   RECORD CONTAINS 115 CHARACTERS
   DATA RECORD SORT-RECORD.
01  SORT-RECORD.
   05  SORT-KEY.
      10  SORT-SHIFT                PIC X(1).
      10  SORT-GRID-LOCATION          PIC X(2).
      10  SORT-REPORT               PIC X(3).
   05  SORT-EXT-RECORD.
      10  SORT-EXT-EMPLOYEE-NUM     PIC X(6).
      10  SORT-EXT-NAME             PIC X(30).
      10  FILLER                   PIC X(73).

WORKING-STORAGE SECTION.
01  TAB1.
   05  TAB-ENTRY OCCURS 10 TIMES
      INDEXED BY TAB-INDX.
      10  WS-SHIFT                 PIC X(1).
      10  WS-GRID-LOCATION           PIC X(2).
      10  WS-REPORT                PIC X(3).
      10  WS-EXT-EMPLOYEE-NUM      PIC X(6).
      10  WS-EXT-NAME              PIC X(30).
      10  FILLER                  PIC X(73).

PROCEDURE DIVISION.
   SORT SORT-FILE
      ON ASCENDING KEY SORT-GRID-LOCATION SORT-SHIFT
      INPUT PROCEDURE 600-SORT3-INPUT
      OUTPUT PROCEDURE 700-SORT3-OUTPUT.

600-SORT3-INPUT.
   PERFORM VARYING TAB-INDX FROM 1 BY 1 UNTIL TAB-INDX > 10
   RELEASE SORT-RECORD FROM TAB-ENTRY(TAB-INDX)
   END-PERFORM.

700-SORT3-OUTPUT.
   PERFORM VARYING TAB-INDX FROM 1 BY 1 UNTIL TAB-INDX > 10
   RETURN SORT-FILE INTO TAB-ENTRY(TAB-INDX)
   AT END DISPLAY 'Out Of Records In SORT File'
   END-RETURN
   END-PERFORM.
```

### related tasks

[“Requesting the sort or merge” on page 212](#)

## Choosing alternate collating sequences

You can sort or merge records on the EBCDIC or ASCII collating sequence, or on another collating sequence. The default collating sequence is EBCDIC unless you code the PROGRAM COLLATING SEQUENCE clause in the OBJECT-COMPUTER paragraph.

To override the default sequence, use the COLLATING SEQUENCE phrase of the SORT or MERGE statement. You can use different collating sequences for each SORT or MERGE statement in your program.

The PROGRAM COLLATING SEQUENCE clause and the COLLATING SEQUENCE phrase apply only to keys of class alphabetic or alphanumeric.

When you sort or merge an ASCII file, you have to request the ASCII collating sequence. To do so, code the `COLLATING SEQUENCE` phrase of the `SORT` or `MERGE` statement, and define the *alphabet-name* as `STANDARD-1` in the `SPECIAL -NAMES` paragraph.

#### related tasks

[“Specifying the collating sequence” on page 6](#)

[“Setting sort or merge criteria” on page 213](#)

#### related references

`OBJECT-COMPUTER` paragraph (*Enterprise COBOL for z/OS Language Reference*)

`SORT` statement (*Enterprise COBOL for z/OS Language Reference*)

Classes and categories of data (*Enterprise COBOL for z/OS Language Reference*)

## Preserving the original sequence of records with equal keys

You can preserve the order of identical collating records from input to output.

Use one of these techniques:

- Install DFSORT with the `EQUALS` option as the default.
- Provide, at run time, an `OPTION` card that has the `EQUALS` keyword in the `IGZSRTCD` data set.
- Use the `WITH DUPLICATES IN ORDER` phrase in the `SORT` statement. Doing so adds the `EQUALS` keyword to the `OPTION` card in the `IGZSRTCD` data set.

Do not use both the `NOEQUALS` keyword on the `OPTION` card *and* the `DUPLICATES` phrase, or the run unit will end.

#### related references

*DFSORT Application Programming Guide* (`OPTION` control statement)

## Determining whether the sort or merge was successful

The DFSORT program returns a completion code of either 0 (successful completion) or 16 (unsuccessful completion) after each sort or merge has finished. The completion code is stored in the `SORT-RETURN` special register.

You should test for successful completion after each `SORT` or `MERGE` statement. For example:

```
SORT SORT-WORK-2
  ON ASCENDING KEY SORT-KEY
  INPUT PROCEDURE IS 600-SORT3-INPUT-PROC
  OUTPUT PROCEDURE IS 700-SORT3-OUTPUT-PROC.
IF SORT-RETURN NOT=0
  DISPLAY "SORT ENDED ABNORMALLY. SORT-RETURN = " SORT-RETURN.
. . .
600-SORT3-INPUT-PROC SECTION.
. . .
700-SORT3-OUTPUT-PROC SECTION.
. . .
```

If you do not reference `SORT-RETURN` anywhere in your program, the COBOL run time tests the completion code. If it is 16, COBOL issues a runtime diagnostic message.

By default, DFSORT diagnostic messages are sent to the `SYSOUT` data set. If you want to change this default, use the `MSGDDN` parameter of the DFSORT `OPTION` control card or use the `SORT-MESSAGE` special register.

If you test `SORT-RETURN` for one or more (but not necessarily all) `SORT` or `MERGE` statements, the COBOL run time does not check the completion code.

#### **related tasks**

[“Checking for sort errors with NOFASTSRT” on page 218](#)

[“Controlling sort behavior” on page 219](#)

#### **related references**

*DFSORT Application Programming Guide* (DFSORT messages and return codes)

## **Stopping a sort or merge operation prematurely**

---

To stop a sort or merge operation, move the integer 16 into the SORT-RETURN special register.

Move 16 into the register in either of the following ways:

- Use MOVE in an input or output procedure.

Sort or merge processing will be stopped immediately after the next RELEASE or RETURN statement is performed.

- Reset the register in a declarative section entered during processing of a USING or GIVING file.

Sort or merge processing will be stopped immediately after the next implicit RELEASE or RETURN is performed, which will occur after a record has been read from or written to the USING or GIVING file.

Control then returns to the statement following the SORT or MERGE statement.

## **Improving sort performance with FASTSRT**

---

Using the FASTSRT compiler option improves the performance of most sort operations. With FASTSRT, the DFSORT product (instead of Enterprise COBOL) performs the I/O on the input and output files you name in the SORT . . . USING and SORT . . . GIVING statements.

The compiler issues informational messages to point out statements in which FASTSRT can improve performance.

#### **Usage notes**

- You cannot use the DFSORT options SORTIN or SORTOUT if you use FASTSRT. The FASTSRT compiler option does not apply to line-sequential files you use as USING or GIVING files.
- If you specify file status and use FASTSRT, file status is ignored during the sort.

#### **related references**

[“FASTSRT” on page 308](#)

[“FASTSRT requirements for JCL” on page 216](#)

[“FASTSRT requirements for sort input and output files” on page 216](#)

## **FASTSRT requirements for JCL**

In the runtime JCL, you must assign the sort work files (SORTWKnn) to a direct-access device, not to tape data sets.

For the input and output files, the DCB parameter of the DD statement must match the FD description.

## **FASTSRT requirements for sort input and output files**

If you specify FASTSRT but your code does not meet FASTSRT requirements, the compiler issues a message and the COBOL run time performs the I/O instead. Your program will not experience the performance improvements that are otherwise possible.

**Note:** The "sort input and output files" that is described in this topic relates to the format 1 SORT statement only.

To use FASTSRT, you must describe and process the input files to the sort and the output files from the sort in these ways:

- You can name only one input file in the USING phrase. You can name only one output file in the GIVING phrase.
- You cannot use an input procedure on an input file nor an output procedure on an output file.

Instead of using input or output procedures, you might be able to use these DFSORT control statements:

- INREC
- OUTFILE
- OUTREC
- INCLUDE
- OMIT
- STOPAFT
- SKIPREC
- SUM

Many DFSORT functions perform the same operations that are common in input or output procedures. Code the appropriate DFSORT control statements instead, and place them either in the IGZSRTCD or SORTCNTL data set.

- Do not code the LINAGE clause for the output FD entry.
- Do not code any INPUT declarative (for input files), OUTPUT declarative (for output files), or file-specific declaratives (for either input or output files) to apply to any FDs used in the sort.
- Do not use a variable relative file as the input or output file.
- Do not use a line-sequential file as the input or output file.
- For either an input or an output file, the record descriptions of the SD and FD entry must define the same format (fixed or variable), and the largest records of the SD and FD entry must define the same record length.

If you code a RELATIVE KEY clause for an output file, it will not be set by the sort.

**Performance tip:** If you block your input and output records, the sort performance could be significantly improved.

### ***QSAM requirements***

- QSAM files must have a record format of fixed, variable, or spanned.
- A QSAM input file can be empty.
- To use the same QSAM file for both input and output, you must describe the file using two different DD statements. For example, in the FILE-CONTROL SECTION you might code this:

```
SELECT FILE-IN ASSIGN INPUTF.
SELECT FILE-OUT ASSIGN OUTPUTF.
```

In the DATA DIVISION, you would have an FD entry for both FILE-IN and FILE-OUT, where FILE-IN and FILE-OUT are identical except for their names.

In the PROCEDURE DIVISION, your SORT statement could look like this:

```
SORT file-name
  ASCENDING KEY data-name-1
  USING FILE-IN GIVING FILE-OUT
```

Then in your JCL, assuming that data set INOUT has been cataloged, you would code:

```
//INPUTF DD DSN=INOUT,DISP=SHR
//OUTPUTF DD DSN=INOUT,DISP=SHR
```

On the other hand, if you code the same file-name in the USING and GIVING phrases, or assign the input and output files the same ddname, then the file can be accepted for FASTSRT either for input or output, but not both. If no other conditions disqualify the file from being eligible for FASTSRT on input, then the file will be accepted for FASTSRT on input, but not on output. If the file was found to be ineligible for FASTSRT on input, it might be eligible for FASTSRT on output.

A QSAM file that qualifies for FASTSRT can be accessed by the COBOL program while the format 1 SORT statement is being performed. For example, if the file is used for FASTSRT on input, you can access it in an output procedure; if it is used for FASTSRT on output, you can access it in an input procedure.

### VSAM requirements

- A VSAM input file must not be empty.
- VSAM files cannot be password-protected.
- You cannot name the same VSAM file in both the USING and GIVING phrases.
- A VSAM file that qualifies for FASTSRT cannot be accessed by the COBOL program until the format 1 SORT statement processing is completed. For example, if the file qualifies for FASTSRT on input, you cannot access it in an output procedure and vice versa. (If you do so, OPEN fails.)

### related tasks

*DFSORT Application Programming Guide*

## Checking for sort errors with NOFASTSRT

When you compile with the NOFASTSRT option, the sort process does not check for errors in open, close, or input or output operations for files that you reference in the USING or GIVING phrase of the format 1 SORT statement. Therefore, you might need to check whether SORT completed successfully.

**Note:** This topic relates to the format 1 SORT statement only.

The code required depends on whether you code a FILE STATUS clause or an ERROR declarative for the files referenced in the USING and GIVING phrases, as shown in the table below.

Table 32. <i>Methods for checking for sort errors with NOFASTSRT</i>		
FILE STATUS clause?	ERROR declarative?	Then do:
No	No	No special coding. Any failure during the sort process causes the program to end abnormally.
Yes	No	Test the SORT - RETURN special register after the format 1 SORT statement, and test the file status key. (Not recommended if you want complete file-status checking, because the file status code is set but COBOL cannot check it.)
Maybe	Yes	In the ERROR declarative, set the SORT - RETURN special register to 16 to stop the sort process and indicate that it was not successful. Test the SORT - RETURN special register after the format 1 SORT statement.

### related tasks

[“Determining whether the sort or merge was successful” on page 215](#)

[“Using file status keys” on page 229](#)

[“Coding ERROR declaratives” on page 228](#)

[“Stopping a sort or merge operation prematurely” on page 216](#)

## Controlling sort behavior

You can control several aspects of sort behavior by inserting values in special registers before the sort or by using compiler options. You might also have a choice of control statements and keywords.

You can verify sort behavior by examining the contents of special registers after the sort.

The table below lists those aspects of sort behavior that you can affect by using special registers or compiler options, and the equivalent sort control statement keywords if any are available.

<i>Table 33. Methods for controlling sort behavior</i>		
To set or test	Use this special register or compiler option	Or this control statement (and keyword if applicable)
Amount of main storage to be reserved	SORT-CORE-SIZE special register	OPTION (keyword RESINV)
Amount of main storage to be used	SORT-CORE-SIZE special register	OPTION (keywords MAINSIZE or MAINSIZE=MAX)
Modal length of records in a file with variable-length records	SORT-MODE-SIZE special register	SMS=nnnnn
Name of sort control statement data set (default IGZSRTCD)	SORT-CONTROL special register	None
Name of sort message file (default SYSOUT)	SORT-MESSAGE special register	OPTION (keyword MSGDDN)
Number of sort records	SORT-FILE-SIZE special register	OPTION (keyword FILSZ)
Sort completion code	SORT-RETURN special register	None

**Sort special registers:** SORT-CONTROL is an eight-character COBOL special register that contains the ddname of the sort control statement file. If you do not want to use the default ddname IGZSRTCD, assign to SORT-CONTROL the ddname of the data set that contains your sort control statements.

The SORT-CORE-SIZE, SORT-FILE-SIZE, SORT-MESSAGE, and SORT-MODE-SIZE special registers are used in the SORT interface if you assign them nondefault values. At run time, however, any parameters in control statements in the sort control statement data set override corresponding settings in the special registers, and a message to that effect is issued.

You can use the SORT-RETURN special register to determine whether the sort or merge was successful and to stop a sort or merge operation prematurely.

A compiler warning message (W-level) is issued for each sort special register that you set in a program.

### related tasks

[“Determining whether the sort or merge was successful” on page 215](#)

[“Stopping a sort or merge operation prematurely” on page 216](#)

[“Changing DFSORT defaults with control statements” on page 220](#)

[“Allocating space for sort files” on page 221](#)

*DFSORT Application Programming Guide* (Using DFSORT program control statements)

### related references

[“Default characteristics of the IGZSRTCD data set” on page 220](#)

## Changing DFSORT defaults with control statements

If you want to change DFSORT system defaults to improve sort performance, pass information to DFSORT through control statements in the runtime data set IGZSRTCD.

The control statements that you can include in IGZSRTCD (in the order listed) are:

1. SMS=nnnnn, where nnnnn is the length in bytes of the most frequently occurring record size. (Use only if the SD file is variable length.)
2. OPTION (except keywords SORTIN or SORTOUT).
3. Other DFSORT control statements (except SORT, MERGE, RECORD, or END).

Code control statements between columns 2 and 71. You can continue a control statement record by ending the line with a comma and starting the next line with a new keyword. You cannot use labels or comments on a record, and a record itself cannot be a DFSORT comment statement.

### related tasks

[“Controlling sort behavior” on page 219](#)

*DFSORT Application Programming Guide* (Using DFSORT program control statements)

### related references

[“Default characteristics of the IGZSRTCD data set” on page 220](#)

## Default characteristics of the IGZSRTCD data set

The IGZSRTCD data set is optional. Its defaults are LRECL=80, BLKSIZE=400, and ddname IGZSRTCD.

You can use a different ddname by coding it in the SORT-CONTROL special register. If you defined a ddname for the SORT-CONTROL data set and you receive the message IGZ0027W, an OPEN failure occurred that you should investigate.

### related tasks

[“Controlling sort behavior” on page 219](#)

## Allocating storage for sort or merge operations

Certain parameters set during the installation of DFSORT determine the amount of storage that DFSORT uses. In general, the more storage DFSORT has available, the faster the sort or merge operations in your program will be.

DFSORT installation should not allocate all the free space in the region for its COBOL operation, however. When your program is running, storage must be available for:

- COBOL programs that are dynamically called from an input or output procedure
- Language Environment runtime library modules
- Data management modules that can be loaded into the region for use by an input or output procedure
- Any storage obtained by these modules

For a specific sort or merge operation, you can override the DFSORT storage values set at installation. To do so, code the MAINSIZE and RESINV keywords on the OPTION control statement in the sort control statement data set, or use the SORT-CORE-SIZE special register.

Be careful not to override the storage allocation to the extent that all the free space in the region is used for sort operations for your COBOL program.

### related tasks

[“Controlling sort behavior” on page 219](#)

*DFSORT Installation and Customization*

### related references

*DFSORT Application Programming Guide* (OPTION control statement)

## Allocating space for sort files

If you use NOFASTSORT or an input procedure, DFSORT does not know the size of the file that you are sorting. This can lead to an out-of-space condition when you sort large files or to overallocation of resources when you sort small files.

If this occurs, you can use the SORT-FILE-SIZE special register to help DFSORT determine the amount of resource (for example, workspace or *hiperspace*) needed for the sort. Set SORT-FILE-SIZE to a reasonable estimate of the number of input records. This value is passed to DFSORT as its FILSZ=En value.

### related tasks

[“Controlling sort behavior” on page 219](#)

[“Coding the input procedure” on page 208](#)

*DFSORT Application Programming Guide*

## Using checkpoint/restart with DFSORT

---

You cannot use checkpoints taken while DFSORT is running under z/OS to restart, unless the checkpoints are taken by DFSORT.

Checkpoints taken by a COBOL program while SORT or MERGE statements execute are invalid; such restarts are detected and canceled.

To take a checkpoint during a sort or merge operation, do these steps:

1. Add a DD statement for SORTCKPT in the JCL.
2. Code the RERUN clause in the I-O-CONTROL paragraph:

```
RERUN ON assignment-name
```

3. Code the CKPT (or CHKPT) keyword on an OPTION control statement in the sort control statement data set (default ddname IGZSRTCD).

### related concepts

Chapter 35, “Interrupts and checkpoint/restart,” on page 619

### related tasks

[“Changing DFSORT defaults with control statements” on page 220](#)

[“Setting checkpoints” on page 619](#)

## Sorting under CICS

---

There is no IBM sort product that is supported under CICS. However, you can use the format 1 SORT statement with a sort program you write that runs under CICS to sort small amounts of data. You can also use the format 2 SORT statement under CICS to sort tables.

You must have both an input and an output procedure for the format 1 SORT statement. In the input procedure, use the RELEASE statement to transfer records from the COBOL program to the sort program before the sort is performed. In the output procedure, use the RETURN statement to transfer records from the sort program to the COBOL program after the sort is performed.

The format 2 SORT statement is supported under CICS and you don't need to write a special SORT program.

### related tasks

[“Coding the input procedure” on page 208](#)

[“Coding the output procedure” on page 210](#)

[“Coding COBOL programs to run under CICS” on page 407](#)

### related references

[“CICS SORT application](#)

[restrictions” on page 222](#)

[“CICS reserved-word table” on page 414](#)

## **CICS SORT application restrictions**

Several restrictions apply to COBOL applications that run under CICS and use the SORT statement.

The restrictions are:

- SORT statements that include the USING or GIVING phrase are not supported.
- Sort control data sets are not supported. Data in the SORT - CONTROL special register is ignored.
- These CICS commands in the input or output procedures can cause unpredictable results:
  - CICS LINK
  - CICS XCTL
  - CICS RETURN
  - CICS HANDLE
  - CICS IGNORE
  - CICS PUSH
  - CICS POP

You can use CICS commands other than these if you use the NOHANDLE or RESP option. Unpredictable results can occur if you do not use NOHANDLE or RESP.

### **related references**

[“CICS reserved-word table” on page 414](#)

---

## Chapter 13. Handling errors

Put code in your programs that anticipates possible system or runtime problems. If you do not include such code, output data or files could be corrupted, and the user might not even be aware that there is a problem.

The error-handling code can take actions such as handling the situation, issuing a message, or halting the program. You might for example create error-detection routines for data-entry errors or for errors as your installation defines them. In any event, coding a warning message is a good idea.

Enterprise COBOL contains special elements to help you anticipate and correct error conditions:

- User-requested dumps
- ON OVERFLOW in STRING and UNSTRING operations
- ON SIZE ERROR in arithmetic operations
- Elements for handling input or output errors
- ON EXCEPTION or ON OVERFLOW in CALL statements
- User-written routines for handling errors

### related tasks

[“Handling errors in joining and splitting strings” on page 224](#)

[“Handling errors in arithmetic operations” on page 224](#)

[“Handling errors in input and output operations” on page 225](#)

[“Handling errors when calling programs” on page 233](#)

[“Writing routines for handling errors” on page 234](#)

---

## Requesting dumps

You can cause a formatted dump of the Language Environment runtime environment and the member language libraries at any prespecified point in your program by coding a call to the Language Environment callable service CEE3DMP.

```
77 Title-1          Pic x(80)  Display.  
77 Options          Pic x(255) Display.  
01 Feedback-code    Pic x(12)  Display.  
.  
.  
.  
    Call "CEE3DMP" Using Title-1, Options, Feedback-code
```

To have symbolic variables included in the formatted dump, compile with the TEST compiler option and use the VARIABLES subparameter of CEE3DMP. You can also request, through runtime options, that a dump be produced for error conditions of your choosing.

You can cause a system dump at any prespecified point in your program. Request an abend without cleanup by calling the Language Environment service CEE3ABD with a cleanup value of zero. This callable service stops the run unit immediately, and a system dump is requested when the abend is issued.

### related references

[“TEST” on page 340](#)

*Language Environment Debugging Guide*

*Language Environment Programming Reference (CEE3DMP--generate dump)*

## Handling errors in joining and splitting strings

During the joining or splitting of strings, the pointer used by STRING or UNSTRING might fall outside the range of the receiving field. A potential overflow condition exists, but COBOL does not let the overflow happen.

Instead, the STRING or UNSTRING operation is not completed, the receiving field remains unchanged, and control passes to the next sequential statement. If you do not code the ON OVERFLOW phrase of the STRING or UNSTRING statement, you are not notified of the incomplete operation.

Consider the following statement:

```
String Item-1 space Item-2 delimited by Item-3
into Item-4
with pointer String-ptr
on overflow
    Display "A string overflow occurred"
End-String
```

These are the data values before and after the statement is performed:

Data item	PICTURE	Value before	Value after
Item-1	X(5)	AAAAA	AAAAA
Item-2	X(5)	EEEEA	EEEEA
Item-3	X(2)	EA	EA
Item-4	X(8)	<i>bbbbbbbb</i> <sup>1</sup>	<i>bbbbbbbb</i> <sup>1</sup>
String-ptr	9(2)	0	0
1. The symbol <i>b</i> represents a blank space.			

Because String-ptr has a value (0) that falls short of the receiving field, an overflow condition occurs and the STRING operation is not completed. (Overflow would also occur if String-ptr were greater than 9.) If ON OVERFLOW had not been specified, you would not be notified that the contents of Item-4 remained unchanged.

## Handling errors in arithmetic operations

The results of arithmetic operations might be larger than the fixed-point field that is to hold them, or you might have tried dividing by zero. In either case, the ON SIZE ERROR clause after the ADD, SUBTRACT, MULTIPLY, DIVIDE, or COMPUTE statement can handle the situation.

For ON SIZE ERROR to work correctly for fixed-point overflow and decimal overflow, you must specify the TRAP(ON) runtime option.

The imperative statement of the ON SIZE ERROR clause will be performed and the result field will not change in these cases:

- Fixed-point overflow
- Division by zero
- Zero raised to the zero power
- Zero raised to a negative number
- Negative number raised to a fractional power

Floating-point exponent overflow occurs when the value of a floating-point computation cannot be represented in the System z floating-point operand format. This type of overflow does not cause SIZE ERROR; an abend occurs instead. You could code a user-written condition handler to intercept the abend and provide your own error recovery logic.

## Example: checking for division by zero

The following example shows how you can code an `ON SIZE ERROR` imperative statement so that the program issues an informative message if division by zero occurs.

```
DIVIDE-TOTAL-COST.  
  DIVIDE TOTAL-COST BY NUMBER-PURCHASED  
    GIVING ANSWER  
    ON SIZE ERROR  
      DISPLAY "ERROR IN DIVIDE-TOTAL-COST PARAGRAPH"  
      DISPLAY "SPENT " TOTAL-COST, " FOR " NUMBER-PURCHASED  
      PERFORM FINISH  
END-DIVIDE  
  
  .  
  .  
  .  
  FINISH.  
  STOP RUN.
```

If division by zero occurs, the program writes a message and halts program execution.

## Handling errors in input and output operations

---

When an input or output operation fails, COBOL does not automatically take corrective action. You choose whether your program will continue running after a less-than-severe input or output error.

You can use any of the following techniques for intercepting and handling certain input or output conditions or errors:


- End-of-file condition (`AT END`)
- `ERROR` declaratives
- `FILE STATUS` clause and file status key
- File system status code
- Imperative-statement phrases in `READ` or `WRITE` statements

For VSAM files, if you specify a `FILE STATUS` clause, you can also test the VSAM status code to direct your program to error-handling logic.


- `INVALID KEY` phrase

To have your program continue, you must code the appropriate error-recovery procedure. You might code, for example, a procedure to check the value of the file status key. If you do not handle an input or output error in any of these ways, a severity-3 Language Environment condition is signaled, which causes the run unit to end if the condition is not handled.

The following figure shows the flow of logic after a VSAM input or output error:



The following figure shows the flow of logic after an input or output error with QSAM or line-sequential files. The error can be from a READ statement, a WRITE statement, or a CLOSE statement with a REEL/UNIT clause (QSAM only).



\*Possible phrases for QSAM are AT END, AT END-OF-PAGE, and INVALID KEY; for line sequential, AT END.

\*\*You need to write the code to test the file status key.

\*\*\*Execution of your COBOL program continues after the input or output statement that caused the error.

#### related tasks

[“Using the end-of-file condition](#)

[\(AT END\)” on page 228](#)

[“Coding ERROR declaratives” on page 228](#)

[“Using file status keys” on page 229](#)

[“Handling errors in QSAM files” on page 163](#)

[“Using VSAM status codes](#)

[\(VSAM files only\)” on page 230](#)

[“Handling errors in line-sequential files” on page 204](#)

[“Coding INVALID KEY phrases” on page 232](#)

#### related references

File status key (*Enterprise COBOL for z/OS Language Reference*)

## Using the end-of-file condition (AT END)

You code the AT END phrase of the READ statement to handle errors or normal conditions, according to your program design. At end-of-file, the AT END phrase is performed. If you do not code an AT END phrase, the associated ERROR declarative is performed.

In many designs, reading sequentially to the end of a file is done intentionally, and the AT END condition is expected. For example, suppose you are processing a file that contains transactions in order to update a master file:

```
PERFORM UNTIL TRANSACTION-EOF = "TRUE"
  READ UPDATE-TRANSACTION-FILE INTO WS-TRANSACTION-RECORD
  AT END
    DISPLAY "END OF TRANSACTION UPDATE FILE REACHED"
    MOVE "TRUE" TO TRANSACTION-EOF
  END READ
END PERFORM
```

Any NOT AT END phrase is performed only if the READ statement completes successfully. If the READ operation fails because of a condition other than end-of-file, neither the AT END nor the NOT AT END phrase is performed. Instead, control passes to the end of the READ statement after any associated declarative procedure is performed.

You might choose not to code either an AT END phrase or an EXCEPTION declarative procedure, but to code a status key clause for the file instead. In that case, control passes to the next sequential instruction after the input or output statement that detected the end-of-file condition. At that place, have some code that takes appropriate action.

### related references

AT END phrases (*Enterprise COBOL for z/OS Language Reference*)

## Coding ERROR declaratives

You can code one or more ERROR declarative procedures that will be given control if an input or output error occurs during the execution of your program. If you do not code such procedures, your job could be canceled or abnormally terminated after an input or output error occurs.

Place each such procedure in the declaratives section of the PROCEDURE DIVISION. You can code:

- A single, common procedure for the entire program
- Procedures for each file open mode (whether INPUT, OUTPUT, I-O, or EXTEND)
- Individual procedures for each file

In an ERROR declarative procedure, you can code corrective action, retry the operation, continue, or end execution. (If you continue processing a blocked file, though, you might lose the remaining records in a block after the record that caused the error.) You can use the ERROR declaratives procedure in combination with the file status key if you want a further analysis of the error.

**Multithreading:** Avoid deadlocks when coding I/O declaratives in multithreaded applications. When an I/O operation results in a transfer of control to an I/O declarative, the automatic serialization lock associated with the file is held during the execution of the statements within the declarative. If you code I/O operations within your declaratives, your logic might result in a deadlock as illustrated by the following sample:

```
Declaratives.
D1 section.
  Use after standard error procedure on F1
  Read F2.
  .
D2 section.
  Use after standard error procedure on F2
  Read F1.
```

```

      . . .
End declaratives.
      Rewrite R1.
      Rewrite R2.

```

When this program is running on two threads, the following sequence of events could occur:

1. Thread 1: Rewrite R1 acquires lock on F1 and encounters I/O error.
2. Thread 1: Enter declarative D1, holding lock on F1.
3. Thread 2: Rewrite R2 acquires lock on F2 and encounters I/O error.
4. Thread 2: Enter declarative D2.
5. Thread 1: Read F2 from declarative D1; wait on F2 lock held by thread 2.
6. Thread 2: Read F1 from declarative D2; wait on F1 lock held by thread 1.
7. Deadlock.

### related references

EXCEPTION/ERROR declarative (*Enterprise COBOL for z/OS Language Reference*)

## Using file status keys

After each input or output statement is performed on a file, the system updates values in the two digit positions of the file status key. In general, a zero in the first position indicates a successful operation, and a zero in both positions means that nothing abnormal occurred.

Establish a file status key by coding:

- The FILE STATUS clause in the FILE-CONTROL paragraph:

```
FILE STATUS IS data-name-1
```

- Data definitions in the DATA DIVISION (WORKING-STORAGE, LOCAL-STORAGE, or LINKAGE SECTION), for example:


```
WORKING-STORAGE SECTION.
01 data-name-1 PIC 9(2) USAGE NATIONAL.
```

Specify the file status key *data-name-1* as a two-character category alphanumeric or category national item, or as a two-digit zoned decimal or national decimal item. This *data-name-1* cannot be variably located.

Your program can check the file status key to discover whether an error occurred, and, if so, what type of error occurred. For example, suppose that a FILE STATUS clause is coded like this:

```
FILE STATUS IS FS-CODE
```

FS-CODE is used by COBOL to hold status information like this:



Follow these rules for each file:

- Define a different file status key for each file.

Doing so means that you can determine the cause of a file input or output exception, such as an application logic error or a disk error.

- Check the file status key after each input or output request.

If the file status key contains a value other than 0, your program can issue an error message or can take action based on that value.

You do not have to reset the file status key code, because it is set after each input or output attempt.

For VSAM files, you can additionally code a second identifier in the FILE STATUS clause to get more detailed information about VSAM input or output requests.

You can use the file status key alone or in conjunction with the INVALID KEY phrase, or to supplement the EXCEPTION or ERROR declarative. Using the file status key in this way gives you precise information about the results of each input or output operation.

[“Example: file status key” on page 230](#)

#### **related tasks**

[“Using VSAM status codes](#)

[\(VSAM files only\)” on page 230](#)

[“Coding INVALID KEY phrases” on page 232](#)

[“Finding and handling input-output](#)

[errors” on page 362](#)

#### **related references**

FILE STATUS clause (*Enterprise COBOL for z/OS Language Reference*)

File status key (*Enterprise COBOL for z/OS Language Reference*)

## **Example: file status key**

The following example shows how you can perform a simple check of the file status key after opening a file.

```
IDENTIFICATION DIVISION.  
PROGRAM-ID. SIMCHK.  
ENVIRONMENT DIVISION.  
INPUT-OUTPUT SECTION.  
FILE-CONTROL.  
    SELECT MASTERFILE ASSIGN TO AS-MASTERA  
    FILE STATUS IS MASTER-CHECK-KEY  
  
DATA DIVISION.  
  
WORKING-STORAGE SECTION.  
01 MASTER-CHECK-KEY          PIC X(2).  
  
PROCEDURE DIVISION.  
    OPEN INPUT MASTERFILE  
    IF MASTER-CHECK-KEY NOT = "00"  
        DISPLAY "Nonzero file status returned from OPEN " MASTER-CHECK-KEY  
    . . .
```

## **Using VSAM status codes (VSAM files only)**

Often the COBOL file status code is too general to pinpoint the disposition of a request. You can get more detailed information about VSAM input or output requests by coding a second data item in the FILE STATUS clause.

```
FILE STATUS IS data-name-1 data-name-8
```


The data item *data-name-1* shown above specifies the COBOL file status key, which you define as a two-character alphanumeric or national data item, or as a two-digit zoned decimal or national decimal item.

The data item *data-name-8* specifies the VSAM status code, which you define as a 6-byte alphanumeric group data item that has three subordinate 2-byte binary fields. The VSAM status code contains meaningful values when the COBOL file status key is not 0.

You can define *data-name-8* in the WORKING-STORAGE SECTION, as in VSAM-CODE below.

```
01 RETURN-STATUS.
  05 FS-CODE          PIC X(2).
  05 VSAM-CODE.
    10 VSAM-R15-RETURN PIC S9(4) Usage Comp-5.
    10 VSAM-FUNCTION   PIC S9(4) Usage Comp-5.
    10 VSAM-FEEDBACK   PIC S9(4) Usage Comp-5.
```

Enterprise COBOL uses *data-name-8* to pass information supplied by VSAM. In the following example, FS-CODE corresponds to *data-name-1* and VSAM-CODE corresponds to *data-name-8*:



[“Example: checking VSAM status codes” on page 231](#)

#### related references

FILE STATUS clause (*Enterprise COBOL for z/OS Language Reference*)  
 File status key (*Enterprise COBOL for z/OS Language Reference*)  
 z/OS DFSMS Macro Instructions for Data Sets (VSAM macro return and reason codes)

## Example: checking VSAM status codes

The following example reads an indexed file (starting at the fifth record), checks the file status key after each input or output request, and displays the VSAM status codes when the file status key is not zero.

This example also illustrates how output from this program might look if the file being processed contained six records.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. EXAMPLE.
ENVIRONMENT DIVISION.
INPUT-OUTPUT SECTION.
FILE-CONTROL.
  SELECT VSAMFILE ASSIGN TO VSAMFILE
  ORGANIZATION IS INDEXED
  ACCESS DYNAMIC
  RECORD KEY IS VSAMFILE-KEY
  FILE STATUS IS FS-CODE VSAM-CODE.
DATA DIVISION.
FILE SECTION.
FD  VSAMFILE
   RECORD 30.
01  VSAMFILE-REC.
   10 VSAMFILE-KEY          PIC X(6).
   10 FILLER                PIC X(24).
WORKING-STORAGE SECTION.
01  RETURN-STATUS.
```

```

05 FS-CODE          PIC XX.
05 VSAM-CODE.
   10 VSAM-RETURN-CODE  PIC S9(2) Usage Binary.
   10 VSAM-COMPONENT-CODE PIC S9(1) Usage Binary.
   10 VSAM-REASON-CODE  PIC S9(3) Usage Binary.
PROCEDURE DIVISION.
  OPEN INPUT VSAMFILE.
  DISPLAY "OPEN INPUT VSAMFILE FS-CODE: " FS-CODE.

  IF FS-CODE NOT = "00"
    PERFORM VSAM-CODE-DISPLAY
    STOP RUN
  END-IF.

  MOVE "000005" TO VSAMFILE-KEY.
  START VSAMFILE KEY IS EQUAL TO VSAMFILE-KEY.
  DISPLAY "START VSAMFILE KEY=" VSAMFILE-KEY
    " FS-CODE: " FS-CODE.
  IF FS-CODE NOT = "00"
    PERFORM VSAM-CODE-DISPLAY
  END-IF.

  IF FS-CODE = "00"
    PERFORM READ-NEXT UNTIL FS-CODE NOT = "00"
  END-IF.

  CLOSE VSAMFILE.
  STOP RUN.

READ-NEXT.
  READ VSAMFILE NEXT.
  DISPLAY "READ NEXT VSAMFILE FS-CODE: " FS-CODE.
  IF FS-CODE NOT = "00"
    PERFORM VSAM-CODE-DISPLAY
  ELSE
    DISPLAY VSAMFILE-REC
  END-IF.

VSAM-CODE-DISPLAY.
  DISPLAY "VSAM-CODE ==>"
    " RETURN: " VSAM-RETURN-CODE,
    " COMPONENT: " VSAM-COMPONENT-CODE,
    " REASON: " VSAM-REASON-CODE.

```

Below is a sample of the output from the example program that checks VSAM status-code information:

```

OPEN INPUT VSAMFILE FS-CODE: 00
START VSAMFILE KEY=000005 FS-CODE: 00
READ NEXT VSAMFILE FS-CODE: 00
000005 THIS IS RECORD NUMBER 5
READ NEXT VSAMFILE FS-CODE: 00
000006 THIS IS RECORD NUMBER 6
READ NEXT VSAMFILE FS-CODE: 10
VSAM-CODE ==> RETURN: 08 COMPONENT: 2 REASON: 004

```

## Coding INVALID KEY phrases

You can include an **INVALID KEY** phrase in **READ**, **START**, **WRITE**, **REWRITE**, and **DELETE** statements for VSAM indexed and relative files. The **INVALID KEY** phrase is given control if an input or output error occurs due to a faulty index key.

You can also include the **INVALID KEY** phrase in **WRITE** requests for QSAM files, but the phrase has limited meaning for QSAM files. It is used only if you try to write to a disk that is full.

Use the **FILE STATUS** clause with the **INVALID KEY** phrase to evaluate the status key and determine the specific **INVALID KEY** condition.

**INVALID KEY** phrases differ from **ERROR** declaratives in several ways. **INVALID KEY** phrases:

- Operate for only limited types of errors. **ERROR** declaratives encompass all forms.
- Are coded directly with the input or output statement. **ERROR** declaratives are coded separately.
- Are specific for a single input or output operation. **ERROR** declaratives are more general.

If you code `INVALID KEY` in a statement that causes an `INVALID KEY` condition, control is transferred to the `INVALID KEY` imperative statement. Any `ERROR` declaratives that you coded are not performed.

If you code a `NOT INVALID KEY` phrase, it is performed only if the statement completes successfully. If the operation fails because of a condition other than `INVALID KEY`, neither the `INVALID KEY` nor the `NOT INVALID KEY` phrase is performed. Instead, after the program performs any associated `ERROR` declaratives, control passes to the end of the statement.

[“Example: FILE STATUS and INVALID KEY” on page 233](#)

## Example: FILE STATUS and INVALID KEY

The following example shows how you can use the file status code and the `INVALID KEY` phrase to determine more specifically why an input or output statement failed.

Assume that you have a file that contains master customer records and you need to update some of these records with information from a transaction update file. The program reads each transaction record, finds the corresponding record in the master file, and makes the necessary updates. The records in both files contain a field for a customer number, and each record in the master file has a unique customer number.

The `FILE-CONTROL` entry for the master file of customer records includes statements that define indexed organization, random access, `MASTER-CUSTOMER-NUMBER` as the prime record key, and `CUSTOMER-FILE-STATUS` as the file status key.

```
. (read the update transaction record)
.
MOVE "TRUE" TO TRANSACTION-MATCH
MOVE UPDATE-CUSTOMER-NUMBER TO MASTER-CUSTOMER-NUMBER
READ MASTER-CUSTOMER-FILE INTO WS-CUSTOMER-RECORD
  INVALID KEY
    DISPLAY "MASTER CUSTOMER RECORD NOT FOUND"
    DISPLAY "FILE STATUS CODE IS: " CUSTOMER-FILE-STATUS
    MOVE "FALSE" TO TRANSACTION-MATCH
  END-READ
```

## Handling errors when calling programs

When a program dynamically calls a separately compiled program, the called program might be unavailable. For example, the system might be out of storage or unable to locate the program object. If the `CALL` statement does not have an `ON EXCEPTION` or `ON OVERFLOW` phrase, your application might abend.

Use the `ON EXCEPTION` phrase to perform a series of statements and to perform your own error handling. For example, in the code fragment below, if program `REPORTA` is unavailable, control passes to the `ON EXCEPTION` phrase.

```
MOVE "REPORTA" TO REPORT-PROG
CALL REPORT-PROG
  ON EXCEPTION
    DISPLAY "Program REPORTA not available, using REPORTB."
    MOVE "REPORTB" TO REPORT-PROG
    CALL REPORT-PROG
  END-CALL
END-CALL
```

The `ON EXCEPTION` phrase applies only to the availability of the called program on its initial load. If the called program is loaded but fails for any other reason (such as initialization), the `ON EXCEPTION` phrase is not performed.

### related tasks

*Enterprise COBOL Migration Guide*

## Writing routines for handling errors

---

You can handle most error conditions that might occur while your program is running by using the `ON EXCEPTION` phrase, `ON SIZE ERROR` phrase, or other language constructs. But if an extraordinary condition such as a machine check occurs, usually your application is abnormally terminated.

Enterprise COBOL and Language Environment provide a way for a user-written program to gain control when such conditions occur. Using Language Environment condition handling, you can write your own error-handling routines in COBOL. They can report, analyze, or even fix up a program and enable it to resume running.

When you write your own error-handling routines for an application, the COBOL programs must be compiled with appropriate compiler options. For more information, see [“OPTIMIZE” on page 325](#).

To have Language Environment pass control to a user-written error program, you must first identify and register its entry point to Language Environment. `PROCEDURE-POINTER` data items enable you to pass the entry address of procedure entry points to Language Environment services.

### **related tasks**

[“Using procedure and function pointers” on page 461](#)

### **related references**

[“OPTIMIZE” on page 325](#)

---

## Part 2. Compiling and debugging your program



---

## Chapter 14. Compiling under z/OS

You can compile Enterprise COBOL programs under z/OS using job control language (JCL), TSO commands, CLISTs, or ISPF panels.

For compiling with JCL, IBM provides a set of cataloged procedures, which can reduce the amount of JCL coding that you need to write. If the cataloged procedures do not meet your needs, you can write your own JCL. Using JCL, you can compile a single program or compile several programs as part of a batch job.

When compiling under TSO, you can use TSO commands, CLISTs, or ISPF panels.

You can also compile in a z/OS UNIX shell by using the `cob2` command.

You might instead want to start the Enterprise COBOL compiler from an assembler program, for example, if your shop has developed a tool or interface that calls the Enterprise COBOL compiler.

As part of the compilation step, you need to define the data sets needed for the compilation and specify any compiler options necessary for your program and the required output.

The compiler translates your COBOL program into language that the computer can process (object code). The compiler also lists errors in your source statements and provides supplementary information to help you debug and tune your program. Use compiler-directing statements and compiler options to control your compilation.

After compiling your program, you need to review the results of the compilation and correct any compiler-detected errors.

### related tasks

[“Compiling with JCL” on page 237](#)

[“Compiling under TSO” on page 244](#)

[Chapter 15, “Compiling under z/OS UNIX,” on page 265](#)

[“Starting the compiler from an assembler program” on page 246](#)

[“Defining compiler input and output” on page 248](#)

[“Specifying compiler options under z/OS” on page 255](#)

[“Compiling multiple programs \(batch compilation\)” on page 258](#)

[“Correcting errors in your source program” on page 262](#)

### related references

[Chapter 18, “Compiler-directing statements,” on page 357](#)

[“Data sets used by the compiler under z/OS” on page 248](#)

[“Compiler options and compiler output under z/OS” on page 257](#)

---

## Compiling with JCL

Include the following information in the JCL for compilation: job description, statement to invoke the compiler, and definitions of the needed data sets (including the directory paths of z/OS UNIX files, if any).

The simplest way to compile your program under z/OS is to code JCL that uses a cataloged procedure. A *cataloged procedure* is a set of job control statements in a partitioned data set called the *procedure library* (SYS1.PROCLIB).

The following JCL shows the general format for a cataloged procedure.

```
//jobname JOB parameters
//stepname EXEC [PROC=]procname[, {PARM=|PARM.stepname=} 'options']
//SYSIN DD data-set parameters
          (source program to be compiled)
/*
//
```

Additional considerations apply when you use cataloged procedures to compile object-oriented programs.

[“Example: sample JCL for a procedural DLL application” on page 483](#)

#### **related tasks**

[“Using a cataloged procedure” on page 238](#)

[“Writing JCL to compile programs” on page 242](#)

[“Specifying compiler options under z/OS” on page 255](#)

[“Specifying compiler options in a batch compilation” on page 259](#)

[“Compiling programs to create DLLs” on page 482](#)

#### **related references**

[“Data sets used by the compiler under z/OS” on page 248](#)

## **Using a cataloged procedure**

Specify a cataloged procedure in an EXEC statement in your JCL.

For example, the following JCL calls the IBM-supplied cataloged procedure IGYWC for compiling an Enterprise COBOL program and defining the required data sets:

```
//JOB1      JOB1
//STEP1    EXEC PROC=IGYWC
//COBOL.SYSIN DD *
000100 IDENTIFICATION DIVISION
        * (the source code)
        .
        .
        .
/*
```

You can omit /\* after the source code. If your source code is stored in a data set, replace SYSIN DD \* with appropriate parameters that describe the data set.

You can use these procedures with any of the job schedulers that are part of z/OS. When a scheduler encounters parameters that it does not require, the scheduler either ignores them or substitutes alternative parameters.

If the compiler options are not explicitly supplied with the procedure, default options established at the installation apply. You can override these default options by using an EXEC statement that includes the required options.

You can specify data sets to be in the z/OS UNIX file system by overriding the corresponding DD statement. However, the compiler utility files (SYSUTx) and copy libraries (SYSLIB) you specify must be MVS data sets.

Additional details about invoking cataloged procedures, overriding and adding to EXEC statements, and overriding and adding to DD statements are in the Language Environment information.

#### **related tasks**

*Language Environment Programming Guide*

#### **related references**

[“Compile procedure \(IGYWC\)” on page 238](#)

[“Compile and link-edit procedure \(IGYWCL\)” on page 240](#)

[“Compile, link-edit, and run procedure \(IGYWCLG\)” on page 241](#)

[MVS Program Management: User's Guide and Reference](#)

## **Compile procedure (IGYWC)**

IGYWC is a single-step cataloged procedure for compiling a program. It produces an object module. The compile steps in all other cataloged procedures that invoke the compiler are similar.

You must supply the following DD statement, indicating the location of the source program, in the input stream:

```
//COBOL.SYSIN DD *      (or appropriate parameters)
```

If you use copybooks in the program that you are compiling, you must also supply a DD statement for SYSLIB or other libraries that you specify in COPY statements. For example:

```
//COBOL.SYSLIB DD DISP=SHR,DSN=DEPT88.BOBS.COBLIB
```

```
//IGYWC PROC LNGPRFX='IGY.V6R1M0',
//          LIBPREFIX='CEE'
//*
//*  COMPILE A COBOL PROGRAM
//*
//*  PARAMETER  DEFAULT VALUE  USAGE
//*  LNGPRFX   IGY.V6R1M0      PREFIX FOR LANGUAGE DATA SET NAMES
//*  LIBPRFX    CEE             PREFIX FOR LIBRARY DATA SET NAMES
//*
//*  CALLER MUST SUPPLY //COBOL.SYSIN DD . . .
//*
//*  CALLER MUST ALSO SUPPLY //COBOL.SYSLIB DD . . . for COPY statements
//*
//COBOL EXEC PGM=IGYCRCTL,REGION=0M
//STEPLIB DD DSN= &LNGPRFX..SIGYCOMP,DISP=SHR          (1)
//          DD DSN= &LIBPRFX..SCEERUN,DISP=SHR
//          DD DSN= &LIBPRFX..SCEERUN2,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN= &&LOADSET,UNIT=SYSALLDA,
//          DISP=(MOD,PASS),SPACE=(CYL,(1,1)),
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT2 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT4 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT5 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT6 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT7 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT8 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT9 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT10 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT11 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT12 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT13 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT14 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT15 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSMDECK DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
```

(1)

STEPLIB can be installation-dependent.

[“Example: JCL for compiling in the z/OS UNIX file system” on page 239](#)

### **Example: JCL for compiling in the z/OS UNIX file system**

The following job uses procedure IGYWC to compile a COBOL program, demo.cb1, that is located in the z/OS UNIX file system. The job writes the generated compiler listing demo.lst, object file demo.o, and SYSDATA file demo.adt in the z/OS UNIX file system.

```
//UNIXDEMO JOB ,
// TIME=(1),MSGLEVEL=(1,1),MSGCLASS=H,CLASS=A,REGION=50M,
// NOTIFY=&SYSUID,USER=&SYSUID
//COMPILE EXEC IGYWC,
// PARM.COBOL='LIST,MAP,RENT,FLAG(I,I),XREF,ADATA'
//SYSPRINT DD PATH='/u/userid/cobol/demo.lst',          (1)
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),                  (2)
// PATHMODE=(SIRUSR,SIWUSR),                          (3)
// FILEDATA=TEXT                                       (4)
//SYSLIN DD PATH='/u/userid/cobol/demo.o',
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),
// PATHMODE=(SIRUSR,SIWUSR)
//SYSDATA DD PATH='/u/userid/cobol/demo.adt',
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),
// PATHMODE=(SIRUSR,SIWUSR)
//SYSIN DD PATH='/u/userid/cobol/demo.cb1',
// PATHOPTS=ORDONLY,
// FILEDATA=TEXT,
// RECFM=F
```

- (1) PATH specifies the path name of a file in the z/OS UNIX file system.
- (2) PATHOPTS indicates the access for the file (such as read or read-write) and sets the status for the file (such as append, create, or truncate).
- (3) PATHMODE indicates the permissions, or file access attributes, to be set when a file is created.
- (4) FILEDATA specifies whether the data is to be treated as text or as binary.

You can use a mixture of files in the z/OS UNIX file system (PATH= ' *unix-directory-path* ') and traditional MVS data sets (DSN= *mvs-data-set-name* ) in the compilation DD statements (shown in this example as overrides). However, the compiler utility files (DD statements SYSUTx) and COPY libraries (DD statements SYSLIB) must be MVS data sets.

#### related references

[“Data sets used by the compiler under z/OS” on page 248](#)

[UNIX System Services Command Reference](#)

[MVS JCL Reference](#)

## Compile and link-edit procedure (IGYWCL)

IGYWCL is a two-step cataloged procedure to compile and link-edit a program.

The COBOL job step produces an object module that is input to the binder (linkage-editor). You can add other object modules. You must supply the following DD statement, indicating the location of the source program, in the input stream:

```
//COBOL.SYSIN DD *          (or appropriate parameters)
```

If the program uses copybooks, you must also supply a DD statement for SYSLIB or other libraries that you specify in COPY statements. For example:

```
//COBOL.SYSLIB DD DISP=SHR,DSN=DEPT88.B0BS.COBLIB
```

```
//IGYWCL PROC  LNGPRFX='IGY.V6R1M0',
//             LIBPRFX='CEE',
//             PGMLIB='&&G0SET',GOPGM=GO
//*
//*  COMPILE AND LINK EDIT A COBOL PROGRAM
//*
//*  PARAMETER  DEFAULT VALUE  USAGE
//*  LNGPRFX   IGY.V6R1M0      PREFIX FOR LANGUAGE DATA SET NAMES
//*  SYSLBLK   3200            BLOCK SIZE FOR OBJECT DATA SET
//*  LIBPRFX   CEE             PREFIX FOR LIBRARY DATA SET NAMES
//*  PGMLIB    &&G0SET         DATA SET NAME FOR LOAD MODULE
//*  GOPGM     GO              MEMBER NAME FOR LOAD MODULE
//*
//*  CALLER MUST SUPPLY //COBOL.SYSIN DD . . .
//*
//*  CALLER MUST ALSO SUPPLY //COBOL.SYSLIB DD . . . for COPY statements
//*
//COBOL EXEC PGM=IGYCRCTL,REGION=0M
//STEPLIB DD DSN=DSN=LIBPRFX..SIGYCOMP,DISP=SHR          (1)
//          DD DSN=DSN=LIBPRFX..SCEERUN,DISP=SHR
//          DD DSN=DSN=LIBPRFX..SCEERUN2,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN=DSN=&&LOADSET,UNIT=SYSALLDA,
//          DISP=(MOD,PASS),SPACE=(CYL,(1,1)),
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT2 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT4 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT5 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
```

```
//SYSUT6 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT7 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT8 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT9 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT10 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT11 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT12 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT13 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT14 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT15 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSMDECK DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//LKED EXEC PGM=IEWBLINK,COND=(8,LT,COBOL),REGION=0M
//SYSLIB DD DSN=LIBPRFX..SCEELKED,DISP=SHR (2)
// DD DSN=LIBPRFX..SCEELKEX,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN=LOADSET,DISP=(OLD,DELETE)
// DD DDNAME=SYSIN
//SYSLMOD DD DSN=PGMLIB(&GOPGM),
// SPACE=(CYL,(3,1,1)),
// UNIT=SYSALLDA,DISP=(MOD,PASS),DSNTYPE=LIBRARY
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
```

(1)  
STEPLIB can be installation-dependent.

(2)  
SYSLIB can be installation-dependent.

## Compile, link-edit, and run procedure (IGYWCLG)

IGYWCLG is a three-step cataloged procedure to compile, link-edit, and run a program.

The COBOL job step produces an object module that is input to the binder (linkage-editor). You can add other object modules. If the COBOL program refers to any data sets, you must also supply DD statements that define these data sets. You must supply the following DD statement, indicating the location of the source program, in the input stream:

```
//COBOL.SYSIN DD * (or appropriate parameters)
```

If the program uses copybooks, you must also supply a DD statement for SYSLIB or other libraries that you specify in COPY statements. For example:

```
//COBOL.SYSLIB DD DISP=SHR,DSN=DEPT88.BOBS.COBLIB
```

```
//IGYWCLG PROC LNGPRFX='IGY.V6R1M0',
// LIBPRFX='CEE',GOPGM=GO
//*
//* COMPILE, LINK EDIT AND RUN A COBOL PROGRAM
//*
//* PARAMETER DEFAULT VALUE USAGE
//* LNGPRFX IGY.V6R1M0 PREFIX FOR LANGUAGE DATA SET NAMES
//* LIBPRFX CEE PREFIX FOR LIBRARY DATA SET NAMES
//* GOPGM GO MEMBER NAME FOR LOAD MODULE
//*
//* CALLER MUST SUPPLY //COBOL.SYSIN DD . . .
//*
//* CALLER MUST ALSO SUPPLY //COBOL.SYSLIB DD . . . for COPY statements
//*
//COBOL EXEC PGM=IGYCRCTL,REGION=0M
//STEPLIB DD DSN=LIBPRFX..SIGYCOMP,DISP=SHR (1)
// DD DSN=LIBPRFX..SCEERUN,DISP=SHR
// DD DSN=LIBPRFX..SCEERUN2,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN=LOADSET,UNIT=SYSALLDA,
// DISP=(MOD,PASS),SPACE=(CYL,(1,1)),
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT2 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT4 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT5 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT6 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
```

```

//SYSUT7 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT8 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT9 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT10 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT11 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT12 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT13 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT14 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT15 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSMDECK DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//LKED EXEC PGM=IEWBLINK,COND=(8,LT,COBOL),REGION=0M
//SYSLIB DD DSN=SYS1.LIBPRFX.SCEELKED,DISP=SHR (2)
// DD DSN=SYS1.LIBPRFX.SCEELKEX,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSLIN DD DSN=SYS1.LOADSET,DISP=(OLD,DELETE)
// DD DNAME=SYSIN
//SYSLMOD DD DSN=SYS1.GOSET(GOPGM),SPACE=(CYL,(1,1,1)),
// UNIT=SYSALLDA,DISP=(MOD,PASS),DSNTYPPE=LIBRARY
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//GO EXEC PGM=SYS1.LKED.SYSLMOD,COND=(8,LT,COBOL),(4,LT,LKED)),
// REGION=0M
//STEPLIB DD DSN=SYS1.LIBPRFX.SCEERUN,DISP=SHR (1)
// DD DSN=SYS1.LIBPRFX.SCEERUN2,DISP=SHR
//SYSPRINT DD SYSOUT=*
//CEEDUMP DD SYSOUT=*
//SYSUDUMP DD SYSOUT=*

```

(1)

STEPLIB can be installation-dependent.

(2)

SYSLIB can be installation-dependent.

In the procedure to run a program (GO statement), a valid *DDName* is up to 8 characters in length. In the ENVIRONMENT DIVISION of the COBOL program, there is a FILE CONTROL paragraph whose *assignment-name* should match the *DDName*. For example:

```
//GO.DDName DD DSN=data-set-name
```

## Writing JCL to compile programs

If the cataloged procedures do not provide you with the flexibility that you need for more complex programs, write your own job control statements. The following example shows the general format of JCL used to compile a program.

```

//jobname JOB acctno,name,MSGCLASS=1 (1)
//stepname EXEC PGM=IGYCRCTL,PARM=(options) (2)
//STEPLIB DD DSN=SYS1.V6R1M0.SIGYCOMP,DISP=SHR (3)
// DD DSN=SYS1.SCEERUN,DISP=SHR
// DD DSN=SYS1.SCEERUN2,DISP=SHR
//SYSUT1 DD UNIT=SYSALLDA,SPACE=(subparms) (4)
//SYSUT2 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT3 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT4 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT5 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT6 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT7 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT8 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT9 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT10 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT11 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT12 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT13 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT14 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSUT15 DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSMDECK DD UNIT=SYSALLDA,SPACE=(subparms)
//SYSPRINT DD SYSOUT=A (5)
//SYSLIN DD DSN=MYPROG,UNIT=SYSALLDA, (6)
// DISP=(MOD,PASS),SPACE=(subparms)
//SYSIN DD DSN=dsname,UNIT=device, (7)
// VOLUME=(subparms),DISP=SHR

```

(1)

The JOB statement indicates the beginning of a job.

(2)

The EXEC statement specifies that the Enterprise COBOL compiler (IGYCRCTL) is to be invoked.

(3)

This DD statement defines the data set where the Enterprise COBOL compiler resides.

The Language Environment SCEERUN and SCEERUN2 data sets must be included in the concatenation (together with the compiler SIGYCOMP data set), unless the Language Environment data sets are available in the LNKLIST.

(4)

The SYSUT DD statements define the utility data sets that the compiler will use to process the source program. All SYSUT files must be on direct-access storage devices.

(5)

The SYSPRINT DD statement defines the data set that receives output from compiler options such as LIST and MAP. SYSOUT=A is the standard designation for data sets whose destination is the system output device.

(6)

The SYSLIN DD statement defines the data set (the object module) that receives output from the OBJECT compiler option.

(7)

The SYSIN DD statement defines the data set (source code) to be used as input to the job step.

You can use a mixture of files in the z/OS UNIX file system (PATH= ' *unix-directory-path* ') and traditional MVS data sets (DSN=*mvs-data-set-name*) in the compilation DD statements for the following data sets:

- Sources files
- Object files
- Listings
- ADATA files
- Debug files
- Executable modules

However, the compiler utility files (DD statements SYSUTx) and COPY libraries (DD statement SYSLIB) must be MVS data sets.

For more examples about the cataloged procedures in JCL, refer to [“Using a cataloged procedure” on page 238](#) and its following topics.

“Example: user-written JCL for compiling” on page 243

“Example: sample JCL for a procedural DLL application” on page 483

#### related references

[MVS JCL Reference](#)

[MVS Program Management: User's Guide and Reference](#)

### Example: user-written JCL for compiling

The following example shows a few possibilities for adapting the basic JCL.

```
//JOB1      JOB                               (1)
//STEP1     EXEC PGM=IGYCRCTL,PARM='OBJECT'   (2)
//STEPLIB   DD DSN=IGY.V6R1M0.SIGYCOMP,DISP=SHR
//          DD DSN=SYS1.SCEERUN,DISP=SHR
//          DD DSN=SYS1.SCEERUN2,DISP=SHR
//SYSUT1     DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSUT2     DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSUT3     DD UNIT=SYSDA,SPACE=(CYL,(1,1))
```

```
//SYSUT4 DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSUT5 DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSUT6 DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSUT7 DD UNIT=SYSDA,SPACE=(CYL,(1,1))
//SYSUT8 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT9 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT10 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT11 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT12 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT13 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT14 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT15 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSMDECK DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSPRINT DD SYSOUT=A
//SYSLIN DD DSN=MYPROG,UNIT=SYSDA,
// DISP=(MOD,PASS),SPACE=(TRK,(3,3))
//SYSIN DD * (3)
000100 IDENTIFICATION DIVISION.
. . .
/* (4)
```

- (1) JOB1 is the name of the job.
- (2) STEP1 is the name of the sole job step in the job. The EXEC statement also specifies that the generated object code should be placed on disk or tape (to be used as input to the link step).
- (3) The asterisk indicates that the input data set follows in the input stream.
- (4) The delimiter statement /\* separates data from subsequent control statements in the input stream.

## Compiling under TSO

Under TSO, you can use TSO commands, command lists (CLISTs), REXX execs, or ISPF to compile programs using traditional MVS data sets. You can use TSO commands or REXX execs to compile programs using z/OS UNIX files.

With each method, you need to allocate the data sets and request the compilation:

1. Use the ALLOCATE command to allocate data sets.

For any compilation, allocate the work data sets (SYSUT $n$ ) and the SYSIN and SYSPRINT data sets.

If you specify certain compiler options, you must allocate other data sets. For example, if you specify the TERMINAL compiler option, you must allocate the SYSTERM data set to receive compiler messages at your terminal.

You can allocate data sets in any order. However, you must allocate all needed data sets before you start to compile.

2. Use the CALL command at the READY prompt to request compilation:

```
CALL 'IGY.V6R1M0.SIGYCOMP(IGYCRCTL)'
```

You can specify the ALLOCATE and CALL commands on the TSO command line, or, if you are not using z/OS UNIX files, you can include them in a CLIST.

You can allocate z/OS UNIX files for all the compiler data sets except the SYSUT $x$  utility data sets and the SYSLIB libraries. ALLOCATE statements have the following form:

```
Allocate File(SYSIN) Path('/u/myu/myap/std/prog2.cbl')
Pathopts(ORDONLY) Filedata(TEXT)
```

[“Example: ALLOCATE and CALL for compiling under TSO” on page 245](#)

[“Example: CLIST for compiling under TSO” on page 245](#)

## related references

[“Data sets used by the compiler under z/OS” on page 248](#)

## Example: ALLOCATE and CALL for compiling under TSO

The following example shows how to specify ALLOCATE and CALL commands when you are compiling under TSO.

```
[READY]
ALLOCATE FILE(SYSUT1) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT2) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT3) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT4) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT5) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT6) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT7) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT8) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT9) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT10) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT11) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT12) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT13) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT14) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSUT15) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSMDECK) CYLINDERS SPACE(1 1)
[READY]
ALLOCATE FILE(SYSPRINT) SYSOUT
[READY]
ALLOCATE FILE(SYSTEM) DATASET(*)
[READY]
ALLOCATE FILE(SYSLIN) DATASET(PROG2.OBJ) NEW TRACKS SPACE(3,3)
[READY]
ALLOCATE FILE(SYSIN) DATASET(PROG2.COBOL) SHR
[READY]
CALL 'IGY.V6R1M0.SIGYCOMP(IGYCRCTL)' 'LIST,NOCOMPILE(S),OBJECT,FLAG(E,E),TERMINAL'
      (COBOL listings and messages)
[READY]
FREE
FILE(SYSUT1,SYSUT2,SYSUT3,SYSUT4,SYSUT5,SYSUT6,SYSUT7,SYSUT8,SYSUT9,SYSUT10,SYSUT11,SYSUT12,
SYSUT13,SYSUT14,SYSUT15,SYSMDECK,SYSPRINT,SYSTEM,
SYSIN,SYSLIN)
[READY]
```

## Example: CLIST for compiling under TSO

The following example shows a CLIST for compiling under TSO. The FREE commands are not required. However, good programming practice dictates that you free files before you allocate them.

```
PROC 1 MEM
CONTROL LIST
FREE F(SYSUT1)
FREE F(SYSUT2)
FREE F(SYSUT3)
FREE F(SYSUT4)
FREE F(SYSUT5)
FREE F(SYSUT6)
FREE F(SYSUT7)
```

```

FREE F(SYSUT8)
FREE F(SYSUT9)
FREE F(SYSUT10)
FREE F(SYSUT11)
FREE F(SYSUT12)
FREE F(SYSUT13)
FREE F(SYSUT14)
FREE F(SYSUT15)
FREE F(SYSMDECK)
FREE F(SYSPRINT)
FREE F(SYSIN)
FREE F(SYSLIN)
ALLOC F(SYSPRINT) SYSOUT
ALLOC F(SYSIN) DA(COBOL.SOURCE(&MEM)) SHR REUSE
ALLOC F(SYSLIN) DA(COBOL.OBJECT(&MEM)) OLD REUSE
ALLOC F(SYSUT1) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT2) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT3) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT4) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT5) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT6) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT7) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT8) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT9) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT10) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT11) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT12) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT13) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT14) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSUT15) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
ALLOC F(SYSMDECK) NEW SPACE(1,1) CYL UNIT(SYSALLDA)
CALL 'IGY.V6R1M0.SIGYCOMP(IGYCRCTL)'

```

## related references

*TSO/E Command Reference*

## Starting the compiler from an assembler program

You can start the Enterprise COBOL compiler from within an assembler program by using the ATTACH or the LINK macro by dynamic invocation. You must identify the compiler options and the ddnames of the data sets to be used during processing.

For example:

```
symbol {LINK|ATTACH} EP=IGYCRCTL,PARAM=(optionlist[,ddnamelist]),VL=1
```

### EP

Specifies the symbolic name of the compiler. The control program (from the library directory entry) determines the entry point at which the program should begin running.

### PARAM

Specifies, as a sublist, address parameters to be passed from the assembler program to the compiler.

The first fullword in the address parameter list contains the address of the COBOL *optionlist*. The second fullword contains the address of the *ddnamelist*.

### optionlist

Specifies the address of a variable-length list that contains the COBOL options specified for compilation. This address must be written even if no list is provided.

The *optionlist* must begin on a halfword boundary. The 2 high-order bytes contain a count of the number of bytes in the remainder of the list. If no options are specified, the count must be zero. The *optionlist* is freeform, with each field separated from the next by a comma. No blanks or zeros should appear. The compiler recognizes only the first 100 characters.

### ddnamelist

Specifies the address of a variable-length list that contains alternative ddnames for the data sets used during compiler processing. If standard ddnames are used, the *ddnamelist* can be omitted.

The *ddnamelist* must begin on a halfword boundary. The 2 high-order bytes contain a count of the number of bytes in the remainder of the list. Each name of less than 8 bytes must be left justified and

padding with blanks. If an alternate ddname is omitted from the list, the standard name is assumed. If the name is omitted, the 8-byte entry must contain binary zeros. You can omit names from the end by shortening the list.

All SYSUT*n* data sets specified must be on direct-access storage devices and have physical sequential organization. They must not reside in the z/OS UNIX file system.

The following table shows the sequence of the 8-byte entries in the *ddnamelist*.

Alternative ddname 8-byte entry	Name for which alternative ddname is substituted
1	SYSLIN
2	Not applicable
3	Not applicable
4	SYSLIB
5	SYSIN
6	SYSPRINT
7	SYSPUNCH
8	SYSUT1
9	SYSUT2
10	SYSUT3
11	SYSUT4
12	SYSTEM
13	SYSUT5
14	SYSUT6
15	SYSUT7
16	SYSADATA
17	SYSJAVA
18	Not applicable
19	SYSMDECK
20	DBRMLIB
21	SYSOPTF
22	SYSUT8
23	SYSUT9
24	SYSUT10
25	SYSUT11
26	SYSUT12
27	SYSUT13
28	SYSUT14
29	SYSUT15

#### VL

Specifies that the sign bit is to be set to 1 in the last fullword of the address parameter list.

When the compiler completes processing, it puts a return code in register 15.

#### related tasks

[“Defining compiler input and output” on page 248](#)

#### related references

[“Data sets used by the compiler under z/OS” on page 248](#)

[“Compiler options and compiler output under z/OS” on page 257](#)

## Defining compiler input and output

You need to define several kinds of data sets that the compiler uses to do its work. The compiler takes input data sets and libraries and produces various types of output, including object code, listings, and messages. The compiler also uses utility data sets during compilation.

#### related tasks

[“Defining the source code data set \(SYSIN\)” on page 251](#)

[“Defining a compiler-option data set \(SYSOPTF\)” on page 252](#)

[“Specifying source libraries \(SYSLIB\)” on page 252](#)

[“Defining the output data set \(SYSPRINT\)” on page 253](#)

[“Directing compiler messages to your terminal \(SYSTEM\)” on page 253](#)

[“Creating object code \(SYSLIN or SYSPUNCH\)” on page 253](#)

[“Defining an associated-data file \(SYSADATA\)” on page 254](#)

[“Defining the Java-source output file \(SYSJAVA\)” on page 254](#)

[“Defining the library-processing output file \(SYSMDECK\)” on page 254](#)

#### related references

[“Data sets used by the compiler under z/OS” on page 248](#)

[“Compiler options and compiler output under z/OS” on page 257](#)

## Data sets used by the compiler under z/OS

The following table lists the function, device requirements, and allowable device classes for each data set that the compiler uses.

Table 34. <i>Compiler data sets</i>						
Type	ddname	Function	Required?	Device requirements	Allowable device classes	Can be in z/OS UNIX file system?
Input	SYSIN <sup>1</sup>	Reading source program	Yes	Card reader; intermediate storage	Any	Yes
	SYSOPTF	Reading compiler options	If OPTFILE is in effect	Card reader; intermediate storage; direct access	Any	Yes
	SYSLIB or other copy libraries <sup>1</sup>	Reading user source libraries (PDSs or PDSEs)	If program has COPY or BASIS statements	Direct access	SYSDA	No

Table 34. **Compiler data sets** (continued)

Type	ddname	Function	Required?	Device requirements	Allowable device classes	Can be in z/OS UNIX file system?
Utility <sup>2</sup>	SYSUT1, SYSUT2, SYSUT3, SYSUT4, SYSUT6	Work data set used by compiler during compilation	Yes	Direct access	SYSALLDA	No
	SYSUT5	Work data set used by compiler during compilation	If program has COPY, REPLACE, or BASIS statements	Direct access	SYSALLDA	No
	SYSUT7	Work data set used by compiler to create listing	Yes	Direct access	SYSALLDA	No
	SYSUT8, SYSUT9, SYSUT10, SYSUT11, SYSUT12, SYSUT13, SYSUT14, SYSUT15	Work data set used by compiler during compilation	Yes	Direct access	SYSALLDA	No

Table 34. **Compiler data sets** (continued)

Type	ddname	Function	Required?	Device requirements	Allowable device classes	Can be in z/OS UNIX file system?
Output	SYSPRINT <sup>1</sup>	Writing storage map, listings, and messages	Yes	Printer; intermediate storage	SYSSQ, SYSDA, standard output class A	Yes
	SYSTEM	Writing progress and diagnostic messages	If TERM is in effect	Output device; TSO terminal		Yes
	SYPUNCH	Creating object code	If DECK is in effect	Card punch; direct access	SYSSQ, SYSDA	Yes
	SYSLIN	Creating object module data set as output from compiler and input to binder (linkage-editor)	If OBJECT is in effect	Direct access	SYSSQ, SYSDA	Yes
	SYSADATA <sup>1</sup>	Writing associated data file records	If ADATA is in effect	Output device		Yes
	SYSJAVA	Creating generated Java source file for a class definition	If compiling a class definition	(Must be a z/OS UNIX file)		Yes
	SYSUDUMP, SYSABEND, or SYSMDUMP	Writing dump	If DUMP is in effect (should be rarely used)	Direct access	SYSDA	Yes
	SYSMDECK	Processing for the MDECK option, or a work data set if NOMDECK is specified.	Yes	Direct access	SYSALLDA	Yes
<p>1. You can use the EXIT option to provide user exits from these data sets.</p> <p>2. Utility data sets must be single volume, and cannot have DSNTYPE=LARGE (SYSUT1 - SYSUT15).</p>						

#### related references

[“Logical record length and block size” on page 250](#)

[“EXIT” on page 305](#)

## Logical record length and block size

For compiler data sets other than the work data sets (SYSUT $n$ ) and z/OS UNIX files, you can set the block size by using the BLKSIZE subparameter of the DCB parameter. The value must be permissible for the

device on which the data set resides. The values you set depend on whether the data sets are fixed length or variable length.

For fixed-length records (RECFM=F or RECFM=FB), LRECL is the logical record length; and BLKSIZE equals LRECL multiplied by  $n$  where  $n$  is equal to the blocking factor.

The following table shows the defined values for the fixed-length data sets. In general, you should not change these values, but you can change the value for the SYSPRINT data set. You can specify BLKSIZE=0, which results in a system-determined block size.

<i>Table 35. Block size of fixed-length compiler data sets</i>			
Data set	RECFM	LRECL (bytes)	BLKSIZE <sup>1</sup>
SYSIN	F or FB	80	$80 \times n$
SYSLIB or other copy libraries	F or FB	80	$80 \times n$
SYSLIN	F or FB	80	$80 \times n$
SYSMDECK	F or FB	80	$80 \times n$
SYSOPTF	F or FB	80	$80 \times n$
SYSPRINT <sup>2</sup>	F or FB	133	$133 \times n$
SYSPUNCH	F or FB	80	$80 \times n$
SYSTEM	F or FB	80	$80 \times n$
1. $n$ = blocking factor 2. If you specify BLKSIZE=0, the system determines the block size.			

For variable-length records (RECFM=V), LRECL is the logical record length, and BLKSIZE equals LRECL plus 4.

<i>Table 36. Block size of variable-length compiler data sets</i>			
Data set	RECFM	LRECL (bytes)	BLKSIZE (bytes) minimum acceptable value
SYSADATA	VB	1020	1024

## Defining the source code data set (SYSIN)

Define the data set that contains your source code by using the SYSIN DD statement as shown below.

```
//SYSIN DD DSN=dsname,UNIT=SYSSQ,VOLUME=(subparms),DISP=SHR
```

You can place your source code or BASIS statement directly in the input stream. To do so, use this SYSIN DD statement:

```
//SYSIN DD *
```

The source code or BASIS statement must follow the DD \* statement. If another job step follows the compilation, the EXEC statement for that step must follow the /\* statement or the last source statement.

## Defining a compiler-option data set (SYSOPTF)

Define a data set that contains the compiler options for your COBOL program by coding the SYSOPTF DD statement as shown below.

```
//SYSOPTF DD DSN=dsname,UNIT=SYSDA,VOLUME=(subparms),DISP=SHR
```

To use a compiler-option data set, specify OPTFILE either as a compiler invocation option or in a PROCESS or CBL statement in your source program.

Within the SYSOPTF data set:

- Specify compiler options in free form between columns 2 and 72, using the same syntax as you use for invocation options or for compiler options in a PROCESS or CBL statement.
- Code an asterisk (\*) in column 1 to cause a line to be treated as a comment.
- Optionally code sequence numbers in columns 73 through 80; those columns are ignored.

You can optionally place the compiler options directly in the input stream after the SYSOPTF DD statement if you compile using the OPTFILE option:

```
//COB      EXEC PGM=IGYCRCTL,PARM='OPTFILE'  
//SYSOPTF DD DATA,DLM=@@  
SSRANGE   ARITH(COMPAT)  
OPTIMIZE  
.  
.  
.  
@@  
//SYSIN    DD . . .
```

You can concatenate multiple SYSOPTF DD statements if you have multiple compiler-option data sets:

```
//SYSOPTF DD DSN=dsname1, . . .  
//        DD DSN=dsname2, . . .
```

Compiler options that are in later data sets in the concatenation take precedence over options in earlier data sets in the concatenation.

### related references

[“Logical record length and block size” on page 250](#)

[“OPTFILE” on page 324](#)

## Specifying source libraries (SYSLIB)

Use SYSLIB DD statements if your program contains COPY or BASIS statements. These DD statements define the libraries (partitioned data sets) that contain the data requested by COPY statements in the source code or by BASIS statements in the input stream.

```
//SYSLIB DD DSN=copylibname,DISP=SHR
```

Concatenate multiple DD statements if you have multiple copy or basis libraries:

```
//SYSLIB DD DSN=PROJECT.USERLIB,DISP=SHR  
//        DD DSN=SYSTEM.COPYX,DISP=SHR
```

Libraries are on direct-access storage devices. They cannot be in the z/OS UNIX file system when you compile with JCL or under TSO.

## Defining the output data set (SYSPRINT)

You can use ddname SYSPRINT to produce a listing. The listing includes the results of the default or requested options of the PARM parameter (that is, diagnostic messages and the object-code listing).

You can direct the output to a SYSOUT data set, a printer, a direct-access storage device, or a magnetic-tape device. For example:

```
//SYSPRINT DD SYSOUT=A
```

The SYSPRINT data set can be a sequential data set, a PDS or PDSE member, or a z/OS UNIX file. For details about how to specify the record format, record length, and block size of the SYSPRINT data set, see the related reference below.

### related references

[“Logical record length and block size” on page 250](#)

## Directing compiler messages to your terminal (SYSTEM)

If you are compiling under TSO, you can define the SYSTEM data set to send compiler messages to your terminal.

```
ALLOC F(SYSTEM) DA(*)
```

You can define SYSTEM in various other ways, for example to a SYSOUT data set, a data set on disk, a file in the z/OS UNIX file system, or to another print class.

## Creating object code (SYSLIN or SYSPUNCH)

When using the OBJECT compiler option, you can store the object code on disk as a traditional MVS data set or a z/OS UNIX file, or on tape. The compiler uses the file that you define in the SYSLIN or SYSPUNCH DD statement.

```
//SYSLIN DD DSNAME=dsname,UNIT=SYSDA,  
// SPACE=(subparms),DISP=(MOD,PASS)
```

Use the DISP parameter of the SYSLIN DD statement to indicate whether the object code data set is to be:

- Passed to the binder (linkage-editor)
- Cataloged
- Kept
- Added to an existing cataloged library

In the example above, the data is created and passed to another job step, the binder (linkage-editor) job step.

Your installation might use the DECK option and the SYSPUNCH DD statement. B is the standard output class for punch data sets:

```
//SYSPUNCH DD SYSOUT=B
```

You do not need the SYSLIN DD statement if the NOOBJECT option is in effect. You do not need the SYSPUNCH DD statement if the NODECK option is in effect.

### related references

[“OBJECT” on page 323](#)

[“DECK” on page 301](#)

## Defining an associated-data file (SYSADATA)

Define a SYSADATA file if you use the ADATA compiler option.

```
//SYSADATA DD DSNAME=dsname,UNIT=SYSDA
```

The SYSADATA file will be a sequential file that contains specific record types that have information about the program that is collected during compilation. The file can be a traditional MVS data set or a z/OS UNIX file.

### related references

[“ADATA” on page 288](#)

## Defining the Java-source output file (SYSJAVA)

Add the SYSJAVA DD statement if you are compiling an OO program. The generated Java source file is written to the SYSJAVA ddname.

```
//SYSJAVA DD PATH='/u/userid/java/Classname.java',  
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),  
// PATHMODE=SIRWXU,  
// FILEDATA=TEXT
```

The SYSJAVA file must be in the z/OS UNIX file system.

### related tasks

[“Compiling OO applications in JCL or TSO/E” on page 277](#)

## Defining the library-processing output file (SYSMDECK)

The SYSMDECK DD allocation is required for all compilations. If you specify the MDECK compiler option, the SYSMDECK DD allocation must specify a permanent MVS data set or a z/OS UNIX file. However, if you use the NOMDECK option, SYSMDECK can alternatively be specified as a utility (temporary) data set.

The following example specifies a permanent dataset name:

```
//SYSMDECK DD DSNAME=dsname,UNIT=SYSDA
```

The following example specifies a z/OS UNIX file:

```
//SYSMDECK DD PATH='/path/filename.dek',  
//FILEDATA=TEXT,  
//PATHOPTS=(ORDWR,OCREAT,OTRUNC),  
//PATHMODE=(SIRUSR,SIWUSR)
```

The following example specifies a utility (temporary) data set:

```
//SYSMDECK DD UNIT=SYSALLDA
```

The SYSMDECK file will contain a copy of the updated input source after library processing, that is, the result of COPY, BASIS, REPLACE, EXEC SQL INCLUDE, and EXEC SQLIMS INCLUDE statements.

### related references

[“MDECK” on page 318](#)

## Specifying compiler options under z/OS

---

The compiler is installed with default compiler options. While installing the compiler, the system programmer can fix compiler option settings to, for example, ensure better performance or maintain certain standards. You cannot override any compiler options that are fixed.

For options that are not fixed, you can override the default settings by specifying compiler options in any of these ways:

- Code them on the PROCESS or CBL statement in COBOL source.
- Include them when you start the compiler, either on the PARM parameter on the EXEC statement in the JCL or on the command line under TSO.
- Include them in a SYSOPTF data set, and specify the OPTFILE compiler option in either of the above ways.

The compiler recognizes the options in the following order of precedence from highest to lowest:

1. Installation defaults that are fixed by your site
2. Values of the BUFSIZE, OUTDD, SQL, and SQLIMS compiler options in effect for the first program in a batch
3. Options specified on PROCESS (or CBL) statements, preceding the IDENTIFICATION DIVISION
4. Options specified on the compiler invocation (JCL PARM parameter or the TSO CALL command)
5. Installation defaults that are not fixed

This order of precedence also determines which options are in effect when conflicting or mutually exclusive options are specified.

The precedence of options in a SYSOPTF data set depends on where you specify the OPTFILE compiler option. For example, if you specify OPTFILE in a PROCESS statement, the SYSOPTF options supersede the options that you specify in the compiler invocation. For further details, see the related reference below about the OPTFILE option.

Most of the options come in pairs; you select one or the other. For example, the option pair for a cross-reference listing is XREF|NOXREF. If you want a cross-reference listing, specify XREF; if you do not, specify NOXREF.

Some options have subparameters. For example, if you want 44 lines per page on your listings, specify LINECOUNT (44).

[“Example: specifying compiler options using JCL” on page 256](#)

[“Example: specifying compiler options under TSO” on page 256](#)

### **related tasks**

[“Defining a compiler-option data set \(SYSOPTF\)” on page 252](#)

[“Specifying compiler options](#)

[in the PROCESS \(CBL\) statement” on page 256](#)

[“Specifying compiler options in a batch compilation” on page 259](#)

### **related references**

[“Compiler options and compiler output under z/OS” on page 257](#)

[Chapter 17, “Compiler options,” on page 283](#)


[“Conflicting compiler options” on page 287](#)

[“OPTFILE” on page 324](#)

## Specifying compiler options in the PROCESS (CBL) statement

Within a COBOL program, you can code most compiler options in PROCESS (CBL) statements. Code the statements before the IDENTIFICATION DIVISION header and before any comment lines or compiler-directing statements.

### PROCESS(CBL) statement syntax



If you do not use a sequence field, you can start a PROCESS statement in column 1 or after. If you use a sequence field, the sequence number must start in column 1 and must contain six characters; the first character must be numeric. If used with a sequence field, PROCESS can start in column 8 or after.

You can use CBL as a synonym for PROCESS. CBL can likewise start in column 1 or after if you do not use a sequence field. If used with a sequence field, CBL can start in column 8 or after.

You must end PROCESS and CBL statements at or before column 72.

Use one or more blanks to separate a PROCESS or CBL statement from the first option in *options-list*. Separate options with a comma or a blank. Do not insert spaces between individual options and their suboptions.

You can code more than one PROCESS or CBL statement. If you do so, the statements must follow one another with no intervening statements. You cannot continue options across multiple PROCESS or CBL statements.

Your programming organization can inhibit the use of PROCESS (CBL) statements by using the default options module of the COBOL compiler. If PROCESS or CBL statements that are not allowed by the organization are found in a COBOL program, the COBOL compiler generates error diagnostics.

### related references

Reference format (*Enterprise COBOL for z/OS Language Reference*)

CBL (PROCESS) statement (*Enterprise COBOL for z/OS Language Reference*)

## Example: specifying compiler options using JCL

The following example shows how to specify compiler options under z/OS using JCL.

```
//STEP1      EXEC PGM=IGYCRCTL,
//              PARM='LIST,NOCOMPILE(S),OBJECT,FLAG(E,E)'
```

## Example: specifying compiler options under TSO

The following example shows how to specify compiler options under TSO.

```
[READY]
CALL 'SYS1.LINKLIB(IGYCRCTL)' 'LIST,NOCOMPILE(S),OBJECT,FLAG(E,E)'
```

## Compiler options and compiler output under z/OS

When the compiler finishes processing your source program, it will have produced one or more outputs, depending on the compiler options that were in effect.

<i>Table 37. Types of compiler output under z/OS</i>		
Compiler option	Compiler output	Type of output
ADATA	Information about the program being compiled	Associated-data file
DLL	Object module that is enabled for DLL support	Object
DUMP	System dump, if compilation ended with abnormal termination (requires SYSUDUMP, SYSABEND, or SYSDUMP DD statement); should be used rarely	Listing
EXPORTALL	Exported symbols for a DLL	Object
FLAG	List of errors that the compiler found in your program	Listing
LIST	Listing of object code in machine and assembler language	Listing
MAP (HEX) or MAP (DEC)	Map of the data items in your program	Listing
MDECK	Expansion of library-processing statements in your program	Library-processing side file
NUMBER	User-supplied line numbers shown in listing	Listing
OBJECT or DECK with COMPILE	Your object code	Object
OFFSET	Map of the relative addresses in your object code	Listing
OPTIMIZE (1) or OPTIMIZE (2)	Optimized object code	Object
RENT	Reentrant object code	Object
SOURCE	Listing of your source program	Listing
SQL	SQL statements and host variable information for DB2® bind process	Database request module (DBRM)
TERMINAL	Progress and diagnostic messages sent to terminal	Terminal
TEST	DWARF format debugging information in the object module, to enable interactive debugging	Object
NOTEST (DWARF)	Basic DWARF format diagnostic information, to enable application failure analysis tools	Object
VBREF	Cross-reference listing of statements in your source program	Listing
XREF	Sorted cross-reference listing of names of procedures, programs, and data	Listing

Listing output from compilation will be in the data set defined by SYSPRINT; object output will be in SYSLIN or SYSPUNCH. Progress and diagnostic messages can be directed to the SYSTERM data set and included in the SYSPRINT data set. The database request module (DBRM) is the data set defined in DBRMLIB.

Save the listings you produced during compilation. You can use them during the testing of your work if you need to debug or tune. You might also use the listings for diagnosis and debugging after the application is in production.

After compilation, fix any errors that the compiler found in your program. If no errors were detected, you can go to the next step in the process: binding (link-editing) your program. (If you used compiler options to suppress object code generation, you must recompile to obtain object code.)

#### **related tasks**

*Language Environment Programming Guide* (Preparing to link-edit and run)

#### **related references**

[“Messages and listings for compiler-detected errors” on page 262](#)

[Chapter 17, “Compiler options,” on page 283](#)

## **Compiling multiple programs (batch compilation)**

---

You can compile a sequence of separate COBOL programs by using a single invocation of the compiler. You can link the object program produced from this compilation into one program object or separate program objects, controlled by the NAME compiler option.

When you compile several programs as part of a batch job, you need to:

- Determine whether you want to create one or more program objects.
- Terminate each program in the sequence.
- Specify compiler options, with an awareness of the effect of compiler options specified in programs within the batch job.

To create separate program objects, precede each set of objects with the NAME compiler option. When the compiler encounters the NAME option, the first program in the sequence and all subsequent programs until the next NAME compiler option is encountered are link-edited into a single program object. Then each successive program that is compiled with the NAME option is included in a separate program object.

Use the END PROGRAM marker to terminate each program in the sequence except the last program in the batch (for which the END PROGRAM marker is optional). Alternatively, you can precede each program in the sequence with a CBL or PROCESS statement.

If you omit the END PROGRAM marker from a program (other than the last program in a sequence of separate programs), the next program in the sequence will be nested in the preceding program. An error can occur in either of the following situations:

- A PROCESS statement is in a program that is now nested.
- A CBL statement is not coded entirely in the sequence number area (columns 1 through 6).

If a CBL statement is coded entirely in the sequence number area (columns 1 through 6), no error message is issued for the CBL statement because it is considered a label for the source statement line.

[“Example: batch compilation” on page 258](#)

#### **related tasks**

[“Specifying compiler options in a batch compilation” on page 259](#)

#### **related references**

[“NAME” on page 319](#)

## **Example: batch compilation**

The following example shows a batch compilation for three programs (PROG1, PROG2, and PROG3) and the creation of two program objects using one invocation of the IGYWCL cataloged procedure.

The following steps occur:

- PROG1 and PROG2 are link-edited together to form one program object that has the name PROG2. The entry point of this program object defaults to the first program in the program object, PROG1.
- PROG3 is link-edited by itself into a program object that has the name PROG3. Because it is the only program in the program object, the entry point is also PROG3.

```
//jobname JOB acctno,name,MSGLEVEL=1
//stepname EXEC IGYWCL
//COBOL.SYSIN DD *
010100 IDENTIFICATION DIVISION.
010200 PROGRAM-ID PROG1.

019000 END PROGRAM PROG1.
020100 IDENTIFICATION DIVISION.
020200 PROGRAM-ID PROG2.

029000 END PROGRAM PROG2.
CBL NAME
030100 IDENTIFICATION DIVISION.
030200 PROGRAM-ID PROG3.

039000 END PROGRAM PROG3.
/*
//LKED.SYSLMOD DD DSN=&&G0SET (1)
/*
//P2 EXEC PGM=PROG2
//STEPLIB DD DSN=&&G0SET,DISP=(SHR,PASS) (2)
. . . (3)
/*
//P3 EXEC PGM=PROG3
//STEPLIB DD DSN=&&G0SET,DISP=(SHR,PASS) (2)
. . . (4)
/*
//
```

(1)

The data-set name for the LKED step SYSLMOD is changed to the temporary name &&G0SET, without any member name.

(2)

The temporary data set &&G0SET is used as the STEPLIB for steps P2 and P3 to run the compiled programs. If the Language Environment library does not reside in shared storage, you must also add the library data set as a DD statement for STEPLIB.

(3)

Other DD statements and input that are required to run PROG1 and PROG2 must be added.

(4)

Other DD statements and input that are required to run PROG3 must be added.

#### related references

*Language Environment Programming Guide* (IBM-supplied cataloged procedures)

## Specifying compiler options in a batch compilation

You can specify compiler options for each program in the batch sequence either with a CBL or PROCESS statement that precedes the program, or upon invocation of the compiler.

If a CBL or PROCESS statement is specified in the current program, the compiler resolves the CBL or PROCESS statements together with the options in effect before the first program. If the current program does not contain CBL or PROCESS statements, the compiler uses the settings of options in effect for the previous program.

You should be aware of the effect of certain compiler options on the precedence of compiler option settings for each program in the batch sequence. Compiler options are recognized in the following order of precedence, from highest to lowest:

1. Installation defaults that are fixed at your site

2. Values of the BUFSIZE, OUTDD, SQL, SQLIMS, and TEST compiler options in effect for the first program in the batch
3. Options on CBL or PROCESS statements, if any, for the current program
4. Options specified in the compiler invocation (JCL PARM or TSO CALL)
5. Installation defaults that are not fixed

If any program in the batch sequence requires the BUFSIZE, OUTDD, SQL, SQLIMS, or TEST option, that option must be in effect for the first program in the batch sequence. (When processing BASIS, COPY, or REPLACE statements, the compiler handles all programs in the batch as a single input file.)

If you specify the option for the batch, you cannot change the NUMBER and SEQUENCE options during the batch compilation. The compiler treats all programs in the batch as a single input file during NUMBER and SEQUENCE processing under the option; therefore, the sequence numbers of the entire input file must be in ascending order.

If the compiler diagnoses the LANGUAGE option on the CBL or PROCESS statement as an error, the language selection reverts to what was in effect before the compiler encountered the first CBL or PROCESS statement. The language in effect during a batch compilation conforms to the rules of processing CBL or PROCESS statements in that environment.

[“Example: precedence of options in a batch compilation” on page 260](#)

[“Example: LANGUAGE option in a batch compilation” on page 261](#)

## Example: precedence of options in a batch compilation

The following example listing shows the precedence of compiler options for batch compilation.

```
PP 5655-EC6 IBM Enterprise COBOL for z/OS 6.1.0 P160211 Date 03/18/2016. . .
Invocation parameters:
NOTERM
PROCESS(CBL) statements:
CBL CURRENCY,FLAG(I,I)
Options in effect: All options are installation defaults unless otherwise noted:
    NOADATA
    ADV
    QUOTE
    ARITH(COMPAT)
    NOAWO
    NOBLOCK0
    BUFSIZE(4096)
    . . .
    CURRENCY      Process option PROGRAM 1
    . . .
    FLAG(I,I)     Process option PROGRAM 1
    . . .
    NOTERM        INVOCATION option
    . . .
End of compilation for program 1
. . .
```

```
PP 5655-EC6 IBM Enterprise COBOL for z/OS 6.1.0 P160211 Date 03/18/2016. . .
PROCESS(CBL) statements:
CBL APOST
Options in effect:
    NOADATA
    ADV
    APOST         Process option PROGRAM 2
    ARITH(COMPAT)
    NOAWO
    NOBLOCK0
    BUFSIZE(4096)
    . . .
    NOCURRENCY    Installation default option for PROGRAM 2
    . . .
    FLAG(I)       Installation default option
```

```
NOTERM          INVOCATION option remains in effect
End of compilation for program 2
```

## Example: LANGUAGE option in a batch compilation

The following example shows the behavior of the LANGUAGE compiler option in a batch environment. The default installation option is ENGLISH (abbreviated EN), and the invocation option is XX, a nonexistent language.

```
CBL LANG(JP),FLAG(I,I),APOST  (1)
  IDENTIFICATION DIVISION.      (2)
  PROGRAM-ID.  COMPILE1.

  END PROGRAM  COMPILE1.
CBL LANGUAGE(YY)                (3)
CBL LANGUAGE(JP),LANG(!!)      (4)
  IDENTIFICATION DIVISION.      (2)
  PROGRAM-ID.  COMPILE2.

  END PROGRAM  COMPILE2.
  IDENTIFICATION DIVISION.
  PROGRAM-ID.  COMPILE3.

  END PROGRAM  COMPILE3.
CBL LANGUAGE(JP),LANGUAGE(YY)  (5)
  . . .
```

- (1) The installation default is EN. The invocation option was XX, a nonexistent language. EN is the language in effect.
- (2) After the CBL statement is scanned, JP is the language in effect.
- (3) CBL resets the language to EN. YY is ignored because it is superseded by JP.
- (4) !! is not alphanumeric and is discarded.
- (5) CBL resets the language to EN. YY supersedes JP but is nonexistent.

For the program COMPILE1, the default language English (EN) is in effect when the compiler scans the invocation options. A diagnostic message is issued in mixed-case English because XX is a nonexistent language identifier. The default EN remains in effect when the compiler scans the CBL statement. The unrecognized option APOST in the CBL statement is diagnosed in mixed-case English because the CBL statement has not completed processing and EN was the last valid language option. After the compiler processes the CBL options, the language in effect becomes Japanese (JP).

In the program COMPILE2, the compiler diagnoses CBL statement errors in mixed-case English because English is the language in effect before the first program is used. If more than one LANGUAGE option is specified, only the last valid language specified is used. In this example, the last valid language is Japanese (JP). Therefore Japanese becomes the language in effect when the compiler finishes processing the CBL options. If you want diagnostics in Japanese for the options in the CBL and PROCESS statements, the language in effect before COMPILE1 must be Japanese.

The program COMPILE3 has no CBL statement. It inherits the language in effect, Japanese (JP), from the previous compilation.

After compiling COMPILE3, the compiler resets the language in effect to English (EN) because of the CBL statement. The language option in the CBL statement resolves the last-specified two-character alphanumeric language identifier, YY. Because YY is nonexistent, the language in effect remains English.

## Correcting errors in your source program

---

Messages about source-code errors indicate where the error occurred (LINEID). The text of a message tells you what the problem is. With this information, you can correct the source program.

Although you should try to correct errors, it is not always necessary to correct source code for every diagnostic message. You can leave a warning-level or informational-level message in a program without much risk, and you might decide that the recoding and compilation that are needed to remove the message are not worth the effort. Severe-level and error-level errors, however, indicate probable program failure and should be corrected.

In contrast with the four lower levels of severities, an unrecoverable (U-level) error might not result from a mistake in your source program. It could come from a flaw in the compiler itself or in the operating system. In such cases, the problem must be resolved, because the compiler is forced to end early and does not produce complete object code or a complete listing. If the message occurs for a program that has many S-level syntax errors, correct those errors and compile the program again. You can also resolve job set-up problems (such as missing data-set definitions or insufficient storage for compiler processing) by making changes to the compile job. If your compile job setup is correct and you have corrected the S-level syntax errors, you need to contact IBM to investigate other U-level errors.

After correcting the errors in your source program, recompile the program. If this second compilation is successful, proceed to the link-editing step. If the compiler still finds problems, repeat the above procedure until only informational messages are returned.

### **related tasks**

[“Generating a list of compiler messages” on page 262](#)

### **related references**

[“Messages and listings for compiler-detected errors” on page 262](#)

## Generating a list of compiler messages

You can generate a complete listing of compiler diagnostic messages with their message numbers, severities, and text by compiling a program that has program-name ERRMSG.

You can code just the PROGRAM-ID paragraph, as shown below, and omit the rest of the program.

```
Identification Division.  
Program-ID. ErrMsg.
```

### **related tasks**

[“Customizing compiler-message severities” on page 693](#)

### **related references**

[“Messages and listings for compiler-detected errors” on page 262](#)

[“Format of compiler diagnostic messages” on page 263](#)

## Messages and listings for compiler-detected errors

As the compiler processes your source program, it checks for COBOL language errors, and issues diagnostic messages. These messages are collated in the compiler listing (subject to the FLAG option).

Each message in the listing provides information about the nature of the problem, its severity, and the compiler phase that detected it. Wherever possible, the message provides specific instructions for correcting an error.

The messages for errors found during processing of compiler options, CBL and PROCESS statements, and BASIS, COPY, or REPLACE statements are displayed near the top of the listing.

The messages for compilation errors (ordered by line number) are displayed near the end of the listing for each program.

A summary of all problems found during compilation is displayed near the bottom of the listing.

#### related tasks

[“Correcting errors in your source program” on page 262](#)

[“Generating a list of compiler messages” on page 262](#)

#### related references

[“Format of compiler diagnostic messages” on page 263](#)

[“Severity codes for compiler diagnostic messages” on page 263](#)

[“FLAG” on page 308](#)

## Format of compiler diagnostic messages

Each message issued by the compiler has a source line number, a message identifier, and message text.

Each message has the following form:

```
nnnnnn IGYppxxxx-l message-text
```

#### nnnnnn

The number of the source statement of the last line that the compiler was processing. Source statement numbers are listed on the source printout of your program. If you specified the **NUMBER** option at compile time, the numbers are the original source program numbers. If you specified **NONUMBER**, the numbers are those generated by the compiler.

#### IGY

A prefix that identifies that the message was issued by the COBOL compiler.

#### pp

Two characters that identify which phase or subphase of the compiler detected the condition that resulted in a message. As an application programmer, you can ignore this information. If you are diagnosing a suspected compiler error, contact IBM for support and include this information.

#### xxxx

A four-digit number that identifies the message.

#### l

A character that indicates the severity level of the message: I, W, E, S, or U.

#### message-text

The message text; for an error message, a short explanation of the condition that caused the error.

**Tip:** If you used the **FLAG** option to suppress messages, there might be additional errors in your program.

#### related references

[“Severity codes for compiler diagnostic messages” on page 263](#)

[“FLAG” on page 308](#)

## Severity codes for compiler diagnostic messages

Conditions that the compiler can detect fall into five levels or categories of severity.

Table 38. <i>Severity codes for compiler diagnostic messages</i>		
Level or category of message	Return code	Purpose
Informational (I)	0	To inform you. No action is required, and the program runs correctly.
Warning (W)	4	To indicate a possible error. The program probably runs correctly as written.

*Table 38. Severity codes for compiler diagnostic messages (continued)*

Level or category of message	Return code	Purpose
Error (E)	8	To indicate a condition that is definitely an error. The compiler attempted to correct the error, but the results of program execution might not be what you expect. You should correct the error.
Severe (S)	12	To indicate a condition that is a serious error. The compiler was unable to correct the error. The program does not run correctly, and execution should not be attempted. Object code might not be created.
Unrecoverable (U)	16	To indicate an error condition of such magnitude that the compilation was terminated.

The final return code at the end of compilation is generally the highest return code that occurred for any message during the compilation.

You can suppress compiler diagnostic messages or change their severities, however, which can have an effect upon the final compilation return code. For details, see the related information.

#### **related tasks**

[“Customizing compiler-message severities” on page 693](#)

#### **related references**

[“Processing of MSGEXIT” on page 691](#)

---

## Chapter 15. Compiling under z/OS UNIX

Compile Enterprise COBOL programs under z/OS UNIX by using the `cob2` command. Under z/OS UNIX, you can compile any COBOL program that you can compile under z/OS. The object code generated by the COBOL compiler can run under z/OS.

As part of the compilation step, you define the files needed for the compilation, and specify any compiler options or compiler-directing statements that are necessary for your program and for the output that you want.

The main job of the compiler is to translate COBOL programs into language that the computer can process (object code). The compiler also lists errors in source statements and provides supplementary information to help you debug and tune programs.

### related tasks

[“Setting environment variables under z/OS UNIX” on page 265](#)

[“Specifying compiler options under z/OS UNIX” on page 266](#)

[“Compiling and linking with the `cob2` command” on page 267](#)

[“Compiling using scripts” on page 271](#)

[“Compiling, linking, and running OO applications under z/OS UNIX” on page 273](#)

### related references

[“Data sets used by the compiler under z/OS” on page 248](#)

[“Compiler options and compiler output under z/OS” on page 257](#)

---

## Setting environment variables under z/OS UNIX

An *environment variable* is a name that is associated with a string of characters and that defines some variable aspect of the program environment. You use environment variables to set values that programs, including the compiler, need.

Set the environment variables for the compiler by using the `export` command. For example, to set the `SYSLIB` variable, issue the `export` command from the shell or from a script file:

```
export SYSLIB=/u/mystuff/copybooks
```

The value that you assign to an environment variable can include other environment variables or the variable itself. The values of these variables apply only when you compile from the shell where you issue the `export` command. If you do not set an environment variable, either a default value is applied or the variable is not defined. The environment-variable names must be uppercase.

The environment variables that you can set for use by the compiler are as follows:

### COBOPT

Specify compiler options separated by blanks or commas. Separate suboptions with commas. Blanks at the beginning or the end of the variable value are ignored. Delimit the list of options with quotation marks if it contains blanks or characters that are significant to the z/OS UNIX shell. For example:

```
export COBOPT="TRUNC(OPT) XREF"
```

### SYSLIB

Specify paths to directories to be used in searching for COBOL copybooks if you do not specify an explicit library-name in the `COPY` statement. Separate multiple paths with a colon. Paths are evaluated in order from the first path to the last in the `export` command. If you set the variable with multiple files of the same name, the first located copy of the file is used.

For COPY statements in which you have not coded an explicit library-name, the compiler searches for copybooks in this order:

1. In the current directory
2. In the paths you specify with the `-I cob2` option
3. In the paths you specify in the SYSLIB environment variable
4. In the locations specified in instances of the COPYLOC option that use the default library name or specify an explicit library name of SYSLIB

If the copybook is not found in any of the z/OS UNIX directories to be searched, and there are instances of the COPYLOC option specified without an explicit library name or specified with the library name SYSLIB, those locations are searched in the order that they were specified.

#### **library-name**

Specify the directory path from which to copy when you specify an explicit library-name in the COPY statement. The environment-variable name is identical to the *library-name* in your program. You must set an environment variable for each library; an error will occur otherwise. The environment-variable name *library-name* must be uppercase.

#### **text-name**

Specify the name of the file from which to copy text. The environment-variable name is identical to the *text-name* in your program. The environment-variable name *text-name* must be uppercase.

#### **related tasks**

[“Specifying compiler options under z/OS UNIX” on page 266](#)

[“Compiling and linking with the cob2 command” on page 267](#)

[“Setting and accessing environment variables” on page 436](#)

#### **related references**

Chapter 18, “Compiler-directing statements,” on page 357

Chapter 17, “Compiler options,” on page 283

COPY statement (*Enterprise COBOL for z/OS Language Reference*)

## **Specifying compiler options under z/OS UNIX**

---

The compiler is installed and set up with default compiler options. While installing the compiler, a system programmer can fix compiler option settings to ensure better performance or maintain certain standards. You cannot override any compiler options that your site has fixed.

For options that are not fixed, you can override the default settings by specifying compiler options in any of three ways:

- Code them on the PROCESS or CBL statement in your COBOL source.
- Specify the `-q` option of the cob2 command.
- Set the COBOPT environment variable.

The compiler recognizes the options in the above order of precedence, from highest to lowest. The order of precedence also determines which options are in effect when conflicting or mutually exclusive options are specified. When you compile using the cob2 command, compiler options are recognized in the following order of precedence, from highest to lowest:

1. Installation defaults fixed as nonoverridable
2. The values of BUFSIZE, SQL, SQLIMS, and OUTDD options in effect for the first program in a batch compilation
3. The values that you specify on PROCESS or CBL statements in COBOL source programs
4. The values that you specify in the cob2 command's `-q` option string
5. The values that you specify in the COBOPT environment variable
6. Installation defaults that are not fixed

**Restrictions:**

- Do not use the SQL compiler option under z/OS UNIX.  
Neither the separate SQL precompiler nor the integrated SQL coprocessor runs under z/OS UNIX.
- Do not use the SQLIMS compiler option under z/OS UNIX.
- The OPTFILE option is ignored when you compile using the cob2 command under z/OS UNIX.

You can use the COBOPT environment variable, which provides a capability that is comparable to OPTFILE, instead.

**related tasks**

[“Specifying compiler options in the PROCESS \(CBL\) statement” on page 256](#)  
[“Setting environment variables under z/OS UNIX” on page 265](#)  
[“Compiling and linking with the cob2 command” on page 267](#)

**related references**

[“Conflicting compiler options” on page 287](#)  
[Chapter 17, “Compiler options,” on page 283](#)

## Compiling and linking with the cob2 command

---

Use the cob2 command to compile and link COBOL programs from the z/OS UNIX shell. You can specify the options and input file-names in any order, using spaces to separate options and names. Any options that you specify apply to all files on the command line.

To compile multiple files (batch compilation), specify multiple source-file names.

When you compile COBOL programs for z/OS UNIX, the RENT option is required. The cob2 command automatically includes the COBOL compiler options RENT and TERM.

The cob2 command invokes the COBOL compiler that is found through the standard MVS search order. If the COBOL compiler is not installed in the LNKLIST, or if more than one level of IBM COBOL compiler is installed on your system, you can specify in the STEPLIB environment variable the compiler PDSE that you want to use. For example, the following statement specifies IGY.V6R1M0 as the compiler PDSE:

```
export STEPLIB=IGY.V6R1M0.SIGYCOMP
```

The cob2 command implicitly uses the z/OS UNIX shell command c89 for the link step. c89 is the shell interface to the linker (the z/OS program management binder).

The default location for compiler input and output is the current directory.

Only files with the suffix .cbl are passed to the compiler; cob2 passes all other files to the linker.

The listing output that you request from the compilation of a COBOL source program *file.cbl* is written to *file.lst*. The listing output that you request from the linker is written to stdout.

The linker causes execution to begin at the first main program.

**related tasks**

[“Creating a DLL under z/OS UNIX” on page 268](#)  
[“Preparing OO applications under z/OS UNIX” on page 274](#)  
*UNIX System Services User's Guide*

**related references**

[“cob2 syntax and options” on page 269](#)  
[“cob2 input and output files” on page 270](#)  
*UNIX System Services Command Reference*

## Creating a DLL under z/OS UNIX

To create a DLL from the z/OS UNIX shell, you must specify the cob2 option `-bdll`.

```
cob2 -o mydll -bdll mysub.cbl
```

When you specify `cob2 -bdll`:

- The COBOL compiler uses the compiler options `DLL`, `EXPORTALL`, and `RENT`, which are required for DLLs.
- The link step produces a DLL definition side file that contains `IMPORT` control statements for each of the names exported by the DLL.

The name of the DLL definition side file is based on the output file-name. If the output name has a suffix, that suffix is replaced with `x` to form the side-file name. For example, if the output file-name is `foo.dll`, the side-file name is `foo.x`.

To use the DLL definition side file later when you create a module that calls that DLL, specify the side file with any other object files (*file.o*) that you need to link. For example, the following command compiles `myappl.cbl`, uses the DLL option to enable `myappl.o` to reference DLLs, and links to produce the module `myappl`:

```
cob2 -o myappl -qdll myappl.cbl mydll.x
```

[“Example: using cob2 to compile and link under z/OS UNIX” on page 268](#)

### related tasks

[Chapter 27, “Creating a DLL or a DLL application,” on page 481](#)

[“Compiling programs to create DLLs” on page 482](#)

### related references

[“cob2 syntax and options” on page 269](#)

[“cob2 input and output files” on page 270](#)

## Example: using cob2 to compile and link under z/OS UNIX

The following examples illustrate the use of `cob2`.

- To compile one file called `alpha.cbl`, enter:

```
cob2 -c alpha.cbl
```

The compiled file is named `alpha.o`.

- To compile two files called `alpha.cbl` and `beta.cbl`, enter:

```
cob2 -c alpha.cbl beta.cbl
```

The compiled files are named `alpha.o` and `beta.o`.

- To link two files, compile them without the `-c` option. For example, to compile and link `alpha.cbl` and `beta.cbl` and generate `gamma`, enter:

```
cob2 alpha.cbl beta.cbl -o gamma
```

This command creates `alpha.o` and `beta.o`, then links `alpha.o`, `beta.o`, and the COBOL libraries. If the link step is successful, it produces an executable program named `gamma`.

- To compile alpha.cbl with the LIST and NODATA options, enter:

```
cob2 -qlist,noadata alpha.cbl
```

## cob2 syntax and options

You can use the options listed below with the cob2 command. (Do not capitalize cob2.)

### cob2 command syntax

→ cob2 ————— filenames →

options

#### -bxxx

Passes the string xxx to the linker as parameters. xxx is a list of linker options in *name=value* format, separated by commas. You must spell out both the name and the value in full (except for the special cases noted below). The name and value are case insensitive. Do not use any spaces between -b and xxx.

If you do not specify a value for an option, a default value of YES is used except for the following options, which have the indicated default values:

- LIST=NOIMPORT
- ALIASES=ALL
- COMPAT=CURRENT
- DYNAM=DLL

One special value for xxx is dll, which specifies that the executable module is to be a DLL. This string is not passed to the linker.

#### -c

Compiles programs but does not link them.

#### -comprc\_ok=n

Controls cob2 behavior on the return code from the compiler. If the return code is less than or equal to *n*, cob2 continues to the link step or, in the compile-only case, exits with a zero return code. If the return code returned by the compiler is greater than *n*, cob2 exits with the same return code. When the c89 command is implicitly invoked by cob2 for the link step, the exit value from the c89 command is used as the return code from the cob2 command.

The default is -comprc\_ok=4.

#### -e xxx

Specifies the name of the program to be used as the entry point of the module. The program must be one of the programs that will be included in the module. If you do not specify -e, the default entry point is the first program (*file.cbl*) or object file (*file.o*) that you specify as a file name on the cob2 command invocation.

#### -g

Prepares the program for debugging. Equivalent to specifying the TEST option with no suboptions.

#### -Ixxx

Adds a path xxx to the directories to be searched for copybooks for which you do not specify a *library-name*.

To specify multiple paths, either use multiple -I options, or use a colon to separate multiple path names within a single -I option value.

For COPY statements in which you have not coded an explicit library-name, the compiler searches for copybooks in the following order:

1. In the current directory
2. In the paths you specify with the `-I cob2` option
3. In the paths you specify in the SYSLIB environment variable
4. In the locations specified in instances of the COPYLOC option that use the default library name or specify an explicit library name of SYSLIB

**-L xxx**

Specifies the directory paths to be used to search for archive libraries specified by the `-l` operand.

**-l xxx**

Specifies the name of an archive library for the linker. The `cob2` command searches for the name `libxxx.a` in the directories specified in the `-L` option, then in the usual search order. (This option is lowercase *l*, not uppercase *L*.)

**-o xxx**

Names the object module `xxx`. If the `-o` option is not used, the name of the object module is `a.out`.

**-qxxx**

Passes `xxx` to the compiler, where `xxx` is a list of compiler options separated by blanks or commas.

Enclose `xxx` in quotation marks if a parenthesis is part of the option or suboption, or if you use blanks to separate options. Do not insert spaces between `-q` and `xxx`.

**-v**

Displays the generated commands that are issued by `cob2` for the compile and link steps, including the options being passed, and executes them. Here is sample output:

```
cob2 -v -o mini -qssrange mini.cbl
compiler: ATTCRCTL PARM=RENT,TERM,SSRANGE /u/userid/cobol/mini.cbl
PP 5655-EC6 IBM Enterprise COBOL for z/OS 6.1.0 in progress ...
End of compilation 1, program mini, no statements flagged.
linker: /bin/c89 -o mini -e // mini.o
```

**-#**

Displays compile and link steps, but does not execute them.

**related tasks**

[“Compiling and linking with the cob2 command” on page 267](#)

[“Creating a DLL under z/OS UNIX” on page 268](#)

[“Setting environment variables under z/OS UNIX” on page 265](#)

## cob2 input and output files

You can specify the following files as input file-names when you use the `cob2` command.

Table 39. <i>Input files to the cob2 command</i>		
File name	Description	Comments
<i>file.cbl</i>	COBOL source file to be compiled and linked	Will not be linked if you specify the <code>cob2</code> option <code>-c</code>
<i>file.a</i>	Archive file	Produced by the <code>ar</code> command, to be used during the link-edit phase
<i>file.o</i>	Object file to be link-edited	Can be produced by the COBOL compiler, the C/C++ compiler, or the assembler
<i>file.x</i>	DLL definition side file	Used during the link-edit phase of an application that references the dynamic link library (DLL)

If you use the `cob2` command, the following files are created in the current directory.

<i>Table 40. Output files from the cob2 command</i>		
<b>File name</b>	<b>Description</b>	<b>Comments</b>
<i>file</i>	Executable module or DLL	Created by the linker if you specify the cob2 option -o <i>file</i>
a.out	Executable module or DLL	Created by the linker if you do not specify the cob2 option -o
<i>file.adt</i>	Associated data (ADATA) file corresponding to input COBOL source program <i>file.cbl</i>	Created by the compiler if you specify compiler option ADATA
<i>file.dek</i>	Extended COBOL source output from library processing	Created by the compiler if you specify compiler option MDECK
<i>file.lst</i>	Listing file corresponding to input COBOL source program <i>file.cbl</i>	Created by the compiler
<i>file.o</i>	Object file corresponding to input COBOL source program <i>file.cbl</i>	Created by the compiler
<i>file.x</i>	DLL definition side file	Created during the cob2 linking phase when creating <i>file.dll</i>
<i>class.java</i>	Java class definition (source)	Created when you compile a class definition

#### **related tasks**

[“Compiling and linking with the cob2 command” on page 267](#)

#### **related references**

[“ADATA” on page 288](#)

[“MDECK” on page 318](#)

[“TEST” on page 340](#)

*UNIX System Services Command Reference*

## Compiling using scripts

If you use a shell script to automate cob2 tasks, you must code option syntax carefully to prevent the shell from passing invalid strings to cob2.

Code option strings in scripts as follows:

- Use an equal sign and colon rather than a left and right parenthesis, respectively, to specify compiler suboptions. For example, code -qOPTIMIZE=1: , XREF instead of -qOPTIMIZE(1) , XREF.
- Use an underscore rather than an apostrophe where a compiler option requires apostrophes for delimiting a suboption.
- Do not use blanks in the option string.



---

## Chapter 16. Compiling, linking, and running OO applications

It is recommended that you compile, link, and run object-oriented (OO) applications in the z/OS UNIX environment. However, with certain limitations explained in the related tasks, it is possible to compile, link, and run OO COBOL applications by using standard batch JCL or TSO/E commands.

### related tasks

[“Compiling, linking, and running OO applications under z/OS UNIX” on page 273](#)

[“Compiling, linking, and running OO applications in JCL or TSO/E” on page 277](#)

[“Using Java SDKs](#)

[for z/OS” on page 280](#)

---

## Compiling, linking, and running OO applications under z/OS UNIX

When you compile, link, and run object-oriented applications in a z/OS UNIX environment, application components reside in the z/OS UNIX file system. You compile and link them by using shell commands, and run them at a shell command prompt or with the BPXBATCH utility from JCL or TSO/E.

### related tasks

[“Compiling OO applications under z/OS UNIX” on page 273](#)

[“Preparing OO applications under z/OS UNIX” on page 274](#)

[“Running OO applications under z/OS UNIX” on page 275](#)

## Compiling OO applications under z/OS UNIX

When you compile OO applications in a z/OS UNIX shell, use the `cob2` command to compile COBOL client programs and class definitions, and the `javac` command to compile Java class definitions to produce *bytecode* (suffix `.class`).

To compile COBOL source code that contains OO syntax such as `INVOKE` statements or class definitions, or that uses Java services, you must use these compiler options: `RENT`, `DLL`, `THREAD`, and `DBCS`. (The `RENT` and `DBCS` options are defaults.)

A COBOL source file that contains a class definition must not contain any other class or program definitions.

When you compile a COBOL class definition, two output files are generated:

- The object file (`.o`) for the class definition.
- A Java source program (`.java`) that contains a class definition that corresponds to the COBOL class definition. Do not edit this generated Java class definition in any way. If you change the COBOL class definition, you must regenerate both the object file and the Java class definition by recompiling the updated COBOL class definition.

If a COBOL client program or class definition includes the file `JNI.cpy` by using a `COPY` statement, specify the `include` subdirectory of the COBOL install directory (typically `/usr/lpp/cobol/include`) in the search order for copybooks. You can specify the `include` subdirectory by using the `-I` option of the `cob2` command or by setting the `SYSLIB` environment variable.

### related tasks

[Chapter 15, “Compiling under z/OS UNIX,” on page 265](#)

[“Preparing OO applications under z/OS UNIX” on page 274](#)

[“Running OO applications under z/OS UNIX” on page 275](#)

[“Setting and accessing environment variables” on page 436](#)

[“Accessing JNI services” on page 601](#)

## related references

[“cob2 syntax and options” on page 269](#)

[“DBCS” on page 301](#)

[“DLL” on page 303](#)

[“RENT” on page 330](#)

[“THREAD” on page 343](#)

## Preparing OO applications under z/OS UNIX

Use the cob2 command to link OO COBOL applications.

To prepare an OO COBOL client program for execution, link the object file with the following two DLL side files to create an executable module:

- `libjvm.x`, which is provided with your IBM Java Software Development Kit.
- `igzcjava.x`, which is provided in the `lib` subdirectory of the `cobol` directory in the z/OS UNIX file system. The typical complete path is `/usr/lpp/cobol/lib/igzcjava.x`. This DLL side file is also available as the member `IGZCJAVA` in the `SCEELIB PDS` (part of Language Environment).

To prepare a COBOL class definition for execution:

1. Link the object file using the two DLL side files mentioned above to create an executable DLL module.

You must name the resulting DLL module `libClassname.so`, where *Classname* is the external class-name. If the class is part of a package and thus there are periods in the external class-name, you must change the periods to underscores in the DLL module name. For example, if class `Account` is part of the `com.acme` package, the external class-name (as defined in the `REPOSITORY` paragraph entry for the class) must be `com.acme.Account`, and the DLL module for the class must be `libcom_acme_Account.so`.

2. Compile the generated Java source with the Java compiler to create a class file (`.class`).

For a COBOL source file `Classname.cbl` that contains the class definition for *Classname*, you would use the following commands to compile and link the components of the application:

Table 41. Commands for compiling and linking a class definition		
Command	Input	Output
<code>cob2 -c -qdll,thread Classname.cbl</code>	<code>Classname.cbl</code>	<code>Classname.o</code> , <code>Classname.java</code>
<code>cob2 -bdll -o libClassname.so Classname.o</code> <code>/usr/lpp/java/J5.0/bin/j9vm/libjvm.x</code> <code>/usr/lpp/cobol/lib/igzcjava.x</code>	<code>Classname.o</code>	<code>libClassname.so</code>
<code>javac Classname.java</code>	<code>Classname.java</code>	<code>Classname.class</code>

After you issue the `cob2` and `javac` commands successfully, you have the executable components for the program: the executable DLL module `libClassname.so` and the class file `Classname.class`. All files from these commands are generated in the current working directory.

[“Example: compiling and linking a COBOL class definition under z/OS UNIX” on page 275](#)

## related tasks

[Chapter 15, “Compiling under z/OS UNIX,” on page 265](#)

[“REPOSITORY paragraph for defining a class” on page 566](#)


## related references

[“cob2 syntax and options” on page 269](#)

[“Object-oriented syntax, and Java 6, Java 7, or Java 8” on page 281](#)

## Example: compiling and linking a COBOL class definition under z/OS UNIX

This example illustrates the commands that you use and the files that are produced when you compile and link a COBOL class definition, `Manager.cbl`, using z/OS UNIX shell commands.



The class file `Manager.class` and the DLL module `libManager.so` are the executable components of the application, and are generated in the current working directory.

## Running OO applications under z/OS UNIX

It is recommended that you run object-oriented COBOL applications as z/OS UNIX applications. You must do so if an application begins with a Java program or the main factory method of a COBOL class.

Specify the directory that contains the DLLs for the COBOL classes in the `LIBPATH` environment variable. Specify the directory paths for the Java class files that are associated with the COBOL classes in the `CLASSPATH` environment variable as follows:

- For classes that are not part of a package, end the class path with the directory that contains the `.class` files.
- For classes that are part of a package, end the class path with the directory that contains the "root" package (the first package in the full package name).
- For a `.jar` file that contains `.class` files, end the class path with the name of the `.jar` file.

Separate multiple path entries with colons.

**Note:** If the `CLASSPATH` environment variable contains the filename wildcard (\*), the wildcard cannot be expanded in the case where the JVM is initialized by the COBOL runtime.

### related tasks

[“Running OO applications that start with a main method” on page 276](#)

[“Running OO applications that start with a COBOL program” on page 276](#)

[“Running J2EE COBOL clients” on page 276](#)

[Chapter 23, “Running COBOL programs under z/OS UNIX,” on page 435](#)

[“Setting and accessing environment variables” on page 436](#)

[Chapter 33, “Writing object-oriented programs,” on page 561](#)

[“Structuring OO applications” on page 598](#)

## Running OO applications that start with a main method

If the first routine of a mixed COBOL and Java application is the main method of a Java class or the main factory method of a COBOL class, run the application by using the `java` command and by specifying the name of the class that contains the main method.

The `java` command initializes the Java virtual machine (JVM). To customize the initialization of the JVM, specify options on the `java` command as in the following examples:

Table 42. <i>java</i> command options for customizing the JVM	
Purpose	Option
To set a system property	<code>-Dname=value</code>
To request that the JVM generate verbose messages about garbage collection	<code>-verbose:gc</code>
To request that the JVM generate verbose messages about class loading	<code>-verbose:class</code>
To request that the JVM generate verbose messages about native methods and other Java Native Interface activity	<code>-verbose:jni</code>
To set the initial Java heap size to <i>value</i> bytes	<code>-Xmsvalue</code>
To set the maximum Java heap size to <i>value</i> bytes	<code>-Xmxvalue</code>

For details about the options that the JVM supports, see the output from the `java -h` command, or see the related references.

### related references

[IBM SDK for Java - Tools Documentation](#)

[WebSphere for z/OS: Applications](#) (Java Naming and Directory Interface (JNDI))

## Running OO applications that start with a COBOL program

If the first routine of a mixed COBOL and Java application is a COBOL program, run the application by specifying the program name at the command prompt. If a JVM is not already running in the process of the COBOL program, the COBOL run time automatically initializes a JVM.

To customize the initialization of the JVM, specify options by setting the `COBJVMINITOPTIONS` environment variable. Use blanks to separate options. For example:

```
export COBJVMINITOPTIONS="-Xms100000000 -Xmx200000000 -verbose:gc"
```

### related tasks

[“Using Java SDKs](#)

[for z/OS” on page 280](#)

[Chapter 23, “Running COBOL programs under z/OS UNIX,” on page 435](#)

[“Setting and accessing environment variables” on page 436](#)

### related references

[IBM SDK for Java - Tools Documentation](#)

[WebSphere for z/OS: Applications](#) (Java Naming and Directory Interface (JNDI))

## Running J2EE COBOL clients

You can use OO syntax in a COBOL program to implement a Java 2 Platform, Enterprise Edition (J2EE) client. You can, for example, invoke methods on enterprise beans that run in the WebSphere for z/OS environment.

Before you run a COBOL J2EE client, you must set the Java system property `java.naming.factory.initial` to access WebSphere naming services. For example:

```
export COBJVMINITOPTIONS  
="-Djava.naming.factory.initial=com.ibm.websphere.naming.WsnInitialContextFactory"
```

[“Example: J2EE client written in COBOL” on page 613](#)

## Compiling, linking, and running OO applications in JCL or TSO/E

It is recommended that you compile, link, and run applications that use OO syntax in the z/OS UNIX environment.

However, in limited circumstances it is possible to compile, prepare, and run OO applications by using standard batch JCL or TSO/E commands. To do so, you must follow the guidelines that are in the related tasks. For example, you might follow this approach for applications that consist of a COBOL main program and subprograms that:

- Access objects that are all implemented in Java
- Access enterprise beans that run in a WebSphere server

### related tasks

[“Compiling OO applications in JCL or TSO/E” on page 277](#)

[“Preparing and running OO applications in JCL or TSO/E” on page 278](#)

[“Compiling, linking, and running OO applications under z/OS UNIX” on page 273](#)

## Compiling OO applications in JCL or TSO/E

If you use batch JCL or TSO/E to compile an OO COBOL program or class definition, the generated object file is written, as usual, to the data set that has ddname SYSLIN or SYSPUNCH. You must use compiler options RENT, DLL, THREAD, and DBCS. (RENT and DBCS are defaults.)

If the COBOL program or class definition uses the JNI environment structure to access JNI callable services, copy the file `JNI.cpy` from the z/OS UNIX file system to a PDS or PDSE member called `JNI`, identify that library with a `SYSLIB DD` statement, and use a `COPY` statement of the form `COPY JNI` in the COBOL source.

A COBOL source file that contains a class definition must not contain any other class or program definitions.

When you compile a COBOL class definition, a Java source program that contains a class definition that corresponds to the COBOL class definition is generated in addition to the object file. Use the `SYSJAVA` ddname to write the generated Java source file to a file in the z/OS UNIX file system. For example:

```
//SYSJAVA DD PATH='/u/userid/java/Classname.java',  
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),  
// PATHMODE=SIRWXU,  
// FILEDATA=TEXT
```

Do not edit this generated Java class definition in any way. If you change the COBOL class definition, you must regenerate both the object file and the Java class definition by recompiling the updated COBOL class definition.

Compile Java class definitions by using the `javac` command from a z/OS UNIX shell command prompt, or by using the `BPXBATCH` utility.

[“Example: compiling, linking, and running an OO application using JCL” on page 279](#)

### related tasks

[“Compiling with JCL” on page 237](#)

[“Compiling under TSO” on page 244](#)

[“Specifying source libraries \(SYSLIB\)” on page 252](#)

[“Defining the Java-source output file \(SYSJAVA\)” on page 254](#)

[“Accessing JNI services” on page 601](#)

[“Compiling OO applications under z/OS UNIX” on page 273](#)

[“Preparing OO applications under z/OS UNIX” on page 274](#)

#### related references

[“DBCS” on page 301](#)

[“DLL” on page 303](#)

[“RENT” on page 330](#)

[“THREAD” on page 343](#)

[Appendix F, “JNI.cpy copybook,” on page 705](#)

[UNIX System Services User's Guide \(The BPXBATCH utility\)](#)

## Preparing and running OO applications in JCL or TSO/E

It is recommended that you run OO applications in a z/OS UNIX environment. To run OO applications from batch JCL or TSO/E, you should therefore use the BPXBATCH utility.

In limited circumstances, however, you can run an OO application by using standard batch JCL (EXEC PGM=COBPROG) or the TSO/E CALL command. To do so, follow these requirements when preparing the application:

- Structure the application to start with a COBOL program. (If an application starts with a Java program or with the main factory method of a COBOL class, you must run the application under z/OS UNIX, and the application components must reside in the z/OS UNIX file system.)
- **Link-edit considerations:** Link the program object for the COBOL program into a PDSE. COBOL programs that contain object-oriented syntax must be link-edited with AMODE 31.
- Ensure that the class files and DLLs associated with the COBOL or Java classes that are used by the application reside in the z/OS UNIX file system. You must name the class files and DLLs as described in the related task about preparing OO applications under z/OS UNIX.
- Specify INCLUDE control statements for the DLL side files libjvm.x and igzccjava.x when you bind the object deck for the main program. For example:

```
INCLUDE '/usr/lpp/java/J5.0/bin/j9vm/libjvm.x'  
INCLUDE '/usr/lpp/cobol/lib/igzccjava.x'
```

- Create a file that contains the environment variable settings that are required for Java. For example, a file /u/userid/javaenv might contain the three lines shown below to set the PATH, LIBPATH, and CLASSPATH environment variables.

```
PATH=/bin:/usr/lpp/java/IBM/J7.1/bin  
LIBPATH=/lib:/usr/lib:/usr/lpp/java/J5.0/bin:/usr/lpp/java/IBM/J7.1/bin/j9vm  
CLASSPATH=./u/userid/applications
```

To customize the initialization of the JVM that will be used by the application, you can set the COBJVMINITOPTIONS environment variable in the same file. For example, to access enterprise beans that run in a WebSphere server, you must set the Java system property java.naming.factory.initial. For details, see the related task about running OO applications.

When you run an OO application that starts with a COBOL program by using standard batch JCL or the TSO/E CALL command, follow these guidelines:

- Use the \_CEE\_ENVFILE environment variable to indicate the location of the file that contains the environment variable settings required by Java. Set \_CEE\_ENVFILE by using the ENVAR runtime option.
- Specify the POSIX(ON) and XPLINK(ON) runtime option.
- Use DD statements to specify files in the z/OS UNIX file system for the standard input, output, and error streams for Java:
  - JAVA IN DD for the input from statements such as c=System.in.read();

- JAVAOUT DD for the output from statements such as `System.out.println(string);`
- JAVAERR DD for the output from statements such as `System.err.println(string);`
- Ensure that the SCEERUN2 and SCEERUN load libraries are available in the system library search order, for example, by using a STEPLIB DD statement.

[“Example: compiling, linking, and running an OO application using JCL” on page 279](#)

#### related tasks

[“Preparing OO applications under z/OS UNIX” on page 274](#)

[“Running OO applications under z/OS UNIX” on page 275](#)

[“Structuring OO applications” on page 598](#)

*UNIX System Services User's Guide* (The BPXBATCH utility)

*Language Environment Programming Guide* (Running an application under batch)

#### related references

*XL C/C++ Programming Guide* (\_CEE\_ENVFILE)

*Language Environment Programming Reference* (ENVAR)

## Example: compiling, linking, and running an OO application using JCL

This example shows sample JCL that you could use to compile, link, and run a COBOL client that invokes a Java method.

The example shows:

- JCL to compile, link, and run an OO COBOL program, TSTHELLO
- A Java class definition, HelloJ, that contains a method that the COBOL program invokes
- A z/OS UNIX file, ENV, that contains the environment variable settings that Java requires

### JCL for program TSTHELLO

```
//TSTHELLO JOB ,
//  TIME=(1),MSGLEVEL=(1,1),MSGCLASS=H,CLASS=A,REGION=200M,
//  NOTIFY=&SYSUID,USER=&SYSUID
//*
// SET COBPRFX='IGY.V6R1M0'
// SET LIBPRFX='CEE'
//*
//COMPILE EXEC PGM=IGYCRCTL,
//SYSLIN DD DSNNAME=&&OBJECT(TSTHELLO),UNIT=VIO,DISP=(NEW,PASS),
//        SPACE=(CYL,(1,1,1))
//SYSPRINT DD SYSOUT=*
//STEPLIB DD DSN=&COBPRFX..SIGYCOMP,DISP=SHR
//        DD DSN=&LIBPRFX..SCEERUN,DISP=SHR
//        DD DSN=&LIBPRFX..SCEERUN2,DISP=SHR
//SYSUT1 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT2 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT3 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT4 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT5 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT6 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT7 DD UNIT=VIO,SPACE=(CYL,(1,1))
//SYSUT8 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT9 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT10 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT11 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT12 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT13 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT14 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSUT15 DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSMDECK DD UNIT=SYSALLDA,SPACE=(CYL,(1,1))
//SYSIN DD *
        cbl dll,thread
        Identification division.
        Program-id. "TSTHELLO" recursive.
        Environment division.
        Configuration section.
        Repository.
        Class HelloJ is "HelloJ".
```

```

Data Division.
Procedure division.
    Display "COBOL program TSTHELLO entered"
    Invoke HelloJ "sayHello"
    Display "Returned from java sayHello to TSTHELLO"
    Goback.
End program "TSTHELLO".

/*
//LKED EXEC PGM=IEWL,PARM='RENT,LIST,LET,DYNAM(DLL),CASE(MIXED)'
//SYSLIB DD DSN=&LIBPRFX..SCEELKED,DISP=SHR
// DD DSN=&LIBPRFX..SCEELKEX,DISP=SHR
//SYSPRINT DD SYSOUT=*
//SYSTEM DD SYSOUT=*
//SYSLMOD DD DSN=&&GOSET(TSTHELLO),DISP=(MOD,PASS),UNIT=VIO,
// SPACE=(CYL,(1,1,1)),DSNTYPE=LIBRARY
//SYSDEFS DD DUMMY
//OBJMOD DD DSN=&&OBJECT,DISP=(OLD,DELETE)
//SYSLIN DD *
INCLUDE OBJMOD(TSTHELLO)
INCLUDE '/usr/lpp/java/J5.0/bin/j9vm/libjvm.x'
INCLUDE '/usr/lpp/cobol/lib/igzcljava.x'

/*
//GO EXEC PGM=TSTHELLO,COND=(4,LT,LKED),
// PARM='/ENVAR("_CEE_ENVFILE=/u/userid/octest/tsthellob/ENV")
// POSIX(ON) XPLINK(ON)'
//STEPLIB DD DSN=*.LKED.SYSLMOD,DISP=PASS
// DD DSN=&LIBPRFX..SCEERUN2,DISP=SHR
// DD DSN=&LIBPRFX..SCEERUN,DISP=SHR
//SYSOUT DD SYSOUT=*
//CEEDUMP DD SYSOUT=*
//SYSUDUMP DD DUMMY
//JAVAOUT DD PATH='/u/userid/octest/tsthellob/javaout',
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),
// PATHMODE=(SIRUSR,SIWUSR,SIRGRP)
//JAVAERR DD PATH='/u/userid/octest/tsthellob/javaerr',
// PATHOPTS=(OWRONLY,OCREAT,OTRUNC),
// PATHMODE=(SIRUSR,SIWUSR,SIRGRP)

```

## Definition of class *HelloJ*

```

class HelloJ {
    public static void sayHello() {
        System.out.println("Hello World, from Java!");
    }
}

```

`HelloJ.java` is compiled with the `javac` command. The resulting `.class` file resides in the z/OS UNIX file system directory `u/userid/octest/tsthellob`, which is specified in the **CLASSPATH** environment variable in the environment variable settings file.

## Environment variable settings file, *ENV*

```

PATH=/bin:/usr/lpp/java/IBM/J7.1/bin.
LIBPATH=/lib:/usr/lib:/usr/lpp/java/J5.0/bin:/usr/lpp/java/IBM/J7.1/bin/j9vm
CLASSPATH=./u/userid/octest/tsthellob

```

The environment variable settings file also resides in directory `u/userid/octest/tsthellob`, as specified in the **\_CEE\_ENVFILE** environment variable in the JCL.

## Using Java SDKs for z/OS

The Java SDKs for z/OS are based on the XPLINK linkage convention defined by Language Environment.

If the application starts with a Java program or the main factory method of a COBOL class, the XPLINK environment is automatically started by the `java` command that starts the JVM and runs the application.

If an application starts with a COBOL program that invokes methods on COBOL or Java classes, you must specify the `XPLINK(ON)` runtime option so that the XPLINK environment is initialized. `XPLINK(ON)` is not recommended as a default setting, however; you should use `XPLINK(ON)` only for applications that specifically require it.

When you are running an application under z/OS UNIX, you can set the XPLINK(ON) option by using the \_CEE\_RUNOPTS environment variable as follows:

```
_CEE_RUNOPTS="XPLINK(ON) "
```

Exporting \_CEE\_RUNOPTS="XPLINK(ON) " so that it is in effect for the entire z/OS UNIX shell session is not recommended, however. Suppose for example that an OO COBOL application starts with a COBOL program called App1Driver. One way to limit the effect of the XPLINK option to the execution of the App1Driver application is to set the \_CEE\_RUNOPTS variable on the command-line invocation of App1Driver as follows:

```
_CEE_RUNOPTS="XPLINK(ON) " App1Driver
```

#### **related tasks**

[“Running OO applications under z/OS UNIX” on page 275](#)

[“Setting and accessing environment variables” on page 436](#)

#### **related references**

[“Object-oriented syntax, and Java 6, Java 7, or Java 8” on page 281](#)

[“Runtime environment variables” on page 437](#)

*Language Environment Programming Reference* (XPLINK)

*XL C/C++ Programming Guide* (\_CEE\_RUNOPTS)

## **Object-oriented syntax, and Java 6, Java 7, or Java 8**

Enterprise COBOL V5.2 and later applications that use object-oriented syntax for Java interoperability are supported with Java 6 or Java 7.

Earlier versions of Enterprise COBOL applications that use object-oriented syntax for Java interoperability were supported with Java SDK 1.4.2 and Java 5. To run these applications with Java 6, Java 7, or Java 8, , do these steps:

1. Recompile and relink the applications using Enterprise COBOL V5.2 or later.
2. Recompile the generated Java class that is associated with each object-oriented COBOL class using the javac command from Java 6, Java 7, or Java 8.

#### **related tasks**

[“Preparing OO applications under z/OS UNIX” on page 274](#)



## Chapter 17. Compiler options

You can direct and control your compilation by using compiler options or by using compiler-directing statements (compiler directives).

Compiler options affect the aspects of your program that are listed in the table below. The linked-to information for each option provides the syntax for specifying the option and describes the option, its parameters, and its interaction with other parameters.

Table 43. <i>Compiler options</i>			
Aspect of your program	Compiler option	Default	Option abbreviations
Source language	<a href="#">“APOST/QUOTE” on page 289</a>	QUOTE	APOST   Q
	<a href="#">“ARITH” on page 291</a>	ARITH (COMPAT)	AR (C   E)
	<a href="#">“CICS” on page 294</a>	NOCICS	None
	<a href="#">“CODEPAGE” on page 295</a>	CODEPAGE (1140)	CP ( <i>ccsid</i> )
	<a href="#">“CURRENCY” on page 299</a>	NOCURRENCY	CURR   NOCURR
	<a href="#">“DBCS” on page 301</a>	DBCS	None
	<a href="#">“NSYMBOL” on page 319</a>	NSYMBOL (NATIONAL)	NS (DBCS   NAT)
	<a href="#">“NUMBER” on page 320</a>	NONUMBER	NUM   NONUM
	<a href="#">“QUALIFY” on page 330</a>	QUALIFY (COMPAT)	QUA (C   E)
	<a href="#">“SEQUENCE” on page 333</a>	SEQUENCE	SEQ   NOSEQ
	<a href="#">“SQL” on page 335</a>	NOSQL	None
	<a href="#">“SQLCCSID” on page 336</a>	SQLCCSID	SQLC   NOSQLC
	<a href="#">“SQLIMS” on page 337</a>	NOSQLIMS	None
	<a href="#">“SUPPRESS” on page 340</a>	SUPPRESS	SUPP
	<a href="#">“WORD” on page 349</a>	NOWORD	WD   NOWD
	<a href="#">“XMLPARSE” on page 350</a>	XMLPARSE (XMLSS)	XP (X)   XP (C)
Date processing	<a href="#">“INTDATE” on page 313</a>	INTDATE (ANSI)	None
Maps and listings	<a href="#">“LANGUAGE” on page 313</a>	LANGUAGE (ENGLISH)	LANG (EN   UE   JA   JP)
	<a href="#">“LINECOUNT” on page 314</a>	LINECOUNT (60)	LC
	<a href="#">“LIST” on page 315</a>	NOLIST	None
	<a href="#">“MAP” on page 316</a>	NOMAP	None
	<a href="#">“OFFSET” on page 324</a>	NOOFFSET	OFF   NOOFF
	<a href="#">“SOURCE” on page 334</a>	SOURCE	S   NOS
	<a href="#">“SPACE” on page 335</a>	SPACE (1)	None
	<a href="#">“TERMINAL” on page 340</a>	NOTERMINAL	TERM   NOTERM
	<a href="#">“VBREF” on page 347</a>	NOVBREF	None
	<a href="#">“XREF” on page 350</a>	XREF (FULL)	X   NOX

Table 43. **Compiler options** (continued)

Aspect of your program	Compiler option	Default	Option abbreviations
Object deck generation	<a href="#">“COMPILE” on page 297</a>	NOCOMPILE(S)	C   NOC
	<a href="#">“COPYRIGHT” on page 299</a>	NOCOPYRIGHT	CPYR   NOCPYR
	<a href="#">“DECK” on page 301</a>	NODECK	D   NOD
	<a href="#">“NAME” on page 319</a>	NONAME, or NAME(NOALIAS) if only NAME is specified	None
	<a href="#">“OBJECT” on page 323</a>	OBJECT	OBJ   NOOBJ
	<a href="#">“PGMNAME” on page 328</a>	PGMNAME(COMPAT)	PGMN(CO   LU   LM)
	<a href="#">“SERVICE” on page 334</a>	NOSERVICE	SERV   NOSERV
Object code control	<a href="#">“ADV” on page 288</a>	ADV	None
	<a href="#">“AFP” on page 289</a>	AFP(VOLATILE)	None
	<a href="#">“ARCH” on page 290</a>	ARCH(7)	None
	<a href="#">“AWO” on page 292</a>	NOAWO	None
	<a href="#">“BLOCK0” on page 293</a>	NOBLOCK0	None
	<a href="#">“DISPSIGN” on page 302</a>	DISPSIGN(COMPAT)	DS(S   C)
	<a href="#">“DLL” on page 303</a>	NODLL	None
	<a href="#">“EXPORTALL” on page 307</a>	NOEXPORTALL	EXP   NOEXP
	<a href="#">“FASTSRT” on page 308</a>	NOFASTSRT	FSRT   NOFSRT
	<a href="#">“HGPR” on page 310</a>	HGPR(PRESERVE)	None
	<a href="#">“INLINE” on page 312</a>	INLINE	INL   NOINL
	<a href="#">“MAXPCF” on page 317</a>	MAXPCF(60000)	None
	<a href="#">“NUMCHECK” on page 320</a>	NONUMCHECK	NONC   NC
	<a href="#">“NUMPROC” on page 322</a>	NUMPROC(NOPFD)	None
	<a href="#">“OPTIMIZE” on page 325</a>	OPTIMIZE(0)	OPT(n)
	<a href="#">“OUTDD” on page 326</a>	OUTDD(SYSOUT)	OUT
	<a href="#">“PARMCHECK” on page 327</a>	NOPARMCHECK	PC   NOPC
	<a href="#">“TRUNC” on page 344</a>	TRUNC(STD)	None
	<a href="#">“VLR” on page 347</a>	VLR(STD)	VLR(C   S)
	<a href="#">“ZONECHECK” on page 352</a>	NOZONECHECK	NOZC   ZC(MSG)   ZC(ABD)
	<a href="#">“ZONEDATA” on page 353</a>	ZONEDATA(PFD)	ZD(PFD)   ZD(MIG)   ZD(NOPFD)
	<a href="#">“ZWB” on page 355</a>	ZWB	None

Table 43. <i>Compiler options</i> (continued)			
Aspect of your program	Compiler option	Default	Option abbreviations
Virtual storage usage	<a href="#">“BUFSIZE” on page 294</a>	4096	BUF
	<a href="#">“DATA” on page 300</a>	DATA(31)	None
	<a href="#">“DYNAM” on page 305</a>	NODYNAM	DYN NODYN
	<a href="#">“RENT” on page 330</a>	RENT	None
	<a href="#">“RMODE” on page 331</a>	AUTO	None
	<a href="#">“STGOPT” on page 339</a>	NOSTGOPT	SO NOSO
Debugging and diagnostics	<a href="#">“DIAGTRUNC” on page 302</a>	NODIAGTRUNC	DTR NODTR
	<a href="#">“DUMP” on page 304</a>	NODUMP	DU NODU
	<a href="#">“FLAG” on page 308</a>	FLAG(I,I)	F NOF
	<a href="#">“FLAGSTD” on page 309</a>	NOFLAGSTD	None
	<a href="#">“INITCHECK” on page 311</a>	NOINITCHECK	IC NOIC
	<a href="#">“RULES” on page 332</a>	NORULES	RULES(ENDP, EVENP, LXPRF, SLCKB)   RULES(NOENDP, NOEVENP, NOLXPRF, NOSLCKB)
	<a href="#">“SSRANGE” on page 338</a>	NOSSRANGE	SSR(ZLEN NOZLEN, MSG   ABD)   NOSSR
	<a href="#">“TEST” on page 340</a>	NOTEST	None
Other	<a href="#">“ADATA” on page 288</a>	NOADATA	None
	<a href="#">“COPYLOC” on page 298</a>	NOCOPYLOC	CPLC
	<a href="#">“EXIT” on page 305</a>	NOEXIT	NOEX EX(INX NOINX, LIBX NOLIBX, PRTX  NOPRTX, ADX NOADX, MSGX  NOMSGX)
	<a href="#">“MDECK” on page 318</a>	NOMDECK	NOMD MD MD(C NOC)
	<a href="#">“OPTFILE” on page 324</a>	None	None
	<a href="#">“THREAD” on page 343</a>	NOTHREAD	None
	<a href="#">“VSAMOPENFS” on page 349</a>	VSAMOPENFS(COMPAT)	VS(C S)

**Installation defaults:** The default compiler options that were set up when your compiler was installed are in effect for your program unless you override those options. (In some installations, certain compiler options are fixed so that you cannot override them. If you have problems with the default options, contact your system administrator.) To determine which are the default options, run a test compilation without specifying any compiler options. The output listing lists the default options in effect at your site.

**Nonoverridable options:** In some installations, certain compiler options are fixed so that you cannot override them. If you have problems with those options, contact your system administrator.

**Option specification:** Compiler options and suboptions are not case sensitive.

**Performance considerations:** The AFP, ARCH, ARITH, AWO, BLOCK0, DYNAM, FASTSRT, HGPR, MAXPCF, NUMCHECK, NUMPROC, OPTIMIZE, PARMCHECK, RENT, SQLCCSID, SSRANGE, STGOPT, TEST, THREAD, TRUNC, ZONECHECK, and ZONEDATA compiler options can affect runtime performance.

**related tasks**

[Chapter 14, “Compiling under z/OS,” on page 237](#)

[“Compiling under TSO” on page 244](#)

[Chapter 15, “Compiling under z/OS UNIX,” on page 265](#)

[Chapter 37, “Tuning your program,” on page 633](#)

**related references**

[“Conflicting compiler options” on page 287](#)

[Chapter 18, “Compiler-directing statements,” on page 357](#)

[“Option settings for 85 COBOL Standard conformance” on page 286](#)

[“Performance-related compiler options” on page 640](#)

## Option settings for 85 COBOL Standard conformance

---

Compiler options and runtime options are required for conformance with the 85 COBOL Standard.

The following compiler options are required:

- ADV
- DYNAM
- NAME (ALIAS) or NAME (NOALIAS)
- NOBLOCK0
- NOCICS
- NODLL
- NOEXPORTALL
- NOFASTSRT
- NOTHREAD
- NOWORD
- NUMPROC (NOPFD)
- PGMNAME (COMPAT) or PGMNAME (LONGUPPER)
- QUALIFY (COMPAT)
- QUOTE
- TRUNC (STD)
- VLR (STANDARD)
- ZWB

You can use the FLAGSTD compiler option to flag nonconforming elements such as IBM extensions.

The following runtime options are required:

- AIXBLD
- CBLQDA (ON)
- TRAP (ON)

**related references**

*Language Environment Programming Reference*

## Conflicting compiler options

The Enterprise COBOL compiler can encounter conflicting compiler options in either of two ways: both the positive and negative form of an option are specified at the same level in the hierarchy of precedence, or mutually exclusive options are specified at the same level in the hierarchy.

When conflicting options are specified at the same level in the hierarchy (such as specifying both DECK and NODECK in a PROCESS or CBL statement), the option specified last takes effect.

If you specify mutually exclusive compiler options at the same level, the compiler generates an error message and forces one of the options to a nonconflicting value. For example, if you specify both OFFSET and LIST in a PROCESS statement in any order, OFFSET takes effect and LIST is ignored.

However, options coded at a higher level of precedence override any options specified at a lower level of precedence. For example, if you code OFFSET in a JCL statement but LIST in a PROCESS statement, LIST takes effect because the options coded in the PROCESS statement and any options forced on by an option coded in the PROCESS statement have higher precedence.

Table 44. *Mutually exclusive compiler options*

Specified	Ignored <sup>1</sup>	Forced on <sup>1</sup>
CICS	DYNAM	NODYNAM
	NORENT	RENT
DLL	DYNAM	NODYNAM
	NORENT	RENT
EXPORTALL	NODLL	DLL
	DYNAM	NODYNAM
	NORENT	RENT
NORENT	RMODE (ANY)	RMODE (24)
NSYMBOL (NATIONAL)	NODBCS	DBCS
OBJECT	DECK	NODECK
OFFSET	LIST	NOLIST
OPTIMIZE (0)	INITCHECK	NOINITCHECK
PGMNAME (LM LU)	NAME	NONAME
TEST	NOOBJECT and NODECK	OBJECT and NODECK
THREAD	NORENT	RENT
WORD	FLAGSTD	NOFLAGSTD
1. Unless in conflict with a fixed installation default option.		

### related tasks

[“Specifying compiler options under z/OS” on page 255](#)

[“Specifying compiler options in a batch compilation” on page 259](#)

[“Specifying compiler options under z/OS UNIX” on page 266](#)


### related references

[“OPTFILE” on page 324](#)

## ADATA

Use ADATA when you want the compiler to create a SYSADATA file that contains records of additional compilation information.

### ADATA option syntax



Default is: NOADATA

Abbreviations are: None

ADATA is required for remote compilation using an IBM Windows COBOL compiler. On z/OS, the SYSADATA file is written to ddname SYSADATA.

The size of the SYSADATA file generally grows with the size of the associated program.

**Option specification:** You cannot specify the ADATA option in a PROCESS (or CBL) statement. You can specify it only in one of the following ways:

- In the PARM parameter of JCL
- As a cob2 command option
- As an installation default
- In the COBOPT environment variable

### related references

[“Setting environment variables under z/OS UNIX” on page 265](#)


[“cob2 syntax and options” on page 269](#)

[Appendix G, “COBOL SYSADATA file contents,” on page 711](#)

## ADV

ADV has meaning only if you use WRITE . . . ADVANCING in your source code. With ADV in effect, the compiler adds 1 byte to the record length to account for the printer control character.

### ADV option syntax



Default is: ADV


Abbreviations are: None

Use NOADV if you already adjusted record length to include 1 byte for the printer control character.

## AFP

The AFP option controls the compiler usage of the Additional Floating Point (AFP) registers that are provided by z/Architecture processors.

### AFP option syntax



The diagram shows the syntax for the AFP option: `AFP( VOLATILE | NOVOLATILE )`. A horizontal line with arrows at both ends represents the option name. Above the line is the word "VOLATILE" and below the line is the word "NOVOLATILE". A vertical line connects the two words, indicating they are mutually exclusive choices.

Default is: AFP (VOLATILE)

Abbreviations are: None

The Enterprise COBOL compiler generates code that uses the full complement of 16 floating point registers (FPR) provided by a z/Architecture processor. These FPRs are as follows:

- Original FPRs, which are numbered 0, 2, 4, and 6
- AFP registers, which are numbered 1, 3, 5, 7, and 8-15

**Note:** If your code runs on a version of CICS Transaction Server that is earlier than V4.1, you must specify AFP (VOLATILE).

### AFP (VOLATILE)

If you specify AFP (VOLATILE), the AFP registers 8-15 are considered volatile, which means that they might be changed by a called subprogram. Therefore, the COBOL compiler generates extra code to protect the values in these registers.


### AFP (NOVOLATILE)

If you specify AFP (NOVOLATILE), the AFP registers 8-15 are considered nonvolatile, which means that they are known to be unchanged or preserved by every called subprogram. Therefore, the compiler can generate more efficient code sequences for programs with floating point operations. It is the normal z/OS architecture convention.

## APOST/QUOTE

Use APOST if you want the figurative constant [ALL] QUOTE or [ALL] QUOTES to represent one or more apostrophe (') characters. Use QUOTE if you want the figurative constant [ALL] QUOTE or [ALL] QUOTES to represent one or more quotation mark (") characters.

### APOST/QUOTE option syntax



The diagram shows the syntax for the APOST/QUOTE option: `APOST | QUOTE`. A horizontal line with arrows at both ends represents the option name. Above the line is the word "QUOTE" and below the line is the word "APOST". A vertical line connects the two words, indicating they are mutually exclusive choices.

Default is: QUOTE


Abbreviations are: Q|APOST

**Delimiters:** You can use either quotation marks or apostrophes as literal delimiters regardless of whether the APOST or QUOTE option is in effect. The delimiter character used as the opening delimiter for a literal must be used as the closing delimiter for that literal.

## ARCH

The ARCH option specifies the machine architecture for which the executable program instructions are to be generated.

### ARCH option syntax



Default is: ARCH(7)

Abbreviations are: None

If you specify a higher ARCH level, the compiler generates code that uses newer and faster instructions. Your application might abend if it runs on a processor with an architecture level lower than what you specified with the ARCH option. Use the ARCH level that matches the lowest machine architecture where your application runs.

Current supported architecture levels and groups of models are as follows:

#### 7

Produces code that uses instructions available on the 2094-xxx (IBM System z9® EC) and 2096-xxx (IBM System z9 BC) models in z/Architecture mode.

Specifically, these ARCH(7) machines and their follow-ons add instructions supported by the following facilities:

- Extended-immediate facility
- Decimal floating point facility. These instructions might be generated if decimal data is used in numeric operations.

#### 8

Produces code that uses instructions available on the 2097-xxx (IBM System z10® EC) and 2098-xxx (IBM System z10 BC) models in z/Architecture mode.

Specifically, these ARCH(8) machines and their follow-ons add instructions supported by the general instruction extensions facility.

#### 9

Produces code that uses instructions available on 2817-xxx (IBM zEnterprise® 196) and 2818-xxx (IBM zEnterprise 114) models in z/Architecture mode.

Specifically, these ARCH(9) machines and their follow-ons add instructions supported by the following facilities:

- High-word facility
- Interlocked access facility
- Load/store-on-condition facility
- Distinct-operands facility
- Population-count facility

#### 10

Produces code that uses instructions available on the 2827-xxx (IBM zEnterprise EC12) and 2828-xxx (IBM zEnterprise BC12) models in z/Architecture mode.

Specifically, these ARCH(10) machines and their follow-ons add instructions supported by the following facilities:

- Execution-hint facility
- Load-and-trap facility
- Miscellaneous-instructions-extension facility
- Transactional-execution facility
- Enhanced decimal floating point facility that enables more efficient conversions between zoned decimal data items and decimal floating point data items. Instead of converting zoned decimal data items to packed decimal data items to perform arithmetic, the compiler converts zoned decimal data items directly to decimal floating point data items, and then back again to zoned decimal data items after the computations are complete.

## 11

Produces code that uses instructions available on 2964-xxx (IBM z13®) and 2965-xxx (IBM z13s®) models in z/Architecture mode.

Specifically, these ARCH(11) machines and their follow-ons add instructions with support of the following facilities:

- Enhanced decimal floating point facility that enables more efficient conversions between packed-decimal data items and decimal floating point intermediate result data items.
- Exploitation of the vector extension facility (SIMD) instructions for some INSPECT REPLACING and INSPECT TALLYING statements.

To use the vector extension facility (SIMD) instructions, the code must be executed on a machine running on z/OS V2.2, or z/OS V2.1 with the PTFs for APARs OA43803 and PI12412 installed.

**Note:** A higher ARCH level includes the facilities of the lower ARCH level. For example, ARCH(11) includes all the facilities of the lower ARCH levels.

For more information about these facilities, see *z/Architecture Principles of Operation*.

## ARITH

ARITH affects the maximum number of digits that you can code for integers, and the number of digits used in fixed-point intermediate results.

### ARITH option syntax

➤ ARITH(  ) ➤

Default is: ARITH(COMPAT)

Abbreviations are: AR(C|E)

When you specify ARITH(EXTEND):

- The maximum number of digit positions that you can specify in the PICTURE clause for packed-decimal, external-decimal, and numeric-edited data items is raised from 18 to 31.
- The maximum number of digits that you can specify in a fixed-point numeric literal is raised from 18 to 31. You can use numeric literals with large precision anywhere that numeric literals are currently allowed, including:
  - Operands of PROCEDURE DIVISION statements
  - VALUE clauses (for numeric data items with large-precision PICTURE)
  - Condition-name values (on numeric data items with large-precision PICTURE)

- The maximum number of digits that you can specify in the arguments to NUMVAL, NUMVAL -C, and NUMVAL -F is raised from 18 to 31.
- The maximum value of the integer argument to the FACTORIAL function is 29.
- Intermediate results in arithmetic statements use *extended mode*.

When you specify ARITH(COMPAT):

- The maximum number of digit positions in the PICTURE clause for packed-decimal, external-decimal, and numeric-edited data items is 18.
- The maximum number of digits in a fixed-point numeric literal is 18.
- The maximum number of digits in the arguments to NUMVAL, NUMVAL -C, and NUMVAL -F is 18.

**Note:** NUMVAL uses long-precision floating point calculations to convert the digits in the argument to the numeric output. At most, 15 decimal digits can be converted accurately to long-precision floating point (as described in the related reference below about conversions and precision). Therefore, if the argument to NUMVAL, NUMVAL -C, or NUMVAL -F has more than 15 digits, it is recommended that you specify the ARITH(EXTEND) compiler option, so that the result will accurately represent the input argument.

- The maximum value of the integer argument to the FACTORIAL function is 28.
- Intermediate results in arithmetic statements use *compatibility mode*.


#### related concepts

Appendix A, “Intermediate results and arithmetic precision,” on page 655  
[“Conversions and precision” on page 50](#)

## AWO

If you specify AWO, an implicit APPLY WRITE-ONLY clause is activated for all QSAM files in the program that have blocked variable-length records.

#### AWO option syntax



Default is: NOAWO

Abbreviations are: None

#### related tasks

[“Optimizing buffer and device space” on page 10](#)

#### related references


[“BLOCK0” on page 293](#)

APPLY WRITE-ONLY clause (*Enterprise COBOL for z/OS Language Reference*)

# BLOCK0

Use BLOCK0 to change the compiler default for QSAM files from unblocked to blocked (as if BLOCK CONTAINS 0 were specified) and thus gain the benefit of system-determined blocking for output files.

## BLOCK0 option syntax



Default is: NOBLOCK0

Abbreviations are: None

Specifying BLOCK0 activates an implicit BLOCK CONTAINS 0 clause for each file in the program that meets the following three criteria:

- The FILE-CONTROL paragraph either specifies ORGANIZATION SEQUENTIAL or omits the ORGANIZATION clause.
- The FD entry does not specify RECORDING MODE U.
- The FD entry does not specify a BLOCK CONTAINS clause.

Files for which the resulting BLOCK CONTAINS 0 clause is in effect have a blocking factor that is determined at run time from the data definition or from the data-set characteristics.

## Interaction of the APPLY WRITE-ONLY clause and the AWO compiler option with BLOCK0:

- If NOBLOCK0 is in effect, and the file description of a file that meets the three criteria listed above specifies APPLY WRITE-ONLY, the compiler issues an error message because APPLY WRITE-ONLY applies only to blocked files. But if BLOCK0 is in effect, the result is that the file is blocked, and the APPLY WRITE-ONLY clause is therefore accepted.
- AWO applies to any QSAM files that have blocked variable-length records. If BLOCK0 is in effect, the result is that more files might be blocked than if NOBLOCK0 were in effect; thus AWO might apply to more files than it otherwise would.

Specifying BLOCK0 for existing programs might result in a change of behavior, and in some cases produce undesirable results for files opened as INPUT. For example:

- The OPEN INPUT statement fails for files for which no block size can be determined.
- Programs that continue after handling nonzero FILE STATUS codes for files opened as INPUT might abnormally terminate when executing subsequent I/O statements on those files.

For these reasons, after compiling with BLOCK0 you should investigate and test the effects on your program.

For recommendations about blocking, see the related reference from the *Enterprise COBOL for z/OS Migration Guide* (in the information about migrating from CMPR2 to NOCMPR2).

## related tasks

[“Optimizing buffer and device space” on page 10](#)

[“Setting block sizes” on page 158](#)

## related references

[“AWO” on page 292](#)

[APPLY WRITE-ONLY clause \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

[BLOCK CONTAINS clause \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)


[Enterprise COBOL for z/OS Migration Guide](#)

(Recommendation for DCB= parameters of JCL)

## BUFSIZE

Use BUFSIZE to allocate an amount of main storage to the buffer for each compiler work data set. Usually, a large buffer size improves the performance of the compiler.

### BUFSIZE option syntax

➡➡ BUFSIZE(  ) ➡➡

Default is: 4096

Abbreviations are: BUF

*nnnnn* specifies a decimal number that must be at least 256.


*nnnK* specifies a decimal number in 1 KB increments, where 1 KB = 1024 bytes.

BUFSIZE cannot exceed the track capacity for the device used, nor can it exceed the maximum allowed by data management services.

## CICS

The CICS compiler option enables the integrated CICS translator and lets you specify CICS suboptions. You must use the CICS option if your COBOL source program contains EXEC CICS or EXEC DLI statements and the program has not been processed by the separate CICS translator.

### CICS option syntax

➡➡  ➡➡

Default is: NOCICS

Abbreviations are: None

Use the CICS option only to compile CICS programs. Programs compiled with the CICS option will not run in a non-CICS environment.

If you specify the NOCICS option, any CICS statements found in the source program are diagnosed and discarded.

Use either quotation marks or apostrophes to delimit the string of CICS suboptions.

You can partition a long CICS suboption string into multiple suboption strings in multiple CBL or PROCESS statements. The CICS suboptions are concatenated in the order of their appearance. For example:

```
//STEP1 EXEC IGYWC, . . .
// PARM.COBOLE='CICS("string1")'
//COBOL.SYSIN DD *
  CBL CICS('string2')
  CBL CICS("string3")
  IDENTIFICATION DIVISION.
  PROGRAM-ID. DRIVER1.
  . . .
```

The compiler passes the following suboption string to the integrated CICS translator:

```
"string1 string2 string3"
```

The concatenated strings are delimited with single spaces as shown. If multiple instances of the same CICS suboption are found, the last specification of that suboption in the concatenated string prevails. The compiler limits the size of the concatenated suboption string to 4 KB.

#### **related concepts**

[“Integrated CICS translator” on page 412](#)

#### **related tasks**

[“Compiling with the CICS option” on page 411](#)

[“Separating CICS suboptions” on page 412](#)

[Defining translator options](#) (*Developing CICS Applications*)

#### **related references**

[“Conflicting compiler options” on page 287](#)

## CODEPAGE

Use CODEPAGE to specify the coded character set identifier (CCSID) for an EBCDIC code page for processing compile-time and runtime COBOL operations that are sensitive to character encoding.

### **CODEPAGE option syntax**

► CODEPAGE( *ccsid* ) ◄

Default is: CODEPAGE (1140)

Abbreviations are: CP (*ccsid*)

*ccsid* must be an integer that represents a valid CCSID for an EBCDIC code page.

The default CCSID 1140 is the equivalent of CCSID 37 (COM EUROPE EBCDIC), but additionally includes the euro symbol.

*ccsid* specifies these encodings:

- The encoding for alphanumeric, national, and DBCS literals in a COBOL source program
- The default encoding of the content of alphanumeric and DBCS data items at run time
- The encoding for DBCS user-defined words when processed by an XML GENERATE statement to create XML element and attribute names
- The default encoding of an XML document created by an XML GENERATE statement if the receiving data item for the document is alphanumeric
- The default encoding assumed for an XML document in an alphanumeric data item when the document is processed by an XML PARSE statement

The CODEPAGE *ccsid* is used when code-page-sensitive operations are performed at compile time or run time, and an explicit CCSID that overrides the default code page is not specified. Such operations include:

- Conversion of literal values to Unicode
- Conversion of alphanumeric data to and from national (Unicode) data as part of move operations, comparison, or the intrinsic functions DISPLAY-OF and NATIONAL-OF
- Object-oriented language such as INVOKE statements or class definitions and method definitions
- XML parsing
- XML generation
- Processing of DBCS names as part of XML generation at run time

- Processing of SQL string host variables if the SQLCCSID option is in effect
- Processing of source code for EXEC SQL statements
- Processing of source code for EXEC SQLIMS statements

However, the encoding of the following items in a COBOL source program is not affected by the CODEPAGE compiler option:

- Data items that have USAGE NATIONAL

These items are always encoded in UTF-16 in big-endian format, CCSID 1200.

- Characters from the basic COBOL character set (see the table of these characters in the related reference below about characters)

Though the encoding of the basic COBOL characters default currency sign (\$), quotation mark ("), and the lowercase Latin letters varies in different EBCDIC code pages, the compiler always interprets these characters using the EBCDIC code page 1140 encoding. In particular, the default currency sign is always the character with value X'5B' (unless changed by the CURRENCY compiler option or the CURRENCY SIGN clause in the SPECIAL-NAMES paragraph), and the quotation mark is always the character with value X'7F'.

Some COBOL operations can override the CODEPAGE *ccsid* by using an explicit encoding specification, for example:

- DISPLAY-OF and NATIONAL-OF intrinsic functions that specify a code page as the second argument
- XML PARSE statements that specify the WITH ENCODING phrase
- XML GENERATE statements that specify the WITH ENCODING phrase

Additionally, you can use the CURRENCY compiler option or the CURRENCY SIGN clause in the SPECIAL-NAMES paragraph to override:

- The default currency symbol used in the PICTURE character-strings for numeric-edited data items in your source program
- The currency sign value used in the content of numeric-edited data items at run time

#### DBCS code pages:

Compile your COBOL program using the CODEPAGE option with the *ccsid* set to one of the EBCDIC multibyte character set (MBCS) CCSIDs shown in the table below if the program contains any of the following items:

- User-defined words formed with DBCS characters
- DBCS (USAGE DISPLAY-1) data items
- DBCS literals

All of the CCSIDs in the table below identify mixed code pages that refer to a combination of SBCS and DBCS coded character sets. These are also the CCSIDs that are supported for mixed data by DB2.

<i>Table 45. EBCDIC multibyte coded character set identifiers</i>			
National language	MBCS CCSID	SBCS CCSID component	DBCS CCSID component
Japanese (Katakana-Kanji)	930	290	300
Japanese (Katakana-Kanji with euro)	1390	8482	16684
Japanese (Katakana-Kanji)	5026	290	4396
Japanese (Latin-Kanji)	939	1027	300
Japanese (Latin-Kanji with euro)	1399	5123	16684
Japanese (Latin-Kanji)	5035	1027	4396

Table 45. **EBCDIC multibyte coded character set identifiers** (continued)

National language	MBCS CCSID	SBCS CCSID component	DBCS CCSID component
Korean	933	833	834
Korean	1364	13121	4930
Simplified Chinese	935	836	837
Simplified Chinese	1388	13124	4933
Traditional Chinese	937	28709	835

**Note:** If you specify the TEST option, you must set the CODEPAGE option to the CCSID that is used for the COBOL source program. In particular, programs that use Japanese characters in DBCS literals or DBCS user-defined words must be compiled with the CODEPAGE option set to a Japanese codepage CCSID.

#### related concepts

[“COBOL and DB2 CCSID determination” on page 422](#)

#### related tasks

[“Using currency signs” on page 61](#)

[Chapter 31, “Processing XML input,” on page 505](#)

[Chapter 32, “Producing XML output,” on page 545](#)

#### related references

[“CURRENCY” on page 299](#)

[“SQLCCSID” on page 336](#)

[“TEST” on page 340](#)


[“The encoding of XML documents” on page 522](#)

Characters (*Enterprise COBOL for z/OS Language Reference*)

## COMPILE

Use the COMPILE option only if you want to force full compilation even in the presence of serious errors. All diagnostics and object code will be generated. Do not try to run the object code if the compilation resulted in serious errors: the results could be unpredictable or an abnormal termination could occur.

#### COMPILE option syntax



Default is: NOCOMPILE (S)

Abbreviations are: C|NOC

Use NOCOMPILE without any suboption to request a syntax check (only diagnostics produced, no object code). If you use NOCOMPILE without any suboption, several compiler options will have no effect because no object code will be produced, for example: DECK, LIST, OBJECT, OFFSET, OPTIMIZE, SSRANGE, and TEST.

Use NOCOMPILE with suboption W, E, or S for conditional full compilation. Full compilation (diagnosis and object code) will stop when the compiler finds an error of the level you specify (or higher), and only syntax checking will continue.

#### related tasks

[“Finding coding errors” on page 365](#)

#### related references


[“Messages and listings for compiler-detected errors” on page 262](#)

## COPYLOC

Use the COPYLOC compiler option to add either a PDSE (or PDS) dataset or z/OS UNIX directory as an additional location to be searched for copy members during the library phase. The location specified by the COPYLOC option is added to the end of the order of locations to search for copy members. For details, see COPY member search order in the Enterprise COBOL for z/OS Language Reference.

COPYLOC is introduced in Enterprise COBOL V6.1 with the PTF for APAR PI96231 installed.

### COPYLOC option syntax



Default is: NOCOPYLOC

Abbreviations are: CPLC | NOCPLC

#### library-name

The library name that the copy location is to be associated with. When *library-name* is not specified, the default is SYSLIB, which is the library name assumed in COPY statements that do not include an explicit library name.

#### dataset-name

The name of a PDS or PDSE dataset in which the compiler should search for copy members when processing COPY statements that refer to library *library-name*.

#### unix-directory-name

The name of a z/OS UNIX directory in which the compiler should search for copy members when processing COPY statements that refer to library *library-name*. The specified path must not exceed 64 characters. To specify a lowercase path, which is standard for z/OS UNIX, the path should be surrounded in quotes. Otherwise, the path name will be converted to uppercase.

Multiple instances of the COPYLOC option are supported. There is no limit on the number of z/OS UNIX directories that can be specified, but there is a limit of 256 datasets that can be specified for searching. Copy locations will be searched in the order that they are specified via the COPYLOC option. This provides users the ability to mix PDSE (or PDS) locations and z/OS UNIX directories in the search.

If the NOCOPYLOC option is specified, any previous instances of the COPYLOC option are ignored.

To control the searching of copy member locations exclusively using the COPYLOC option, you should avoid using any of the existing methods for indicating copybook locations, such as, allocating datasets to a ddname in JCL, or specifying the -I option of the cob2 command. If the compiler is invoked from cob2, you should also avoid keeping copy members in the current directory, because the current directory will always be searched before the COPYLOC locations are being searched.

**Tip:** You might find it convenient to control searching of copy members exclusively using the COPYLOC option, especially when the compiler is invoked from the cob2 command.

When COPYLOC options are specified in CBL statements, they can be used only on the first program of a batch program. Therefore, if a file has multiple COBOL programs in it, there can be CBL statements with COPYLOC options preceding the first program, but not the other programs. The COPYLOC options specified for the first program (and COPYLOC options specified in PARM of JCL or COPYLOC options specified as cob2 command options under z/OS UNIX) apply to all programs in a file. The copy locations specified in COPYLOC options found in CBL cards will be searched after copy locations found in COPYLOC options specified as invocation parameters.

### Example

```
COPYLOC(MYLIB,DSN(USERID.COBOL.COPYLIB1))  
COPYLOC(MYLIB,PATH('/home/userid/copylib1'))  
COPYLOC(MYLIB,DSN(USERID.COBOL.COPYLIB2))
```

For COPY statements that reference library name MYLIB explicitly, if the preceding options were specified in a single invocation of the compiler and a copy member could not be found in the locations specified in JCL (or in locations indicated for a cob2 compile), additional searching for the copy member will be done in the following places sequentially:

1. *USERID.COBOL.COPYLIB1* dataset
2. z/OS UNIX directory */home/userid/copylib1*
3. *USERID.COBOL.COPYLIB2* dataset

### related references

COPY statement (*Enterprise COBOL for z/OS Language Reference*)


COPY member search order (*Enterprise COBOL for z/OS Language Reference*)

ALLOWCOPYLOC (*Enterprise COBOL Customization Guide*)

## COPYRIGHT

Use COPYRIGHT to place a string in the object module if the object module is generated. If the object is linked into a program object, the string is loaded into memory with that program object.

### COPYRIGHT option syntax



Default is: NOCOPYRIGHT


Abbreviations are: CPYR|NOCPYR

The *copyright string* is limited to 64 characters in length.

## CURRENCY

You can use the CURRENCY option to provide an alternate default currency symbol to be used for a COBOL program. (The default currency symbol is the dollar sign (\$).)

### CURRENCY option syntax



Default is: NOCURRENCY

Abbreviations are: CURR|NOCURR

NOCURRENCY specifies that no alternate default currency symbol will be used.

To change the default currency symbol, specify CURRENCY (*literal*), where *literal* is a valid COBOL alphanumeric literal (optionally a hexadecimal literal) that represents a single character. The literal must not be from the following list:

- Digits zero (0) through nine (9)
- Uppercase alphabetic characters A B C D E G N P R S V X Z or their lowercase equivalents
- The space
- Special characters \* + - / , . ; ( ) " =
- A figurative constant
- A null-terminated literal
- A DBCS literal
- A national literal

If your program processes only one currency type, you can use the CURRENCY option as an alternative to the CURRENCY SIGN clause for indicating the currency symbol you will use in the PICTURE clause of your program. If your program processes more than one currency type, you should use the CURRENCY SIGN clause with the WITH PICTURE SYMBOL phrase to specify the different currency sign types.

If you use both the CURRENCY option and the CURRENCY SIGN clause in a program, the CURRENCY option is ignored. Currency symbols specified in the CURRENCY SIGN clause or clauses can be used in PICTURE clauses.

When the NOCURRENCY option is in effect and you omit the CURRENCY SIGN clause, the dollar sign (\$) is used as the PICTURE symbol for the currency sign.

**Delimiter:** You can delimit the CURRENCY option literal with either quotation marks or apostrophes, regardless of the APOST | QUOTE compiler option setting.


#### related tasks

[“Using currency signs” on page 61](#)

## DATA

The DATA option affects whether storage for dynamic data areas and other dynamic runtime storage is obtained from above or below the 16 MB line.

#### DATA option syntax

➡ DATA(  ) ➡

Default is: DATA(31)

Abbreviations are: None

For reentrant programs, the DATA compiler option and the HEAP runtime option control whether storage for dynamic data areas (such as WORKING-STORAGE and FD record areas) is obtained from below the 16 MB line (DATA(24)) or from unrestricted storage (DATA(31)). (DATA does not affect the location of LOCAL-STORAGE data; the STACK runtime option controls that location instead, along with the AMODE of the program.)

Specify DATA(24) for programs that run in 31-bit addressing mode and that pass data arguments to programs in 24-bit addressing mode. Doing so ensures that the data will be addressable by the called program.

**External data and QSAM buffers:** The DATA option interacts with other compiler options and runtime options that affect storage and its addressability. See the related information for details.

The DATA compiler option setting influences how ALLOCATE acquires storage:

- If DATA(24) is in effect and the LOC 31 phrase of the ALLOCATE statement is not specified, ALLOCATE acquires storage from below the 16 MB line.
- If DATA(31) is in effect and the LOC 24 phrase of the ALLOCATE statement is not specified, ALLOCATE will attempt to acquire storage from above the 16 MB line.

#### related concepts

[“Storage and its addressability” on page 37](#)

#### related tasks

[“Making programs reentrant” on page 464](#)

*Language Environment Programming Guide* (Using runtime options)

#### related references

[“Allocation of buffers for QSAM files” on page 170](#)

[“RENT” on page 330](#)


ALLOCATE statement

(*Enterprise COBOL for z/OS Language Reference*)

## DBCS

Using DBCS causes the compiler to recognize X'0E' (SO) and X'0F' (SI) as shift codes for the double-byte portion of an alphanumeric literal.

#### DBCS option syntax



Default is: DBCS

Abbreviations are: None

With DBCS in effect, the double-byte portion of the literal is syntax-checked and the literal remains category alphanumeric.


#### related references

[“Conflicting compiler options” on page 287](#)

## DECK

Use DECK to produce object code in the form of 80-column records. If you use the DECK option, be certain that SYSPUNCH is defined in your JCL for compilation.

#### DECK option syntax



Default is: NODECK

Abbreviations are: D|NOD


### related tasks

[“Creating object code \(SYSLIN or SYSPUNCH\)” on page 253](#)

## DIAGTRUNC

DIAGTRUNC causes the compiler to issue a severity-4 (Warning) diagnostic message for MOVE statements that have numeric receivers when the receiving data item has fewer integer positions than the sending data item or literal. In statements that have multiple receivers, the message is issued separately for each receiver that could be truncated.

### DIAGTRUNC option syntax



Default is: NODIAGTRUNC

Abbreviations are: DTR | NODTR

The diagnostic message is also issued for implicit moves associated with statements such as these:

- INITIALIZE
- READ . . . INTO
- RELEASE . . . FROM
- RETURN . . . INTO
- REWRITE . . . FROM
- WRITE . . . FROM

The diagnostic message is also issued for moves to numeric receivers from alphanumeric data-names or literal senders, except when the sending field is reference modified.

There is no diagnostic message for COMP-5 receivers, nor for binary receivers when you specify the TRUNC (BIN) option.

### related concepts

[“Formats for numeric data” on page 45](#)

[“Reference modifiers” on page 108](#)


### related references

[“TRUNC” on page 344](#)

## DISPSIGN

The DISPSIGN option controls output formatting for DISPLAY of signed numeric items.

### DISPSIGN option syntax



Default is: DISPSIGN (COMPAT)

Abbreviations are: DS (C | S)

### DISPSIGN(COMPAT)

If you specify DISPSIGN(COMPAT), formatting for displayed values of signed numeric items is compatible with prior versions of Enterprise COBOL. Overpunch signs are generated in some cases.

### DISPSIGN(SEP)

If you specify DISPSIGN(SEP), the displayed values for signed binary, signed packed-decimal, or overpunch signed zoned-decimal items are always formatted with a leading separate sign.

The following example shows the DISPLAY output with the DISPSIGN(COMPAT) option or the DISPSIGN(SEP) option specified:


Table 46. DISPLAY output with the DISPSIGN(COMPAT) option or the DISPSIGN(SEP) option specified:		
Data items	DISPLAY output with the DISPSIGN(COMPAT) option specified	DISPLAY output with the DISPSIGN(SEP) option specified
Unsigned binary	111	111
Positive binary	111	+111
Negative binary	11J	-111
Unsigned packed-decimal	222	222
Positive packed-decimal	222	+222
Negative packed-decimal	22K	-222
Zoned-decimal unsigned	333	333
Zoned-decimal trailing positive	33C	+333
Zoned-decimal trailing negative	33L	-333
Zoned-decimal leading positive	C33	+333
Zoned-decimal leading negative	L33	-333

## DLL

Use DLL to instruct the compiler to generate an object module that is enabled for dynamic link library (DLL) support. DLL enablement is required if the program will be part of a DLL, will reference DLLs, or if the program contains object-oriented COBOL syntax such as INVOKE statements or class definitions.

**Note:** The DLL option can be overridden for particular CALL statements by using the CALLINTERFACE directive.

### DLL option syntax



Default is: NODLL

Abbreviations are: None

**Link-edit considerations:** COBOL programs that are compiled with the DLL option must be link-edited with the RENT and AMODE 31 link-edit options.

NODLL instructs the compiler to generate an object module that is not enabled for DLL usage.

### related tasks

[“Making dynamic calls” on page 452](#)

## related references


[“Conflicting compiler options” on page 287](#)

CALLINTERFACE (*Enterprise COBOL for z/OS Language Reference*)

# DUMP

Use DUMP to produce a system dump at compile time for an internal compiler error.

## DUMP option syntax



Default is: NODUMP

Abbreviations are: DU|NODU

**Not for general use:** The DUMP option should be used only at the request of an IBM representative.

The dump, which consists of a listing of the compiler's registers and a storage dump, is intended primarily for diagnostic personnel for determining errors in the compiler.

If you use the DUMP option, include a DD statement at compile time to define SYSABEND, SYSUDUMP, or SYSMDUMP.

With DUMP, the compiler will not issue a diagnostic message before abnormal termination processing. Instead, a user abend will be issued with an IGYppnnnn message. In general, a message IGYppnnnn corresponds to a compile-time user abend nnnn. However, both IGYpp5nnn and IGYpp1nnn messages produce a user abend of 1nnn. You can usually distinguish whether the message is really a 5nnn or a 1nnn by recompiling with the NODUMP option.

Use NODUMP if you want normal termination processing, including:

- Diagnostic messages produced so far in compilation.
- A description of the error.
- The name of the compiler phase currently executing.
- The line number of the COBOL statement being processed when the error was found. (If you compiled with OPTIMIZE (1 | 2), the line number might not always be correct; for some errors, it will be the last line in the program.)
- The contents of the general purpose registers.

Using the DUMP and OPTIMIZE (1 | 2) compiler options together could cause the compiler to produce a system dump instead of the following optimizer message:

```
"IGYOP3124-W This statement may cause a program exception at
execution time."
```

This situation does not represent a compiler error. Using the NODUMP option will allow the compiler to issue message IGYOP3124-W and continue processing.

## related tasks

*Language Environment Debugging Guide* (Understanding abend codes)

## related references

[“Conflicting compiler options” on page 287](#)

## DYNAM


---

Use DYNAM to cause nonnested, separately compiled programs invoked through the CALL *literal* statement to be loaded for CALL, and deleted for CANCEL, dynamically at run time.

**Note:** The DYNAM option can be overridden for particular CALL statements by using the CALLINTERFACE directive.

CALL *identifier* statements always result in a runtime load of the target program and are not affected by this option.

### DYNAM option syntax



Default is: NODYNAM

Abbreviations are: DYN|NODYN

**Restriction:** The DYNAM compiler option must not be used in the following cases:

- COBOL programs that are processed by the CICS translator or the CICS compiler option
- COBOL programs that have EXEC SQL statements and are run under CICS or DB2 call attach facility (CAF)

If your COBOL program calls programs that have been linked as dynamic link libraries (DLLs), you must not use the DYNAM option. You must instead compile the program with the NODYNAM and DLL options.

### related tasks

[“Making both static and dynamic calls” on page 456](#)

[“Choosing the DYNAM or NODYNAM compiler option” on page 426](#)

### related references

[“Conflicting compiler options” on page 287](#)

CALLINTERFACE (*Enterprise COBOL for z/OS Language Reference*)

## EXIT

---


Use the EXIT option to provide user-supplied modules in place of various compiler functions.

For compiler input, use the INEXIT and LIBEXIT suboptions to provide modules in place of SYSIN and SYSLIB (or copy library), respectively. For compiler output, use the PRTEXTIT suboption to provide a module in place of SYSPRINT.

To provide a module that will be called for each SYSADATA record immediately after the record has been written out to the file, use the ADEXIT suboption.

To customize compiler messages (change their severity or suppress them, including converting FIPS (FLAGSTD) messages to diagnostic messages to which you assign a severity), use the MSGEXIT suboption. The module that you provide to customize the messages will be called each time the compiler issues a diagnostic message or a FIPS message.

## EXIT option syntax



Default is: NOEXIT

Abbreviations are: NOEX | EX (INX | NOINX, LIBX | NOLIBX, PRTX | NOPRTX, ADX | NOADX, MSGX | NOMSGX)

You can specify the suboptions in any order, and can separate them by either commas or spaces. If you specify both the positive and negative form of a suboption, the form specified last takes effect. If you specify the same suboption more than once, the last one specified takes effect.

If you specify the EXIT option without specifying at least one suboption, NOEXIT will be in effect.

You can specify the EXIT option only at invocation in the JCL PARM field (under TSO/E, in a command argument) or at installation time. Do not specify the EXIT option in a PROCESS (CBL) statement.

### **INEXIT(['str1'],mod1)**

The compiler reads source code from a user-supplied program object (where *mod1* is the module name) instead of SYSIN.

### **LIBEXIT(['str2'],mod2)**

The compiler obtains copybooks from a user-supplied program object (where *mod2* is the module name) instead of *library-name* or SYSLIB. For use with either COPY or BASIS statements.

### **PRTEXIT(['str3'],mod3)**

The compiler passes printer-destined output to the user-supplied program object (where *mod3* is the module name) instead of SYSPRINT.

### **ADEXIT(['str4'],mod4)**

The compiler passes the SYSADATA output to the user-supplied program object (where *mod4* is the module name).

### **MSGEXIT(['str5'],mod5)**

The compiler passes the message number, and passes the default severity of a compiler diagnostic message, or the category (as a numeric code) of a FIPS compiler message, to the user-supplied program object (where *mod5* is the module name).

The names *mod1*, *mod2*, *mod3*, *mod4*, and *mod5* can refer to the same module.

The suboptions *str1*, *str2*, *str3*, *str4*, and *str5* are character strings that are passed to the program object. These strings are optional. They can be up to 64 characters in length, and you must enclose them in a pair of apostrophes ( ' '). You can use any character in the strings, but any included apostrophes must be doubled ( " ). Lowercase characters are folded to uppercase.

If one of *str1*, *str2*, *str3*, *str4*, or *str5* is specified, that string is passed to the appropriate user-exit module in the following format, where LL is a halfword (on a halfword boundary) that contains the length of the string.

LL *string*

[“Example: MSGEXIT user exit” on page 695](#)

Compiler exit modules that are specified on the EXIT option can be implemented either in an assembler language or in a high-level programming language such as COBOL. However, when exits are written in a Language Environment conforming programming language or Language Environment conforming assembler language, the exit must be reentrant.

The Enterprise COBOL compiler automatically manages a preinitialized Language Environment at compile time, and calls compiler exits within this environment. Therefore, the following rules apply:

- Compiler exits are run as subprograms instead of main programs.
- Compiler exits must not include logic for explicitly initializing or terminating Language Environment. In particular, exits must not use the RTEREUS runtime option, the IGZERRE callable service, or the CEEPIPI callable service for environment management.
- Compiler exits must not use the STOP RUN statement.

#### **related references**

[“Conflicting compiler options” on page 287](#)

[“FLAGSTD” on page 309](#)

[Appendix E, “EXIT compiler option,” on page 683](#)

## **EXPORTALL**

Use EXPORTALL to instruct the compiler to automatically export the PROGRAM-ID name and each alternate entry-point name from each program definition when the object deck is link-edited to form a DLL.

#### **EXPORTALL option syntax**



Default is: NOEXPORTALL

Abbreviations are: EXP|NOEXP

With these symbols exported from the DLL, the exported program and entry-point names can be called from programs in the root program object, in other DLL program objects in the application, and from programs that are linked into that DLL.

Specification of the EXPORTALL option requires that the RENT linker option also be used.

NOEXPORTALL instructs the compiler to not export any symbols. In this case the programs are accessible only from other routines that are link-edited into the same program object as the COBOL program definition.


#### **related references**

[“Conflicting compiler options” on page 287](#)

## FASTSRT

Use FASTSRT to let IBM DFSORT, or an equivalent product, perform sort input and output instead of Enterprise COBOL. It applies only to sorting files by using the format 1 SORT (that is, file SORT) statement.

### FASTSRT option syntax



Default is: NOFASTSRT

Abbreviations are: FSRT|NOFSRT


### related tasks

[“Improving sort performance with FASTSRT” on page 216](#)

## FLAG

Use FLAG(*x*) to produce diagnostic messages at the end of the source listing for errors of a severity level *x* or above.

### FLAG option syntax



Default is: FLAG(I, I)

Abbreviations are: F|NOF

*x* and *y* can be either I, W, E, S, or U.

Use FLAG(*x*, *y*) to produce diagnostic messages for errors of severity level *x* or above at the end of the source listing, with error messages of severity *y* and above to be embedded directly in the source listing. The severity coded for *y* must not be lower than the severity coded for *x*. To use FLAG(*x*, *y*), you must also specify the SOURCE compiler option.

Error messages in the source listing are set off by the embedding of the statement number in an arrow that points to the message code. The message code is followed by the message text. For example:

```
000413      MOVE CORR WS-DATE TO HEADER-DATE
==000413==>  IGYPS2121-S      " WS-DATE " was not defined as a data-name. . . .
```

When FLAG(*x*, *y*) is in effect, most messages of severity *y* and above are embedded in the listing after the line that caused the message. Messages with the IGYCB prefix will never be embedded in the source. (See the related reference below for information about messages for exceptions.)

Use NOFLAG to suppress error flagging. NOFLAG does not suppress error messages for compiler options.

### Embedded messages

- Embedding level-U messages is not recommended. The specification of embedded level-U messages is accepted, but does not produce any messages in the source.

- The FLAG option does not affect diagnostic messages that are produced before the compiler options are processed.
- Diagnostic messages that are produced during processing of compiler options, CBL or PROCESS statements, or BASIS, COPY, or REPLACE statements are not embedded in the source listing. All such messages appear at the beginning of the compiler output.
- Diagnostic messages with the IGYCB prefix are not embedded in the source listing. All such messages appear at the end of the compiler output, regardless of the setting of the FLAG option.
- Messages that are produced during processing of the \*CONTROL or \*CBL statement are not embedded in the source listing.

#### related references

[“Messages and listings for compiler-detected errors” on page 262](#)


## FLAGSTD

Use FLAGSTD to specify the level or subset of the 85 COBOL Standard to be regarded as conforming, and to get informational messages about the 85 COBOL Standard elements that are included in your program.

You can specify any of the following items for flagging:

- A selected Federal Information Processing Standard (FIPS) COBOL subset
- Any of the optional modules
- Obsolete language elements
- Any combination of subset and optional modules
- Any combination of subset and obsolete elements
- IBM extensions (these are flagged any time that FLAGSTD is specified, and identified as "nonconforming nonstandard")

#### FLAGSTD option syntax



Default is: NOFLAGSTD

Abbreviations are: None

x specifies the subset of the 85 COBOL Standard to be regarded as conforming:

#### M

Language elements that are not from the minimum subset are to be flagged as "nonconforming standard."

#### I

Language elements that are not from the minimum or the intermediate subset are to be flagged as "nonconforming standard."

#### H

The high subset is being used and elements will not be flagged by subset. Elements that are IBM extensions will be flagged as "nonconforming Standard, IBM extension."

yy specifies, by a single character or combination of any two, the optional modules to be included in the subset:

#### D

Elements from debug module level 1 are not flagged as "nonconforming standard."

## N

Elements from segmentation module level 1 are not flagged as "nonconforming standard."

## S

Elements from segmentation module level 2 are not flagged as "nonconforming standard."

If S is specified, N is included (N is a subset of S).

0 (the letter) specifies that obsolete language elements are flagged as "obsolete."

The informational messages appear in the source program listing, and identify:

- The element as "obsolete," "nonconforming standard," or "nonconforming nonstandard" (a language element that is both obsolete and nonconforming is flagged as obsolete only)
- The clause, statement, or header that contains the element
- The source program line and beginning location of the clause, statement, or header that contains the element
- The subset or optional module to which the element belongs

FLAGSTD requires the standard set of reserved words.

In the following example, the line number and column where a flagged clause, statement, or header occurred are shown with the associated message code and text. After that is a summary of the total number of flagged items and their type.

LINE	COL	CODE	FIPS MESSAGE TEXT
		IGYDS8211	Comment lines before "IDENTIFICATION DIVISION": nonconforming nonstandard, IBM extension to ANS/ISO 1985.
11.14		IGYDS8111	"GLOBAL clause": nonconforming standard, ANS/ISO 1985 high subset.
59.12		IGYPS8169	"USE FOR DEBUGGING statement": obsolete element in ANS/ISO 1985.
FIPS MESSAGES TOTAL			
		STANDARD	NONSTANDARD
		1	1
		OBSOLETE	1

You can convert FIPS informational messages into diagnostic messages, and can suppress FIPS messages, by using the MSGEXIT suboption of the EXIT compiler option. For details, see the related reference about the processing of MSGEXIT, and see the related task.

### related tasks

["Customizing compiler-message severities" on page 693](#)

### related references


["Conflicting compiler options" on page 287](#)

["Processing of MSGEXIT" on page 691](#)

## HGPR

The HGPR option controls the compiler usage of the 64-bit registers provided by z/Architecture processors.

### HGPR option syntax

➤ HGPR(  ) ➤

Default is: HGPR(PRESERVE)

Abbreviations are: None

The Enterprise COBOL compiler uses the 64-bit width of the z/Architecture General Purpose Registers (GPRs). HGPR stands for "High-halves of 64-bit GPRs", which means the use of native 64-bit instructions.

### HGPR(PRESERVE)

If you specify HGPR(PRESERVE), the compiler preserves the high halves of the 64-bit GPRs that a program is using, by saving them in the prolog for the function and restoring them in the epilog. The PRESERVE suboption is necessary only if the caller of the program is not Enterprise COBOL, Enterprise PL/I, or z/OS XL C/C++ compiler-generated code.


### HGPR(NOPRESERVE)

If you specify HGPR(NOPRESERVE), the compiler omits preserving the high-halves of the 64-bit GPRs that a program is using, which improves performance.

## INITCHECK

Use the INITCHECK option to have the compiler check for uninitialized data items and issue warning messages when they are used without being initialized.

### INITCHECK option syntax



Default is: NOINITCHECK

Suboption default is: INITCHECK(LAX) if INITCHECK is specified with no suboption

Abbreviations are: IC | NOIC

### NOINITCHECK

If NOINITCHECK is in effect, the compiler will not issue any warning messages for uninitialized data items.

### INITCHECK(LAX | STRICT)

If INITCHECK or INITCHECK(LAX) is in effect, the compiler will check for uninitialized data items and issue a warning message when a data item is used without being initialized. However, if a data item is initialized on at least one logical path to a statement, no warning message will be issued.

If INITCHECK(STRICT) is in effect, the compiler will still check for uninitialized data items and issue a warning message when a data item is used without being initialized. However, unlike INITCHECK(LAX), INITCHECK(STRICT) will issue a warning message about uninitialized data for a data item used in a statement unless the data item is initialized on all logical paths to the statement.

Here is a sample program to illustrate the behavior differences between specifying INITCHECK(LAX) versus INITCHECK(STRICT). Y and Z represent some data items, with no value clauses:

```
PROCEDURE DIVISION.
  IF Y > 5
    MOVE 2 TO Z
  END-IF
  DISPLAY Z
```

Z is initialized on one path to the DISPLAY statement but not the other, so if INITCHECK(LAX) is in effect, a warning message will be issued for Y only, while INITCHECK(STRICT) will also issue a warning message for Z.

#### Restrictions:

- The INITCHECK option analyzes data items in the WORKING-STORAGE SECTION and LOCAL-STORAGE SECTION only. In particular, it does not analyze data items in the LINKAGE SECTION or FILE SECTION.
- The INITCHECK analysis does not track external or global data items.
- The INITCHECK analysis does not track individual elements in tables independently. Instead, if one element of a table is initialized, all corresponding elements of the table are considered to be initialized. This applies to both fixed-length and variable-length tables.
- The INITCHECK analysis does not track the initialization of items if it happens through a pointer. For example, if a pointer to an uninitialized data item is created by using ADDRESS-OF, and that data item is initialized through that pointer, the INITCHECK analysis might also issue a warning message.
- For uninitialized data items being passed BY REFERENCE, no warning messages will be issued. However, the INITCHECK analysis will warn about uninitialized data items being passed BY CONTENT and BY VALUE.
- The INITCHECK option does not track individual bytes of reference-modified data items accurately. Instead, if a data item is accessed by using a reference modification, this data item is considered to be initialized.
- If a data item is in a group with other items that have had their address taken, for example, as the result of being an SQL host variable, then that data item will also be considered to have its address taken, and the set of all address taken data items is always considered to be set by any call to an external function.


#### Notes:

- All of the INITCHECK analyses occur at compile time only.
- The INITCHECK option has no effect on the behavior or performance of the program after it has been compiled.
- Use of the INITCHECK option might increase compile time and memory consumption.
- INITCHECK is more accurate when used with OPT(1) or OPT(2), but it is also helpful when used with OPT(0).

## INLINE

The INLINE compiler option controls whether the inlining of procedures (paragraphs or sections) referenced by PERFORM statements in the source program is allowed.

#### INLINE option syntax



Default is: INLINE

Abbreviations are: INL | NOINL

#### INLINE

INLINE is a potential performance-boosting option.

Specifying INLINE causes the compiler to allow the inlining of procedures referenced by PERFORM statements in the source program when OPTIMIZE(1) or OPTIMIZE(2) is in effect. Whether or not to inline procedures in a specific PERFORM block is determined by the compiler.

*Inlining*<sup>1</sup> can be prevented for specific paragraphs by using the `>>INLINE ON` and `>>INLINE OFF` directives in the program source code when memory usage is a concern and there is a desire to reduce the overall size of the executable, such as in a CICS region.

**Note:**

1. The word *inlining* here implies that the compiler might choose to replace the `PERFORM` of a procedure (paragraph or section) with a copy of that procedure's code. By inserting the procedure code at the location of the `PERFORM`, the compiler saves the overhead of branching logic to and from the procedure.

**NOINLINE**

Specifying `NOINLINE` causes no inlining of procedures referenced by `PERFORM` statements, regardless of the optimization level in effect. `NOINLINE` can be specified in cases where there is a desire to reduce the overall size of the executable when memory usage is a concern, such as in a CICS region. `NOINLINE` cannot be overridden by using the `>>INLINE ON` directive.

**related references**

`INLINE` directive (*Enterprise COBOL for z/OS Language Reference*)

## INTDATE

`INTDATE (ANSI)` instructs the compiler to use the 85 COBOL Standard starting date for integer dates used with date intrinsic functions. Day 1 is Jan 1, 1601. `INTDATE (LILIAN)` instructs the compiler to use the Language Environment Lilian starting date for integer dates used with date intrinsic functions. Day 1 is Oct 15, 1582.

**INTDATE option syntax**

►► `INTDATE( 
ANSI
LILIAN
 )` ◄◄

Default is: `INTDATE (ANSI)`

Abbreviations are: None

With `INTDATE (LILIAN)`, the date intrinsic functions return results that are compatible with the Language Environment date callable services.

**Usage note:** When `INTDATE (LILIAN)` is in effect, `CEEGBLDY` is not usable because you have no way to turn an ANSI integer into a meaningful date by using either intrinsic functions or callable services. If you code a `CALL literal` statement with `CEEGBLDY` as the target of the call when `INTDATE (LILIAN)` is in effect, the compiler diagnoses this and converts the call target to `CEEDAYS`.

**related tasks**

[“Using date callable services” on page 57](#)

## LANGUAGE

Use the `LANGUAGE` option to select the language in which compiler output will be printed. The information that will be printed in the selected language includes diagnostic messages, source listing page and scale headers, FIPS message headers, message summary headers, compilation summary, and headers and notations that result from the selection of certain compiler options (`MAP`, `XREF`, `VBREF`, and `FLAGSTD`).

**LANGUAGE option syntax**

►► `LANGUAGE( name )` ◄◄

Default is: `LANGUAGE (ENGLISH)`

Abbreviations are: LANG (EN|UE|JA|JP)

*name* specifies the language for compiler output messages. Possible values for the LANGUAGE option are shown in the table below.

Table 47. Values of the LANGUAGE compiler option		
Name	Abbreviation <sup>1</sup>	Output language
ENGLISH	EN	Mixed-case English (the default)
JAPANESE <sup>3</sup>	JA, JP	Japanese, using the Japanese character set
UENGLISH <sup>2, 3</sup>	UE	Uppercase English
<p>1. If your installation's system programmer has provided a language other than those described, you must specify at least the first two characters of this other language's name.</p> <p>2. To specify a language other than UENGLISH, the appropriate language feature must be installed.</p> <p>3. To change to uppercase English or Japanese compiler messages, in addition to using the LANGUAGE compiler option, you must also set the Language Environment runtime option NATLANG at compile time. We recommend using CEEOPTS DD in the compile JCL.</p> <p>For example, to change messages to Japanese, use the LANGUAGE (JA) compiler option and also specify the NATLANG LE runtime option at compile time:</p> <pre>//CEEOPTS DD *               NATLANG(JPN) /*</pre>		

If the LANGUAGE option is changed at compile time (using CBL or PROCESS statements), some initial text will be printed using the language that was in effect at the time the compiler was started.

**NATLANG:** The NATLANG runtime option allows you to control the national language to be used for the runtime environment, including error messages, month names, and day-of-the-week names. The LANGUAGE compiler option and the NATLANG runtime option act independently of each other. You can use them together with neither taking precedence over the other.

## LINECOUNT

Use LINECOUNT(*nnn*) to specify the number of lines to be printed on each page of the compilation listing, or use LINECOUNT(0) to suppress pagination.

### LINECOUNT option syntax

►► LINECOUNT(*nnn*) ◄◄

Default is: LINECOUNT(60)

Abbreviations are: LC

*nnn* must be an integer between 10 and 255, or 0.

If you specify LINECOUNT(0), no page ejects are generated in the compilation listing.

The compiler uses three lines of *nnn* for titles. For example, if you specify LINECOUNT(60), 57 lines of source code are printed on each page of the output listing.

# LIST

Use the LIST compiler option to produce a listing of the assembler-language expansion of your source code.

## LIST option syntax



Default is: NOLIST

Abbreviations are: None

These items will also be written to the output listing:

- Constant area
- Program prolog areas (PPA1, PPA2, PPA3, PPA4)
- Time stamp, compiler version, and build level information
- Compiler options and program information
- Base locator table
- External symbols dictionary
- Static maps
- Automatic maps

The output is generated if:

- You specify the COMPILE option, or the NOCOMPILE(x) option is in effect and an error of level x or higher does not occur.
- You do not specify the OFFSET option.

If you want to limit the assembler listing output, use \*CONTROL (or \*CBL) LIST or NOLIST statements in the PROCEDURE DIVISION. Source statements that follow a \*CONTROL NOLIST statement are not included in the listing until a subsequent \*CONTROL LIST statement switches the output back to normal LIST format.

### related tasks

[“Getting listings” on page 370](#)

### related references


[“Conflicting compiler options” on page 287](#)

\*CONTROL (\*CBL) statement (*Enterprise COBOL for z/OS Language Reference*)

# MAP

Use the MAP option to create a listing of the DATA DIVISION items and all implicitly declared items. You can also specify whether hexadecimal or decimal offsets are shown for MAP output in the listing.

## MAP option syntax



Default is: NOMAP

Suboption default is: MAP (HEX) if MAP is specified with no suboption

Abbreviations are: None

### HEX

If you specify MAP (HEX), data item offsets within groups will be in hexadecimal notation.

### DEC

If you specify MAP (DEC), data item offsets within groups will be in decimal notation.

The output includes the following items:

- DATA DIVISION map
- Nested program structure map, and program attributes
- Size of the program's WORKING-STORAGE and LOCAL-STORAGE and its location in the object code if the program is compiled with the NORENT option

If you want to limit the MAP output, use \*CONTROL MAP or NOMAP statements in the DATA DIVISION. Source statements that follow \*CONTROL NOMAP are not included in the listing until a \*CONTROL MAP statement switches the output back to normal MAP format. For example:

```
*CONTROL NOMAP          *CBL NOMAP
   01  A                  01  A
   02  B                  02  B
*CONTROL MAP             *CBL MAP
```

When the MAP (HEX | DEC) option is in effect, you also get an embedded MAP report in the source code listing. The condensed MAP information is shown to the right of data-name definitions in the WORKING-STORAGE SECTION, FILE SECTION, LOCAL-STORAGE SECTION, and LINKAGE SECTION of the DATA DIVISION. When both XREF data and an embedded MAP summary are on the same line, the embedded MAP summary is listed first.

[“Example: MAP output” on page 375](#)

### related concepts

[Chapter 19, “Debugging,” on page 361](#)

### related tasks

[“Getting listings” on page 370](#)

### related references

\*CONTROL (\*CBL) statement (*Enterprise COBOL for z/OS Language Reference*)

## MAXPCF

Use the MAXPCF option to specify a maximum program complexity factor value. The program complexity factor (PCF) is computed by the compiler and the computed value is in the listing file. If the PCF of your program exceeds the maximum value, the compiler will automatically reduce the optimization level to speed up the compilation and use less storage. Therefore, when you compile a suite of programs, you do not have to specify an OPTIMIZE option value for each program.

### MAXPCF option syntax

➡ MAXPCF(*n*) ➡

Default is: MAXPCF (60000)

Abbreviations are: None

*n* must be an integer of 0 - 999999.

The aspects of the program taken into consideration when computing the complexity factor include:

- The number of COBOL statements in the PROCEDURE DIVISION, including generated statements from the CICS, SQL or SQLIMS options, and the expansion of COPY and REPLACE statements
- Initialization operations for WORKING-STORAGE or LOCAL-STORAGE data items with value clauses
- Operations for variable-length groups or subgroups in the DATA DIVISION, which compute their size at run time

**Note:** PCF is not a metric to measure how complex a program is. It is merely a count of COBOL items that can cause problems for optimization when there are a lot of them. To measure program complexity, you should use something like the [Metrics](#) feature provided by IBM Developer for z/OS.

For large and complex programs, you can use the MAXPCF option to set a threshold on the program complexity that the compiler attempts to optimize. Lower the MAXPCF value to reduce the optimization level, hence the compiler needs less memory and compilation time. Raise the MAXPCF value to attempt to optimize the programs at the cost of longer compilation time.

If you specify MAXPCF (0), no limit is enforced on the complexity of the program, and the MAXPCF option has no effect.

If you specify MAXPCF(*n*) and *n* is not zero, when the program complexity factor exceeds *n*, any specification of OPTIMIZE (1) or OPTIMIZE (2) is reset to OPTIMIZE (0), and a warning message is generated.

If the COBOL source file contains a sequence of source programs (a batch compile), the MAXPCF limit is applied on a per program basis.

### Notes:

- If the OPTIMIZE (1) or OPTIMIZE (2) option is set at installation time as a fixed, nonoverridable option, then MAXPCF (*n*) with a nonzero *n* is an option conflict. In this case, the OPTIMIZE option takes precedence and the MAXPCF (0) option is forced on.
- If you attempt to optimize a program larger than the default threshold by raising the value of MAXPCF to *n* where *n* is greater than the default, or by specifying MAXPCF (0), the compiler might take excessive time to compile or fail to compile because of insufficient memory.

### related references

[“OPTIMIZE” on page 325](#)


## MDECK

The MDECK compiler option specifies that a copy of the updated input source after library processing (that is, the result of COPY, BASIS, REPLACE, EXEC SQL INCLUDE, and EXEC SQLIMS INCLUDE statements) is written to a file.

If Enterprise COBOL is running under z/OS UNIX, the MDECK output is written in the current directory to a file that has the same name as the COBOL source file and a suffix of .dek. For Enterprise COBOL running under TSO or batch, the MDECK output is written to the data set defined by the SYSMDECK DD allocation, which must specify an MVS data set that has RECFM F or FB and an LRECL of 80 bytes.

**Note:** When compiling under z/OS TSO or batch, the COBOL compiler requires the SYSMDECK data set allocation for all compilations, no matter if you specify the MDECK or NOMDECK option. The SYSMDECK DD allocation can be specified as either a temporary dataset or a permanent cataloged/uncataloged data set.

### MDECK option syntax



Default is: NOMDECK

Abbreviations are: NOMD | MD | MD (C | NOC)

### Option specification:

You cannot specify the MDECK option in a PROCESS (or CBL) statement. You can specify it only in one of the following ways:

- In the PARM parameter of JCL
- As a cob2 command option
- As an installation default
- In the **COBOPT** environment variable

### Suboptions:

- When MDECK (COMPILE) is in effect, compilation continues normally after library processing and generation of the MDECK output file have completed, subject to the settings of the COMPILE|NOCOMPILE, DECK|NODECK, and OBJECT|NOOBJECT compiler options.
- When MDECK (NOCOMPILE) is in effect, compilation is terminated after library processing has completed and the expanded source program file has been written. The compiler does no further syntax checking or code generation regardless of the settings of the COMPILE, DECK, and OBJECT compiler options.

If you specify MDECK with no suboption, MDECK (COMPILE) is implied.

### Contents of the MDECK output file:

If you use the MDECK option with programs that contain EXEC CICS, EXEC SQL, or EXEC SQLIMS statements, these EXEC statements are included in the MDECK output as is. However, if you compile using the SQL or SQLIMS option, the corresponding EXEC SQL INCLUDE or EXEC SQLIMS INCLUDE statements are expanded in the MDECK output.

CBL, PROCESS, \*CONTROL, and \*CBL card images are passed to the MDECK output file in the proper locations.

For a batch compilation (multiple COBOL source programs in a single input file), a single MDECK output file that contains the complete expanded source is created.

Any SEQUENCE compiler-option processing is reflected in the MDECK file.

COPY statements are included in the MDECK file as comments.

#### related tasks

[“Starting the compiler from an assembler program” on page 246](#)

[“Defining the library-processing output file \(SYSMDECK\)” on page 254](#)

#### related references

[“Conflicting compiler options” on page 287](#)


[Chapter 18, “Compiler-directing statements,” on page 357](#)

## NAME

Use NAME to generate a link-edit NAME card for each object module. You can also use NAME to generate names for each program object when you are doing batch compilations.

When NAME is specified, a NAME card is appended to each object module that is created. Program object names are formed using the rules for forming module names from PROGRAM- ID statements.

#### NAME option syntax



Default is: NONAME, or NAME (NOALIAS) if only NAME is specified

Abbreviations are: None

If you specify NAME (ALIAS), and your program contains ENTRY statements, a link-edit ALIAS card is generated for each ENTRY statement.

#### related references

PROGRAM-ID paragraph (*Enterprise COBOL for z/OS Language Reference*)

## NSYMBOL

The NSYMBOL option controls the interpretation of the N symbol used in literals and PICTURE clauses, indicating whether national or DBCS processing is assumed.

#### NSYMBOL option syntax



Default is: NSYMBOL (NATIONAL)

Abbreviations are: NS (NAT | DBCS)

With NSYMBOL (NATIONAL):

- Data items defined with a PICTURE clause that consists only of the symbol N without the USAGE clause are treated as if the USAGE NATIONAL clause is specified.

- Literals of the form N" . . ." or N' . . .' are treated as national literals.

With NSYMBOL (DBCS):

- Data items defined with a PICTURE clause that consists only of the symbol N without the USAGE clause are treated as if the USAGE DISPLAY-1 clause is specified.
- Literals of the form N" . . ." or N' . . .' are treated as DBCS literals.

The NSYMBOL (DBCS) option provides compatibility with previous releases of IBM COBOL, and the NSYMBOL (NATIONAL) option makes the handling of the above language elements consistent with the 2002 COBOL Standard in this regard.

NSYMBOL (NATIONAL) is recommended for applications that use Unicode data or object-oriented syntax for Java interoperability.


#### related references

[“Conflicting compiler options” on page 287](#)

## NUMBER

Use the NUMBER compiler option if you have line numbers in your source code and want those numbers to be used in error messages and SOURCE, MAP, LIST, and XREF listings.

#### NUMBER option syntax



Default is: NONUMBER

Abbreviations are: NUM|NONUM

If you request NUMBER, the compiler checks columns 1 through 6 to make sure that they contain only numbers and that the numbers are in numeric collating sequence. (In contrast, SEQUENCE checks the characters in these columns according to EBCDIC collating sequence.) When a line number is found to be out of sequence, the compiler assigns to it a line number with a value one higher than the line number of the preceding statement. The compiler flags the new value with two asterisks and includes in the listing a message indicating an out-of-sequence error. Sequence-checking continues with the next statement, based on the newly assigned value of the previous line.

If you use COPY statements and NUMBER is in effect, be sure that your source program line numbers and the copybook line numbers are coordinated.


If you are doing a batch compilation and NUMBER is in effect, all programs in the batch compile will be treated as a single input file. The sequence numbers of the entire input file must be in ascending order.

Use NONUMBER if you do not have line numbers in your source code, or if you want the compiler to ignore the line numbers you do have in your source code. With NONUMBER in effect, the compiler generates line numbers for your source statements and uses those numbers as references in listings.

## NUMCHECK

The NUMCHECK compiler option tells the compiler whether to generate extra code to validate data items when they are used as sending data items. For zoned decimal (numeric USAGE DISPLAY) and packed decimal (COMP-3) data items, the compiler generates implicit numeric class tests for each sending field. For binary data items, the compiler generates SIZE ERROR checking to see whether the data item has more digits than its PICTURE clause allows.

## NUMCHECK option syntax



Default is: NONUMCHECK

Suboption defaults are:

- If no suboption is specified, defaults are ZON(ALPHNUM), PAC, BIN and MSG. For example, NUMCHECK has the same effect as NUMCHECK(ZON(ALPHNUM), PAC, BIN, MSG).
- If no datatype suboption is specified, default datatype suboptions are ZON(ALPHNUM), PAC, and BIN. For example, NUMCHECK(ABD) has the same effect as NUMCHECK(ZON(ALPHNUM), PAC, BIN, ABD).
- If only one datatype suboption is specified, defaults are NOZON, NOPAC, NOBIN, and MSG. For example, NUMCHECK(BIN) has the same effect as NUMCHECK(NOZON, NOPAC, BIN, MSG).
- If all datatype suboptions are specified with NO, then the listing will show NONUMCHECK. For example, NUMCHECK(NOZON, NOPAC, NOBIN) has the same effect as NONUMCHECK.

Abbreviations are: NONC | NC

### ZON [(ALPHNUM | NOALPHNUM)] | NOZON

Specifying ZON or ZON(ALPHNUM) causes the compiler to generate code for an implicit numeric class test for zoned decimal (numeric USAGE DISPLAY) data items that are used as sending data items in COBOL statements.

Specifying ZON(NOALPHNUM) causes the compiler to generate code for an implicit numeric class test for zoned decimal (numeric USAGE DISPLAY) data items that are used as sending data items in COBOL statements, except when they are used in a comparison with an alphanumeric data item, alphanumeric literal or alphanumeric figurative constant.

Receivers are not checked, unless they are both a sender and a receiver, such as data item B in the following sample statements:

```
ADD A TO B
```

```
DIVIDE A INTO B
```

```
COMPUTE B = A + B
```

```
INITIALIZE B REPLACING ALPHANUMERIC BY B
```

This checking is done before the data is used in each statement:

- If the data is NOT NUMERIC, either a warning message for NUMCHECK(ZON,MSG) or a terminating message for NUMCHECK(ZON,ABD) is issued.
- If the data is NUMERIC, the external behavior of the statement is the same as NUMCHECK(NOZON), other than being slower.

#### PAC | NOPAC

Specifying PAC causes the compiler to generate code for an implicit numeric class test for packed decimal (COMP-3) data items that are used as sending data items in COBOL statements. For packed decimal data items that have an even number of digits, the unused bits are checked for ones.

**Restriction:** For CALL statements, NUMCHECK(ZON) and NUMCHECK(PAC) check BY CONTENT data items that are zoned decimal or packed decimal, but they do not check BY REFERENCE parameters. (Neither zoned decimal nor packed decimal data items can be specified in a BY VALUE phrase.)

#### BIN | NOBIN

Specifying BIN causes the compiler to generate code similar to ON SIZE ERROR to test if binary data items contents are bigger than the PICTURE clause. This extra code will be generated only for binary data items that are used as sending data items, and COMP-5 data items will not get this ON SIZE ERROR code generated.

#### MSG | ABD

Determines whether the message issued for invalid data is a warning level message to continue processing or a terminating level message to cause anabend:

- If MSG is in effect, a runtime warning message with the line number, data item name, data item content, and program name is issued. Also, the affected statements will still be executed.
- If ABD is in effect, a terminating message is issued that causes anabend.

**Performance considerations:** NUMCHECK is much slower than NONUMCHECK, depending on how many zoned decimal (numeric USAGE DISPLAY) data items, packed decimal (COMP-3) data items, and binary data items are used in a COBOL program.

**Note:** In Enterprise COBOL V6.1 with PTF for APAR PI71625 installed, ZONECHECK is deprecated but is tolerated for compatibility, and it is replaced by NUMCHECK(ZON(ALPHNUM)).

#### related tasks

[“Checking for incompatible data \(numeric class test\)” on page 51](#)

#### related references

[“NUMPROC” on page 322](#)

[“TRUNC” on page 344](#)


[“ZONECHECK” on page 352](#)

[“ZONEDATA” on page 353](#)

## NUMPROC

Use NUMPROC(NOPFD) if your internal decimal and zoned decimal data might use nonpreferred signs.

#### NUMPROC option syntax

➤ NUMPROC(  ) ➤

Default is: NUMPROC(NOPFD)

Abbreviations are: None

The compiler accepts any valid sign configuration: X'A', X'B', X'C', X'D', X'E', or X'F'. NUMPROC(NOPFD) is the recommended option in most cases.

**Performance considerations:** NUMPROC (PFD) improves the performance of processing internal decimal and zoned decimal data. Use this option however only if your numeric data agrees exactly with the following IBM system standards:

- **Zoned decimal, unsigned:** High-order 4 bits of the sign byte contain X'F'.
- **Zoned decimal, signed overpunch:** High-order 4 bits of the sign byte contain X'C' if a number is positive or 0, and X'D' if it is not.
- **Zoned decimal, separate sign:** Separate sign contains the character '+' if a number is positive or 0, and '-' if it is not.
- **Internal decimal, unsigned:** Low-order 4 bits of the low-order byte contain X'F'.
- **Internal decimal, signed:** Low-order 4 bits of the low-order byte contain X'C' if a number is positive or 0, and X'D' if it is not.

Data produced by COBOL arithmetic statements conforms to the IBM system standards described above. However, using REDEFINES and group moves could change data so that it no longer conforms. If you use NUMPROC (PFD), use the INITIALIZE statement to initialize data fields, rather than using group moves.

Using NUMPROC (PFD) can affect class tests for numeric data. Use NUMPROC (NOPFD) if a COBOL program calls programs written in PL/I or FORTRAN.

Sign representation is affected not only by the NUMPROC option, but also by the NUMCLS installation option.

#### related tasks

[“Checking for incompatible data \(numeric class test\)” on page 51](#)


#### related references

[“Sign representation of zoned and packed-decimal data” on page 51](#)

## OBJECT

Use OBJECT to write the generated object code to a file to be used as input for the binder.

#### OBJECT option syntax



Default is: OBJECT

Abbreviations are: OBJ|NOOBJ

If you specify OBJECT, include a SYSLIN DD statement in your JCL for compilation.

The only difference between DECK and OBJECT is in the routing of output to the data sets:

- DECK output goes to the data set associated with ddname SYSPUNCH.
- OBJECT output goes to the data set associated with ddname SYSLIN.

Use the option that your installation guidelines recommend.


#### related references

[“Conflicting compiler options” on page 287](#)

## OFFSET

Use OFFSET to produce a condensed PROCEDURE DIVISION listing.

### OFFSET option syntax



Default is: NOOFFSET

Abbreviations are: OFF|NOOFF

With OFFSET, the condensed PROCEDURE DIVISION listing will contain line numbers, statement references, and the location of the first instruction generated for each statement.

These items will also be written to the output listing:

- Constant area
- Program prolog areas (PPA1, PPA2, PPA3, PPA4)
- Time stamp and compiler version information
- Compiler options and program information
- Base locator table
- External symbols dictionary
- Static maps
- Automatic maps

### Notes:

- The optimizer might inline paragraphs, move code around or indeed place it after the body of the program if little used, such as the error message formatting code. This might make the OFFSET report less useful than it was with previous compilers. You can refer to the LIST output instead (note that OFFSET and LIST are mutually exclusive options). For details, see [“Reading LIST output” on page 381](#).
- Due to the out of line code used for error message formatting, Language Environment generated offsets, as indicated in "From compile unit {name} at entry point {name} at compile unit offset {offset} . . .", might be outside the offset range of the program. In these cases, refer to the statement number in the COBOL message (IGZnnnns) to locate the problem.

### related references

[“Conflicting compiler options” on page 287](#)

[“Example: OFFSET compiler output” on page 402](#)

## OPTFILE

Use OPTFILE to enable the specifying of COBOL compiler options in a data set. Using a compiler-option data set circumvents the 100-character limit on options specified in a JCL PARM string.

### OPTFILE option syntax

➤ OPTFILE ➤

Default is: None

Abbreviations are: None

You can specify OPTFILE as a compiler invocation option or in the PROCESS or CBL statement in your COBOL source program. OPTFILE cannot be specified as an installation default.

OPTFILE is ignored if you compile using the cob2 command in the z/OS UNIX environment. (In that environment, the COBOPT environment variable provides a capability that is comparable to OPTFILE.)

If OPTFILE is in effect, compiler options are read from the data set that you identify in a SYSOPTF DD statement. A SYSOPTF data set must have RECFM F or FB and an LRECL of 80 bytes. For further details about the format of a SYSOPTF data set, see the related task below about defining a compiler-option data set.

The precedence of options in the SYSOPTF data set is determined by where you specify the OPTFILE option. For example, if you specify OPTFILE in the invocation PARM string, an option specified later in the PARM string supersedes any option specified in the SYSOPTF data set that conflicts with it.

(Conceptually, OPTFILE in an options specification is replaced with the options that are in the SYSOPTF data set; then the usual rules about precedence of compiler options and conflicting compiler options apply.)

If you start the COBOL compiler from within an assembler program, you can use the alternate ddname list to specify a ddname to be used instead of SYSOPTF to identify the compiler-option data set.

#### related tasks

[“Starting the compiler from an assembler program” on page 246](#)

[“Defining a compiler-option data set \(SYSOPTF\)” on page 252](#)

[“Specifying compiler options under z/OS” on page 255](#)

[Chapter 15, “Compiling under z/OS UNIX,” on page 265](#)

#### related references

[“Conflicting compiler options” on page 287](#)

## OPTIMIZE

Use OPTIMIZE to reduce the run time of your object program. Optimization might also reduce the amount of storage your object program uses.

#### OPTIMIZE option syntax

➔ OPTIMIZE — ( { 0 1 2 } ) ➔

Default is: OPTIMIZE(0)

Abbreviations are: OPT(0), OPT(1), or OPT(2)

Optimizations are performed under the assumption that the program and data are valid, given the compiler options. For example, external decimal data that has USAGE DISPLAY must be valid unless ZONEDATA(MIG|NOPFD) is used to allow invalid zone bits. Digits and sign codes must be valid no matter what options are used. If the program or data is invalid, programs might behave differently at different levels of optimization or between different versions of Enterprise COBOL.

- OPTIMIZE(0) specifies limited optimizations, which result in the shortest compilation time. When the TEST option is specified, full debug capabilities are available.
- OPTIMIZE(1) specifies optimizations that improve application runtime performance. Optimizations at this level include basic inlining, strength reduction, simplification of complex operations into equivalent simpler operations, removal of some unreachable code and block rearrangement. Also, OPTIMIZE(1) includes some intrablock optimizations such as common subexpression elimination and value propagation. When the TEST option is specified, most debug capabilities are available.
- OPTIMIZE(2) specifies further optimizations, which include more aggressive simplifications and instruction scheduling. Also, some interblock optimizations such as global value propagation and loop invariant code motion are included. When the TEST option is specified, some debug capabilities are available.

When OPTIMIZE (1) or OPTIMIZE (2) is used without the TEST compiler option, care must be taken with user-written condition handlers registered via the Language Environment service CEEHDLR. In particular, if a condition handler accesses data items that are not defined local to the condition handler program themselves (for example, data items defined in the application as EXTERNAL), such data items must be defined with the VOLATILE clause to ensure that the handler uses the latest value of the data item, or the condition handler program can be compiled with the TEST compiler option. The use of the VOLATILE clause is preferred over the use of the TEST option because the use of the TEST option can reduce optimization for the entire program, while VOLATILE localizes the reduced optimization.

For more information about the VOLATILE clause, see VOLATILE clause in the *Enterprise COBOL for z/OS Language Reference*.

When OPTIMIZE (1) or OPTIMIZE (2) is in effect, specifying INLINE causes the compiler to consider inlining procedures for PERFORM statements. For details, see [“INLINE” on page 312](#).

**Note:** Since Enterprise COBOL V5, the NOOPTIMIZE, OPTIMIZE, OPTIMIZE (STD), and OPTIMIZE (FULL) options are removed but are tolerated for compatibility. If one of those options is specified, it is mapped to the new option or options as follows:

Table 48. Mapping of removed options to new options	
Removed options	New options
NOOPTIMIZE	OPTIMIZE (0)
OPTIMIZE	OPTIMIZE (1)
OPTIMIZE (STD)	OPTIMIZE (1)
OPTIMIZE (FULL)	OPTIMIZE (1) and STGOPT

#### related concepts

[“Optimization” on page 638](#)

#### related tasks

[“Writing routines for handling errors” on page 234](#)

#### related references

[“Conflicting compiler options” on page 287](#)

[“MAXPCF” on page 317](#)

[“TEST” on page 340](#)

[“STGOPT” on page 339](#)

VOLATILE clause (*Enterprise COBOL for z/OS Language Reference*)

## OUTDD

Use OUTDD to specify that you want DISPLAY output that is directed to the system logical output device to go to a specific ddname.

You can specify a file in the z/OS UNIX file system with the ddname named in OUTDD. To understand where output is directed when this ddname is not allocated, see the related task about displaying data.

#### OUTDD option syntax

➤ OUTDD( *ddname* ) ➤

Default is: OUTDD(SYSOUT)

Abbreviations are: OUT

If the OUTDD compiler option and the Language Environment MSGFILE runtime option specify the same ddname (both default to SYSOUT), DISPLAY output to the system logical output device is written using Language Environment message facilities.

**Restriction:** The OUTDD option has no effect under CICS.

#### related tasks

“Displaying data on the system logical output device” on page 34  
“Coding COBOL programs to run under CICS” on page 407

#### related references

*Language Environment Programming Reference (MSGFILE)*


## PARMCHECK

The PARMCHECK option tells the compiler to generate an extra data item following the last item in WORKING-STORAGE. This buffer data item is then used at run time to check whether a called subprogram corrupted data beyond the end of WORKING-STORAGE.

PARMCHECK is introduced in Enterprise COBOL V6.1 with the PTF for APAR PI78089 installed.

When a calling program is compiled with PARMCHECK, the compiler generates a buffer following the last data item in the WORKING-STORAGE section. At run time, before each call, the buffer is set to ALL x'AA'. After each call, the buffer is checked to see whether it was changed. The PARMCHECK option can help with your migration from COBOL V4 and earlier compilers to COBOL V6 and later compilers, and can also be used to clean up and check for good programming practices.

#### PARMCHECK option syntax



Default is: NOPARMCHECK

Abbreviations are: NOPC|PC

Suboption defaults are:

- If no suboption is specified, default is PARMCHECK(MSG,100).
- If only MSG or ABD is specified, default is PARMCHECK(MSG|ABD,100). For example, PC(ABD)=PC(ABD,100).
- If only *n* is specified, default is PARMCHECK(MSG,*n*). For example, PC(5000)=PC(MSG,5000).

#### MSG|ABD

Determines whether the message issued for subprogram corruption of data is a warning level message to continue processing or a terminating level message to cause an abend:

- If MSG is in effect, a runtime warning message with the name of the parameter, the line number of the CALL statement, and the program name is issued. Also, this check is done after the affected CALL statement is executed.
- If ABD is in effect, a similar message is issued, but with a terminating level that causes an abend.

#### *n*

The size in bytes of the buffer to be added after the last item in WORKING-STORAGE. Must be an integer in the range of 1 to 9999.

**Performance considerations:** PARMCHECK will cause the compiler to generate slower code for programs with CALL statements. NOPARMCHECK should be in effect for good performance.


## related references

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

# PGMNAME

The PGMNAME option controls the handling of program-names and entry-point names.

### PGMNAME option syntax



Default is: PGMNAME (COMPAT)

Abbreviations are: PGMN (LM|LU|CO)

LONGUPPER can be abbreviated as UPPER, LU, or U. LONGMIXED can be abbreviated as MIXED, LM, or M.

PGMNAME controls the handling of names used in the following contexts:

- Program-names defined in the PROGRAM-ID paragraph
- Program entry-point names in the ENTRY statement
- Program-name references in:
  - CALL statements that reference nested programs, statically linked programs, or DLLs
  - SET *procedure-pointer* or *function-pointer* statements that reference statically linked programs or DLLs
  - CANCEL statements that reference nested programs

## PGMNAME(COMPAT)

With PGMNAME (COMPAT), program-names are handled in a manner compatible with older versions of COBOL compilers:

- The program-name can be up to 30 characters in length.
- All the characters used in the name must be alphabetic, digits, the hyphen, or the underscore, except that if the program-name is a literal and is in the outermost program, then the literal can also contain the extension characters @, #, and \$, and the first character can be an underscore.
- At least one character must be alphabetic.
- The hyphen cannot be used as the first or last character.

External program-names are processed by the compiler as follows:

- They are folded to uppercase.
- They are truncated to eight characters.
- Hyphens are translated to zero (0).
- If the first character is not alphabetic, and is not an underscore, it is converted as follows:
  - 1-9 are translated to A-I.
  - Anything else is translated to J.

## PGMNAME(LONGUPPER)

With PGMNAME (LONGUPPER), program-names that are specified in the PROGRAM-ID paragraph as COBOL user-defined words must follow the normal COBOL rules for forming a user-defined word:

- The program-name can be up to 30 characters in length.

- All the characters used in the name must be alphabetic, digits, the hyphen, or the underscore.
- At least one character must be alphabetic.
- The hyphen cannot be used as the first or last character.
- The underscore cannot be used as the first character.

When a program-name is specified as a literal, in either a definition or a reference, then:

- The program-name can be up to 160 characters in length.
- All the characters used in the name must be alphabetic, digits, the hyphen, or the underscore.
- At least one character must be alphabetic.
- The hyphen cannot be used as the first or last character.
- The underscore can be used in any position.

External program-names are processed by the compiler as follows:

- They are folded to uppercase.
- Hyphens are translated to zero (0).
- If the first character is not alphabetic, and is not an underscore, it is converted as follows:
  - 1-9 are translated to A-I.
  - Anything else is translated to J.

Names of nested programs are folded to uppercase by the compiler but otherwise are processed as is, without truncation or translation.

## PGMNAME(LONGMIXED)

With PGMNAME (LONGMIXED), program-names are processed as is, without truncation, translation, or folding to uppercase.

If you want to use a PROGRAM-ID that is longer than eight characters, enclose it in single quotation marks or apostrophes (') and use PGMNAME (LONGMIXED).

With PGMNAME (LONGMIXED), all program-name definitions must be specified using the literal format of the program-name in the PROGRAM- ID paragraph or ENTRY statement. The literal user for a program-name can contain any character in the range X'41' -X'FE'.

## Usage notes

- The following elements are not affected by the PGMNAME option:
  - Class-names and method-names.
  - System-names (assignment-names in SELECT . . . ASSIGN, and text-names or library-names in COPY statements).
  - Dynamic calls.
 

Dynamic calls are resolved with truncation of the program-name to eight characters, folding to uppercase, and translation of embedded hyphens or a leading digit.
  - CANCEL of nonnested programs. Name resolution uses the same mechanism as for a dynamic call.
- **Link-edit considerations:** COBOL programs that are compiled with the PGMNAME (LONGUPPER) or PGMNAME (LONGMIXED) option must be link-edited in AMODE 31.
- Dynamic calls are not permitted to COBOL programs compiled with the PGMNAME (LONGMIXED) or PGMNAME (LONGUPPER) options unless the program-name is less than or equal to 8 bytes, and all uppercase. In addition, the name of the program must be identical to the name of the module that contains it.
- When using the extended character set supported by PGMNAME (LONGMIXED), be sure to use names that conform to the binder (linkage-editor) or system conventions that apply, depending on the mechanism used to resolve the names.

Using characters such as commas or parentheses is not recommended, because these characters are used in the syntax of binder (linkage-editor) control statements.


#### related references

PROGRAM-ID paragraph (*Enterprise COBOL for z/OS Language Reference*)

## QUALIFY

QUALIFY affects qualification rules and controls whether to extend qualification rules so that some data items that cannot be referenced under COBOL Standard rules can be referenced.

#### QUALIFY option syntax

➤ QUALIFY(  ) ➤

Default is: QUALIFY (COMPAT)

Abbreviations are: QUA (C | E)

#### QUALIFY (COMPAT)

If QUALIFY (COMPAT) is in effect, references to data items must be unique.

#### QUALIFY (EXTEND)

If QUALIFY (EXTEND) is in effect, qualification rules are extended so that some references that are not unique by COBOL standard rules can be unique. If every level in the containing hierarchy of names is specified, the set of qualifiers is called a *complete set of qualifiers*. If there is only one data item with a specific complete set of qualifiers, the reference resolves to that data item, even if the same set of qualifiers can match with another reference as an incomplete set of qualifiers.

#### Example


```
01 A.  
  02 B.  
    03 C PIC X.  
    03 A PIC X.  
  02 C PIC X.  
.  
.  
.  
  Move space to C of A      *> Refers to 02 level C (unique only with  
QUALIFY(EXTEND))  
  Move space to A          *> Refers to 01 level A (unique only with  
QUALIFY(EXTEND))  
  Move space to C of B of A *> Refers to 03 level C (unique by COBOL standard  
rules)  
  Move space to C of B      *> Refers to 03 level C (unique by COBOL standard  
rules)
```

## RENT

A program compiled as RENT is generated as a reentrant object program. A program compiled as NORENT is generated as a nonreentrant object program.

Either a reentrant or a nonreentrant program can be invoked as a main program or as a subprogram.

#### RENT option syntax

➤  ➤

Default is: RENT

Abbreviations are: None

**DATA and RMODE settings:** The RENT option interacts with other compiler options that affect storage and its addressability. Use the DATA (24 | 31) option for reentrant programs to control whether dynamic data areas are allocated in unrestricted storage or in storage obtained from below 16 MB. Compile programs with RENT if they will be run in virtual storage addresses above 16 MB.

Execution of nonreentrant programs above 16 MB is not supported. Programs compiled with NORENT must be RMODE 24.

The setting of the DATA option does not affect programs compiled with NORENT.

For information about which Enterprise COBOL programs need to be reentrant, see the related task about making programs reentrant.

**Link-edit considerations:** If all programs in a program object are compiled with RENT, it is recommended that the program object be link-edited with the RENT binder (linkage-editor) option. Use the REUS binder (linkage-editor) option instead if the program object will also contain any non-COBOL programs that are only serially reusable.

If any program in a program object is not reentrant, the program object must not be link-edited with the RENT or REUS link-edit attributes. The NOREUS binder (linkage-editor) option is needed to ensure that the CANCEL statement will guarantee a fresh copy of the program on a subsequent CALL.

#### related concepts

[“Storage and its addressability” on page 37](#)

#### related tasks

[“Making programs reentrant” on page 464](#)

*DB2 Application Programming and SQL Guide* (Using reentrant code)

#### related references

[“Conflicting compiler options” on page 287](#)


[“DATA” on page 300](#)

[“RMODE” on page 331](#)

## RMODE

The RMODE setting influences the RMODE (residency mode) of your generated object program.

#### RMODE option syntax



Default is: AUTO

Abbreviations are: None

A program compiled with the RMODE (AUTO) option will have RMODE 24 if NORENT is specified, or RMODE ANY if RENT is specified. RMODE AUTO is compatible with older compilers such as VS COBOL II, which produced RMODE 24 for programs compiled with NORENT, and RMODE ANY for programs compiled with RENT.

A program compiled with the RMODE (24) option will have RMODE 24 whether NORENT or RENT is specified.

A program compiled with the RMODE (ANY) option must also be compiled with the RENT option. The program will have the RMODE ANY attribute.

If the NORENT option is specified, the RMODE (24) or RMODE(AUTO) compiler option must be specified. Overriding the module RMODE with a binder option or control statement is not supported.

**DATA and RENT:** The RMODE option interacts with other compiler options and runtime options that affect storage and its addressability. For information about passing data between programs with different modes, see the related concept about storage and its addressability.

**Link-edit considerations:** If the object code that COBOL generates has an attribute of RMODE 24, you must link-edit the code into an RMODE 24 module. If the object code that COBOL generates has an attribute of RMODE ANY, you can link-edit the code into either an RMODE ANY or RMODE 24 module.

#### related concepts

[“Storage and its addressability” on page 37](#)


#### related references

[“Allocation of buffers for QSAM files” on page 170](#)

[“Conflicting compiler options” on page 287](#)

## RULES

You can use the RULES option to request information about your program from the compiler to improve the program by flagging certain types of source code at compile time.



Default is: NORULES

Abbreviations are:

- ENDP = ENDPERIOD
- EVENP = EVENPACK
- LXPRF = LAXPERF
- SLCKB = SLACKBYTES

You can specify the following suboptions for RULES:

#### ENDPERIOD | NOENDPERIOD

The default is ENDPERIOD. Specifying NOENDPERIOD causes the compiler to issue warning messages when the scope of a conditional statement is terminated by a period instead of an explicit scope terminator END-\*.

#### EVENPACK | NOEVENPACK

The default is EVENPACK. Specifying NOEVENPACK causes the compiler to issue warning messages for any USAGE PACKED-DECIMAL (COMP-3) data items that have an even number of digits because those data items whose unused bits are not zero can lead to an unexpected program behavior.

**Note:** RULES(NOEVENTPACK) helps compilers to identify even-length USAGE PACKED-DECIMAL (COMP-3) data items. However, it is not necessary to change those data items to odd-length items when the related database schema uses even-length packed values.

#### **LAXPERF | NOLAXPERF**

The default is LAXPERF. Specifying NOLAXPERF suboption causes the compiler to issue warning messages for usage of inefficient COBOL features. These features might include USAGE DISPLAY numeric data items in arithmetic statements, large amounts of space padding in MOVE statements, inefficient compiler options, and other cases.

#### **SLACKBYTES | NOSLACKBYTES**

The default is SLACKBYTES. Specifying NOSLACKBYTES causes the compiler to issue warning messages for any SYNCHRONIZED data items that cause the compiler to add slack bytes, either slack bytes within records or slack bytes between records. Each data item that causes slack bytes to be added gets a compiler diagnostic.

If the RULES option is specified with no suboptions, the default is RULES(ENDPERIOD, EVENPACK, LAXPERF, SLACKBYTES).

#### **Notes:**

- It is not necessary to specify all of the suboptions for RULES. If a suboption is not specified, the default value of that suboption takes effect. For example, if you specify RULES(NOENDP, NOSLCKB), RULES(NOENDP, EVENP, LXPRF, NOSLCKB) takes effect.
- You can optionally use the RULES option with the MSGEXIT suboption of the EXIT compiler option to enforce local coding standards. For example, if you want to ensure that no programmers use periods instead of explicit scope delimiters to delimit conditional statements, you can change the severity of the ENDPERIOD message from Warning level (RC=4) to Severe level (RC=12). For a sample of how to modify the severity of this and other RULES messages, see the sample MSGEXIT in SIGYSAMP called IGYMSGXT.

#### **related references**


*SYNCHRONIZED clause (Enterprise COBOL for z/OS Language Reference)*

## SEQUENCE

When you use SEQUENCE, the compiler examines columns 1 through 6 to check that the source statements are arranged in ascending order according to their EBCDIC collating sequence. The compiler issues a diagnostic message if any statements are not in ascending order.

Source statements with blanks in columns 1 through 6 do not participate in this sequence check and do not result in messages.

#### **SEQUENCE option syntax**



Default is: SEQUENCE

Abbreviations are: SEQ|NOSEQ

If you use COPY statements with the SEQUENCE option in effect, be sure that your source program's sequence fields and the copybook sequence fields are coordinated.

If you use NUMBER and SEQUENCE, the sequence is checked according to numeric, rather than EBCDIC, collating sequence.

If you are doing a batch compilation and SEQUENCE is in effect, all programs in the batch compilation are treated as a single input file. The sequence numbers of the entire input file must be in ascending order.

Use NOSEQUENCE to suppress this checking and the diagnostic messages.


#### related tasks

[“Finding line sequence problems” on page 366](#)

## SERVICE

Use SERVICE to place a string in the object module if the object module is generated. If the object module is linked into a program object, the string is loaded into memory with this program object. If the Language Environment dump includes a traceback, this string is included in that traceback.

#### SERVICE option syntax



Default is: NOSERVICE


Abbreviations are: SERV|NOSERV

The *service string* is limited to 64 characters in length.

## SOURCE

Use SOURCE to get a listing of your source program. This listing will include any statements embedded by PROCESS or COPY statements.

#### SOURCE option syntax



Default is: SOURCE

Abbreviations are: S|NOS

You must specify SOURCE if you want embedded messages in the source listing.

Use NOSOURCE to suppress the source code from the compiler output listing.

If you want to limit the SOURCE output, use \*CONTROL SOURCE or NOSOURCE statements in your PROCEDURE DIVISION. Source statements that follow a \*CONTROL NOSOURCE statement are not included in the listing until a subsequent \*CONTROL SOURCE statement switches the output back to normal SOURCE format.

[“Example: MAP output” on page 375](#)


#### related references

\*CONTROL (\*CBL) statement (*Enterprise COBOL for z/OS Language Reference*)

## SPACE

Use SPACE to select single-, double-, or triple-spacing in your source code listing.

### SPACE option syntax



Default is: SPACE (1)

Abbreviations are: None

SPACE has meaning only when the SOURCE compiler option is in effect.


### related references

["SOURCE" on page 334](#)

## SQL

Use the SQL compiler option to enable the DB2 coprocessor and to specify DB2 suboptions. You must specify the SQL option if a COBOL source program contains SQL statements (EXEC SQL statements) and the program has not been processed by the DB2 precompiler.

### SQL option syntax



Default is: NOSQL

Abbreviations are: None

When you use the SQL option, the DB2 coprocessor writes the database request module (DBRM) to ddname DBRMLIB. DB2 must be available on the machine on which you compile.

If you specify the NOSQL option, any SQL statements found in the source program are diagnosed and discarded.

Use either quotation marks or apostrophes to delimit the string of DB2 suboptions.

You can partition a long suboption string into multiple suboption strings in multiple CBL statements. For example:

```
//STEP1 EXEC IGYWC, . . .
// PARM.COBOL='SQL("string1")'
//COBOL.SYSIN DD *
  CBL SQL("string2")
  CBL SQL('string3')
  IDENTIFICATION DIVISION.
  PROGRAM-ID. DRIVER1.
  . . .
```

The DB2 suboptions are concatenated in the order of their appearance. Thus in the example above, the compiler passes the following suboption string to the DB2 coprocessor:

```
"string1 string2 string3"
```

The concatenated strings are delimited with single spaces as shown. If multiple instances of the same DB2 option are found, the last specification of each option prevails. The compiler limits the length of the concatenated DB2 suboption string to 4 KB.

#### **related concepts**

[“DB2 coprocessor” on page 417](#)

[“COBOL and DB2 CCSID determination” on page 422](#)

#### **related tasks**

[“Compiling with the SQL option” on page 421](#)

[“Separating DB2 suboptions” on page 422](#)


#### **related references**

[“Conflicting compiler options” on page 287](#)

## **SQLCCSID**

Use the SQLCCSID compiler option to control whether the CODEPAGE compiler option will influence the processing of SQL statements in your COBOL programs.

#### **SQLCCSID option syntax**



Default is: SQLCCSID

Abbreviations are: SQLC|NOSQLC

The SQLCCSID option has an effect only if you use the integrated DB2 coprocessor (SQL compiler option).

If SQLCCSID is in effect, the setting of the CODEPAGE compiler option will influence the processing of SQL statements within your COBOL programs when you use the integrated DB2 coprocessor.

If NOSQLCCSID is in effect:

1. The CODEPAGE compiler option will only be used as the encoding for string literals and the COBOL application source that includes converted SQL statements;
2. DB2 (character string) host variables will not be affected by the CODEPAGE compiler option. Instead, the encoding for DB2 (character string) host variables will come from the CCSID value found in the DSNHDECP file, which means DB2 (via DSNHDECP) determines the encoding of the DB2 data (host variables).

#### **related concepts**

[“DB2 coprocessor” on page 417](#)

[“COBOL and DB2 CCSID determination” on page 422](#)

#### **related tasks**

[“Programming with the SQLCCSID or NOSQLCCSID option” on page 423](#)

#### **related references**

[“Code-page determination for string host variables in SQL statements” on page 423](#)


[“CODEPAGE” on page 295](#)

[“SQL” on page 335](#)

## SQLIMS

Use the SQLIMS compiler option to enable the IMS SQL coprocessor and to specify Information Management System (IMS) suboptions. You must specify the SQLIMS option if a COBOL source program contains SQLIMS statements (EXEC SQLIMS statements).

### SQLIMS option syntax



Default: NOSQLIMS

Abbreviation: None

If you specify the NOSQLIMS option, any SQLIMS statements that are found in the source program are diagnosed and discarded.

Use either quotation marks or apostrophes to delimit the string of IMS suboptions.

You can partition a long suboption string into multiple suboption strings in multiple CBL statements. For example:

```
//STEP1 EXEC IGYWC, . . .
// PARM.COBOL='SQLIMS("string1")'
//COBOL.SYSIN DD *
    CBL SQLIMS("string2")
    CBL SQLIMS('string3')
    IDENTIFICATION DIVISION.
    PROGRAM-ID. DRIVER1.
    . . .
```

The IMS suboptions are concatenated in the order of their appearance. Thus in the proceeding example, the compiler passes the following suboption strings to the IMS SQL coprocessor:

```
"string1 string2 string3"
```

The concatenated strings are delimited with single spaces as shown. If multiple instances of the same IMS suboption are found, the last specification of each suboption takes effect. The compiler limits the length of the concatenated IMS suboption string to 4 KB.

### related concepts

[“IMS SQL coprocessor” on page 427](#)

### related tasks

[“Compiling with the SQLIMS option” on page 429](#)


[“Separating IMS suboptions” on page 430](#)

### related references

[“Conflicting compiler options” on page 287](#)

## SSRANGE

Use SSRANGE to generate code that checks for out-of-range storage references.



Default is: NOSSRANGE

Suboption default is: NOZLEN , ABD if only SSRANGE is specified.

Abbreviations are: SSR|NOSSR

SSRANGE generates code that checks whether subscripts, including ALL subscripts, or indexes try to reference areas outside the region of their associated tables. Each subscript or index is not individually checked for validity. Instead, the effective address is checked to ensure that it does not reference outside the table.

If you specify SSRANGE with no suboptions, it will be accepted as a specification of SSRANGE (NOZLEN , ABD) .

**Note:** If the SSRANGE option is in effect, range checks are generated by the compiler and the checks are always conducted at run time. You cannot disable the compiled-in range checks at run time by specifying the runtime option CHECK (OFF) .

Variable-length items are also checked to ensure that references are within their maximum defined length.

Reference modification expressions are checked to ensure that:

- The starting position is greater than or equal to 1.
- The starting position is not greater than the current length of the subject data item.
- The length value (if specified) is greater than or equal to 1.
- The starting position and length value (if specified) do not reference an area beyond the end of the subject data item.

The ZLEN and NOZLEN suboptions control how the compiler checks reference modification lengths:

- If ZLEN is in effect, the compiler will generate code to ensure that reference modification lengths are greater than or equal to zero. Zero-length reference modification specifications will not get an SSRANGE error at run time.
- If NOZLEN is in effect, the compiler will generate code to ensure that reference modification lengths are greater than or equal to 1. Zero-length reference modification specifications will get an SSRANGE error at run time. This is compatible with how SSRANGE behaved in previous COBOL versions.

The MSG and ABD suboptions control the runtime behavior of the COBOL program when a range check fails.

- If MSG is in effect and a range check fails, a runtime warning message will be issued. Also, the affected statements will still be executed. The program will continue and might potentially identify other out-of-range conditions.

- If ABD is in effect and a range check fails, the first out-of-range condition will result in a runtime error message and the program will ABEND. You can find the next potential out-of-range condition by fixing the first out-of-range condition and then recompiling and running the program again. To identify all other potential out-of-range conditions, you might need to repeat this process several times.

For unbounded groups or their subordinate items, checking is done only for reference modification expressions. Subscripted or indexed references to tables subordinate to an unbounded group are not checked.

#### related concepts

[“Reference modifiers” on page 108](#)


#### related tasks

[“Checking for valid ranges” on page 366](#)

## STGOPT

The STGOPT option controls storage optimization.

#### STGOPT option syntax



Default is: NOSTGOPT

Abbreviations are: SO|NOSO

If you specify STGOPT, the compiler might discard any or all of the following data items, and does not allocate storage for them.

- Unreferenced LOCAL - STORAGE and non-external WORKING - STORAGE level-77 and level-01 elementary data items
- Non-external level-01 group items if none of their subordinate items are referenced
- Unreferenced special registers

**Note:** The STGOPT option is ignored for data items that have the VOLATILE clause. For details, see VOLATILE clause in the *Enterprise COBOL for z/OS Language Reference*.

The compiler will not generate code to initialize discarded data items to the values in their VALUE clauses.


In addition, with STGOPT, data items in the LOCAL - STORAGE SECTION can be reordered in memory to optimize performance.

When NOSTGOPT is in effect, the storage for all data items, including unreferenced data items, is allocated by the compiler, data items are never reordered to improve performance, and all data items defined with a VALUE clause are guaranteed to be initialized, even if they are unreferenced.

## SUPPRESS

Use the NOSUPPRESS option to ignore the SUPPRESS phrase of all COPY statements in a program so that copybook information can appear in the listing. The copybook information can be used by debuggers, tools, and so on, without users needing to modify their source code.

### SUPPRESS option syntax



Default is: SUPPRESS

Abbreviations are: SUPP|NOSUPP

### NOSUPPRESS

Ignores the SUPPRESS phrase of COPY statements.


### SUPPRESS

Enables the SUPPRESS phrase of COPY statements.

## TERMINAL

Use TERMINAL to send progress and diagnostic messages to the SYSTERM ddname.

### TERMINAL option syntax



Default is: NOTERMINAL


Abbreviations are: TERM|NOTERM

Use NOTERMINAL if you do not want this additional output.

## TEST

Use TEST to produce object code that enables debugging and problem determination tools such as Debug Tool and Fault Analyzer. With TEST, you can also enable the inclusion of symbolic variables in the formatted dumps that are produced by Language Environment.

### TEST option syntax



Option default is: NOTEST (NODWARF)

Suboption defaults are:

- NODWARF if only NOTEST is specified
- NOEJPD,SOURCE if only TEST is specified

Abbreviations are: None

Suboption abbreviation is: NOS | S

## NOTEST suboptions

### DWARF

If NOTEST (DWARF) is in effect, basic DWARF diagnostic information is included in the application module. This option enables the best usability for application failure analysis tools, such as CEEDUMP and IBM Fault Analyzer. With NOTEST (DWARF), the debugging information is a subset of the DWARF information that is available with TEST. The DWARF diagnostic information that is produced when NOTEST (DWARF) is in effect cannot be used with IBM Debug Tool.

Debugging information generated by the compiler is in the industry-standard DWARF format. For more information about DWARF, see [About Common Debug Architecture](#) in the *DWARF/ELF Extensions Library Reference*.

### NODWARF

If NOTEST (NODWARF) is in effect, DWARF diagnostic information is not included in the application module.

## TEST suboptions

When the TEST option is specified, DWARF debugging information is included in the application module.

The EJPD and NOEJPD suboptions control enablement of the Debug Tool commands JUMPTO and GOTO in production debugging sessions. These suboptions take effect only if you specify the TEST option and a non-zero OPTIMIZE level (OPTIMIZE (1) or OPTIMIZE (2)).

### EJPD

If you specify TEST (EJPD) and a non-zero OPTIMIZE level:

- The JUMPTO and GOTO commands are enabled.
- The amount of program optimization is reduced. Optimization is done within statements, but most optimizations do not cross statement boundaries.

### NOEJPD

If you specify TEST (NOEJPD) and a non-zero OPTIMIZE level:

- The JUMPTO and GOTO commands are not enabled. However, you can still use JUMPTO and GOTO if you use the SET WARNING OFF Debug Tool command. In this scenario, JUMPTO and GOTO will have unpredictable results.
- The normal amount of program optimization is done.

### SOURCE

If you specify TEST (SOURCE), the generated DWARF debug information generated by the compiler includes the expanded source code, and the compiler listing is not needed by IBM Debug Tool.

### NOSOURCE

If you specify TEST (NOSOURCE), the generated DWARF debugging information does not include the expanded source code, and you will not be able to use IBM Debug Tool.

**Note:** If you specify the TEST option, you must set the CODEPAGE option to the CCSID that is used for the COBOL source program. In particular, programs that use Japanese characters in DBCS literals or DBCS user-defined words must be compiled with the CODEPAGE option set to a Japanese codepage CCSID. For more information, see [“CODEPAGE”](#) on page 295.

## Performance versus debugging capability:

You can control the amount of debugging capability that you get and so also the program performance, as follows:

- For the best performance, but with some restrictions on debugging, compile using a non-zero OPTIMIZE level, STGOPT and TEST (NOEJPD).
  - The Debug Tool commands JUMPTO and GOTO are not supported. However, you can still use JUMPTO and GOTO if you use the SET WARNING OFF Debug Tool command. In this scenario, JUMPTO and GOTO will have unpredictable results.
  - Except for the DESCRIBE ATTRIBUTES command, Debug Tool commands cannot refer to any data item that was discarded from a program by the STGOPT option.
  - The Debug Tool command AT CALL *entry-name* is not supported.
- For some reduction in program performance from the production-debugging scenario above, but to enable predictable behavior for the Debug Tool commands JUMPTO and GOTO, specify a non-zero OPTIMIZE level and TEST (EJPD).

The restrictions above about referring to items discarded by the STGOPT option, and about the AT CALL command also apply when you use a non-zero OPTIMIZE level and TEST (EJPD).

- For slowest performance but maximum debugging capability, specify OPTIMIZE (0), NOSTGOPT and TEST.

The OPTIMIZE (0) option causes the compiler to generate slower code, but all Debug Tool commands are supported.

### Language Environment:

The TEST option specified with any of its suboptions can improve your formatted dumps from Language Environment by adding these two features to the dumps:

- A line number that indicates the failing statement, rather than just an offset
- The values of the program variables

With NOTEST (DWARF), the dump will have program variables and the line number of the failing statement. With NOTEST (NODWARF), the dump will not have program variables nor the line number of the failing statement.

Enterprise COBOL uses the Language Environment-provided dump services to produce dumps that are consistent in content and format with those that are produced by other Language Environment-conforming member languages.

Whether Language Environment produces a dump for unhandled conditions depends on the setting of the runtime option TERMTHDACT. If you specify TERMTHDACT (DUMP), a dump is generated when a condition of severity 2 or greater goes unhandled.

### LLA/VLF managed programs where DWARF diagnostic information is included:

When DWARF diagnostic information is included in the object program because of the TEST (NOSEPARATE) or other equivalent options and the program is staged to VLF, the information cannot be extracted from the program. The execution JCL requires the use of the IGZLOAD DD, the STEPLIB DD, or both to specify the location of any LLA/VLF managed libraries from which the application will load programs that have been staged to VLF. Otherwise, the COBOL variable information and the statement numbers in the traceback will be missing in the CEEDUMP and a diagnostic message will appear in the CEEDUMP. For more information, see *Diagnostic messages in CEEDUMPs for IBM Enterprise COBOL for z/OS* at <https://www.ibm.com/support/pages/diagnostic-messages-ceedumps-ibm-enterprise-cobol-zos>.

For each program staged to VLF, the following steps are taken to extract the DWARF diagnostic information:

1. The COBOL Runtime checks for the allocation of the IGZLOAD DD. It then checks if the library is associated with the IGZLOAD DD contains a member, for example, a COBOL program, whose name matches the program staged to VLF.
2. If the previous step was unsuccessful because the IGZLOAD DD was not allocated or the member was not found, the same process is attempted using the STEPLIB DD.

3. If the member is found, and the checksum that is stored with the DWARF diagnostic information retrieved from the member matches the checksum of the compile unit in the executing program, the information is extracted from the member.

Note that if duplicate members exist in the IGZLOAD DD concatenation or in the STEPLIB DD concatenation respectively, the first occurrence in the DD concatenation is used to obtain the checksum.

A mismatch can occur if a revised copy of the program is placed into a LLA/VLF managed library, but the environment-appropriate refresh for the staged LLA/VLF program has not been completed.

For example, you can allocate the IGZLOAD DD with DSN=USER . COBOL . LOADLIB when all of the following conditions are met:

- USER . COBOL . LOADLIB is in LNKLST.
- USER . COBOL . LOADLIB (PGM1) is staged to VLF.
- PGM1 is executed from USER . COBOL . LOADLIB in LNKLST.

```
//G01      EXEC  PGM=PGM1,                * CALLED FROM LNKLST
//STEPLIB  DD    DSN=CEE1.SCEERUN,DISP=SHR
//IGZLOAD  DD    DSN=USER.COBOL.LOADLIB,DISP=SHR * CONTAINS PGM1
```

If a program is LLA/VLF managed and staged to VLF, and is executed from one of the data sets in LNKLST, there is a need to allocate the IGZLOAD DD. However, if the program resides in one of the data sets in the STEPLIB DD, there is no need to allocate the IGZLOAD DD.

**related concepts**

*DWARF/ELF Extensions Library Reference* (About Common Debug Architecture)

**related tasks**


“Using the debugger” on page 370  
*Language Environment Debugging Guide* (Generating a Language Environment dump with TERMTHDACT)  
*z/OS Debugger User's Guide* (Special considerations while using the TEST runtime option)

**related references**

“Logical record length and block size” on page 250  
“cob2 input and output files” on page 270  
“Conflicting compiler options” on page 287  
“OPTIMIZE” on page 325  
*Language Environment Programming Reference* (TEST | NOTEST)

**THREAD**

THREAD indicates that a COBOL program is to be enabled for execution in a Language Environment enclave that has multiple POSIX threads or PL/I tasks.



Default is: NOTHREAD

Abbreviations are: None

A program that has been compiled using the THREAD option can also be used in a nonthreaded application. However, if a COBOL program is to be run in a threaded application, all the COBOL programs in the Language Environment enclave must be compiled using the THREAD option.

NOTHREAD indicates that the COBOL program is not to be enabled for execution in an enclave that has multiple POSIX threads or PL/I tasks.

Programs that are compiled using compilers earlier than Enterprise COBOL are treated as if compiled using NOTHREAD.

If the THREAD option is in effect, the following elements are not supported. If encountered, they are diagnosed as errors:

- ALTER statement
- DEBUG-ITEM special register
- GO TO statement without procedure-name
- INITIAL phrase in PROGRAM-ID clause
- Nested programs
- RERUN
- Segmentation module
- SORT or MERGE statements
- STOP *literal* statement
- USE FOR DEBUGGING statement

Additionally, some language constructs have different semantics than in the nonthreaded case.

Although threaded applications are subject to a number of programming and environment restrictions, the use of a program in nonthreaded applications is not so restricted. For example, a program compiled using the THREAD option can run in the CICS and IMS environments, can run AMODE 24, and can call and be called by other programs that are not enabled for multithreading, provided that the application does not contain multiple POSIX threads or PL/I tasks at run time.

Programs compiled using the THREAD option are supported in the reusable environment that is created by calling the Language Environment preinitialization routine CEEPIPI. But a reusable environment created by using the RTEREUS runtime option is not supported for programs compiled using the THREAD option.

**Performance consideration:** If you use the THREAD option, you can expect some runtime performance degradation due to the overhead of serialization logic that is automatically generated.

#### related tasks

Chapter 28, “Preparing COBOL programs for multithreading,” on page 491


#### related references

“Conflicting compiler options” on page 287

## TRUNC

TRUNC affects the way that binary data is truncated during moves and arithmetic operations.

#### TRUNC option syntax



Default is: TRUNC (STD)

Abbreviations are: None

TRUNC has no effect on COMP-5 data items; COMP-5 items are handled as if TRUNC (BIN) is in effect regardless of the TRUNC suboption specified.

#### **TRUNC (STD)**

TRUNC (STD) applies only to USAGE BINARY receiving fields in MOVE statements and arithmetic expressions. When TRUNC (STD) is in effect, the final result of an arithmetic expression, or the sending field in the MOVE statement, is truncated to the number of digits in the PICTURE clause of the BINARY receiving field.

#### **TRUNC (OPT)**

TRUNC (OPT) is a performance option. When TRUNC (OPT) is in effect, the compiler assumes that data conforms to PICTURE specifications in USAGE BINARY receiving fields in MOVE statements and arithmetic expressions. The results are manipulated in the most optimal way, either truncating to the number of digits in the PICTURE clause, or to the size of the binary field in storage (halfword, fullword, or doubleword).

#### **Tips:**

- Use the TRUNC (OPT) option only if you are sure that the data being moved into the binary areas will not have a value with larger precision than that defined by the PICTURE clause for the binary item. Otherwise, unpredictable results could occur. This truncation is performed in the most efficient manner possible; therefore, the results are dependent on the particular code sequence generated. It is not possible to predict the truncation without seeing the code sequence generated for a particular statement.

#### **TRUNC (BIN)**

The TRUNC (BIN) option applies to all COBOL language that processes USAGE BINARY data. When TRUNC (BIN) is in effect, all binary items (USAGE COMP, COMP-4, or BINARY) are handled as native hardware binary items, that is, as if they were each individually declared USAGE COMP-5:

- BINARY receiving fields are truncated only at halfword, fullword, or doubleword boundaries.
- BINARY sending fields are handled as halfwords, fullwords, or doublewords when the receiver is numeric; TRUNC (BIN) has no effect when the receiver is not numeric.
- The full binary content of fields is significant.
- DISPLAY will convert the entire content of binary fields with no truncation.

**Recommendations:** TRUNC (BIN) is the recommended option for programs that use binary values set by other products. Other products, such as IMS, DB2, C/C++, FORTRAN, and PL/I, might place values in COBOL binary data items that do not conform to the PICTURE clause of the data items. You can use TRUNC (OPT) with CICS programs provided that your data conforms to the PICTURE clause for your BINARY data items.

USAGE COMP-5 has the effect of applying TRUNC (BIN) behavior to individual data items. Therefore, you can avoid the performance overhead of using TRUNC (BIN) for every binary data item by specifying COMP-5 on only some of the binary data items, such as those data items that are passed to non-COBOL programs or other products and subsystems. The use of COMP-5 is not affected by the TRUNC suboption in effect.

**Large literals in VALUE clauses:** When you use the compiler option TRUNC (BIN), numeric literals specified in VALUE clauses for binary data items (COMP, COMP-4, or BINARY) can generally contain a value of magnitude up to the capacity of the native binary representation (2, 4, or 8 bytes) rather than being limited to the value implied by the number of 9s in the PICTURE clause.

**Note:** With PH11667 installed, when TRUNC (BIN) and NUMCHECK (BIN) are both in effect and an error message or an abend is generated, if you don't intend to switch to TRUNC (STD | OPT), you can turn off NUMCHECK (BIN) to reduce the execution time of the application and avoid an error message or an abend; if you intend to switch to TRUNC (STD | OPT) later for better performance, you must correct the data.

## TRUNC example 1

```
01  BIN-VAR      PIC S99 USAGE BINARY.  
   . . .  
   MOVE 123451 to BIN-VAR
```

The following table shows values of the data items after the MOVE statement.

Data item	Decimal	Hex	Display
Sender	123451	00 01 E2 3B	123451
Receiver TRUNC (STD)	51	00 33	51
Receiver TRUNC (OPT)	-7621	E2 3B	2J
Receiver TRUNC (BIN)	-7621	E2 3B	762J

A halfword of storage is allocated for BIN-VAR. The result of this MOVE statement if the program is compiled with the TRUNC (STD) option is 51; the field is truncated to conform to the PICTURE clause.

If you compile the program with TRUNC (BIN), the result of the MOVE statement is -7621. The reason for the unusual result is that nonzero high-order digits are truncated. Here, the generated code sequence would merely move the lower halfword quantity X'E23B' to the receiver. Because the new truncated value overflows into the sign bit of the binary halfword, the value becomes a negative number.

It is better not to compile this MOVE statement with TRUNC (OPT), because 123451 has greater precision than the PICTURE clause for BIN-VAR. With TRUNC (OPT), the results are again -7621. This is because the best performance was obtained by not doing a decimal truncation.

## TRUNC example 2

```
01  BIN-VAR      PIC 9(6)  USAGE BINARY  
   . . .  
   MOVE 1234567891 to BIN-VAR
```

The following table shows values of the data items after the MOVE statement.

Data item	Decimal	Hex	Display
Sender	1234567891	49 96 02 D3	1234567891
Receiver TRUNC (STD)	567891	00 08 AA 53	567891
Receiver TRUNC (OPT)	567891	53 AA 08 00	567891
Receiver TRUNC (BIN)	1234567891	49 96 02 D3	1234567891

When you specify TRUNC (STD), the sending data is truncated to six integer digits to conform to the PICTURE clause of the BINARY receiver.

When you specify TRUNC (OPT), the compiler assumes the sending data is not larger than the PICTURE clause precision of the BINARY receiver. The most efficient code sequence in this case is truncation as if TRUNC (STD) were in effect.

When you specify TRUNC (BIN), no truncation occurs because all of the sending data fits into the binary fullword allocated for BIN-VAR.

### related concepts

[“Formats for numeric data” on page 45](#)

### related tasks

[“Compiling with the CICS option” on page 411](#)

### related references


[“NUMCHECK” on page 320](#)

VALUE clause (*Enterprise COBOL for z/OS Language Reference*)

## VBREF

Use VBREF to get a cross-reference between all statements used in the source program and the line numbers in which they are used. VBREF also produces a summary of the number of times each statement was used in the program.

### VBREF option syntax



Default is: NOVBREF

Abbreviations are: None

Use NOVBREF for more efficient compilation.

## VLR

The VLR option affects the file status returned from READ statements for variable-length records when the length of record returned is inconsistent with the record descriptions. It eases your migration from earlier versions to Enterprise COBOL V6, if your programs have READ statements that result in a record length conflict.

### VLR option syntax



Default is: VLR(STANDARD)

Abbreviations are: VLR(C|S)

After the execution of a READ statement:

- If the number of character positions in the record that is read is less than the minimum size specified by the record description entries for the file, the portion of the record area that is to the right of the last valid character read is undefined.
- If the number of character positions in the record that is read is greater than the maximum size specified by the record description entries for the file, the record is truncated on the right to the maximum size.

In either of these cases, the READ statement is successful, and the file status is set to either 00 (hiding the record length conflict condition) or 04 (indicating that a record length conflict has occurred), depending on the VLR compiler option setting.

### VLR(COMPAT)

VLR(COMPAT) checks the size of the read record against the "VERYING IN SIZE FROM min TO max" declaration of the FD clause. If you specify VLR(COMPAT), you get the status value of 00 when READ statements encounter a record length conflict.

**Note:** This setting can hide I/O problems that can arise with the wrong length read situation. Use the VLR (COMPAT) option with caution, and check for correct READ statements.

## VLR (STANDARD)

VLR (STANDARD) checks the size of the read record against the declaration of the FD level 01 clause. If you specify VLR (STANDARD), you get the status value of 04 when READ statements encounter a record length conflict.

You can add code to test for FS=04 to avoid accessing undefined data in a record and also avoid getting protection exceptions for attempting to reference a part of the record that was truncated.

The following example shows how VLR option checks the size of the read record against the declaration of the FD clause and FD level 01 clause.

```
FD MYDD
  block contains 0 records
  record varying in size from 10 to 80
  recording mode V.
01 REC-20
  02 PIC X(20).
01 REC-50.
  02 PIC X(50).
```

Table 49. Length of record read and file status

Length of record read	=5 < min varying < min level 01	= 15 >= min varying < min level 01	= 40 >= min varying <= max varying >= min level 01 <= max level 01	= 70 >= min varying <= max varying > max level 01
COBOL V4	FS=04	FS=00	FS=00	FS=00
COBOL V6 VLR (COMPAT)	FS=04	FS=00	FS=00	FS=00
COBOL V6 VLR (STANDARD)	FS=04	FS=04	FS=00	FS=04

Using VLR (STANDARD) can result in more reliable code and fewer I/O problems because the file status will tell you when a "wrong length READ" might occur. A new compiler message, MSGIGYP3178, can also help you avoid I/O problems by telling you if a program has a possibility of a "wrong length READ". This message can be used to assist with migration from VLR (COMPAT) to VLR (STANDARD) by indicating the possible "wrong length READ" that you can solve by correcting the File Definition (FD). You can also raise the severity of the message so that the program must be corrected in order to run. To do this, use the MSGEXIT suboption of the EXIT compiler option to change the severity of message MSGIGYP3178 from I (RC=0) to S (RC=12), E (RC=8), or W (RC=4). If you are not interested in seeing this message, you can suppress the message completely.

## related references


["EXIT" on page 305](#)

Variable length records - wrong length READ  
(Enterprise COBOL Migration Guide)

## VSAMOPENFS

The VSAMOPENFS option affects the user file status reported from successful VSAM OPEN statements that require verified file integrity check.

### VSAMOPENFS option syntax



The diagram shows the syntax for the VSAMOPENFS option. It starts with a right-pointing arrow, followed by the text 'VSAMOPENFS(', then a horizontal line. Above this line is the word 'COMPAT' with a bracket connecting it to the line. Below the line is the word 'SUCC' with a bracket connecting it to the line. The line ends with a closing parenthesis ')', followed by a double-headed arrow.

```
➡ VSAMOPENFS( COMPAT  
SUCC ) ➡
```

Default is: VSAMOPENFS (COMPAT)

Abbreviations are: VS (C | S)

### COMPAT

If you specify VSAMOPENFS (COMPAT), the statement returns the file status 97 when a VSAM OPEN statement is successfully verified. This is compatible with pre-V6 COBOL runtime behavior.


### SUCC

If you specify VSAMOPENFS (SUCC), the statement returns the file status 00 when a VSAM OPEN statement is successfully verified. This allows users to simply check for 0 in the first digit of the returned file status, as they usually do with other successful operations.

## WORD

Use WORD(xxxx) to specify that an alternate reserved-word table is to be used during compilation.

### WORD option syntax



The diagram shows the syntax for the WORD option. It starts with a right-pointing arrow, followed by a horizontal line. Above this line is the word 'NOWORD' with a bracket connecting it to the line. Below the line is the text 'WORD( xxxx)' with a bracket connecting it to the line. The line ends with a double-headed arrow.

```
➡ NOWORD  
WORD( xxxx) ➡
```

Default is: NOWORD

Abbreviations are: WD|NOWD

xxxx specifies the ending characters of the name of the reserved-word table (IGYCxxxx) to be used in your compilation. IGYC are the first four standard characters of the name, and xxxx can be one to four characters in length.

Alternate reserved-word tables provide changes to the IBM-supplied default reserved-word table. Your systems programmer might have created one or more alternate reserved-word tables for your site. See your systems programmer for the names of alternate reserved-word tables.

Enterprise COBOL provides an alternate reserved-word table (IGYCCICS) specifically for CICS applications. It is set up to flag COBOL words not supported under CICS with an error message. If you want to use this CICS reserved-word table during your compilation, specify the compiler option WORD (CICS).

### related tasks

[“Compiling with the CICS option” on page 411](#)

### related references


[“Conflicting compiler options” on page 287](#)

[“CICS reserved-word table” on page 414](#)

## XMLPARSE

Use XMLPARSE to select the parser to be used for processing XML input, and, therefore, the XML processing capabilities that are available to your program.

### XMLPARSE option syntax



The diagram shows the syntax for the XMLPARSE statement. It starts with a right-pointing arrow followed by 'XMLPARSE('. Then, there is a horizontal line. Above this line is 'XMLSS' with a bracket connecting it to the line. Below the line is 'COMPAT' with a bracket connecting it to the line. The line ends with a closing parenthesis ')', followed by a double-headed arrow.

```
➡ XMLPARSE( XMLSS COMPAT ) ➡
```

Default is: XMLSS

Abbreviations are: XP (X | C)

If you specify the XMLPARSE (XMLSS) option, XML PARSE statements are processed using the z/OS XML System Services parser. The following XML parsing capabilities are available only if you specify XMLPARSE (XMLSS):

- Validation of XML input documents against an XML schema (by using the VALIDATING phrase of the XML PARSE statement)
- Enhanced namespace processing (special registers XML -NAMESPACE, XML -NNAMESPACE, XML -NAMESPACE-PREFIX, and XML -NNAMESPACE-PREFIX)
- Automatic conversion of document fragments to Unicode UTF-16 (by using the RETURNING NATIONAL phrase of the XML PARSE statement)
- Specification of the encoding of the input document (by using the ENCODING phrase of the XML PARSE statement)
- Direct parsing of XML documents encoded in UTF-8
- Parsing of XML documents, a buffer of XML at a time
- Offloading of XML parsing to System z Application Assist Processors (zAAPs)

If you specify the XMLPARSE (COMPAT) option, XML PARSE statements are processed using the XML parser that is a built-in component of the COBOL library. The XML PARSE statement results and operational behaviors are then compatible with those obtained with Enterprise COBOL Version 3, and also with Version 4 when XMLPARSE (COMPAT) was used, and the advanced features described above for XMLPARSE (XMLSS) are not available.

### related tasks

[Chapter 31, “Processing XML input,” on page 505](#)


### related references

XML PARSE statement (*Enterprise COBOL for z/OS Language Reference*)  
*z/OS XML System Services User's Guide and Reference*

## XREF

Use XREF to produce a sorted cross-reference listing.

### XREF option syntax



The diagram shows the syntax for the XREF statement. It starts with a right-pointing arrow followed by 'XREF'. Then, there is a horizontal line. Above this line is 'FULL' with a bracket connecting it to the line. Below the line is 'SHORT' with a bracket connecting it to the line. The line is enclosed in parentheses '('. The line ends with a closing parenthesis ')', followed by a double-headed arrow.

```
➡ XREF ( FULL SHORT ) ➡
```

Below the main line, there is another horizontal line labeled 'NOXREF' with a double-headed arrow at its end.

Default is: XREF (FULL)

Abbreviations are: X|NOX

You can choose XREF, XREF (FULL), or XREF (SHORT). If you specify XREF without any suboptions, XREF (FULL) will be in effect.

A section of the listing shows all the program-names, data-names, and procedure-names that are referenced in your program, and the line numbers where those names are defined. External program-names are identified.

[“Example: XREF output: data-name cross-references” on page 398](#)

[“Example: XREF output: program-name cross-references” on page 399](#)

A section is also included that cross-references COPY or BASIS statements in the program with the data sets or files from which associated copybooks were obtained.

[“Example: XREF output: COPY/BASIS cross-references” on page 400](#)

EBCDIC data-names and procedure-names are listed in alphanumeric order. DBCS data-names and procedure-names are listed based on their physical order in the program; they are shown before the EBCDIC data-names and procedure-names unless the DBCSXREF installation option is selected with a DBCS ordering program. In that case, DBCS data-names and procedure-names are in the order specified by the DBCS ordering program.

If you use XREF and SOURCE, data-name and procedure-name cross-reference information is printed on the same line as the original source. Line-number references or other information appears on the right-hand side of the listing page. On the right of source lines that reference an intrinsic function, the letters IFN are printed with the line number of the locations where the function arguments are defined. Information included in the embedded references lets you know if an identifier is undefined (UND) or defined more than once (DUP), if items are implicitly defined (IMP) (such as special registers or figurative constants), or if a program-name is external (EXT).

If you use XREF and NOSOURCE, you get only the sorted cross-reference listing.

XREF (SHORT) prints only the explicitly referenced data items in the cross-reference listing.

XREF (SHORT) applies to DBCS data-names and procedure-names as well as to single-byte names.

NOXREF suppresses this listing.

### **Usage notes**

- Group names used in a MOVE CORRESPONDING statement are in the XREF listing. The elementary names in those groups are also listed.
- In the data-name XREF listing, line numbers that are preceded by the letter M indicate that the data item is explicitly modified by a statement on that line.
- XREF listings take additional storage.
- If there is more than one data set in your SYSLIB concatenation, in some cases the COPY/BASIS cross-reference might be incomplete or missing. This loss can occur if XREF is set only in a CBL or PROCESS statement, and XREFOPT=NO is set as an installation default or NOXREF is coded in your JCL PARM parameter.

To ensure that the COPY/BASIS cross-reference is complete, either verify with your system programmer that XREFOPT=FULL or XREFOPT=SHORT is your installation default, or code the XREF option in your JCL PARM parameter.

### **related concepts**

[Chapter 19, “Debugging,” on page 361](#)

### **related tasks**

[“Getting listings” on page 370](#)

## related references


*Language Environment Debugging Guide* (COBOL compiler options)

# ZONECHECK

Use the ZONECHECK option to have the compiler generate IF NUMERIC class tests for zoned decimal data items that are used as sending data items.

**Note:** In Enterprise COBOL V6.1 with PTF for APAR PI71625 installed, ZONECHECK is deprecated but is tolerated for compatibility, and it is replaced by NUMCHECK (ZON (ALPHNUM) ).

### ZONECHECK option syntax



Default is: NOZONECHECK

Abbreviations are: NOZC|ZC (MSG) |ZC (ABD)

### MSG

The MSG suboption requests that an IF NUMERIC test be done on every use of zoned decimal data items as senders, and if the data is invalid (for example, NOT NUMERIC), a runtime warning message with the line number, data item name, data item content, and program name is issued. Also, the affected statements will still be executed. ZONECHECK (MSG) is treated as if NUMCHECK (ZON ,MSG) were in effect.

### ABD

The ABD suboption requests that an IF NUMERIC test be done on every use of zoned decimal data items as senders, and if the data is invalid (for example, NOT NUMERIC), a terminating message is issued that causes an abend. ZONECHECK (ABD) is treated as if NUMCHECK (ZON ,ABD) were in effect.

Both ZONECHECK (MSG) and ZONECHECK (ABD) result in the compiler generating an implicit numeric class test for each zoned decimal data item that is referenced as a sender in a COBOL statement. Receivers are not checked, unless they are both a sender and a receiver, such as data item B in the following sample statements:

```
ADD A TO B
```

```
DIVIDE A INTO B
```

```
COMPUTE B = A + B
```

```
INITIALIZE B REPLACING ALPHANUMERIC BY B
```

This checking is done before the data item is used in each statement:

- If the data item is NOT NUMERIC, either a warning message for ZONECHECK (MSG) or a terminating message for ZONECHECK (ABD) is issued.
- If the data item is NUMERIC, the external behavior of the statement is the same as NOZONECHECK, other than being slower.

**Restriction:** For CALL statements, ZONECHECK checks BY CONTENT and BY VALUE data items that are numeric USAGE DISPLAY only, but it does not check BY REFERENCE parameters.

**Performance considerations:** ZONECHECK(MSG) and ZONECHECK(ABD) are much slower than NOZONECHECK, depending on how many zoned decimal data items are used in COBOL statements in a program.

#### related tasks

[“Checking for incompatible data \(numeric class test\)” on page 51](#)

#### related references

[“NUMCHECK” on page 320](#)


[“NUMPROC” on page 322](#)

[“ZONEDATA” on page 353](#)

## ZONEDATA

The ZONEDATA option tells the compiler whether the data in USAGE DISPLAY and PACKED-DECIMAL data items is valid, and if not, what the behavior of the compiler should be.

#### ZONEDATA option syntax



Default is: ZONEDATA(PFD)

Abbreviations are: ZD(PFD) | ZD(MIG) | ZD(NOPFD)

Each digit of a valid zoned decimal number is represented by a single byte from X'F0' through X'F9'. The 4 high-order bits of each byte are zone bits, and the 4 low-order bits of each byte contain the value of the digit. The 4 high-order bits of the low-order byte for SIGN TRAILING represent the sign of the item. The sign is in the high-order byte with SIGN LEADING, or in a separate byte for SIGN IS SEPARATE.

#### ZONEDATA(PFD)

When the ZONEDATA(PFD) option is in effect, the compiler assumes that all data in USAGE DISPLAY and PACKED-DECIMAL data items is valid, and generates the most efficient code possible to make numeric comparisons. For example, the compiler might generate a string comparison to avoid numeric conversion.

#### ZONEDATA(MIG)

When the ZONEDATA(MIG) option is in effect, the compiler generates instructions to do numeric comparisons that ignore the zone bits of each digit in zoned decimal data items. For example, the zoned decimal value is converted to packed-decimal with a PACK instruction before the comparison. The compiler will also avoid performing known optimizations that might produce a different result than COBOL V4 (or earlier versions) when a zoned decimal or packed decimal data item has invalid digits or an invalid sign code, or when a zoned decimal data item has invalid zone bits.

#### ZONEDATA(NOPFD)

When the ZONEDATA(NOPFD) option is in effect, the compiler generates instructions for numeric comparisons or an alphanumeric comparison of zoned decimal data in the same manner as COBOL V4 (or earlier versions) does when using NUMPROC(NOPFD | PFD) with COBOL V4 (or earlier versions) :

- In the cases where COBOL V4 (or earlier versions) considered the zone bits, the compiler generates an alphanumeric comparison which will also consider the zone bits of each digit in zoned decimal data items. The zoned decimal value remains as zoned decimal.
- In the cases where COBOL V4 (or earlier versions) ignored the zone bits, the compiler generates numeric comparisons that ignore the zone bits of each digit in zoned decimal data items. The zoned decimal value is converted to packed-decimal with a PACK instruction before the comparison.

In order for the compiler to generate comparisons of zoned decimal data in the same way that COBOL V4 (or earlier versions) did, the NUMPROC suboption used in COBOL V6 must match the NUMPROC suboption used in COBOL V4 (or earlier versions):

- To get the COBOL V4 (or earlier versions) NUMPROC (NOPFD) behavior in COBOL V6, use ZONEDATA (NOPFD) and NUMPROC (NOPFD) in COBOL V6.
- To get the COBOL V4 (or earlier versions) NUMPROC (PFD) behavior in COBOL V6, use ZONEDATA (NOPFD) and NUMPROC (PFD) in COBOL V6.

The compiler will also avoid performing known optimizations that might produce a different result than COBOL V4 (or earlier versions) when a zoned decimal or packed decimal data item has invalid digits or an invalid sign code, or when a zoned decimal data item has invalid zone bits.

**Note:** The sign code must be a valid sign code according to the NUMPROC compiler option setting. In addition, the low-order byte must have a valid zone (x'F') for unsigned and signed with either SIGN IS LEADING or SIGN IS SEPARATE.

**Note:** The ZONEDATA option affects the behaviour of MOVE statements, comparisons, and computations for USAGE DISPLAY or PACKED-DECIMAL data items that could contain invalid digits, an invalid sign code, or invalid zone bits.

In the following example, you can see a data item with an invalid zone bit 4 in the zone bits in the middle of data item VALUE1, forced in by REDEFINES:

```
77 VALUE0 PIC X(4) VALUE '00 0'.          *> x'F0F040F0'
77 VALUE1 REDEFINES VALUE0 PIC 9(4).
PROCEDURE DIVISION.
  IF VALUE1 = ZERO
    DISPLAY 'ZONEDATA(MIG) is in effect ' VALUE1
  ELSE
    DISPLAY 'ZONEDATA(NOPFD | PFD) is in effect ' VALUE1
  END-IF
```

In this example:

- With COBOL V4 (or earlier versions) or earlier versions, the test is true if the NUMPROC (MIG) option is used, and false for NUMPROC (NOPFD | PFD).
- With COBOL V5 or later versions:
  - When using ZONEDATA (PFD), the test is true at OPT (0) and false at OPT (1 | 2).
  - When using ZONEDATA (NOPFD), the test is false at any OPT setting.

In all, to ease your migration to COBOL V6:

- If your digits, sign code, and zone bits are valid, use ZONEDATA (PFD) and the same NUMPROC setting that you used with COBOL V4 (or earlier versions) when using COBOL V6.
- If you have invalid digits, invalid sign code, or invalid zone bits:
  - If you used NUMPROC (MIG) with COBOL V4 (or earlier versions), use ZONEDATA (MIG) and NUMPROC (NOPFD) with COBOL V6.
  - If you used NUMPROC (NOPFD) with COBOL V4 (or earlier versions), use ZONEDATA (NOPFD) and NUMPROC (NOPFD) with COBOL V6.
  - If you used NUMPROC (PFD) with COBOL V4 (or earlier versions), use ZONEDATA (NOPFD) and NUMPROC (PFD) with COBOL V6.

**Note:** It is not always possible to entirely match the behaviour of the old compiler even with these options when faced with clearly invalid data. For example, even for compares, ZONEDATA (NOPFD) isn't going to give the same result in all cases as COBOL V4.

**Performance considerations:** ZONEDATA (PFD) gives better runtime performance than ZONEDATA (NOPFD | MIG) does. ZONEDATA (NOPFD | MIG) disables some of the optimizations that NUMPROC (PFD) can give.

### related tasks

[“Checking for incompatible data \(numeric class test\)” on page 51](#)

### related references

[“NUMCHECK” on page 320](#)

[“NUMPROC” on page 322](#)


[“ZONECHECK” on page 352](#)

## ZWB

---

If you compile using ZWB, the compiler removes the sign from a signed zoned decimal (DISPLAY) field before comparing this field to an alphanumeric elementary field during execution.

### ZWB option syntax



Default is: ZWB

Abbreviations are: None

If the zoned decimal item is a scaled item (that is, it contains the symbol P in its PICTURE string), comparisons that use the decimal item are not affected by ZWB. Such items always have their sign removed before the comparison is made to an alphanumeric field.

ZWB affects how a program runs. The same COBOL program can produce different results depending on the setting of this option.

Use NOZWB if you want to test input numeric fields for SPACES.



## Chapter 18. Compiler-directing statements

Several statements help you to direct the compilation of your program.

These are the compiler-directing statements:

### **BASIS statement**

This extended source program library statement provides a complete COBOL program as the source for a compilation. For rules of formation and processing, see the description of *text-name* for the COPY statement.

### **CALLINTERFACE directive**


The CALLINTERFACE directive specifies the interface convention for CALL and SET statements. The convention specified stays in effect until another CALLINTERFACE directive is encountered in the source.

The CALLINTERFACE directive can be used only in the procedure division and its effect is limited to the current compilation unit.

### **\*CONTROL (\*CBL) statement**

This compiler-directing statement selectively suppresses or allows output to be produced. The names \*CONTROL and \*CBL are synonymous.

### **COPY statement**



This library statement places prewritten text into a COBOL program.

Neither *text-name* nor *library-name* need to be unique within a program. They can be identical to other user-defined words in the program, except that they cannot contain the underscore.

The uniqueness of *text-name* and *library-name* is determined after the formation and conversion rules for a system-dependent name have been applied. If *library-name* is omitted, SYSLIB is assumed.

### **Compiling with JCL:**

*text-name*, *library-name*, and *literal-1* and *literal-2* are processed as follows:

- The name (which can be from one to 30 characters long) is truncated to eight characters. Only the first eight characters of *text-name* and *library-name* are used as the identifying name. These eight characters must be unique within any COBOL library.
- The name is folded to uppercase.
- Hyphens that are not the first or last character are translated to zero (0), and a warning message is issued.
- If the first character is numeric, then the characters 1-9 are translated to A-I, zero (0) is converted to J, and a warning message is issued.

For example:

```
COPY INVOICES1Q  
COPY "Company-#Employees" IN Personellib
```

In the IN/OF phrase, *library-name* is the ddname that identifies the partitioned data set to be copied from. Use a DD statement such as in the following example to define *library-name*:

```
//COPYLIB DD DSN=ABC.COB,VOLUME=SER=111111,  
//          DISP=SHR,UNIT=3380
```

To specify more than one copy library, use either JCL or a combination of JCL and the IN/OF phrase. Using just JCL, concatenate data sets in your DD statement for SYSLIB. Alternatively, define multiple DD statements and include the IN/OF phrase in your COPY statements.

The maximum block size for the copy library depends on the device on which your data set resides.

### Compiling in the z/OS UNIX shell:

When you compile using the cob2 command, copybooks are included from the z/OS UNIX file system. *text-name*, *library-name*, and *literal-1* and *literal-2* are processed as follows:

- User-defined words are folded to uppercase. Literals are not folded. Because UNIX is case sensitive, if your file-name is lowercase or mixed case, you must specify it as a literal.
- If *text-name* is a literal and *library-name* is omitted, *text-name* is used directly: as a file-name, a relative path name, or an absolute path name (if the first character is /). For example:

```
COPY "MyInc"  
COPY "x/MyInc"  
COPY "/u/user1/MyInc"
```

- If *text-name* is a user-defined word, and an environment variable of that name is defined, the value of the environment variable is used as the name of the file that contains the copybook.

If an environment variable of that name is not defined, the copybook is searched for under the following names, in this order:

1. *text-name.cpy*
2. *text-name.CPY*
3. *text-name.cbl*
4. *text-name.CBL*
5. *text-name.cob*
6. *text-name.COB*
7. *text-name*

- If *library-name* is a literal, it is treated as the actual path, relative or absolute, from which to copy file *text-name*.
- If *library-name* is a user-defined word, it is treated as an environment variable. The value of the environment variable is used as the path. If the environment variable is not set, an error occurs.
- If both *library-name* and *text-name* are specified, the compiler forms the path name for the copybook by concatenating *library-name* and *text-name* with a path separator (/) inserted between the two values. For example, suppose you have the following setting for COPY MYCOPY OF MYLIB:

```
export MYCOPY=mystuff/today.cpy  
export MYLIB=/u/user1
```

These settings result in:

```
/u/user1/mystuff/today.cpy
```

If *library-name* is an environment variable that identifies the path from which copybooks are to be copied, use an `export` command to define *library-name*, as in this example:

```
export COPYLIB=/u/mystuff/copybooks
```

The name of the environment variable must be uppercase. To specify more than one copy library, set the environment variable to multiple path names delimited by colon (:).

If *library-name* is omitted and *text-name* is not an absolute path name, the copybook is searched for in this order:

1. In the current directory
2. In the paths specified on the `-I cob2` option
3. In the paths specified in the `SYSLIB` environment variable

For additional information about the `COPY` statement, for example, the rules for text replacement, see the related reference.

#### **DELETE statement**

This extended source library statement removes COBOL statements from the BASIS source program.

#### **EJECT statement**

This compiler-directing statement specifies that the next source statement is to be printed at the top of the next page.

#### **ENTER statement**

The statement is treated as a comment.

#### **INSERT statement**

This library statement adds COBOL statements to the BASIS source program.

#### **PROCESS (CBL) statement**

This statement, which you place before the `IDENTIFICATION DIVISION` header of an outermost program, indicates which compiler options are to be used during compilation of the program.

#### **REPLACE statement**

This statement is used to replace source program text.

#### **SERVICE LABEL statement**

This statement is generated by the CICS translator to indicate control flow, and should be used at the resume point for a call to `CEE3SRP`. It is not intended for general use.

#### **SKIP1/2/3 statement**

These statements indicate lines to be skipped in the source listing.

#### **TITLE statement**

This statement specifies that a title (header) should be printed at the top of each page of the source listing.

#### **USE statement**

The `USE` statement provides *declaratives* to specify these elements:

- Error-handling procedures: `EXCEPTION/ERROR`
- Debugging lines and sections: `DEBUGGING`

#### **related tasks**

[“Changing the header of a source listing” on page 5](#)

[“Specifying compiler options under z/OS” on page 255](#)

[“Specifying compiler options under z/OS UNIX” on page 266](#)

[“Setting environment variables](#)

[under z/OS UNIX” on page 265](#)  
[“Eliminating repetitive coding” on page 647](#)

**related references**

[“cob2 syntax and options” on page 269](#)  
CALLINTERFACE (*Enterprise COBOL for z/OS Language Reference*)  
COPY statement (*Enterprise COBOL for z/OS Language Reference*)

---

## Chapter 19. Debugging

You can choose between two different approaches to determine the cause of problems in the behavior of your application: source-language debugging or interactive debugging.

For source-language debugging, COBOL provides several language elements, compiler options, and listing outputs that make debugging easier.

If the problem with your program is not easily detected and you do not have a debugger available, you might need to analyze a storage dump of your program.

For interactive debugging, you can use Debug Tool. Debug Tool offers these productivity enhancements:

- Interactive debugging (in full-screen or line mode), or debugging in batch mode

During an interactive full-screen mode session, you can use Debug Tool's full-screen services and session panel windows on a 3270 device to debug your program while it is running.

- COBOL-like commands

For each high-level language supported, commands for coding actions to be taken at breakpoints are provided in a syntax similar to that programming language.

- Mixed-language debugging

You can debug an application that contains programs written in a different language. Debug Tool automatically determines the language of the program or subprogram being run.

- COBOL-CICS debugging

Debug Tool supports the debugging of CICS applications in both interactive and batch mode.

- Support for remote debugging

Workstation users can use the IBM Debug Tool Plug-in for Eclipse or the IBM Problem Determination Tools with Rational Developer for System z for debugging programs that run on z/OS.

### related tasks

[“Debugging with source language” on page 361](#)

[“Debugging using compiler options” on page 365](#)

[“Using the debugger” on page 370](#)

[“Getting listings” on page 370](#)

*z/OS Debugger User's Guide*

### related references

*Debug Tool Reference and Messages*

*Language Environment Debugging Guide* (Formatting and analyzing system dumps, Debugging example COBOL programs)

---

## Debugging with source language

You can use several COBOL language features to pinpoint the cause of a failure in a program.

If a failing program is part of a large application that is already in production (precluding source updates), write a small test case to simulate the failing part of the program. Code debugging features in the test case to help detect these problems:

- Errors in program logic
- Input-output errors
- Mismatches of data types
- Uninitialized data
- Problems with procedures

**related tasks**

[“Tracing program logic” on page 362](#)

[“Finding and handling input-output errors” on page 362](#)

[“Validating data” on page 363](#)

[“Moving, initializing or setting uninitialized data” on page 363](#)

[“Generating information about procedures” on page 363](#)

**related references**

Source language debugging (*Enterprise COBOL for z/OS Language Reference*)

## Tracing program logic

Trace the logic of your program by adding DISPLAY statements.

For example, if you determine that the problem is in an EVALUATE statement or in a set of nested IF statements, use DISPLAY statements in each path to see the logic flow. If you determine that the calculation of a numeric value is causing the problem, use DISPLAY statements to check the value of some interim results.

If you use explicit scope terminators to end statements in your program, the logic is more apparent and therefore easier to trace.

To determine whether a particular routine started and finished, you might insert code like this into your program:

```
DISPLAY "ENTER CHECK PROCEDURE"  
  .  
  . (checking procedure routine)  
  .  
DISPLAY "FINISHED CHECK PROCEDURE"
```

After you are sure that the routine works correctly, disable the DISPLAY statements in one of two ways:

- Put an asterisk in column 7 of each DISPLAY statement line to convert it to a comment line.
- Put a D in column 7 of each DISPLAY statement to convert it to a comment line. When you want to reactivate these statements, include a WITH DEBUGGING MODE clause in the ENVIRONMENT DIVISION; the D in column 7 is ignored and the DISPLAY statements are implemented.

Before you put the program into production, delete or disable the debugging aids you used and recompile the program. The program will run more efficiently and use less storage.

**related concepts**

[“Scope terminators” on page 19](#)

**related references**

DISPLAY statement (*Enterprise COBOL for z/OS Language Reference*)

## Finding and handling input-output errors

File status keys can help you determine whether your program errors are due to input-output errors occurring on the storage media.

To use file status keys in debugging, check for a nonzero value in the status key after each input-output statement. If the value is nonzero (as reported in an error message), look at the coding of the input-output procedures in the program. You can also include procedures to correct the error based on the value of the status key.

If you determine that a problem lies in an input-output procedure, include the USE EXCEPTION/ERROR declarative to help debug the problem. Then, when a file fails to open, the appropriate EXCEPTION/

ERROR declarative is performed. The appropriate declarative might be a specific one for the file or one provided for the open attributes INPUT, OUTPUT, I - O, or EXTEND.

Code each USE AFTER STANDARD ERROR statement in a section that follows the DECLARATIVES keyword in the PROCEDURE DIVISION.

#### **related tasks**

[“Coding ERROR declaratives” on page 228](#)

[“Using file status keys” on page 229](#)

#### **related references**

File status key (*Enterprise COBOL for z/OS Language Reference*)

## **Validating data**

If you suspect that your program is trying to perform arithmetic on nonnumeric data or is receiving the wrong type of data on an input record, use the class test (the class condition) to validate the type of data.

You can use the class test to check whether the content of a data item is ALPHABETIC, ALPHABETIC-LOWER, ALPHABETIC-UPPER, DBCS, KANJI, or NUMERIC. If the data item is described implicitly or explicitly as USAGE NATIONAL, the class test checks the national character representation of the characters associated with the specified character class.

You can use the UVALID intrinsic function to check whether a national data item contains valid UTF-16 encoded data, or whether an alphanumeric or alphabetic item contains valid UTF-8 encoded data.

#### **related tasks**

[“Coding conditional expressions” on page 93](#)

[“Testing for valid DBCS characters” on page 144](#)

#### **related references**

Class condition (*Enterprise COBOL for z/OS Language Reference*)

UVALID (*Enterprise COBOL for z/OS Language Reference*)

## **Moving, initializing or setting uninitialized data**

Use an INITIALIZE or SET statement to initialize a table or data item when you suspect that a problem might be caused by residual data in those fields.

If the problem happens intermittently and not always with the same data, it could be that a switch was not initialized but is generally set to the right value (0 or 1) by chance. By using a SET statement to ensure that the switch is initialized, you can determine that the uninitialized switch is the cause of the problem or remove it as a possible cause.

#### **related references**

INITIALIZE statement (*Enterprise COBOL for z/OS Language Reference*)

SET statement (*Enterprise COBOL for z/OS Language Reference*)

[“INITCHECK” on page 311](#)

## **Generating information about procedures**

Generate information about your program or test case and how it is running by coding the USE FOR DEBUGGING declarative. This declarative lets you include statements in the program and indicate when they should be performed when you run your program.

For example, to determine how many times a procedure is run, you could include a debugging procedure in the USE FOR DEBUGGING declarative and use a counter to keep track of the number of times that control passes to that procedure. You can use the counter technique to check items such as these:

- How many times a PERFORM statement runs, and thus whether a particular routine is being used and whether the control structure is correct

- How many times a loop runs, and thus whether the loop is executing and whether the number for the loop is accurate

You can use debugging lines or debugging statements or both in your program.

*Debugging lines* are statements that are identified by a D in column 7. To make debugging lines in your program active, code the WITH DEBUGGING MODE clause on the SOURCE - COMPUTER line in the ENVIRONMENT DIVISION. Otherwise debugging lines are treated as comments.

*Debugging statements* are the statements that are coded in the DECLARATIVES section of the PROCEDURE DIVISION. Code each USE FOR DEBUGGING declarative in a separate section. Code the debugging statements as follows:

- Only in a DECLARATIVES section.
- Following the header USE FOR DEBUGGING.
- Only in the outermost program; they are not valid in nested programs. Debugging statements are also never triggered by procedures that are contained in nested programs.

To use debugging statements in your program, you must include the WITH DEBUGGING MODE clause and use the DEBUG runtime option.

#### Options restrictions:

- You cannot use the USE FOR DEBUGGING declarative in a program that you compile with the THREAD option.

[“Example: USE FOR DEBUGGING” on page 364](#)

#### related references

SOURCE-COMPUTER paragraph (*Enterprise COBOL for z/OS Language Reference*)

Debugging lines (*Enterprise COBOL for z/OS Language Reference*)

Debugging sections (*Enterprise COBOL for z/OS Language Reference*)

DEBUGGING declarative (*Enterprise COBOL for z/OS Language Reference*)

## Example: USE FOR DEBUGGING

This example shows the kind of statements that are needed to use a DISPLAY statement and a USE FOR DEBUGGING declarative to test a program.

The DISPLAY statement writes information to the terminal or to an output data set. The USE FOR DEBUGGING declarative is used with a counter to show how many times a routine runs.

```

Environment Division.
.
.
Data Division.
.
.
Working-Storage Section.
. . . (other entries your program needs)
01 Trace-Msg    PIC X(30) Value " Trace for Procedure-Name : ".
01 Total       PIC 9(9)  Value 1.
.
.
Procedure Division.
Declaratives.
Debug-Declaratives Section.
    Use For Debugging On Some-Routine.
Debug-Declaratives-Paragraph.
    Display Trace-Msg, Debug-Name, Total.
End Declaratives.

Main-Program Section.
. . . (source program statements)
Perform Some-Routine.
. . . (source program statements)
Stop Run.
Some-Routine.
. . . (whatever statements you need in this paragraph)
Add 1 To Total.
Some-Routine-End.

```

The DISPLAY statement in the DECLARATIVES SECTION issues this message every time the procedure Some-Routine runs:

```
Trace For Procedure-Name : Some-Routine 22
```

The number at the end of the message, 22, is the value accumulated in the data item Total; it indicates the number of times Some-Routine has run. The statements in the debugging declarative are performed before the named procedure runs.

You can also use the DISPLAY statement to trace program execution and show the flow through the program. You do this by dropping Total from the DISPLAY statement and changing the USE FOR DEBUGGING declarative in the DECLARATIVES SECTION to:

```
USE FOR DEBUGGING ON ALL PROCEDURES.
```

As a result, a message is displayed before each nondebugging procedure in the outermost program runs.

## Debugging using compiler options

You can use certain compiler options to help you find errors in your program, find various elements in your program, obtain listings, and prepare your program for debugging.

You can find the following errors by using compiler options (the options are shown in parentheses):

- Syntax errors such as duplicate data-names (NOCOMPILE)
- Missing sections (SEQUENCE)
- Invalid subscript values (SSRANGE)

You can find the following elements in your program by using compiler options:

- Error messages and locations of the associated errors (FLAG)
- Program entity definitions and references; text-names and library-names from COPY or BASIS statements, and the associated data sets or files from which copybooks are obtained (XREF)
- Data items in the DATA DIVISION (MAP)
- Statement references (VBREF)

You can get a copy of your source (SOURCE) or a listing of generated code (LIST).

You prepare your program for debugging by using the TEST compiler option.

### related tasks

[“Finding coding errors” on page 365](#)

[“Finding line sequence problems” on page 366](#)

[“Checking for valid ranges” on page 366](#)

[“Selecting the level of error to be diagnosed” on page 367](#)

[“Finding program entity definitions and references” on page 369](#)

[“Listing data items” on page 369](#)

[“Getting listings” on page 370](#)

### related references

[Chapter 17, “Compiler options,” on page 283](#)

## Finding coding errors

Use the NOCOMPILE option to compile conditionally or to only check syntax. When used with the SOURCE option, NOCOMPILE produces a listing that will help you find coding mistakes such as missing definitions, improperly defined data items, and duplicate data-names.

If you are compiling in the TSO foreground, you can send the messages to your screen by using the TERM compiler option and defining your data set as the SYSTERM data set.

**Checking syntax only:** To only check the syntax of your program, and not produce object code, use NOCOMPILE without a suboption. If you also specify the SOURCE option, the compiler produces a listing.

When you specify NOCOMPILE, several compiler options are suppressed. See the related reference below about the COMPILE option for details.

**Compiling conditionally:** To compile conditionally, use NOCOMPILE(x), where x is one of the severity levels of errors. Your program is compiled if all the errors are of a lower severity than x. The severity levels that you can use, from highest to lowest, are S (severe), E (error), and W (warning).

If an error of level x or higher occurs, the compilation stops and your program is only checked for syntax.

**related references**

[“COMPILE” on page 297](#)

## Finding line sequence problems

Use the SEQUENCE compiler option to find statements that are out of sequence. Breaks in sequence indicate that a section of a source program was moved or deleted.

When you use SEQUENCE, the compiler checks the source statement numbers to determine whether they are in ascending sequence. Two asterisks are placed beside statement numbers that are out of sequence. The total number of these statements is printed as the first line in the diagnostics after the source listing.

**related references**

[“SEQUENCE” on page 333](#)

## Checking for valid ranges

Use the SSRANGE compiler option to check whether addresses fall within proper ranges.

SSRANGE causes the following addresses to be checked:

- Subscripted or indexed data references: Is the effective address of the specified table element within the maximum boundary of the containing group? (This checking is not done for UNBOUNDED tables and groups.)
- Variable-length data references (a reference to a data item that contains an OCCURS DEPENDING ON clause): Is the actual length greater than or equal to zero, and within the maximum defined length for the group data item? (This checking is not done for UNBOUNDED groups.)
- Reference-modified data references: Are the offset and length positive? Is the sum of the offset and length within the maximum length for the data item?

If the SSRANGE option is in effect, checking is performed at run time if the COBOL statement that contains the indexed, subscripted, variable-length, or reference-modified data item is executed.

If an effective address is outside the range of the data item that contains the referenced data, an error message is generated and the program stops. The message identifies the table or identifier that was referenced and the line number where the error occurred. Additional information is provided depending on the type of reference that caused the error.

If all subscripts, indices, and reference modifiers in a given data reference are literals and they result in a reference outside the data item, the error is diagnosed at compile time regardless of the setting of the SSRANGE option.

**Performance consideration:** SSRANGE can somewhat degrade performance because of the extra overhead to check each subscripted or indexed item.

**related references**

[“SSRANGE” on page 338](#)

[“Performance-related compiler options” on page 640](#)

# Selecting the level of error to be diagnosed

Use the FLAG compiler option to specify the level of error to be diagnosed during compilation and to indicate whether error messages are to be embedded in the listing. Use FLAG(I) or FLAG(I,I) to be notified of all errors.

Specify as the first parameter the lowest severity level of the syntax-error messages to be issued. Optionally specify the second parameter as the lowest level of the syntax-error messages to be embedded in the source listing. This severity level must be the same or higher than the level for the first parameter. If you specify both parameters, you must also specify the SOURCE compiler option.

Table 50. Severity levels of compiler messages	
Severity level	Resulting messages
U (unrecoverable)	U messages only
S (severe)	All S and U messages
E (error)	All E, S, and U messages
W (warning)	All W, E, S, and U messages
I (informational)	All messages

When you specify the second parameter, each syntax-error message (except a U-level message) is embedded in the source listing at the point where the compiler had enough information to detect that error. All embedded messages (except those issued by the library compiler phase) directly follow the statement to which they refer. The number of the statement that had the error is also included with the message. Embedded messages are repeated with the rest of the diagnostic messages at the end of the source listing.

**Note:** You can suppress some error messages and change the severity of others with the MSGEXIT suboption of the [EXIT option](#).

When you specify the NOSOURCE compiler option, the syntax-error messages are included only at the end of the listing. Messages for unrecoverable errors are not embedded in the source listing, because an error of this severity terminates the compilation.

[“Example: embedded messages” on page 367](#)

## related tasks

[“Generating a list of compiler messages” on page 262](#)

## related references

[“Severity codes for compiler diagnostic messages” on page 263](#)

[“Messages and listings for compiler-detected errors” on page 262](#)

[“FLAG” on page 308](#)

## Example: embedded messages

The following example shows the embedded messages generated by specifying a second parameter to the FLAG option. Some messages in the summary apply to more than one COBOL statement.

```
LineID  PL SL  ----+--A-1-B--+-----2-----3-----4-----5-----6-----7-|-----8  Map
and Cross Reference
...
090671**      /
090672**      *****
090673**      ***          I N I T I A L I Z E   P A R A G R A P H          **
090674**      ***  Open files. Accept date, time and format header lines.    **
090675**      ***    Load location-table.                                   **
090676**      *****
090677**      100-initialize-paragraph.
090678**      move spaces to ws-transaction-record                                IMP
331
```

```

090679**          move spaces to ws-commuter-record          IMP
307
090680**          move zeroes to commuter-zipcode            IMP
318
090681**          move zeroes to commuter-home-phone         IMP
319
090682**          move zeroes to commuter-work-phone         IMP
320
090683**          move zeroes to commuter-update-date        IMP
324
090684**          open input update-transaction-file          204
==090684==> IGYPS2052-S An error was found in the definition of file "LOCATION-FILE". The
                    reference to this file was discarded.
090685**          location-file                                193
090686**          i-o commuter-file                          181
090687**          output print-file                          217
090688**          if commuter-file-status not = "00" and not = "97" 241
090689**          1      display "100-OPEN"
090690**          1      move 100 to comp-code                231
090691**          1      perform 500-vsam-error              91069
090692**          1      perform 900-abnormal-termination    91114
090693**          end-if
090694**          accept ws-date from date                    UND
==090694==> IGYPS2121-S "WS-DATE" was not defined as a data-name. The statement was discarded.
090695**          move corr ws-date to header-date            UND
455
==090695==> IGYPS2121-S "WS-DATE" was not defined as a data-name. The statement was discarded.
090696**          accept ws-time from time                    UND
==090696==> IGYPS2121-S "WS-TIME" was not defined as a data-name. The statement was discarded.
090697**          move corr ws-time to header-time            UND
449
==090697==> IGYPS2121-S "WS-TIME" was not defined as a data-name. The statement was discarded.
090698**          read location-file                          193
==090698==> IGYPS2053-S An error was found in the definition of file "LOCATION-FILE". This
                    input/output statement was discarded.
090699**          at end
090700**          1      set location-eof to true              256
090701**          end-read
...
LineID Message code Message text
IGYSC0090-W 1700 sequence errors were found in this program.
IGYSC3002-I A severe error was found in the program. The "OPTIMIZE" compiler option was
cancelled.
160 IGYDS1089-S "ASSIGNN" was invalid. Scanning was resumed at the next area "A" item, level-
number, or
193 IGYGR1207-S The "ASSIGN" clause was missing or invalid in the "SELECT" entry for file
"LOCATION-FILE".
269 IGYDS1066-S The file definition was discarded.
item. "REDEFINES" object "WS-DATE" was not the immediately preceding level-1 data
90602 IGYPS2052-S The "REDEFINES" clause was discarded.
this file An error was found in the definition of file "LOCATION-FILE". The reference to
90694 IGYPS2121-S was discarded. Same message on line: 90684
"WS-DATE" was not defined as a data-name. The statement was discarded.
90696 IGYPS2121-S Same message on line: 90695
"WS-TIME" was not defined as a data-name. The statement was discarded.
90698 IGYPS2053-S Same message on line: 90697
An error was found in the definition of file "LOCATION-FILE". This input/
output statement
was discarded. Same message on line: 90709
Messages Total Informational Warning Error Severe Terminating
Printed: 13 1 1 11
* Statistics for COBOL program IGYTCARA:
* Source records = 1755
* Data Division statements = 295
* Procedure Division statements = 479
* Generated COBOL statements = 0
* Program complexity factor = 486
End of compilation 1, program IGYTCARA, highest severity 12.
Return code 12

```

## Finding program entity definitions and references

Use the XREF (FULL) compiler option to find out where a data-name, procedure-name, or program-name is defined and referenced. Use it also to produce a cross-reference of COPY or BASIS statements to the data sets or files from which copybooks were obtained.

A sorted cross-reference includes the line number where the data-name, procedure-name, or program-name was defined and the line numbers of all references to it.

To include only the explicitly referenced data items, use the XREF (SHORT) option.

Use both the XREF (either FULL or SHORT) and the SOURCE options to print a modified cross-reference to the right of the source listing. This embedded cross-reference shows the line number where the data-name or procedure-name was defined.

For further details, see the related reference about the XREF compiler option.

[“Example: XREF output: data-name cross-references” on page 398](#)

[“Example: XREF output: program-name cross-references” on page 399](#)

[“Example: XREF output: COPY/BASIS cross-references” on page 400](#)

[“Example: XREF output: embedded cross-reference” on page 401](#)

### related tasks

[“Getting listings” on page 370](#)

### related references

[“XREF” on page 350](#)

## Listing data items

Use the MAP (HEX | DEC) compiler option to create a listing of the DATA DIVISION items and all implicitly declared items. Use the MAP output to locate the contents of a data item in a system dump.

When you specify the MAP (HEX | DEC) option, an embedded MAP summary that contains condensed MAP information is generated to the right of the COBOL source data definition.

- If you specify MAP (HEX) or MAP with no suboption, data item offsets within groups will be in hexadecimal notation.
- If you specify MAP (DEC), data item offsets within groups will be in decimal notation.

When both XREF data and an embedded MAP summary are on the same line, the embedded summary is printed first.

You can select or inhibit parts of the MAP listing and embedded MAP summary by using \*CONTROL MAP | NOMAP (or \*CBL MAP | NOMAP) statements throughout the source. For example:

```
*CONTROL NOMAP
01  A
02  B
*CONTROL MAP
```

[“Example: MAP output” on page 375](#)

### related tasks

[“Getting listings” on page 370](#)

### related references

[“MAP” on page 316](#)

## Using the debugger

You can use Debug Tool to debug your Enterprise COBOL programs. Use the TEST compiler option to prepare your COBOL program so that you can step through the executable program with the debugger.

For remote debugging, there is an Eclipse plugin that provides a client graphical user interface to the debugging information provided by the Debug Tool engine running under z/OS or z/OS UNIX. The IBM Debug Tool Plug-in for Eclipse is included with IBM Developer for z/OS and also with the IBM Problem Determination Tools Studio.

You can specify the TEST suboption NOSOURCE to have smaller object programs stored on disk. The loaded size does not change, the debug information is never loaded unless requested, for example, by a debugger such as Debug Tool or by LE (for CEEDUMP). With the NOSOURCE suboption, you will not be able to see the source in the Debug Tool source window.

Specify the OPTIMIZE(0), NOSTGOPT and TEST compiler options to get the most debugging function.

Specify a non-zero OPTIMIZE level, NOSTGOPT and TEST(EJPD) compiler options to get better performance with a few restrictions on debugging function.

Specify a non-zero OPTIMIZE level, STGOPT and TEST(NOEJPD) compiler options to get the best performance but still be able to use Debug Tool, with some restrictions on debugging function.

For details about which compiler options to use for maximum debugging capability versus best performance, see the related reference about the TEST compiler option.

### related tasks

*z/OS Debugger User's Guide* (Preparing your program for debugging)

### related references

[“TEST” on page 340](#)

## Getting listings

Get the information that you need for debugging by requesting the appropriate compiler listing with the use of compiler options.

**Attention:** The listings produced by the compiler are not a programming interface and are subject to change.

Table 51. Using compiler options to get listings			
Use	Listing	Contents	Compiler option
To check a list of the options in effect for the program, statistics about the content of the program, and diagnostic messages about the compilation	Short listing	<ul style="list-style-type: none"><li>List of options in effect for the program</li><li>Statistics about the content of the program</li><li>Diagnostic messages about the compilation<sup>1</sup></li></ul>	NOSOURCE, NOXREF, NOVBREF, NOMAP, NOOFFSET, NOLIST
To aid in testing and debugging your program; to have a record after the program has been debugged	Source listing	Copy of your source	<a href="#">“SOURCE” on page 334</a>

**Table 51. Using compiler options to get listings** (continued)

Use	Listing	Contents	Compiler option
To find certain data items in a storage dump; to see the final storage allocation after reentrancy or optimization has been accounted for; to see where programs are defined and check their attributes	Map of DATA DIVISION items	All DATA DIVISION items and all implicitly declared items  Embedded map summary (in the right margin of the listing for lines in the DATA DIVISION that contain data declarations)  Nested program map (if the program contains nested programs)	<a href="#">“MAP” on page 316<sup>2</sup></a>
To find where a name is defined, referenced, or modified; to determine the context (such as whether a statement was used in a PERFORM block) in which a procedure is referenced; to determine the data set or file from which a copybook was obtained	Sorted cross-reference listing of names; sorted cross-reference listing of COPY/BASIS statements and copybook data sets or files	Data-names, procedure-names, and program-names; references to these names  COPY/BASIS text-names and library names, and the data sets or files from which associated copybooks were obtained  Embedded modified cross-reference provides line numbers where data-names and procedure-names were defined	<a href="#">“XREF” on page 350<sup>2,3</sup></a>
To find the failing statement in a program or the address in storage of a data item that is moved while the program is running	PROCEDURE DIVISION code and assembler code produced by the compiler <sup>3</sup>	Generated code	<a href="#">“LIST” on page 315<sup>2,4</sup></a>
To verify you still have a valid logic path after you move or add PROCEDURE DIVISION sections	Condensed PROCEDURE DIVISION listing	Condensed statement listing, global tables, WORKING-STORAGE information, and literals	<a href="#">“OFFSET” on page 324</a>
To find an instance of a certain statement	Alphabetic listing of statements	Each statement used, number of times each statement was used, line numbers where each statement was used	<a href="#">“VBREF” on page 347</a>

Table 51. *Using compiler options to get listings* (continued)

Use	Listing	Contents	Compiler option
<ol style="list-style-type: none"> <li>1. To eliminate messages, turn off the options (such as FLAG) that govern the level of compile diagnostic information. You can also selectively suppress messages by using the MSGEXIT suboption of the EXIT compiler option.</li> <li>2. To use your line numbers in the compiled program, use the NUMBER compiler option. The compiler checks the sequence of your source statement line numbers in columns 1 through 6 as the statements are read in. When it finds a line number out of sequence, the compiler assigns to it a number with a value one higher than the line number of the preceding statement. The new value is flagged with two asterisks. A diagnostic message indicating an out-of-sequence error is included in the compilation listing.</li> <li>3. The context of the procedure reference is indicated by the characters preceding the line number.</li> <li>4. You can control the listing of generated object code by selectively placing *CONTROL LIST and *CONTROL NOLIST (or equivalently, *CBL LIST and *CBL NOLIST) statements in your source. Note that the *CONTROL statement is different than the PROCESS (or CBL) statement.</li> </ol> <p>The output is generated if:</p> <ul style="list-style-type: none"> <li>• You specify the COMPILE option (or the NOCOMPILE(x) option is in effect and an error level x or higher does not occur).</li> <li>• You do not specify the OFFSET option. OFFSET and LIST are mutually exclusive options with OFFSET taking precedence.</li> </ul>			

[“Example: short listing” on page 372](#)

[“Example: SOURCE and NUMBER output” on page 375](#)

[“Example: MAP output” on page 375](#)

[“Example: embedded map summary” on page 377](#)

[“Example: nested program map” on page 381](#)

[“Example: XREF output: data-name cross-references” on page 398](#)

[“Example: XREF output: program-name cross-references” on page 399](#)

[“Example: XREF output: COPY/BASIS cross-references” on page 400](#)

[“Example: XREF output: embedded cross-reference” on page 401](#)

[“Example: OFFSET compiler output” on page 402](#)

[“Example: VBREF compiler output” on page 403](#)

#### related tasks

[“Generating a list of compiler messages” on page 262](#)

[“Reading LIST output” on page 381](#)

*Language Environment Debugging Guide* (Debugging COBOL programs)

#### related references

[“Messages and listings for compiler-detected errors” on page 262](#)

## Example: short listing

The parenthetical numbers shown in the listing below correspond to numbered explanations that follow the listing. For illustrative purposes, some errors that cause diagnostic messages were deliberately introduced.

```

Invocation parameters:      (1)
  OPTFILE
PROCESS(CBL) statements:   (2)
  CBL NODECK
  CBL NOADV,NODYN,NOName,NONUMBER,QUOTE,SEQ,DUMP
  CBL NOSOURCE, NOXREF, NOVBREF, NOMAP, NOOFFSET, NOLIST
Options from SYSOPTF:      (3)
  C,NODU,FLAG(I),X,MAP,NOLIST,RENT,OPT(1),SSR
TEST TRUNC(OPT)
Options in effect:         (4)
  NOADATA

```

```

NOADV
  AFP(VOLATILE)
  QUOTE
  ARCH(7)
  ARITH(COMPAT)
NOAWO
NOBLOCK0
  BUFSIZE(4096)
NOCICS
  CODEPAGE(1140)
  COMPILE
NOCOPYRIGHT
NOCURRENCY
  DATA(31)
  DBCS
NODECK
NODIAGTRUNC
  DISPSIGN(COMPAT)
NODLL
  DUMP
NODYNAM
NOEXIT
NOEXPORTALL
NOFASTSRT
  FLAG(I)
NOFLAGSTD
  HGPR(PRESERVE)
  INTDATE(ANSI)
  LANGUAGE(EN)
  LINECOUNT(60)
NOLIST
NOMAP
  MAXPCF(60000)
NOMDECK
NONAME
  NSYMBOL(NATIONAL)
NONUMBER
  NUMPROC(NOPFD)
  OBJECT
NOOFFSET
  OPTIMIZE(1)
  OUTDD(SYSOUT)
  PGMNAME(COMPAT)
  QUALIFY(COMPAT)
  RENT
  RMODE(AUTO)
NORULES
NOSERVICE
  SEQUENCE
NOSOURCE
  SPACE(1)
NOSQL
  SQLCCSID
NOSQLIMS
  SSRANGE(NOZLEN)
NOSTGOPT
SUPPRESS
NOTERM
  TEST(NOJPD,SOURCE)
NOTHREAD
  TRUNC(OPT)
NOVBREF
  VLR(COMPAT)
  VSAMOPENFS(COMPAT)
NOWORD
  XMLPARSE(XMLSS)
NOXREF
NOZONECHECK
  ZONEDATA(PFD)
ZWB

```

LineID	Message code	Message text (5)
	IGYSC3002-I	A severe error was found in the program. The "OPTIMIZE" and the "STGOPT" compiler options were cancelled.
160	IGYDS1089-S	"ASSIGNN" was invalid. Scanning was resumed at the next area "A" item, level-number, or the start of the next clause.
192	IGYDS1050-E	File "LOCATION-FILE" contained no data record descriptions. The file definition was discarded.

```

192 IGYGR1207-S The "ASSIGN" clause was missing or invalid in the "SELECT" entry for file "LOCATION-
FILE".
The file definition was discarded.

888 IGYPS2052-S An error was found in the definition of file "LOCATION-FILE". The reference to this
file
was discarded.
Same message on line: 979

1000 IGYPS2121-S "WS-DATE" was not defined as a data-name. The statement was discarded.
Same message on line: 1001

1004 IGYPS2053-S An error was found in the definition of file "LOCATION-FILE". This input/output
statement
was discarded.
Same message on line: 1016

1015 IGYPS2121-S "LOC-CODE" was not defined as a data-name. The statement was discarded.

1212 IGYPS2121-S "WS-NUMERIC-DATE" was not defined as a data-name. The statement was discarded.

1655 IGYPG3113-W Truncation of high-order digit positions may occur due to precision of intermediate
results
exceeding 30 digits.
Messages Total Informational Warning Error Severe Terminating (6)
Printed: 13 1 1 1 10
* Statistics for COBOL program IGYTCARA: (7)
* Source records = 1755
* Data Division statements = 295
* Procedure Division statements = 479
* Generated COBOL statements = 0
* Program complexity factor = 486
End of compilation 1, program IGYTCARA, highest severity 12. (8)
Return code 12

```

(1)

Message about options passed to the compiler at compiler invocation. This message does not appear if no options were passed.

#### **OPTFILE**

Requests options from a SYSOPTF data set.

(2)

Options coded in the PROCESS (or CBL) statement.

#### **NOOFFSET**

Suppresses a condensed listing of the PROCEDURE DIVISION.

#### **NOMAP**

Suppresses a map report of the items defined in the DATA DIVISION.

(3)

Options obtained from the SYSOPTF data set (because the OPTFILE compiler option was specified).

#### **NOLIST**

Suppresses an assembler-language expansion of the source code.

#### **TEST**

The program was compiled for use with debugging and problem determination tools (such as Debug Tool and Fault Analyzer) and to get local variables listed in CEEDUMP.

(4)

Status of options at the start of this compilation.

(5)

Program diagnostics. The first message refers you to any library phase diagnostics. Diagnostics for the library phase are presented at the beginning of the listing.

(6)

Count of diagnostic messages in this program, grouped by severity level.

(7)

Program statistics for the program IGYTCARA.

(8)

Program statistics for the compilation unit. When you perform a batch compilation, the return code is the highest message severity level for the entire compilation.

## Example: SOURCE and NUMBER output

In the portion of the listing shown below, the programmer numbered two of the statements out of sequence. The note numbers in the listing correspond to numbered explanations that follow the listing.

```

      (1)
LineID  PL SL  ----*A-1-B-+----2-+----3-+----4-+----5-+----6-+----7-+----8 Map and Cross Reference
      (2)  (3)  (4)
000870      /*****
000871      ***          D O   M A I N   L O G I C          **
000872      ***
000873      *** Initialization. Read and process update transactions until **
000874      *** EOE. Close files and stop run.          **
000875      ****
000876      procedure division.
000877          000-do-main-logic.
000878              display "PROGRAM IGYTCARA - Beginning".
000879              perform 050-create-vsam-master-file.          930
000880              perform 100-initialize-paragraph.          982
000881              read update-transaction-file into ws-transaction-record
000882                  at end
000883                  set transaction-eof to true          253
000884              end-read.
000885              IA4410 perform until transaction-eof          253
000886                  perform 200-edit-update-transaction
000887                      1 IA4430 if no-errors          1050
000888                          2 perform 300-update-commuter-record
000889                              1 else          372
000890                                  2 perform 400-print-transaction-errors
000891                                      1 end-if          1159
000892                                      1 perform 410-re-initialize-fields
000893                                          1 IA4480 read update-transaction-file into ws-transaction-record
000894                                              1 at end          1373
000895                                                  2 IA4500 set transaction-eof to true          203 338
000896                                                  1 IA4510 end-read          253
000897                                                  IA4520 end-perform.
000898                                  close commuter-file update-transaction-file location-file
000899                                  print-file.          180 203 192
000900
000901          *-----*
000902          * File status checked after I/O operation.          *
000903          *-----*
000904
000905      IA4600 if not i-o-okay          241
000906      1 display "000-close"
000907      1 move 0000 to comp-code          230
000908      1 IA4620 perform 500-vsam-error          1386
000909      1 perform 900-abnormal-termination          1432
000910      IA4630 end-if.
000911      ****
000912      * Paragraphs 1100 and 1200 illustrates the intrinsic *
000913      * function computations.          *
000914      ****
000915      perform 1100-print-i-f-headings.          1441
000916      perform 1200-print-i-f-data.          1481
000917      display " ".
000918      display " ".
000919      display "PROGRAM IGYTCARA - Normal end".
000920      stop run.
```

(1)

Scale line, which labels Area A, Area B, and source-code column numbers

(2)

Source-code line number assigned by the compiler

(3)

Program (PL) and statement (SL) nesting level

(4)

Columns 1 through 6 of program (the sequence number area)

## Example: MAP output

The following example shows output from the MAP option. The numbers used in the explanation below correspond to the numbers that annotate the output.

(1)  
Data Definition Attribute codes (rightmost column) have the following meanings:

D = Object of OCCURS DEPENDING	G = GLOBAL	S = Spanned file
E = EXTERNAL	O = Has OCCURS clause	U = Undefined format file
F = Fixed-length file	OG = Group has own length definition	V = Variable-length file
FB = Fixed-length blocked file	R = REDEFINES	VB = Variable-length blocked file
X = Unallocated		

(2) Source LineID	(3) Hierarchy and Data Name	(4)	(5) Base Locator	(6) Displacement Structure	(7) Asmblr Data Definition	(8) Data Type	(9) Data Def Attributes
4	PROGRAM-ID IGYTCARA						*
58	FD COMMUTER-FILE		BLF=00001			VSAM	F
60	1 COMMUTER-RECORD		BLF=00001		DS 0CL80	Group	
61	2 COMMUTER-KEY		BLF=00001	000000000	DS 16C	Display	
62	2 FILLER		BLF=00001	000000016	DS 64C	Display	
64	FD COMMUTER-FILE-MST		BLF=00002			VSAM	F
66	1 COMMUTER-RECORD-MST		BLF=00002		DS 0CL80	Group	
67	2 COMMUTER-KEY-MST		BLF=00002	000000000	DS 16C	Display	
68	2 FILLER		BLF=00002	000000016	DS 64C	Display	
140	1 STATUS-AREA				DS 0CL8	Group	
141	2 COMMUTER-FILE-STATUS			000000000	DS 2C	Display	
142	88 I-O-OKAY						
143	2 COMMUTER-VSAM-STATUS			000000002	DS 0CL6	Group	
144	3 VSAM-R15-RETURN-CODE			000000002	DS 2C	Binary	
145	3 VSAM-FUNCTION-CODE			000000004	DS 2C	Binary	
146	3 VSAM-FEEDBACK-CODE			000000006	DS 2C	Binary	
148	77 UPDATE-FILE-STATUS				DS 2C	Display	
149	77 LOCCODE-FILE-STATUS				DS 2C	Display	
150	77 UPDPRINT-FILE-STATUS				DS 2C	Display	
152	1 FLAGS				DS 0CL3	Group	
153	2 TRANSACTION-EOF-FLAG			000000000	DS 1C	Display	
154	88 TRANSACTION-EOF						
155	2 LOCATION-EOF-FLAG			000000001	DS 1C	Display	
156	88 LOCATION-EOF						
157	2 TRANSACTION-MATCH-FLAG			000000002	DS 1C	Display	
158	88 TRANSACTION-MATCH						
159	88 TRANSACTION-MATCH-OFF						
216	1 WS-COMMUTER-RECORD		BLX=00001		DS 0CL81	Group	E
217	2 WS-COMMUTER-KEY		BLX=00001	000000000	DS 0CL16	Group	E
218	3 WS-COMMUTER-GENERIC-KEY		BLX=00001	000000000	DS 0CL5	Group	E
219	4 COMMUTER-SHIFT		BLX=00001	000000000	DS 1C	Display	E
220	4 COMMUTER-HOME-CODE		BLX=00001	000000001	DS 2C	Display	E
221	4 COMMUTER-WORK-CODE		BLX=00001	000000003	DS 2C	Display	E
222	3 COMMUTER-NAME		BLX=00001	000000005	DS 9C	Display	E
223	3 COMMUTER-INITIALS		BLX=00001	000000014	DS 2C	Display	E
224	2 COMMUTER-ADDRESS		BLX=00001	000000016	DS 18C	Display	E
225	2 COMMUTER-CITY		BLX=00001	000000034	DS 13C	Display	E
226	2 COMMUTER-STATE		BLX=00001	000000047	DS 2C	Display	E
227	2 COMMUTER-ZIPCODE		BLX=00001	000000049	DS 3P	Packed-Dec	E
396	1 DETAIL1-LINE		BLL=00001		DS 0CL121	Group	
397	2 FILLER		BLL=00001	000000000	DS 2C	Display	
398	2 PRINT-TRANSACTION-CODE		BLL=00001	000000002	DS 1C	Display	
399	2 FILLER		BLL=00001	000000003	DS 4C	Display	
400	2 PRINT-RECORD-TYPE		BLL=00001	000000007	DS 3C	Display	
401	2 FILLER		BLL=00001	000000010	DS 3C	Display	
402	2 PRINT-SHIFT		BLL=00001	000000013	DS 1C	Display	
403	2 FILLER		BLL=00001	000000014	DS 1C	Display	
404	2 PRINT-HOME-CODE		BLL=00001	000000015	DS 2C	Display	
405	2 FILLER		BLL=00001	000000017	DS 1C	Display	
406	2 PRINT-WORK-CODE		BLL=00001	000000018	DS 2C	Display	
407	2 FILLER		BLL=00001	000000020	DS 2C	Display	
408	2 PRINT-NAME		BLL=00001	000000022	DS 9C	Display	
454	1 DETAILX-LINE		BLL=XXXXX		DS 0CL121	Group	X
455	2 FILLER		BLL=XXXXX		DS 36C	Display	X
456	2 PRINT-CITY		BLL=XXXXX		DS 13C	Display	X
457	2 FILLER		BLL=XXXXX		DS 3C	Display	X
458	2 PRINT-STATE		BLL=XXXXX		DS 2C	Display	X
459	2 FILLER		BLL=XXXXX		DS 1C	Display	X
460	2 PRINT-ZIPCODE		BLL=XXXXX		DS 5C	Display	X
461	2 FILLER		BLL=XXXXX		DS 1C	Display	X
462	2 PRINT-WORK-PHONE		BLL=XXXXX		DS 14C	Display	X
463	2 FILLER		BLL=XXXXX		DS 1C	Display	X
464	2 PRINT-WORK-JUNCTION		BLL=XXXXX		DS 25C	Display	X
465	2 FILLER		BLL=XXXXX		DS 20C	Display	X (10)
467	1 DETAIL2-LINE		BLL=00002		DS 0CL121	Group	
468	2 FILLER		BLL=00002	000000000	DS 36C	Display	
469	2 PRINT-CITY		BLL=00002	000000036	DS 13C	Display	
470	2 FILLER		BLL=00002	000000049	DS 3C	Display	
471	2 PRINT-STATE		BLL=00002	000000052	DS 2C	Display	
472	2 FILLER		BLL=00002	000000054	DS 1C	Display	
473	2 PRINT-ZIPCODE		BLL=00002	000000055	DS 5C	Display	
474	2 FILLER		BLL=00002	000000060	DS 1C	Display	
475	2 PRINT-WORK-PHONE		BLL=00002	000000061	DS 14C	Display	
476	2 FILLER		BLL=00002	000000075	DS 1C	Display	
477	2 PRINT-WORK-JUNCTION		BLL=00002	000000076	DS 25C	Display	
478	2 FILLER		BLL=00002	000000101	DS 20C	Display	

(1) Explanations of the data definition attribute codes.

(2) Source line number where the data item was defined.

(3) Level definition or number. The compiler generates this number in the following way:

- First level of any hierarchy is always 01. Increase 1 for each level (any item you coded as level 02 through 49).

- Level-numbers 66, 77, and 88, and the indicators FD and SD, are not changed.

(4)

Data-name that is used in the source module in source order.

(5)

Base locator used for this data item.

(6)

Hexadecimal displacement from the beginning of the containing structure if the MAP (HEX) option is in effect. If the MAP (DEC) option is in effect, decimal displacement is shown.

(7)

Pseudoassembler code showing how the data is defined. When a structure contains variable-length fields, the maximum length of the structure is shown.

(8)

Data type and usage.

(9)

Data definition attribute codes. The definitions are explained at the top of the DATA DIVISION map.

(10)

DETAILX-LINE was not referenced in the PROCEDURE DIVISION. Because STGOPT was specified, DETAILX-LINE was deleted, resulting in the base locator being set to XXXXX.

[“Example: embedded map summary” on page 377](#)

[“Example: nested program map” on page 381](#)

## related references

[“Terms used in MAP output” on page 378](#)

[“Symbols used in LIST and MAP output” on page 379](#)

## Example: embedded map summary

The following example shows an embedded map summary from specifying the MAP option. The summary appears in the right margin of the listing for lines in the DATA DIVISION that contain data declarations.

000002	Identification Division.			
000003				
000004	Program-id. IGYTCARA.			
000054	Data division.			
000055	File section.			
000056				
000058	FD COMMUTER-FILE			
000059	record 80 characters.			
000060	01 commuter-record.		(1)	(2) (3)
000061	05 commuter-key	PIC x(16).	BLF=00001	0CL80
000062	05 filler	PIC x(64).	BLF=00001,000000000	16C
			BLF=00001,000000016	64C
000105	Working-storage section.			
000106	01 Working-storage-for-IGYTCARA	pic x.		1C
000107				
000108	77 comp-code	pic S9999 comp.		2C
000109	77 ws-type	pic x(3) value spaces.		3C
000135	01 i-f-status-area.			0CL2
000136	05 i-f-file-status	pic x(2).	000000000	2C
000137	88 i-o-successful	value zeroes.		
000138				
000139				
000140	01 status-area.			0CL8
000141	05 commuter-file-status	pic x(2).	000000000	2C
000142	88 i-o-okay	value zeroes.		
000143	05 commuter-vsam-status.			0CL6
000144	10 vsam-r15-return-code	pic 9(2) comp.	000000002	2C
000145	10 vsam-function-code	pic 9(1) comp.	000000004	2C
000146	10 vsam-feedback-code	pic 9(3) comp.	000000006	2C
000147				
000148	77 update-file-status	pic xx.		2C
000149	77 loccode-file-status	pic xx.		2C
000150	77 updprint-file-status	pic xx.		2C
000151				
000216	01 ws-commuter-record EXTERNAL.		BLX=00001	0CL81
000217	05 ws-commuter-key.		BLX=00001,000000000	0CL16

```

000218      10 ws-commuter-generic-key.          BLX=00001,000000000 0CL5
000219          15 commuter-shift                pic x.          BLX=00001,000000000 1C
000220          15 commuter-home-code             pic xx.         BLX=00001,000000001 2C
000221          15 commuter-work-code            pic xx.         BLX=00001,000000003 2C
000222      10 commuter-name                     pic x(9).        BLX=00001,000000005 9C
000223      10 commuter-initials                 pic xx.          BLX=00001,000000014 2C
000224      05 commuter-address                   pic x(18).       BLX=00001,000000016 18C
000225      05 commuter-city                     pic x(13).       BLX=00001,000000034 13C
000226      05 commuter-state                    pic xx.          BLX=00001,000000047 2C
000227      05 commuter-zipcode                  pic 9(5) comp-3.   BLX=00001,000000049 3P

000395      Linkage Section.
000396      01 detail1-line.
000397          05 filler                        pic xx.          BLL=00001,000000000 2C
000398          05 print-transaction-code        pic x.            BLL=00001,000000002 1C
000399          05 filler                        pic x(4).        BLL=00001,000000003 4C
000400          05 print-record-type              pic x(3).        BLL=00001,000000007 3C
000401          05 filler                        pic xxx.         BLL=00001,000000010 3C
000402          05 print-shift                   pic x.          BLL=00001,000000013 1C
000403          05 filler                        pic x.          BLL=00001,000000014 1C
000404          05 print-home-code               pic xx.         BLL=00001,000000015 2C
000405          05 filler                        pic x.          BLL=00001,000000017 1C
000406          05 print-work-code              pic xx.         BLL=00001,000000018 2C
000407          05 filler                        pic xx.         BLL=00001,000000020 2C
000408          05 print-name                    pic x(9).       BLL=00001,000000022 9C
000409          05 filler                        pic xx.          BLL=00001,000000031 2C
000410          05 print-initials                pic xx.         BLL=00001,000000033 2C

000487      procedure division.
000488          000-do-main-logic.
000489              display "PROGRAM IGYTCARA - Beginning".

```

- (1) Base locator used for this data item
- (2) Decimal displacement from the beginning of the containing structure. It indicates that the MAP (DEC) option is in effect. If you specified the MAP (HEX) option or MAP with no suboption, hexadecimal displacement is shown.
- (3) Pseudoassembler code showing how the data is defined

#### related references

[“Symbols used in LIST and MAP output” on page 379](#)

## Terms used in MAP output

The following table describes the terms used in the listings produced by the MAP compiler option.

Table 52. <i>Terms used in MAP output</i>		
Term	Definition	Description
ALPHABETIC	DS <i>n</i> C	Alphabetic data item (PICTURE A)
ALPHA-EDIT	DS <i>n</i> C	Alphabetic-edited data item
AN-EDIT	DS <i>n</i> C	Alphanumeric-edited data item
BINARY	DS 1H <sup>2</sup> , 1F <sup>2</sup> , 2F <sup>2</sup> , 2C, 4C, or 8C	Binary data item (USAGE BINARY, COMPUTATIONAL, or COMPUTATIONAL-5)
COMP-1	DS 4C	Single-precision internal floating-point data item (USAGE COMPUTATIONAL-1)
COMP-2	DS 8C	Double-precision internal floating-point data item (USAGE COMPUTATIONAL-2)
DBCS	DS <i>n</i> C	DBCS data item (USAGE DISPLAY-1)
DBCS-EDIT	DS <i>n</i> C	DBCS-edited data item (USAGE DISPLAY-1)
DISP-FLOAT	DS <i>n</i> C	Display floating-point data item (USAGE DISPLAY)

<i>Table 52. Terms used in MAP output (continued)</i>		
Term	Definition	Description
DISPLAY	DS <i>n</i> C	Alphanumeric data item (PICTURE X)
DISP-NUM	DS <i>n</i> C	Zoned decimal data item (USAGE DISPLAY)
DISP-NUM-EDIT	DS <i>n</i> C	Numeric-edited data item (USAGE DISPLAY)
FD		File definition
FUNCTION-PTR	DS <i>n</i> C	Function pointer (USAGE FUNCTION-POINTER)
GROUP	DS OCL <i>n</i> <sup>1</sup>	Fixed-length alphanumeric group data item
GRP-VARLEN	DS OCL <i>n</i> <sup>1</sup>	Variable-length alphanumeric group data item
INDEX	DS <i>n</i> C	Index data item (USAGE INDEX)
INDEX-NAME	DS <i>n</i> C	Index name
NATIONAL	DS <i>n</i> C	Category national data item (USAGE NATIONAL)
NAT-EDIT	DS <i>n</i> C	National-edited data item (USAGE NATIONAL)
NAT-FLOAT	DS <i>n</i> C	National floating-point data item (USAGE NATIONAL)
NAT-GROUP	DS OCL <i>n</i> <sup>1</sup>	National group (GROUP-USAGE NATIONAL)
NAT-GRP-VARLEN	DS OCL <i>n</i> <sup>1</sup>	National variable-length group (GROUP-USAGE NATIONAL)
NAT-NUM	DS <i>n</i> C	National decimal data item (USAGE NATIONAL)
NAT-NUM-EDIT	DS <i>n</i> C	National numeric-edited data item (USAGE NATIONAL)
OBJECT-REF	DS <i>n</i> C	Object-reference data item (USAGE OBJECT REFERENCE)
PACKED-DEC	DS <i>n</i> P	Internal decimal data item (USAGE PACKED-DECIMAL or COMPUTATIONAL - 3)
POINTER	DS <i>n</i> C	Pointer data item (USAGE POINTER)
PROCEDURE-PTR	DS <i>n</i> C	Procedure pointer (USAGE PROCEDURE-POINTER)
SD		Sort file definition
VSAM, QSAM, LINESEQ		File processing method
1-49, 77		Level-numbers for data descriptions
66		Level-number for RENAMES
88		Level-number for condition-names
1. <i>n</i> is the size in bytes for fixed-length groups and the maximum size in bytes for variable-length groups. 2. If the SYNCHRONIZED clause appears, these fields are used.		

## Symbols used in LIST and MAP output

The following table describes the symbols used in the listings produced by the LIST or MAP option.

<i>Table 53. Symbols used in LIST and MAP output</i>	
Symbol	Definition
BLF_ <i>n</i> <sup>1</sup>	Base locator for files

<i>Table 53. Symbols used in LIST and MAP output (continued)</i>	
<b>Symbol</b>	<b>Definition</b>
BLL_n <sup>1</sup>	Base locator for LINKAGE SECTION
BLO_n <sup>1</sup>	Base locator for object instance data
BLT_n <sup>1</sup>	Base locator for XML - TEXT and XML - NTEXT
BLV_n <sup>1</sup>	Base locator for variably located data
BLX_n <sup>1</sup>	Base locator for external data
ODOsv_cell	ODO save cell number
Pfm_cell	PERFORM cell number
Pfmsv_cell	Perform save cell number
TSN=N	Temporary created by the compiler
VLC_cell	Variable-length cell (ODO)
VN_cell	Variable name cell for PERFORM statement
VNGO_cell	Variable name cell for ALTER statement
VNI_cell	Variable name initialization
#Calc00000000n	Code to compute addresses of data that is present after an OCCURS DEPENDING ON clause
#WSVal00000000n	Code to initialize the WORKING-STORAGE area for a procedure
_ArgumentList	Outgoing arguments to a procedure
_ACON	Address of a symbol
_BEtempNNN	Temporary created by the optimizer
_CAA	Address of the start of the Language Environment Common Anchor Area
_CACHED_\$STATIC	Copy of the start address of the static area (for this procedure)
_CONSTANT_AREA+n	Offset in the Constant Area
_CRENT	Address of the writeable static area (for this module), from the CAA
_incomingArgumentList	Incoming parameters to the procedure
_parentDSA	For a nested procedure, it is the address of its parent's stack
_QCON	Offset to a symbol
_returnValue	Return value of the procedure
_VTS_n	Temporary created by the optimizer
1. n is the number of the entry. For base locators, it can also be XXXXX, indicating a data item that was deleted by STGOPT processing.	

## Example: nested program map

This example shows a map of nested procedures produced by specifying the MAP compiler option. Numbers in parentheses refer to notes that follow the example.

```
Nested Program Map
Program Attribute codes (rightmost column) have the following meanings:
  C = COMMON
  I = INITIAL (1)
  U = PROCEDURE DIVISION USING... (5)
Source Nesting
LineID Level Program Name from PROGRAM-ID paragraph Program
(2)120 0 NESTMAIN. . . . . U
120 1 (4) SUBPR01 . . . . . I,C,U
(2)199 2 NESTED1 . . . . . I,C,U
253 1 SUBPR02 . . . . . U
335 2 NESTED2 . . . . . C,U
(3)
```

- (1) Explanations of the program attribute codes
- (2) Source line number where the program was defined
- (3) Depth of program nesting
- (4) Program-name
- (5) Program attribute codes

## Reading LIST output

Parts of the LIST compiler output might be useful to you for debugging a program.

The LIST compiler option produces several pieces of output:

- An assembler listing of the initialization code for the program (program signature information bytes) from which you can verify program characteristics such as:
  - Compiler options in effect
  - Types of data items present
  - statements used in the PROCEDURE DIVISION
- An assembler listing of the source code for the program

From the address in storage of the instruction that was executing when an abend occurred, you can find the COBOL statement that corresponds to that instruction. After you find the address of the failing instruction, go to the assembler listing and find the statement for which that instruction was generated. The line number is in the 3rd column of the assembler listing for your program. Using the line number, you can locate the STATEMENT by looking at the corresponding line in the Source Output section of the listing.

- Information about WORKING-STORAGE. This information is contained in the Data Division Map and in the Static Map.
- A description of the writeable static area (WSA) is found in the Static Map or WSA24 Map sections of the listing. The symbols in WORKING-STORAGE area of the source are mapped into the writable static area that is shown in the Static Map.

You can use the Data Division Map along with the Static Map section to find the location of data items defined in WORKING-STORAGE. These data items reside in the Writeable Static Area (WSA

or WSA24). The Static Map gives the offset of each level-1 data item relative to the beginning of the writable static area. The Data Division Map section gives the offset of the level-*n* data items relative to their respective level-1 member. By using both pieces of information, you can determine the offset of any data member within the writable static area.

If you compile with the DATA24 option, data items mapped below the line will appear in the WSA24 Map. You can follow the same process to determine their locations.

- Information about the constants and the literals used in the program. The Constant Area contains information about the constants and literals in the program, as well as those created by the compiler. This section contains the offset of each constant or literal within the Constant Area.
- Program prolog areas (PPA1, PPA2, PPA3, PPA4) contain information about the characteristics of the compiled program.
- Externals symbols dictionary contains the list of external symbols defined by or referred to, in your program.
- Map of the dynamic save area (DSA)

The map of the DSA (also known as the *stack frame*) contains information about the contents of the storage acquired each time a separately compiled procedure is entered.

You do not need to be able to program in assembler language to understand the LIST output. The comments that accompany most of the assembler code provide you with a conceptual understanding of the functions performed by the code.

[“Example: Program initialization code” on page 390](#)

[“Example: MD5 signature” on page 391](#)

[“Example: Timestamp and version information” on page 392](#)

[“Example: Compiler options and program information” on page 392](#)

[“Example: Assembler code generated from source code” on page 392](#)

[“Example: Program prolog areas” on page 393](#)

[“Example: Static map ” on page 394](#)

[“Example: Constant area” on page 395](#)

[“Example: Base locator table” on page 396](#)

[“Example: External symbols” on page 397](#)

[“Example: DSA memory map \(Automatic map\)” on page 397](#)

## related references

[“Signature information bytes” on page 382](#)

[“Example: MAP output” on page 375](#)

*Language Environment Programming Guide* (Stack storage overview)

## Signature information bytes

The tables in this topic show program signature information that is part of the listing of program initialization code provided when you use the LIST compiler option.

Table 54. <i>Compiler options in the INFO BYTE section</i>		
Offset in decimal	Option	Value
00	CODEPAGE	CCSID value specified for EBCDIC code page

<i>Table 54. Compiler options in the INFO BYTE section (continued)</i>		
Offset in decimal	Option	Value
02	ARCH	7
		8
		9
		10
		11
03	OPTIMIZE	0
		1
		2

The INFO BYTE section of the listing also provides the following values:

- The number of DATA DIVISION statements
- The number of PROCEDURE DIVISION statements

In the following table, different signature bytes represent different information:

- Signature bytes 1-5, and 26-31 refer to compiler options
- Signature bytes 6-7 refer to DATA DIVISION items
- Signature byte 8 refers to ENVIRONMENT DIVISION items
- Signature bytes 9-25 refer to PROCEDURE DIVISION statements and items

<i>Table 55. Signature information bytes</i>				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
04	28	0	SQL	NOSQL
		1	CICS	NOCICS
		2	MDECK	NOMDECK
		3	SQLCCSID	NOSQLCCSID
		4	OPTFILE	NOOPTFILE
		5	XMLPARSE (XMLSS)	XMLPARSE (COMPAT)
		6	BLOCK0	NOBLOCK0
		7	DISPSIGN (SEP)	DISPSIGN (COMPAT)

Table 55. <i>Signature information bytes</i> (continued)				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
05	29	0	Program uses Java-based OO syntax	
		1	Program uses RANDOM function	
		2	Program uses NATIONAL data (Unicode)	
		3	XML PARSE with schema validation	
		4	STGOPT	NOSTGOPT
		5	AFP (VOLATILE)	AFP (NOVOLATILE)
		6	HGPR (PRESERVE)	HGPR (NOPRESERVE)
		7	NOTEST (DWARF)	Not NOTEST (DWARF)
06	30	0	QUALIFY (EXTEND)	QUALIFY (COMPAT)
		1	VLR (COMPAT)	VLR (STANDARD)
		2	COPYRIGHT string specified	COPYRIGHT string not specified
		3	SERVICE string specified	SERVICE string not specified
		4	ZONEDATA (MIG)	Not ZONEDATA (MIG)
		5	ZONEDATA (NOPFD)	Not ZONEDATA (NOPFD)
07	31	0	NUMCHECK (ZON [ (ALPHNUM) ] )	Not NUMCHECK (ZON [ (ALPHNUM) ] )
		1	NUMCHECK (PAC)	Not NUMCHECK (PAC)
		2	NUMCHECK (BIN)	Not NUMCHECK (BIN)
				NONUMCHECK is in effect if bits 0, 1, and 2 are off
		3	NUMCHECK (ABD)	NUMCHECK (MSG) (if any bit of 0, 1, or 2 is on)
		4	PARMCHECK	NOPARMCHECK
		5	PARMCHECK (ABD) (if bit 4 is on)	PARMCHECK (MSG) (if bit 4 is on)
		6	NUMCHECK (ZON (NOALPHNUM) )	Not NUMCHECK (ZON (NOALPHNUM) )
08	1	0	ADV	NOADV
		1	APOST	QUOTE
		2	DATA (31)	DATA (24)
		3	DECK	NODECK
		4	DUMP	NODUMP
		5	DYNAM	NODYNAM
		6	FASTSRT	NOFASTSRT
		7	SQLIMS	NOSQLIMS

Table 55. <i>Signature information bytes</i> (continued)				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
09	2	0	LIB (always on)	
		1	LIST	NOLIST
		2	MAP (HEX), MAP (DEC)	NOMAP
		3	NUM	NONUM
		4	OBJECT	NOOBJECT
		5	OFFSET	NOOFFSET
		6	OPT (1), OPT (2)	NOOPT, OPT (0)
		7	OUTDD	NOOUTDD
10	3	0	NUMPROC (PFD)	NUMPROC (NOPFD)
		1	RENT	NORENT
		2	RESIDENT (always on)	
		3	SEQUENCE	NOSEQUENCE
		4	Reserved	
		5	SOURCE	NOSOURCE
		6	Not NOSSRANGE	NOSSRANGE
		7	TERM	NOTERM
11	4	0	TEST	NOTEST
		1	TRUNC (STD)	Not TRUNC (STD)
		2	WORD	NOWORD
		3	VBREF	NOVBREF
		4	XREF	NOXREF
		5	ZWB	NOZWB
		6	NAME	NONAME
		7		NOCMPR2 (always off)
12	5	0	Reserved	NONUMPROC
		1	NUMCLS=ALT	NUMCLS=PRIM
		2	DBCS	NODBCS
		3	AWO	NOAWO
		4	TRUNC (BIN)	Not TRUNC (BIN)
		5	ADATA	NOADATA
		6	CURRENCY	NOCURRENCY
		7	Compilation unit is a class	Compilation unit is a program

Table 55. <i>Signature information bytes</i> (continued)				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
13	6	0	QSAM file descriptor	
		1	VSAM sequential file descriptor	
		2	VSAM indexed file descriptor	
		3	VSAM relative file descriptor	
		4	CODE-SET clause (ASCII files) in file descriptor	
		5	Spanned records	
		6	PIC G or PIC N (DBCS data item)	
		7	OCCURS DEPENDING ON clause in data description entry	
14	7	0	SYNCHRONIZED clause in data description entry	
		1	JUSTIFIED clause in data description entry	
		2	USAGE IS POINTER item	
		3	Complex OCCURS DEPENDING ON clause	
		4	External floating-point items in the DATA DIVISION	
		5	Internal floating-point items in the DATA DIVISION	
		6	Line-sequential file	
		7	USAGE IS PROCEDURE-POINTER or FUNCTION-POINTER item	
15	8	0	FILE STATUS clause in FILE-CONTROL paragraph	
		1	RERUN clause in I-O-CONTROL paragraph of INPUT-OUTPUT SECTION	
		2	UPSI switch defined in SPECIAL-NAMES paragraph	
		3	WSOPT: Bit to indicate the method used by the compiler to manage WORKING-STORAGE SECTION. For more information, see <i>COBOL-specific vendor interfaces</i> in the <i>z/OS Language Environment Vendor Interfaces</i> .	
		4	VSAMOPENFS	
16	9	0	ACCEPT	
		1	ADD	
		2	ALTER	
		3	CALL	
		4	CANCEL	
		6	CLOSE	
17	10	0	COMPUTE	
		2	DELETE	
		4	DISPLAY	
		5	DIVIDE	

Table 55. <i>Signature information bytes</i> (continued)				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
18	11	1	END - PERFORM	
		2	ENTER	
		3	ENTRY	
		4	EXIT	
		5	EXEC	
		6	GO TO	
		7	IF	
19	12	0	INITIALIZE	
		1	INVOKE	
		2	INSPECT	
		3	MERGE	
		4	MOVE	
		5	MULTIPLY	
		6	OPEN	
20	13	0	READ	
		2	RELEASE	
		3	RETURN	
		4	REWRITE	
		5	SEARCH	
		7	SET	
21	14	0	SORT	
		1	START	
		2	STOP	
		3	STRING	
		4	SUBTRACT	
		7	UNSTRING	

Table 55. *Signature information bytes (continued)*

Offset in decimal	Signature byte	Bit	Item	
			On	Off
22	15	0	USE	
		1	WRITE	
		2	CONTINUE	
		3	END-ADD	
		4	END-CALL	
		5	END-COMPUTE	
		6	END-DELETE	
		7	END-DIVIDE	
23	16	0	END-EVALUATE	
		1	END-IF	
		2	END-MULTIPLY	
		3	END-READ	
		4	END-RETURN	
		5	END-REWRITE	
		6	END-SEARCH	
		7	END-START	
24	17	0	END-STRING	
		1	END-SUBTRACT	
		2	END-UNSTRING	
		3	END-WRITE	
		4	GOBACK	
		5	EVALUATE	
		7	SERVICE	
25	18	0	END-INVOKE	
		1	END-EXEC	
		2	XML	
		3	END-XML	
		4	ALLOCATE	
		5	FREE	
		6	JSON	
		7	END-JSON	
26	19	0-7	Reserved	

Table 55. <i>Signature information bytes (continued)</i>				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
27	20	0-7	Reserved	
28	21	0	Hexadecimal literal	
		1	Altered GO TO	
		2	I-O ERROR declarative	
		4	DEBUGGING declarative	
		5	Program segmentation	
		6	OPEN . . . EXTEND	
		7	EXIT PROGRAM	
29	22	0	CALL literal	
		1	CALL identifier	
		2	CALL . . . ON OVERFLOW	
		3	CALL . . . LENGTH OF	
		4	CALL . . . ADDRESS OF	
		5	CLOSE . . . REEL/UNIT	
		6	Exponentiation used	
30	23	7	Floating-point items used	
		0	COPY	
		1	BASIS	
		2	DBCS name in program	
		3	Shift-out and Shift-in in program	
		4	SUPPRESS   NOSUPPRESS	
		5	SSRANGE (ZLEN) (if bit 6 in byte 3 is on)	SSRANGE (NOZLEN) (if bit 6 in byte 3 is on)
40	24	6	SSRANGE (ABD) (if bit 6 in byte 3 is on)	SSRANGE (MSG) (if bit 6 in byte 3 is on)
		7	INLINE   NOINLINE	
		0	DBCS literal	
		1	REPLACE	
		2	Reference modification was used.	
		3	Nested program	
		4	INITIAL	
		5	COMMON	
		6	SELECT . . . OPTIONAL	
		7	EXTERNAL	

Table 55. <i>Signature information bytes (continued)</i>				
Offset in decimal	Signature byte	Bit	Item	
			On	Off
41	25	0	GLOBAL	
		1	RECORD IS VARYING	
		2	VOLATILE	
		5	Intrinsic function was used	
		6	Z-literal found	
		7	RECURSIVE	
42	26	0	RMODE (ANY)	Not RMODE (ANY)
		1-3	Reserved	
		4	Reserved	
		5	INTDATE (LILIAN)	INTDATE (ANSI)
		6	Reserved	
		7	Reserved	
43	27	0	PGMNAME (LONGUPPER)	Not PGMNAME (LONGUPPER)
		1	PGMNAME (LONGMIXED)	Not PGMNAME (LONGMIXED)
		2	DLL	NODLL
		3	EXPORTALL	NOEXPORTALL
		4	TEST (SOURCE)	Not TEST (SOURCE)
		5	ARITH (EXTEND)	ARITH (COMPAT)
		6	THREAD	NOTHREAD
		7	TEST (EJPD)	TEST (NOEJPD)
44	28	0-7	Build level info	

**Check return code:** A return code greater than 4 from the compiler could mean that some of the statements shown in the information bytes might have been discarded from the program.

#### related references

[“LIST” on page 315](#)

*z/OS Language Environment Vendor Interfaces* (COBOL-specific vendor interfaces)

### Example: Program initialization code

A listing of the program initialization code gives you information about the characteristics of the COBOL source program. Interpret the program signature information bytes to verify characteristics of your program.

(1)	(2)	(3)	(4)	(5)
000000		000003	PROC	IGYTCARA
000000	47F0 F014	000003	BC	R15,20(,R15)
000004	01C3 C5C5	000003	DC	X'01C3C5C5'
000008	0000 0978	000003	DC	X'00000978'
00000C	0000 8910	000003	DC	X'00008910'
000010	47F0 F001	000003	BC	R15,1(,R15)
000014		000003	EQU	*
		L3282:		
				# Skip over constant area
				# Eyecatcher: CEE
				# Stack Size
				# Offset to PPA1
				# Wrong Entry Point: cause exception

000014	90EC	D00C	000003	STM	R14,R12,12(,R13)	# Save GPRs Used
000018	4110	F024	000003	LA	R1,36(,R15)	# Args for boot strap routine
00001C	98EF	F034	000003	LM	R14,R15,52(,R15)	#
000020	07FF		000003	BR	R15	# Branch to boot strap routine
000022	0000		000003	DC	X'0000'	# Available half-word
000024			000003	L3284: EQU	*	# Boot Strap Info Block
000024	0000	0000	000003	DC	X'00000000'	# address of entry label
000028	0000	0000	000003	DC	X'00000000'	# WSA24 allocation size
00002C	0000	8A0C	000003	DC	X'00008A0C'	# address of Saved Option String
000030	0000	8948	000003	DC	X'00008948'	# address of entry point name
000034	0000	0054	000003	DC	X'00000054'	# A(Label L3283)
000038	0000	0000	000003	DC	X'00000000'	# address of boot strap routine(IGZXBST)
00003C			000003	L3285: EQU	*	# CEE Parameter Block
00003C	0000	0024	000003	DC	X'00000024'	# address of infoBlockLabel
000040	0000	8A1C	000003	DC	X'00008A1C'	# A(PARMCEE-CEEPPARMBlock)
000044			000003	L3280: EQU	*	# Handle growing stack
000044	58F0	C31C	000003	L	R15,796(,R12)	# Load CEECAA0GETS
000048	184E		000003	LR	R4,R14	# Required NAB
00004A	05EF		000003	BALR	R14,R15	# Extend Stack
00004C	0000	0000	000003	DC	X'00000000'	# Argument list size = 0
000050	A7F4	0009	000003	J	L3281	# Branch back
000054			000003	@MAINENT DS	0H	# PRIMARY ENTRY POINT ADDRESS
000054			000003	L3283: EQU	*	# User Code Entry Point
000054	18EF		000003	LR	R14,R15	# Load NAB
000056	4100	E978	000003	LA	R0,2424(,R14)	# New NAB Address
00005A	5500	C314	000003	CL	R0,788(,R12)	# Exceed current storage segment?
00005E	A724	FFF3	000003	JH	L3280	# Yes: branch to recovery code
000062			000003	L3281: EQU	*	# Stack now has sufficient room
000062	5000	E04C	000003	ST	R0,76(,R14)	# Update NAB
000066	A708	0010	000003	LHI	R0,16	# COBOL Language Word upper half
00006A	8900	0010	000003	SLL	R0,16	# shift to upper half of register
00006E	A70A	0301	000003	AHI	R0,769	# add COBOL Language Word lower half
000072	5000	E000	000003	ST	R0,0(,R14)	# Save Language Word
000076	50D0	E004	000003	ST	R13,4(,R14)	# Save Back Chain
00007A	18DE		000003	LR	R13,R14	# Set new DSA
00007C	4100	D6D0	000003	LA	R0,1744(,R13)	# Address of COBDSACB
000080	5000	D074	000003	ST	R0,116(,R13)	# Saved in member slot1
000084	4100	0000	000003	LA	R0,0(,R0)	#
000088	5000	D070	000003	ST	R0,112(,R13)	# zero member slot0

- (1) Offset from the start of the COBOL program
- (2) Hexadecimal representation of assembler instructions
- (3) Source line number
- (4) Pseudo-assembler representation of the code generated for the COBOL program
- (5) Comments that explain the pseudo-assembler code

## related references

[“Signature information bytes” on page 382](#)

## Example: MD5 signature

The following example shows LIST output about the MD5 signature. This information is also included in the DWARF debugging data in the application module. MD5 signature is located at 16 bytes before the Timestamp and Version Information section.

000608	AAEE	60C2	DAA3	=X'AAEE60C2DAA3'	md5 signature
00060E	776D	AEB5	E753	=X'776DAEB5E753'	md5 signature
000614	E767	C4E1		=X'E767C4E1'	md5 signature

**Note:** The MD5 signature is shown only if the TEST option is specified or if -g is specified with **cob2** under z/OS UNIX.

The presence or absence of the MD5 signature is indicated by a compilation flag bit of the PPA2. If the bit is set to 1, the MD5 signature is present; if the bit is set to 0, the MD5 signature is absent. For details about PPA2, see *z/OS Language Environment Vendor Interfaces*.

## related references

[“Example: Program prolog areas” on page 393](#)

## Example: Timestamp and version information

The following example shows LIST output about the version of the compiler and the data and time of compilation.

```
                                Timestamp and Version Information
0029C8  F2F0  F1F3              =C'2013'          Compiled Year
0029CC  F0F3  F2F7              =C'0327'          Compiled Date MMDD
0029D0  F1F2  F3F1  F2F2        =C'123122'         Compiled Time HHMMSS
0029D6  F0F6  F0F1  F0F0        =C'060100'         VERSION/RELEASE/MOD LEVEL OF
PROD
                                Timestamp and Version End
```

## Example: Compiler options and program information

The following example shows LIST output for the compiler options and program information.

```
DATA VALIDATION AND UPDATE PROGRAM  IGYTCARA Date 03/18/2016 Time 10:48:16

                                Compiler Options and Program Information Section
(1)  (2)  (3)                                (4)                                (5)
0029DC      0030                                =X'0030'          Size of Compiler Options and Prog Info Section
0029DE  (+00) 0474                                =X'0474'          UNSIGNED BINARY CODE PAGE CCSID VALUE
0029E0  (+02) 06                                =X'06'           ARCHITECTURE LEVEL
0029E1  (+03) 00                                =X'00'           OPTIMIZATION LEVEL
0029E2  (+04) 1406                                =X'1406'          INFO. BYTES 28-29
0029E4  (+06) 0000                                =X'0000'          RESERVED
0029E6  (+08) A04875CC2001                        =X'A04875CC2001'  INFO. BYTES 1-6
0029EC  (+14) 100010884909                        =X'100010884909'  INFO. BYTES 7-12
0029F2  (+20) 002008800C00                        =X'002008800C00'  INFO. BYTES 13-18
0029F8  (+26) 000001A000                        =X'000001A000'    INFO. BYTES 19-23
0029FD  (+31) 00                                =X'00'           COBOL SIGNATURE LEVEL
0029FE  (+32) 0000002F                        =X'0000002F'      # DATA DIVISION STATEMENTS
002A02  (+36) 0000005B                        =X'0000005B'      # PROCEDURE DIVISION STATEMENTS
002A06  (+40) 18808008                        =X'18808008'      INFO. BYTES 24-27
002A0A  (+44) E2F1F6F0F1F1F540                  =C'P160115'       BUILD LEVEL INFO

                                Compiler Options and Program Information Section End
```

- (1) Offset in the program object
- (2) Offset in decimal
- (3) Contents of the bytes in hexadecimal format
- (4) Assembler representation of the bytes
- (5) Explanation of the bytes in the section

## Example: Assembler code generated from source code

The following example shows a listing of the assembler code that is generated from source code when you use the LIST compiler option. You can use this listing to find the COBOL statement that corresponds to the instruction that failed.

```
000964:      display "PROGRAM IGYTCARA - Beginning".                                (1)
(2)      (3)      (4)      (5)      (6)
0001EA  E320 3394 0171  000964      LAY      R2,5012(,R3)      #
0001F0  D203 05E8 2000  000964      MVC      1512(4,R13),0(R2)  #
0001F6  E320 3398 0171  000964      LAY      R2,5016(,R3)      #
0001FC  D203 05EC 2000  000964      MVC      1516(4,R13),0(R2)  #
000202  4120 39C8      000964      LA       R2,2504(,R3)      #
000206  5020 05F0      000964      ST       R2,1520(,R13)    #
00020A  E320 338C 0171  000964      LAY      R2,5004(,R3)      #
000210  D203 05F4 2000  000964      MVC      1524(4,R13),0(R2)  #
000216  E320 339C 0171  000964      LAY      R2,5020(,R3)      #
00021C  D203 05F8 2000  000964      MVC      1528(4,R13),0(R2)  #
000222  D703 05FC 05FC  000964      XC       1532(4,R13),1532(R13) #
000228  4110 05E8      000964      LA       R1,1512(,R13)    #
00022C  E3F0 31D4 0158  000964      LY       R15,4564(,R3)    #
000232  58C0 0D80      000964      L        R12,128(,R13)    #
000236  0DEF      000964      BASR     R14,R15          #
000965:      perform 050-create-vsam-master-file.
```

000238	5820	D670	000965	L	R2,1648(,R13)	# VN_cell
00023C	5020	D544	000965	ST	R2,1348(,R13)	# PfmSv_Cell
000240	C020	0000 0007	000965	LARL	R2	
000246	5020	D670	000965	ST	R2,1648(,R13)	# VN_cell
00024A	A7F4	02F4	000965	J	050-CREATE-VSAM-MASTER-FILE	
00024E	5820	D544	000965	L	R2,1348(,R13)	# PfmSv_Cell
000252	5020	D670	000965	ST	R2,1648(,R13)	# VN_cell

- (1) Source code interspersed with the pseudo-assembler instructions
- (2) Relative location of the object code instruction in the module, in hexadecimal notation
- (3) Object code instructions, in hexadecimal notation  
The first two or four hexadecimal digits are the instruction, and the remaining digits are the instruction operands. Some instructions have two operands.
- (4) Source line number associated with this assembler code
- (5) Object code instructions, in compiler-generated pseudo assembler
- (6) Explanation of the instruction and the operands used by the instructions

#### related references

[“Symbols used in LIST and MAP output” on page 379](#)

## Example: Program prolog areas

The following example shows LIST output for the program prolog area. The Program Prologue Area (PPA) is comprised of several sections that contain information about the compiled program.

There is a PPA1 for every procedure in your program, including procedures generated by the compiler. The offset to its corresponding PPA1 is recorded at offset 12 (X'C') from the start of each procedure. The PPA1 contains information about the procedure as well as offsets to the PPA2 and PPA3 sections.

For details on how to use the program prolog areas to locate information in the listing file, see *z/OS Language Environment Vendor Interfaces*.

DATA VALIDATION AND UPDATE PROGRAM IGYTCARA Date 03/18/2016 Time 10:48:16			
1	2	3	4
	PPA1: Entry Point Constants		
0081E0	1CCEA506	=F'483304710'	Flags
0081E4	00008310	=A(PPA2-IGYTCARA)	
0081E8	00008378	=A(PPA3-IGYTCARA)	
0081EC	00000000	=F'0'	No EPD
0081F0	FFFE0000	=F'-131072'	Register Save Mask
0081F4	40000000	=F'1073741824'	Member Flags
0081F8	90	=AL1(144)	Flags
0081F9	000978	=AL3(2424)	Callee's DSA use/8
0081FC	0000	=AL1(0)	Flags
0081FE	0012	=H'18'	Offset/2 to CDL
008200	D00006D0	=F'-805304624'	State variable location
008204	00000000	=F'0'	CDL function length/2
008208	00000000	=F'0'	CDL function EP offset
00820C	00000000	=F'0'	CDL prolog
008210	00000000	=F'0'	CDL epilog
008214	00000000	=F'0'	CDL end
008218	0008 ****	AL2(8),C'IGYTCARA'	
	PPA1 End		

There is one PPA2 for each program. The offset to the PPA2 is recorded in each PPA1. The PPA2 contains offsets to the Time Stamp and Version Information section of the listing as well as to the PPA4 section.

If the TEST option is not in effect, the PPA2 section looks like this:

PPA2: Entry Point Constants			
000800	04002203	=F'67117571'	Flags
000804	FFFFFF800	=A(CEESTART-PPA2)	
000808	00000058	=F'88'	A(PPA4-PPA2)
00080C	FFFFFFF80	=A(TIMESTAMP-PPA2)	
000810	FFFFFF800	=A(PrimaryEntryPoint-PPA2)	

000814	02200000	PPA2	End	=F'35651584'	Flags
--------	----------	------	-----	--------------	-------

If the TEST option is in effect, the PPA2 section looks like this:

PPA2: Entry Point Constants					
000830	04002203			=F'67117571'	Flags
000834	FFFFFF7D0			=A(CEESTART-PPA2)	
000838	00000058			=F'88'	A(PPA4-PPA2)
00083C	FFFFFFF80			=A(TIMESTAMP-PPA2)	
000840	FFFFFF7D0			=A(PrimaryEntryPoint-PPA2)	
000844	02600000			=F'39845888'	Flags
		PPA2	End		

There is one PPA3 for each program (including each nested program) in a COBOL source file. Each entry contains offsets, relative to the PPA3 itself, to the base locator table and to the special register table. The PPA3 also contains an offset from the start of the program to the first COBOL statement.

PPA3: Entry Point Constants					
0014D8	00000000			=F'0'	Flags
0014DC	000000C0			=F'192'	A(Base_Locator_Table-PPA3)
0014E0	000000D8			=F'216'	A(Special_Register_Table-PPA3)
0014E0	00000184			=X'184'	A(User_Entry-CUEntry)
		PPA3	End		

There is one PPA4 for each program. It has offsets to various compiler generated tables, such as the writable static area ( the Static Map and WSA24 sections). The offset to the PPA4 is recorded in a field of the PPA2.

PPA4: Entry Point Constants					
008340	08000000			=F'134217728'	Flags 1
008344	00020100			=F'131328'	Flags 2
008348	00000000			=F'0'	A(NORENTstatic)
00834C	00000000			=F'0'	Q(RENTstatic)
008350	00000000			=F'0'	A(DATA24_31_address_cell-RENTstatic)
008354	FFFF7CC0			=F'-33600'	A(Code-PPA4)
008358	00008398			=F'33688'	Code Length
00835C	00000000			=F'0'	Length NORENTstatic
008360	00002204			=F'8708'	Length RENTstatic
008364	00000000			=F'0'	Length DATA24_31
008368	002A			=X'2A'	A(CUName-PPA4)
008372	00000090			=X'90'	Offset UsrWrkStrg
008376	0000000B			=X'B'	Length UsrWrkStrg
00837A	00			=X'0'	Has Externals
		PPA4	End		

- 1 Relative location, in hexadecimal format, of the PPA field in the object module
- 2 The contents of the field, in hexadecimal
- 3 An assembler-like syntax defining the field
- 4 A description of the contents of the field.

#### related references

*z/OS Language Environment Vendor Interfaces*

WORKING-STORAGE SECTION changes (*Enterprise COBOL for z/OS Migration Guide*)

### Example: Static map

The three map sections in the listing, STATIC MAP, WORKING-STORAGE MAP, and WSA 24 MAP are collectively called the static maps of a program. The storage for these areas is allocated at the start of the program and persists until the end of the run unit or until the program is canceled.

The layout of these three map sections is similar:

- The first column shows the offset of the item from a block of storage allocated by the compiler.
- The second column is the size of the symbol, including all of its sublevel members.
- The third column is the name of the area being described.

See the following `STATIC MAP` as an example of the layout. If the `NORENT` compiler option is in effect, the `WORKING-STORAGE` data items are mapped in the `STATIC MAP` section. For COBOL data items, the offset is the offset to the start of the level-01 data item from the block of storage allocated by the compiler. The starting address of this block resides in the `Constant Area`.

```

          * * * * *   S T A T I C   M A P   * * * * *

OFFSET (HEX)  LENGTH (HEX)  NAME

           0           4      BLI_Ptrs
           4           C      BLT_Ptrs
          10          60      GPCB
          70           4      WS-BASE-ADDRESS
          74           8      TS2=6

```

If the `RENT` and `DATA(31)` compiler options are in effect, the `WORKING-STORAGE` data items are shown under the `WORKING-STORAGE MAP`. If the `RENT` and `DATA(24)` options are in effect, the `WORKING-STORAGE` data items are shown under the `WSA 24 MAP`. A `STATIC MAP` section is also shown where compiler generated internal data items and locators are mapped.

```

          * * * * *   W S A   2 4   M A P   * * * * *

OFFSET (HEX)  LENGTH (HEX)  NAME

           0           4      JNIEVPTR
           8           2      RETURN-CODE
          10           2      SORT-RETURN
          18           8      SORT-CONTROL
          20           4      SORT-CORE-SIZE
          28           4      SORT-FILE-SIZE
          30           4      SORT-MODE-SIZE
          38           8      SORT-MESSAGE
          40           4      TALLY
          48           1      SHIFT-OUT
          50           1      SHIFT-IN
          58           4      XML-CODE
          60          1E      XML-EVENT
          80           4      XML-INFORMATION
          88          50      COMMUTER-FILE
          D8          50      COMMUTER-FILE-MST
         128          7A      PRINT-FILE
         1A8           1      WORKING-STORAGE-FOR-IGYCARA
         1B0           2      COMP-CODE
         1B8           3      WS-TYPE
         1C0           2      I-F-STATUS-AREA
         1C8           8      STATUS-AREA
         1D0           2      UPDATE-FILE-STATUS

```

## Example: Constant area

The following example shows `LIST` output about strings and other literals from the COBOL source as well as those generated by the compiler.

The compiler generates loads from (and stores to) the `Constant Area` by loading the starting address of `Constant Area` and adding the fixed offsets to the respective constants or literals.

```

          (1) (2)  CONSTANT AREA:  (3)  (4)

006A98 (+0)  00CCDDFF 00000000 C9C7E8E3 C3C1D9C1 00000000 00000000 C9C7E9E2 D9E3C3C4
|. . . . . IGYTCARA. . . . . IGZSRCTD|
006AB8 (+32)  40000A00 40000000 00000008 00000000 E2E8E2D6 E4E34040 00100000 00000000
|. . . . . SYSOUT . . . . .
006AD8 (+64)  0E000000 00000001 0F000000 0000001E 00000000 40000000 00000003 0064003C
|. . . . .
006AF8 (+96)  000FE800 9F0F0000 00000011 00000000 E3D9C1D5 E2C1C3E3 4B40C3D6 C4C50000 |. . Y. . . . . TRANSACT.
CODE. . . |
006B18 (+128) 0000000E 00000000 E2C8C9C6 E340C3D6 C4C54040 40400000 C8D6D4C5 40D3D6C3 |. . . . . SHIFT CODE ..HOME
LOC|
006B38 (+160) 4B40C3D6 C4C50000 E6D6D9D2 40D3D6C3 4B40C3D6 C4C50000 D3C1E2E3 40D5C1D4 |. CODE..WORK LOC. CODE..LAST
NAM|
006B58 (+192) C5404040 40400000 C9D5C9E3 C9C1D3E2 40404040 40400000 C4E4D7D3 C9C3C1E3 |
E ..INITIALS ..DUPLICAT|
006B78 (+224) C540D9C5 C34B0000 D9C5C34B 40D5D6E3 40C6D6E4 D5C40000 C1C4C4D9 C5E2E240 |E REC...REC. NOT
FOUND..ADDRESS |
006B98 (+256) 40404040 40400000 C3C9E3E8 40404040 40404040 40400000 E2E3C1E3 C540C3D6 | ..CITY ..STATE

```

CO	006BB8 (+288)	C4C54040 40400000 E9C9D7C3 D6C4C540 40404040 40400000 C8D6D4C5 40D7C8D6	DE	..ZIPCODE	..HOME
PHO	006BD8 (+320)	D5C54040 40400000 E6D6D9D2 40D7C8D6 D5C54040 40400000 C8D6D4C5 40D1E4D5	NE	..WORK PHONE	..HOME
JUN	006BF8 (+352)	C3E3C9D6 D5400000 E6D6D9D2 40D1E4D5 C3E3C9D6 D5400000 C4D9C9E5 C9D5C740	CTION	..WORK	
JUNCTION ..DRIVING	006C18 (+384)	E2E3C1E3 E4E20000 40D9C5D7 D6D9E340 407B7A40 C9C7E8E3 C3C1D9C1 40404040	STATUS..	REPORT	#:
IGYTCARA	006C38 (+416)	40404040 40404040 40404040 40404040 40404040 40404040 40404000 00000033			
	006C58 (+448)	C3D6D4D4 E4E3C5D9 40C6C9D3 C540E4D7 C4C1E3C5 40D3C9E2 E3404040 40404040	COMMUTER	FILE	UPDATE
LIST	006C78 (+480)	40404040 40404040 40404040 40404040 40400000 00000032 40404040 40404040			
	006C98 (+512)	D7C1C7C5 407B7A40 00000000 00000010 40D7D9D6 C7D9C1D4 407B7A40 C9C7E8E3	PAGE #:	.....	PROGRAM #:
IGYT	006CB8 (+544)	C3C1D9C1 40404040 404040D9 E4D540E3 C9D4C57A 40000000 00000025 7A000000	CARA		RUN
TIME: .....	006CD8 (+576)	00000030 00000000 D9E4D540 C4C1E3C5 7A400000 0000000A 61000000 0000000B	.....		RUN
DATE: .....					

- (1) Offset in csect.
- (2) Offset in base 10.
- (3) 8 columns containing the bytes in the Constant Area
- (4) Character representation. A dot (.) is used for non-printable characters.

## Example: Base locator table

The following example shows LIST output for the base locator table.

Base Locator Table			
008AB0	01	=X'1'	Table Version
008AB1	00	=X'0'	Reserved
008AB2	0008	=H'8'	Header length
008AB4	00000010	=F'16'	Array byte length
008AB8	2A00	=X'2A00'	Flags & info (element 1)
008ABA	00000014	=X'14'	Offset to cells
008ABE	03	=X'3'	Cell count
008ABF	0A00	=X'A00'	Flags & info (element 2)
008AC1	00000000	=X'0'	Offset to cells
008AC5	05	=X'5'	Cell count
008AC6	0000	=X'0'	Flags & info (end of
array)			
Base Locator Table End			

For more information about the base locator table, see *z/OS Language Environment Vendor Interfaces*.

### related references

*z/OS Language Environment Vendor Interfaces* (Base locator table)

## Example: Special register table

The following example shows LIST output for the special register table. The special register table has a similar format to the base locator table.

Special Register Table			
0015B0	01	=X'1'	Table Version
0015B1	00	=X'0'	Reserved
0015B2	0008	=H'8'	Header length
0015B4	00000006	=F'6'	Array byte length
0015B8	12	=X'12'	Flags & info (element 1)
0015B9	00000018	=X'18'	Offset to cells
0015BD	00	=X'0'	Flags & info (end of
array)			
Special Register Table End			

Each entry in the special register table consists of the following items:

- A byte which represents the following information:

- Special register ID number (bits 0 - 4). ID = 1 represents the RETURN-CODE register
- Access mode (bits 5 - 8)
  - MODE = 0; Base Address = Top of Stack
  - MODE = 1; Base Addr = NORENT Static
  - MODE = 2; Base Addr = 32-bit RENT static
  - MODE = 3; 24-bit NORENT static
- An offset to the special register

The end of the special register table is indicated by a null byte.

## Example: External symbols

The following example shows LIST output for external symbols defined by, or referred to in your program. The external symbol dictionary contains one entry per external symbol defined by or referred to in the program.

Each entry contains the address, length and symbol type. Symbol types are:

### ED

External Definition

### SD

Section Definition

### LD

Label Definition

### ER

External Reference

### PR

Pseudo Register

E X T E R N A L		S Y M B O L		D I C T I O N A R Y	
	TYPE	ID	ADDR	LENGTH	NAME
	SD	1	000000	000000	IGYTCARA
	ED	2	000000	000000	C_CEESG003
	ED	3	000000	008AC8	C_CODE
	LD	4	000000	000000	IGYTCARA#C
	ER	5	000000	000000	CEESTART
	ER	6	000000	000000	CEEBETBL
	ED	7	000000	000000	C_WSA
	PR	8	000000	002204	IGYTCARA#S
	ED	9	000000	000022	B_IDRL
	ER	10	000000	000000	IGZXBST
	ER	11	000000	000000	IGYTCARA
	ER	12	000000	000000	IGZXPRS
	ER	13	000000	000000	IGZXCMSG
	ER	14	000000	000000	IGZXDSP
	ER	15	000000	000000	IGZXVCLS

## Example: DSA memory map (Automatic map)

The following example shows LIST output for the dynamic save area (DSA). The DSA contains information about the contents of the storage acquired when a separately compiled procedure is entered.

* * * * *		A U T O M A T I C		M A P		* * * * *	
<b>1</b>	<b>2</b>	<b>3</b>					
OFFSET (HEX)	LENGTH (HEX)	NAME					

Block name: IGYTCARA

80	4	_@CAA
C8	3	_BEtemp200
CC	3	_BEtemp204
D0	3	_BEtemp208
D4	3	_BEtemp212
D8	3	_BEtemp216
DC	3	_BEtemp220
E0	3	_BEtemp224
E4	3	_BEtemp228
E8	10	_BEtemp232
F8	20	_BEtemp248
118	20	_BEtemp280
138	4	_BEtemp312
13C	4	_BEtemp316
140	4	_BEtemp320
144	4	_BEtemp324
148	4	_BEtemp328
14C	4	_BEtemp332
150	4	_BEtemp336
154	4	_BEtemp340
158	4	_BEtemp344
15C	4	_BEtemp348
160	4	_BEtemp352
164	4	_BEtemp356
168	4	_BEtemp360
16C	4	_BEtemp364
170	4	_BEtemp368
174	4	_BEtemp372
178	4	_BEtemp376

(1)

Hexadecimal offset of the DSA field from the start of the DSA

(2)

Length (in hexadecimal) of the DSA field

(3)

Symbol name

## Example: XREF output: data-name cross-references

The following example shows a sorted cross-reference of data-names that is produced by the XREF compiler option. Numbers in parentheses refer to notes after the example.

An "M" preceding a data-name reference indicates that the data-name is modified by this reference.

(1) Defined	(2) Cross-reference of data-names	(3) References
265	ABEND-ITEM1	
266	ABEND-ITEM2	
347	ADD-CODE . . . . .	1102 1162
381	ADDRESS-ERROR. . . . .	M1126
280	AREA-CODE. . . . .	1236 1261 1324 1345
382	CITY-ERROR . . . . .	M1129

(4)

Context usage is indicated by the letter preceding a procedure-name reference. These letters and their meanings are:

A = ALTER (procedure-name)  
D = GO TO (procedure-name) DEPENDING ON  
E = End of range of (PERFORM) through (procedure-name)  
G = GO TO (procedure-name)  
P = PERFORM (procedure-name)  
T = (ALTER) TO PROCEED TO (procedure-name)  
U = USE FOR DEBUGGING (procedure-name)

(5) Defined	(6) Cross-reference of procedures	(7) References
877	000-DO-MAIN-LOGIC	
930	050-CREATE-STL-MASTER-FILE . .	P879
982	100-INITIALIZE-PARAGRAPH . . .	P880
1441	1100-PRINT-I-F-HEADINGS. . . .	P915

```

1481 1200-PRINT-I-F-DATA. . . . . P916
1543 1210-GET-MILES-TIME. . . . . P1510
1636 1220-STORE-MILES-TIME. . . . . P1511
1652 1230-PRINT-SUB-I-F-DATA. . . . P1532
1676 1240-COMPUTE-SUMMARY . . . . . P1533
1050 200-EDIT-UPDATE-TRANSACTION. . P886
1124 210-EDIT-THE-REST. . . . . P1116
1159 300-UPDATE-COMMUTER-RECORD . . P888
1207 310-FORMAT-COMMUTER-RECORD . . P1164 P1179
1258 320-PRINT-COMMUTER-RECORD. . . P1165 P1176 P1182 P1192
1288 330-PRINT-REPORT . . . . . P1178 P1202 P1256 P1280 P1340 P1365 P1369
1312 400-PRINT-TRANSACTION-ERRORS . P890

```

Cross-reference of data-names:

(1)

Line number where the name was defined.

(2)

Data-name.

(3)

Line numbers where the name was used. If M precedes the line number, the data item was explicitly modified at the location.

Cross-reference of procedure references:

(4)

Explanations of the context usage codes for procedure references.

(5)

Line number where the procedure-name is defined.

(6)

Procedure-name.

(7)

Line numbers where the procedure is referenced, and the context usage code for the procedure.

[“Example: XREF output: program-name cross-references” on page 399](#)

[“Example: XREF output: COPY/BASIS cross-references” on page 400](#)

[“Example: XREF output: embedded cross-reference” on page 401](#)

## Example: XREF output: program-name cross-references

The following example shows a sorted cross-reference of program-names produced by the XREF compiler option. Numbers in parentheses refer to notes that follow the example.

(1) Defined	(2) Cross-reference of programs	(3) References
EXTERNAL	EXTERNAL1. . . . .	25
2	X. . . . .	41
12	X1. . . . .	33 7
20	X11. . . . .	25 16
27	X12. . . . .	32 17
35	X2. . . . .	40 8

(1)

Line number where the program-name was defined. If the program is external, the word EXTERNAL is displayed instead of a definition line number.

(2)

Program-name.

(3)

Line numbers where the program is referenced.

## Example: XREF output: COPY/BASIS cross-references

The following example shows a sorted cross-reference of copybooks to the library-names and data-set names of the associated copybooks, produced by the XREF compiler option under z/OS. Numbers in parentheses refer to notes after the example.

COPY/BASIS cross-reference of text-names, library names				
(1) Text-name (Member)	(1) Library (DDNAME)	(2) File name (Data set name)	(3) Concat Level	(4) ISPF Created
ACTIONS	OTHERLIB	USERID.COBOL.COPY	0	1992/07/11
ACTIONS	SYSLIB	USERID.COBOL.COPY	0	1992/07/11
CUSTOMER	ALTDDXXY	USERID.COBOL.LIB3	0	2007/06/01
CUSTOMER	SYSLIB	USERID.COBOL.LIB2PDSE	1	2007/06/07
HOUSE	ALTDDXXY	USERID.COBOL.LIB2	1	2007/06/07
HOUSE	SYSLIB	USERID.COBOL.LIB2PDSE	1	
IMOTOR	SYSLIB	USERID.COBOL.LIB4X	3	2007/06/07
ISOVERFY	SYSLIB	USERID.COBOL.COPY	0	
NSMAP	SYSLIB	USERID.COBOL.LIB3	2	

(1)

Text-name and library (an abbreviation for library-name) are from the statement COPY *text-name* OF *library-name* in the source, for example, Copy ACTIONS OF OTHERLIB.

(2)

The name of the data set from which the COPY member was copied.

(3)

Abbreviation for concatenation level. Indicates how many levels deep a given data set is from the first data set in the concatenation for a given ddname.

For example, four data sets in the example above are concatenated to ddname SYSLIB:

DDNAME	DSNAME	(concatenation level)
SYSLIB DD	DSN=USERID.COBOL.COPY,	0
DD	DSN=USERID.COBOL.LIB2PDSE,	1
DD	DSN=USERID.COBOL.LIB3,	2
DD	DSN=USERID.COBOL.LIB4X	3

Thus for example member NSMAP shown in the listing above was found in data set USERID.COBOL.LIB3, which is two levels down from the first data set in the SYSLIB concatenation.

(4)

Creation date is shown if the PDSE was edited with STATS ON in ISPF.

**Tip:** Under z/OS, if there is more than one data set in your SYSLIB concatenation, the COPY/BASIS cross-reference might in some cases be incomplete or missing. For details, see the related reference about the XREF compiler option.

If you compile in the z/OS UNIX shell, the cross-reference looks like the excerpt shown below.

COPY/BASIS cross-reference of text-names, library names, and file names		
(5) Text-name	(5) Library-name	(6) File name
'/copydir/copyM.cbl'	SYSLIB	/u/JSMITH/cobol//copydir/copyM.cbl
'/copyA.cpy'	SYSLIB	/u/JSMITH/cobol//copyA.cpy
'cobol/copyA.cpy'	ALTDD2	/u/JSMITH/cobol/copyA.cpy
'copy/stuff.cpy'	ALTDD2	/u/JSMITH/copy/stuff.cpy

```
'copydir/copyM.cbl'      SYSLIB          /u/JSMITH/cobol/copydir/copyM.cbl
'copydir/copyM.cbl'      SYSLIB (default) /u/JSMITH/cobol/copydir/copyM.cbl
'stuff.cpy'              ALTDD           /u/JSMITH/copy/stuff.cpy
"copyA.cpy"              (7) SYSLIB (default) /u/JSMITH/cobol/copyA.cpy
"reallyXXVeryLongLon>   SYSLIB (default) (8)<JSMITH/cobol/
reallyXXVeryLongLongName.cpy
OTHERDD                  ALTDD2          /u/JSMITH//copy/other.cob
. . .
```

Note: Some names were truncated. > = truncated on right < = truncated on left

(5)

From the COPY statement in the source; for example the COPY statement corresponding to the third item in the cross-reference above would be:

```
COPY 'cobol/copyA.cpy' OF ALTDD2
```

(6)

The fully qualified path of the file from which the COPY member was copied

(7)

Truncation of a long text-name or library-name on the right is marked by a greater-than sign (>).

(8)

Truncation of a long file name on the left is marked by a less-than sign (<).

## related references

[“XREF” on page 350](#)

## Example: XREF output: embedded cross-reference

The following example shows a modified cross-reference that is embedded in the source listing. The cross-reference is produced by the XREF compiler option.

```
LineID  PL SL  -----*A-1-B-----2-----3-----4-----5-----6-----7-|-----8  Map and Cross Reference
000878      procedure division.
000879      000-do-main-logic.
000880          display "PROGRAM IGYTCARA - Beginning".
000881          perform 050-create-vsam-master-file.                932 (1)
000882          perform 100-initialize-paragraph.                    984
000883          read update-transaction-file into ws-transaction-record
000884              at end                                           204 340
000885      1          set transaction-eof to true                    254
000886          end-read.
000984      100-initialize-paragraph.
000985          move spaces to ws-transaction-record                IMP 340 (2)
000986          move spaces to ws-commuter-record                   IMP 316
000987          move zeroes to commuter-zipcode                     IMP 327
000988          move zeroes to commuter-home-phone                  IMP 328
000989          move zeroes to commuter-work-phone                  IMP 329
000990          move zeroes to commuter-update-date                 IMP 333
000991          open input update-transaction-file                 204
000992              location-file                                  193
000993              i-o commuter-file                              181
000994              output print-file                              217
001442      1100-print-i-f-headings.
001443
001444          open output print-file.                               217
001445
001446          move function when-compiled to when-comp.            IFN 698 (2)
001447          move when-comp (5:2) to compile-month.              698 640
001448          move when-comp (7:2) to compile-day.                  698 642
001449          move when-comp (3:2) to compile-year.                 698 644
001450
001451          move function current-date (5:2) to current-month.    IFN 649
001452          move function current-date (7:2) to current-day.      IFN 651
001453          move function current-date (3:2) to current-year.     IFN 653
001454
001455          write print-record from i-f-header-line-1            222 635
001456              after new-page.                                   138
. . .
```

(1)

Line number of the definition of the data-name or procedure-name in the program

(2)

Special definition symbols:

**UND**

The user name is undefined.

**DUP**

The user name is defined more than once.

**IMP**

Implicitly defined name, such as special registers and figurative constants.

**IFN**

Intrinsic function reference.

**EXT**

External reference.

**\***

The program-name is unresolved because the NOCOMPILE option is in effect.

## Example: OFFSET compiler output

The following example shows a compiler listing that has a condensed statement listing, global tables, WORKING-STORAGE information, and literals. The listing is output from the OFFSET compiler option.

DATA VALIDATION AND UPDATE PROGRAM IGYTCARA Date 03/18/2016 Time 10:48:16

(1)	(2)	(3)									
LINE #	HEXLOC	VERB	LINE #	HEXLOC	VERB	LINE #	HEXLOC	VERB	LINE #	HEXLOC	VERB
000880	0026F0	DISPLAY	000881	002702	PERFORM	000933	002702	OPEN			
000934	002722	IF	000935	00272C	DISPLAY	000936	002736	PERFORM			
001389	002736	DISPLAY	001390	002740	DISPLAY	001391	00274A	DISPLAY			
001392	002754	DISPLAY	001393	00275E	DISPLAY	001394	002768	DISPLAY			
001395	002772	DISPLAY	000937	00277C	PERFORM	001434	00277C	DISPLAY			
001435	002786	STOP	000939	0027A2	MOVE	000940	0027AC	WRITE			
000941	0027D6	IF	000942	0027E0	DISPLAY	000943	0027EA	PERFORM			
001389	0027EA	DISPLAY	001390	0027F4	DISPLAY	001391	0027FE	DISPLAY			
001392	002808	DISPLAY	001393	002812	DISPLAY	001394	00281C	DISPLAY			
001395	002826	DISPLAY	000944	002830	DISPLAY	000945	00283A	PERFORM			
001403	00283A	DISPLAY	001404	002844	DISPLAY	001405	00284E	DISPLAY			
001406	002858	DISPLAY	001407	002862	CALL	000947	002888	CLOSE			

(1)

Line number. Your line numbers or compiler-generated line numbers are listed.

(2)

Offset, from the start of the program, of the code generated for this statement (in hexadecimal notation).

The statements are listed in the order in which they occur and are listed once for each time they are used.

(3)

Statement used.

**Notes:**

- The optimizer might inline paragraphs, move code around or indeed place it after the body of the program if little used, such as the error message formatting code. This might make the OFFSET report less useful than it was with previous compilers. You can refer to the LIST output instead (note that OFFSET and LIST are mutually exclusive options). For details, see [“Reading LIST output” on page 381](#).
- Due to the out of line code used for error message formatting, Language Environment generated offsets, as indicated in "From compile unit {name} at entry point {name} at compile unit offset {offset} . . .", might be outside the offset range of the program. In these cases, refer to the statement number in the COBOL message (IGZnnnns) to locate the problem.

## related references

[“OFFSET” on page 324](#)

## Example: VBREF compiler output

The following example shows an alphabetic listing of all the statements in a program, and shows where each is referenced. The listing is produced by the VBREF compiler option.

(1)	(2)	(3)
2	ACCEPT . . . . .	1010 1012
2	ADD . . . . .	1290 1306
1	CALL . . . . .	1406
5	CLOSE . . . . .	898 945 970 1526 1535
20	COMPUTE . . . . .	1506 1640 1644 1657 1660 1663 1664 1665 1678 1682 1686 1691 1696 1701 1709 1713
		1718 1723 1728 1733
2	CONTINUE . . . . .	1062 1069
2	DELETE . . . . .	964 1193
48	DISPLAY . . . . .	878 906 917 918 919 933 940 942 947 953 960 966 972 996 997 998 999 1003 1006 1037
		1090 1168 1171 1185 1195 1387 1388 1389 1390 1391 1392 1393 1401 1402 1403 1404
		1405 1433 1485 1486 1492 1497 1498 1520 1521 1528 1529 1624
2	EVALUATE . . . . .	1161 1557
47	IF . . . . .	887 905 932 939 946 952 959 965 971 993 1002 1036 1051 1054 1071 1074 1077 1089
		1102 1111 1115 1125 1128 1131 1134 1137 1141 1145 1148 1151 1167 1184 1194 1240
		1247 1265 1272 1289 1321 1330 1339 1351 1361 1484 1496 1519 1527
183	MOVE . . . . .	907 937 957 983 984 985 986 987 988 1004 1011 1013 1025 1038 1052 1055 1060 1067
		1072 1075 1078 1079 1080 1081 1082 1083 1091 1103 1112 1126 1129 1132 1135 1139
		1143 1146 1149 1152 1160 1163 1169 1175 1177 1180 1181 1186 1191 1196 1201 1208
		1209 1210 1211 1212 1213 1214 1215 1216 1217 1218 1219 1220 1221 1222 1229 1230
		1231 1232 1233 1234 1235 1239 1241 1244 1248 1250 1251 1253 1254 1255 1257 1258
		1259 1260 1264 1266 1269 1273 1275 1276 1278 1279 1291 1294 1299 1301 1303 1307
		1313 1314 1315 1316 1317 1318 1319 1320 1322 1323 1327 1328 1331 1333 1334 1336
		1338 1341 1342 1343 1344 1348 1349 1352 1354 1355 1357 1362 1364 1368 1374 1375
		1376 1377 1378 1379 1380 1381 1414 1417 1422 1425 1445 1446 1447 1448 1450 1451
		1452 1457 1464 1489 1502 1507 1508 1509 1517 1551 1561 1566 1571 1576 1581 1586
		1591 1596 1601 1606 1611 1616 1621 1626 1627 1679 1683 1688 1693 1698 1703 1710
		1715 1720 1725 1730 1735
5	OPEN . . . . .	931 951 989 1443 1483
62	PERFORM . . . . .	879 880 885 886 888 890 892 908 909 915 916 934 935 941 943 948 949 954 955 961
		962 967 968 973 974 1000 1005 1008 1023 1039 1092 1093 1116 1164 1165 1170 1172
		1176 1178 1179 1182 1187 1188 1192 1197 1198 1202 1246 1256 1271 1280 1329 1340
		1350 1359 1365 1369 1504 1510 1511 1532 1533
8	READ . . . . .	881 893 958 1014 1026 1085 1490 1514
1	REWRITE . . . . .	1183
4	SEARCH . . . . .	1058 1065 1413 1421
46	SET . . . . .	883 895 1016 1028 1041 1057 1064 1084 1087 1363 1412 1420 1493 1499 1516 1522 1548
		1550 1559 1560 1564 1565 1569 1570 1574 1575 1579 1580 1584 1585 1589 1590 1594
		1595 1599 1600 1604 1605 1609 1610 1614 1615 1619 1620 1639 1643
2	STOP . . . . .	920 1434
4	STRING . . . . .	1236 1261 1324 1345
33	WRITE . . . . .	938 1166 1292 1293 1295 1296 1297 1298 1300 1302 1305 1454 1459 1462 1465 1467 1469
		1471 1512 1654 1655 1667 1668 1669 1740 1742 1744 1745 1746 1747 1748 1749 1750

- (1) Number of times the statement is used in the program
- (2) statement
- (3) Line numbers where the statement is used



---

## Part 3. Targeting COBOL programs for certain environments



---

## Chapter 20. Developing COBOL programs for CICS

COBOL programs that are written for CICS can run under CICS Transaction Server. CICS COBOL application programs that use CICS services must use the CICS command-level interface.

When you use the CICS compiler option, the Enterprise COBOL compiler handles both native COBOL statements and embedded CICS statements in the source program. You can still use the separate CICS translator to translate CICS statements to COBOL code, but use of the integrated CICS translator is recommended instead.

After you compile and bind your program, you need to do some other steps such as updating CICS tables before you can run the COBOL program under CICS. However, these CICS topics are beyond the scope of COBOL information. For further information, see the related tasks.

You can determine how runtime errors are handled by setting the CBLPSHPOP runtime option. For information about CICS HANDLE and CBLPSHPOP, see the related tasks.

### related concepts

[“Integrated CICS translator” on page 412](#)

### related tasks

[“Coding COBOL programs to run under CICS” on page 407](#)

[“Compiling with the CICS option” on page 411](#)

[“Using the separate CICS translator” on page 413](#)

[“Handling errors by using CICS HANDLE” on page 415](#)

*Language Environment Programming Guide* (Condition handling under CICS:  
using the CBLPSHPOP runtime option)

[Developing CICS Applications](#)

### related references

[“CICS” on page 294](#)

---

## Coding COBOL programs to run under CICS

To code a program to run under CICS, code CICS commands in the PROCEDURE DIVISION by using the EXEC CICS command format.

```
EXEC CICS command-name command-options  
END-EXEC
```

CICS commands have the basic format shown above. Within EXEC commands, use the space as a word separator; do not use a comma or a semicolon. Do not code COBOL statements within EXEC CICS commands.

**Restriction:** You cannot run COBOL programs that have object-oriented syntax for Java interoperability in CICS. In addition, if you write programs to run under CICS, do not use the following code:

- FILE-CONTROL entry in the ENVIRONMENT DIVISION, unless the FILE-CONTROL entry is used for a SORT statement
- FILE SECTION of the DATA DIVISION, unless the FILE SECTION is used for a SORT statement
- User-specified parameters to the main program
- USE declaratives (except USE FOR DEBUGGING)
- These COBOL language statements:
  - ACCEPT format 1: data transfer (you can use format-2 ACCEPT to retrieve the system date and time)
  - CLOSE

- DELETE
- DISPLAY UPON CONSOLE
- DISPLAY UPON SYSPUNCH
- MERGE
- OPEN
- READ
- RERUN
- REWRITE
- START
- STOP *literal*
- WRITE

If you plan to use the separate CICS translator, you must put any REPLACE statements that contain EXEC commands after the PROCEDURE DIVISION header for the program, otherwise the commands will not be translated.

**Coding file input and output:** You must use CICS commands for most input and output processing. Therefore, do not describe files or code any OPEN, CLOSE, READ, START, REWRITE, WRITE, or DELETE statements. Instead, use CICS commands to retrieve, update, insert, and delete data.

**Coding a COBOL program to run above the 16 MB line:** Under Enterprise COBOL, the following restrictions apply when you code a COBOL program to run above the 16 MB line:

- If you use IMS/ESA® without DBCTL, DL/I CALL statements are supported only if all the data passed in the call resides below the 16 MB line. Therefore, you must specify the DATA(24) compiler option. However, if you use IMS/ESA with DBCTL, you can use the DATA(31) compiler option instead and pass data that resides above the 16 MB line.

If you use EXEC DLI instead of DL/I CALL statements, you can specify DATA(31) regardless of the level of the IMS product.

- If the receiving program is link-edited with AMODE 31, addresses that are passed must be 31 bits long, or 24 bits long with the leftmost byte set to zeros.
- If the receiving program is link-edited with AMODE 24, addresses that are passed must be 24 bits long.

**Displaying the contents of data items:** DISPLAY to the system logical output device (SYSOUT, SYSLIST, SYSLST) is supported under CICS. The DISPLAY output is written to the Language Environment message file (transient data queue CESE). DISPLAY . . . UPON CONSOLE and DISPLAY . . . UPON SYSPUNCH, however, are not allowed. You can specify the DISPSIGN option to control output formatting for DISPLAY of signed numeric items.

#### **related concepts**

[“Integrated CICS translator” on page 412](#)

#### **related tasks**

[“Sorting under CICS” on page 221](#)

[“Getting the system date under CICS” on page 409](#)

[“Calling to or from COBOL programs” on page 409](#)

[“Determining the success of ECI calls” on page 410](#)

[“Using the separate CICS translator” on page 413](#)

#### **related references**

[“CICS SORT application restrictions” on page 222](#)

[“DISPSIGN” on page 302](#)

## Getting the system date under CICS

To retrieve the system date in a CICS program, use a format-2 ACCEPT statement or the CURRENT-DATE intrinsic function.

You can use any of these format-2 ACCEPT statements in CICS to get the system date:

- ACCEPT *identifier-2* FROM DATE (two-digit year)
- ACCEPT *identifier-2* FROM DATE YYYYMMDD
- ACCEPT *identifier-2* FROM DAY (two-digit year)
- ACCEPT *identifier-2* FROM DAY YYYYDDD
- ACCEPT *identifier-2* FROM DAY-OF-WEEK (one-digit integer, where 1 represents Monday)

You can use this format-2 ACCEPT statement in CICS to get the system time:

- ACCEPT *identifier-2* FROM TIME

Alternatively, you can use the CURRENT-DATE intrinsic function, which can also provide the time.

These methods work in both CICS and non-CICS environments.

Do not use a format-1 ACCEPT statement in a CICS program.

### related tasks

[“Assigning input from a screen or file \(ACCEPT\)” on page 33](#)

### related references

CURRENT-DATE (*Enterprise COBOL for z/OS Language Reference*)

## Calling to or from COBOL programs

You can make calls to or from VS COBOL II, COBOL for MVS & VM, COBOL for OS/390 & VM, and Enterprise COBOL programs by using the CALL statement.

If you are calling a separately compiled COBOL program that was processed with either the separate CICS translator or the integrated CICS translator, you must pass DFHEIBLK and DFHCOMMAREA as the first two parameters in the CALL statement.

Called programs that are processed by the separate CICS translator or the integrated CICS translator can contain any function that is supported by CICS for the language.

### Dynamic calls:

You can use COBOL dynamic calls when running under CICS. If a COBOL program contains EXEC CICS statements or contains EXEC SQL statements, the NODYNAM compiler option is required. To dynamically call a program in this case, you can use CALL *identifier* with the NODYNAM compiler option.

If a COBOL program contains no EXEC CICS statements and contains no EXEC SQL statements, there is no requirement to compile with NODYNAM. To dynamically call a program in this case, you can use either CALL *literal* with the DYNAM compiler option, or CALL *identifier*.

**Note:** END-EXEC cannot be followed by a period when it is associated with EXEC CICS statements even though it is required for EXEC SQL statements.

You must define dynamically called programs in the CICS program processing table (PPT) if you are not using CICS autoinstall. Under CICS, COBOL programs do not support dynamic calls to subprograms that have the RELOAD=YES option coded in their CICS PROGRAM definition. Dynamic calls to programs that are defined with RELOAD=YES can cause a storage shortage. Use the RELOAD=NO option for programs that are to be dynamically called by COBOL.

### Interlanguage communication (ILC):

Support for ILC with other high-level languages is available. Where ILC is not supported, you can use CICS LINK, XCTL, and RETURN instead.

The following table shows the calling relationship between COBOL and assembler programs. In the table, assembler programs that conform to the interface that is described in the *Language Environment Programming Guide* are called *Language Environment-conforming* assembler programs. Those that do not conform to the interface are *non-Language Environment-conforming* assembler programs.

<b>Table 56. Calls between COBOL and assembler under CICS</b>		
<b>Calls between COBOL and assembler programs</b>	<b>Language Environment-conforming assembler program</b>	<b>Non-Language Environment-conforming assembler program</b>
From an Enterprise COBOL program to the assembler program?	Yes	Yes
From the assembler program to an Enterprise COBOL program?	Yes	No

### **Nested programs:**

When you compile with the integrated CICS translator, the translator generates the DFHEIBLK and DFHCOMMAREA control blocks with the GLOBAL clause in the outermost program. Therefore if you code nested programs, you do not have to pass these control blocks as arguments on calls to the nested programs.

If you code nested programs and you plan to use the separate CICS translator, pass DFHEIBLK and DFHCOMMAREA as parameters to the nested programs that contain EXEC commands or references to the EXEC interface block (EIB). You must pass the same parameters also to any program that forms part of the control hierarchy between such a program and its top-level program.

### **related concepts**

[“Integrated CICS translator” on page 412](#)

### **related tasks**

[“Using the separate CICS translator” on page 413](#)

[“Choosing the DYNAM or NODYNAM compiler option” on page 426](#)

[“Handling errors when calling programs” on page 233](#)

*Language Environment Writing ILC Communication Applications (ILC under CICS)*

*Using EXCI with CICS*

*Language Environment Programming Guide*

### **related references**

[“DYNAM” on page 305](#)

## **Determining the success of ECI calls**

After calls to the external CICS interface (ECI), the content of the RETURN-CODE special register is set to an unpredictable value. Therefore, even if your COBOL program terminates normally after successfully using the external CICS interface, the job step could end with an undefined return code.

To ensure that a meaningful return code occurs at termination, set the RETURN-CODE special register before you terminate your program. To make the job return code reflect the status of the last call to CICS, set the RETURN-CODE special register based on the response codes from the last call to the external CICS interface.

### **related tasks**

[Using EXCI with CICS](#)

## Compiling with the CICS option

Use the CICS compiler option to enable the integrated CICS translator and to specify CICS suboptions.

If you specify the NOCICS option, the compiler diagnoses and discards any CICS statements that it finds in your source program. If you have already used the separate CICS translator, you must use NOCICS.

You can specify the CICS option in any of the compiler option sources: compiler invocation, PROCESS or CBL statements, or installation default. If the CICS option is the COBOL installation default, you cannot specify CICS suboptions. However, making the CICS option the installation default is not recommended, because the changes that are made by the integrated CICS translator are not appropriate for non-CICS applications.

All CBL or PROCESS statements must precede any comment lines, in accordance with the rules for Enterprise COBOL.

The COBOL compiler passes to the integrated CICS translator the CICS suboption string that you provide in the CICS compiler option. The compiler does not analyze the suboption string.

When you use the integrated CICS translator, you must compile with the following options:

<i>Table 57. Compiler options required for the integrated CICS translator</i>	
Compiler option	Comment
AFP	If your code runs on a version of CICS Transaction Server that is earlier than V4.1, you must specify AFP (VOLATILE).
CICS	If you specify DYNAM or NORENT, the compiler forces NODYNAM and RENT on.
NODYNAM	Must be in effect with CICS
RENT	Must be in effect with CICS

In addition, IBM recommends that you use the compiler option WORD(CICS) to cause the compiler to flag language elements that are not supported under CICS.

To compile your program with the integrated CICS translator, you can use the standard JCL procedural statements that are supplied with COBOL. In addition to specifying the above compiler options, you must change your JCL in two ways:

- Specify the STEPLIB override for the COBOL step.
- Add the data set that contains the integrated CICS translator services, unless these services are in the linklist.

The default name of the data set for CICS Transaction Server V6R1 is CICSTS61.CICS.SDFHLOAD, but your installation might have changed the name. For example, you might have the following line in your JCL:

```
//STEPLIB DD DSN=CICSTS61.CICS.SDFHLOAD,DISP=SHR
```

The COBOL compiler listing includes the error diagnostics (such as syntax errors in the CICS statements) that the integrated CICS translator generates. The listing reflects the input source; it does not include the COBOL statements that the integrated CICS translator generates.

**Compiling a sequence of programs:** When you use the CICS option to compile a source file that contains a sequence of COBOL programs, the order of precedence of the options from highest to lowest is:

- Options that are specified in the CBL or PROCESS card that initiates the unit of compilation
- Options that are specified when the compiler is started
- CICS default options

**related concepts**

[“Integrated CICS translator” on page 412](#)

**related tasks**

[“Coding COBOL programs to run under CICS” on page 407](#)

[“Separating CICS suboptions” on page 412](#)

[Developing CICS Applications](#)

**related references**

[“CICS” on page 294](#)

[“Conflicting compiler options” on page 287](#)

## Separating CICS suboptions

You can partition the specification of CICS suboptions into multiple CBL statements. CICS suboptions are cumulative. The compiler concatenates them from multiple sources in the order that they are specified.

For example, suppose that a JCL file has the following code:

```
//STEP1 EXEC IGYWC, . . .  
//PARM.COBOL="CICS("FLAG(I)")"  
//COBOL.SYSIN DD *  
CBL CICS("DEBUG")  
CBL CICS("LINKAGE")  
IDENTIFICATION DIVISION.  
PROGRAM-ID. COBOL1.
```

During compilation, the compiler passes the following CICS suboption string to the integrated CICS translator:

```
"FLAG(I) DEBUG LINKAGE"
```

The concatenated strings are delimited with single spaces and with a pair of quotation marks (" ") or a pair of apostrophes (') around the group. When the compiler finds multiple instances of the same CICS suboption, the last specification of the suboption in the concatenated string takes effect. The compiler limits the length of the concatenated CICS suboption string to 4 KB.

**related references**

[“CICS” on page 294](#)

## Integrated CICS translator

When you compile a COBOL program using the CICS compiler option, the COBOL compiler works with the integrated CICS translator to handle both native COBOL and embedded CICS statements in the source program.

When the compiler encounters CICS statements, and at other significant points in the source program, the compiler interfaces with the integrated CICS translator. All text between EXEC CICS and END-EXEC statements is passed to the translator. The translator takes appropriate actions and then returns to the compiler, typically indicating which native language statements to generate.

Although you can still translate embedded CICS statements separately, it is recommended that you use the integrated CICS translator instead. Certain restrictions that apply when you use the separate translator do not apply when you use the integrated translator, and using the integrated translator provides several advantages:

- You can use Debug Tool to debug the original source instead of the expanded source that the separate CICS translator generates.
- You do not need to separately translate the EXEC CICS or EXEC DLI statements that are in copybooks.
- There is no intermediate data set for a translated but not compiled version of the source program.
- Only one output listing instead of two is produced.

- Using nested programs that contain EXEC CICS statements is simpler. DFHCOMMAREA and DFHEIBLK are generated with the GLOBAL attribute in the outermost program. You do not need to pass them as arguments on calls to nested programs or specify them in the USING phrase of the PROCEDURE DIVISION header of nested programs.
- You can keep nested programs that contain EXEC CICS statements in separate files, and include those nested programs by using COPY statements.
- REPLACE statements can affect EXEC CICS statements.
- You can compile programs that contain CICS statements in a batch compilation (compilation of a sequence of programs).
- Because the compiler generates binary fields in CICS control blocks with format COMP-5 instead of BINARY, there is no dependency on the setting of the TRUNC compiler option. You can use any setting of the TRUNC option in CICS programs, subject only to the requirements of the application logic and use of user-defined binary fields.

**Note:** The CICS documentation states that the EXCI translator option is not supported for programs compiled with the integrated CICS translator, but CICS has reversed this position. You can now compile with the EXCI translator option and ignore the warning message DFH7006I.

#### related concepts

[Developing CICS Applications](#) (The integrated CICS translator)

#### related tasks

[“Coding COBOL programs to run under CICS” on page 407](#)

[“Compiling with the CICS option” on page 411](#)

#### related references

[“CICS” on page 294](#)

[“TRUNC” on page 344](#)

## Using the separate CICS translator

To run a COBOL program under CICS, you can use the separate CICS translator to convert the CICS commands to COBOL statements, and then compile and link the program to create the executable module. However, using the CICS translator that is integrated with Enterprise COBOL is recommended. The separate CICS translator has not been updated for newer COBOL language such as floating comment delimiters, JSON GENERATE, and compiler directives. To use the latest features of the COBOL compiler, use the integrated CICS translator.

To translate CICS statements separately, use the COBOL3 translator option. This option causes the following line to be inserted:

```
CBL RENT,NODYNAM,
```

You can suppress the insertion of a CBL statement by using the CICS translator option NOCBLCARD.

After you use the separate CICS translator, use the following compiler options when you compile the program:

Table 58. <i>Compiler options required for the separate CICS translator</i>	
Required compiler option	Condition
RENT	
NODYNAM	The program is translated by the CICS translator.

In addition, IBM recommends that you use the compiler option WORD(CICS) to cause the compiler to flag language elements that are not supported under CICS.

The following TRUNC compiler option recommendations are based on expected values for binary data items:

<i>Table 59. TRUNC compiler options recommended for the separate CICS translator</i>	
<b>Recommended compiler option</b>	<b>Condition</b>
TRUNC (OPT)	All binary data items conform to the PICTURE and USAGE clause for those data items.
TRUNC (BIN)	Not all binary data items conform to the PICTURE and USAGE clause for those data items.

For example, if you use the separate CICS translator and have a data item defined as PIC S9(8) BINARY that might receive a value greater than eight digits, use the TRUNC (BIN) compiler option, change the item to USAGE COMP-5, or change the PICTURE clause.

You might also want to avoid using these options, which have no effect:

- ADV
- FASTSRT
- OUTDD

The input data set for the compiler is the data set that you received as a result of translation, which is SYSPUNCH by default.

#### **related concepts**

[“Integrated CICS translator” on page 412](#)

#### **related tasks**

[“Compiling with the CICS option” on page 411](#)

## **CICS reserved-word table**

COBOL provides an alternate reserved-word table (IGYCCICS) for CICS application programs. If you use the compiler option WORD (CICS), COBOL words that are not supported under CICS are flagged with an error message.

In addition to the COBOL words restricted by the IBM-supplied default reserved-word table, the IBM-supplied CICS reserved-word table restricts the following COBOL words:

- CLOSE
- DELETE
- FD
- **FILE**
- **FILE-CONTROL**
- **INPUT-OUTPUT**
- I-O-CONTROL
- MERGE
- OPEN
- READ
- RERUN
- REWRITE
- **SD**
- **SORT**

- START
- WRITE

If you intend to use the SORT statement under CICS (COBOL supports an interface for the SORT statement under CICS), you must change the CICS reserved-word table to remove the words in **bold** above from the list of words marked as restricted.

#### **related tasks**

[“Compiling with the CICS option” on page 411](#)

[“Sorting under CICS” on page 221](#)

#### **related references**

[“WORD” on page 349](#)

## Handling errors by using CICS HANDLE

---

The setting of the CBLPSHPOP runtime option affects the state of the HANDLE specifications when a program calls COBOL subprograms using a CALL statement.

When CBLPSHPOP is ON and a COBOL subprogram (not a nested program) is called with a CALL statement, the following actions occur:

1. As part of program initialization, the run time suspends the HANDLE specifications of the calling program (using EXEC CICS PUSH HANDLE).
2. The default actions for HANDLE apply until the called program issues its own HANDLE commands.
3. As part of program termination, the run time reinstates the HANDLE specifications of the calling program (using EXEC CICS POP HANDLE).

If you use the CICS HANDLE CONDITION or CICS HANDLE AID commands, the LABEL specified for the CICS HANDLE command must be in the same PROCEDURE DIVISION as the CICS command that causes branching to the CICS HANDLE label. You cannot use the CICS HANDLE commands with the LABEL option to handle conditions, aids, or abends that were caused by another program invoked with the COBOL CALL statement. Attempts to perform cross-program branching by using the CICS HANDLE command with the LABEL option result in a transaction abend.

If a condition, aid, or abend occurs in a nested program, the LABEL for the condition, aid, or abend must be in the same nested program; otherwise unpredictable results occur.

**Performance considerations:** When CBLPSHPOP is OFF, the run time does not perform CICS PUSH or POP on a CALL to any COBOL subprogram. If the subprograms do not use any of the EXEC CICS condition-handling commands, you can run with CBLPSHPOP (OFF), thus eliminating the overhead of the PUSH HANDLE and POP HANDLE commands. As a result, performance can be improved compared to running with CBLPSHPOP (ON).

If you are migrating an application from the VS COBOL II run time to the Language Environment run time, see the related reference for information about the CBLPSHPOP option for additional considerations.

[“Example: handling errors by using CICS HANDLE” on page 415](#)

#### **related tasks**

[“Running efficiently with CICS, IMS, or VSAM” on page 644](#)

#### **related references**

*Enterprise COBOL Migration Guide*

*Enterprise COBOL Version 6 Release 1 Performance Tuning Guide*

## Example: handling errors by using CICS HANDLE

The following example shows the use of CICS HANDLE in COBOL programs.

Program A has a CICS HANDLE CONDITION command and program B has no CICS HANDLE commands. Program A calls program B; program A also calls nested program A1. A condition is handled in one of three scenarios.

(1)

CBLPSHPOP(ON): If the CICS READ command in program B causes a condition, the condition is not handled by program A (the HANDLE specifications are suspended because the run time performs a CICS PUSH HANDLE). The condition turns into a transaction abend.

(2)

CBLPSHPOP(OFF): If the CICS READ command in program B causes a condition, the condition is not handled by program A (the run time diagnoses the attempt to perform cross-program branching by using a CICS HANDLE command with the LABEL option). The condition turns into a transaction abend.

(3)

If the CICS READ command in nested program A1 causes a condition, the flow of control goes to label ERR-1, and unpredictable results occur.

```
*****
*   Program A                               *
*****
ID DIVISION.
PROGRAM-ID. A.

PROCEDURE DIVISION.
    EXEC CICS HANDLE CONDITION
        ERROR(ERR-1)
    END-EXEC.
    CALL 'B' USING DFHEIBLK DFHCOMMAREA.
    CALL 'A1'.

THE-END.
EXEC CICS RETURN END-EXEC.
ERR-1.

*   Nested program A1.
ID DIVISION.
PROGRAM-ID. A1.
PROCEDURE DIVISION.
    EXEC CICS READ                               (3)
        FILE('LEDGER')
        INTO(RECORD)
        RIDFLD(ACCTNO)
    END-EXEC.
END PROGRAM A1.
END PROGRAM A.

*
*****
*   Program B                               *
*****
ID DIVISION.
PROGRAM-ID. B.

PROCEDURE DIVISION.
    EXEC CICS READ                               (1) (2)
        FILE('MASTER')
        INTO(RECORD)
        RIDFLD(ACCTNO)
    END-EXEC.
END PROGRAM B.
```

---

## Chapter 21. Programming for a DB2 environment

In general, the coding for a COBOL program will be the same if you want the program to access a DB2 database. However, to retrieve, update, insert, and delete DB2 data and use other DB2 services, you must use SQL statements.

To communicate with DB2, do these steps:

- Code any SQL statements that you need, delimiting them with EXEC SQL and END-EXEC statements.
- Either use the DB2 stand-alone precompiler, or compile with the SQL compiler option and use the DB2 coprocessor.

### related concepts

[“DB2 coprocessor” on page 417](#)

[“COBOL and DB2 CCSID determination” on page 422](#)

### related tasks

[“Coding SQL statements” on page 418](#)

[“Compiling with the SQL option” on page 421](#)

[“Choosing the DYNAM or NODYNAM compiler option” on page 426](#)

### related references

[“Differences in how the DB2 precompiler and coprocessor behave” on page 424](#)

---

## DB2 coprocessor

When you use the DB2 coprocessor (called *SQL statement coprocessor* by DB2), the compiler handles your source programs that contain embedded SQL statements without your having to use a separate precompile step.

To use the DB2 coprocessor, specify the SQL compiler option.

When the compiler encounters SQL statements in the source program, it interfaces with the DB2 coprocessor. All text between EXEC SQL and END-EXEC statements is passed to the coprocessor. The coprocessor takes appropriate actions for the SQL statements and indicates to the compiler which native COBOL statements to generate for them.

Although the use of a separate precompile step continues to be supported, it is recommended that you use the coprocessor instead:

- Interactive debugging with Debug Tool is enhanced when you use the coprocessor because you see the SQL statements (not the generated COBOL source) in the listing.
- The COBOL compiler listing includes the error diagnostics (such as syntax errors in the SQL statements) that the DB2 coprocessor generates.
- Certain restrictions on the use of COBOL language that apply when you use the precompile step do not apply when you use the DB2 coprocessor. With the coprocessor:
  - You can use SQL statements in any nested program. (With the precompiler, SQL statements are restricted to the outermost program.)
  - You can use SQL statements in copybooks.
  - REPLACE statements work in SQL statements.

Compiling with the DB2 coprocessor generates a DB2 database request module (DBRM) along with the usual COBOL compiler outputs such as object module and listing. The DBRM writes to the data set that you specified in the DBRMLIB DD statement in the JCL for the COBOL compile step. As input to the DB2 bind process, the DBRM data set contains information about the SQL statements and host variables in the program.

**related concepts**

[“COBOL and DB2 CCSID determination” on page 422](#)

**related tasks**

[“Compiling with the SQL option” on page 421](#)

**related references**

[“Differences in how the DB2 precompiler and coprocessor behave” on page 424](#)

[“SQL” on page 335](#)

## Coding SQL statements

---

Delimit SQL statements with EXEC SQL and END-EXEC. The EXEC SQL and END-EXEC delimiters must each be complete on one line. You cannot continue them across multiple lines. Do not code COBOL statements within EXEC SQL statements.

You also need to do these special steps:

- Code an EXEC SQL INCLUDE statement to include an SQL communication area (SQLCA) in the WORKING-STORAGE SECTION or LOCAL-STORAGE SECTION of the outermost program. LOCAL-STORAGE is recommended for recursive programs and programs that use the THREAD compiler option.
- Define all host variables that you use in SQL statements in the WORKING-STORAGE SECTION, LOCAL-STORAGE SECTION, or LINKAGE SECTION. However, you do not need to identify them with EXEC SQL BEGIN DECLARE SECTION and EXEC SQL END DECLARE SECTION.

**Restriction:** You cannot use SQL statements in object-oriented classes or methods.

**related tasks**

[“Using SQL INCLUDE with the DB2 coprocessor” on page 418](#)

[“Using character data in SQL statements” on page 419](#)

[“Using national decimal data in SQL statements” on page 420](#)

[“Using national group items in SQL statements” on page 420](#)

[“Using binary items in SQL statements” on page 420](#)

[“Determining the success of SQL statements” on page 421](#)

*DB2 Application Programming and SQL Guide* (Coding SQL statements in a COBOL application)

**related references**

[“Code-page determination for string host variables in SQL statements” on page 423](#)

*DB2 SQL Reference*

## Using SQL INCLUDE with the DB2 coprocessor

An SQL INCLUDE statement is treated identically to a native COBOL COPY statement when you use the SQL compiler option.

The following two lines are therefore treated the same way. (The period that ends the EXEC SQL INCLUDE statement is required.)

```
EXEC SQL INCLUDE name END-EXEC.  
COPY "name".
```

The processing of the *name* in an SQL INCLUDE statement follows the same rules as those of the literal in a COPY *literal-1* statement that does not have a REPLACING phrase.

The library search order for SQL INCLUDE statements is the same SYSLIB concatenation as the compiler uses to resolve COBOL COPY statements that do not specify a library-name.

### related references

[Chapter 18, “Compiler-directing statements,” on page 357](#)

[“Differences in how the DB2 precompiler and coprocessor behave” on page 424](#)

COPY statement (*Enterprise COBOL for z/OS Language Reference*)

## Using character data in SQL statements

You can code any of the following USAGE clauses to describe host variables for character data that you use in EXEC SQL statements: USAGE DISPLAY for single-byte or UTF-8 data, USAGE DISPLAY-1 for DBCS data, or USAGE NATIONAL for UTF-16 data.

When you use the stand-alone DB2 precompiler, you must specify the code page (CCSID) in EXEC SQL DECLARE statements for host variables that are declared with USAGE NATIONAL. You must specify the code page for host variables that are declared with USAGE DISPLAY or DISPLAY-1 only if the CCSID that is in effect for the COBOL CODEPAGE compiler option does not match the CCSIDs that are used by DB2 for character and graphic data.

Consider the following code. The two highlighted statements are unnecessary when you use the integrated DB2 coprocessor (with the SQLCCSID compiler option, as detailed in the related concept below), because the code-page information is handled implicitly.

```
CBL CODEPAGE(1140) NSYMBOL(NATIONAL)

WORKING-STORAGE SECTION.
  EXEC SQL INCLUDE SQLCA END-EXEC.
01 INT1 PIC S9(4) USAGE COMP.
01 C1140.
   49 C1140-LEN PIC S9(4) USAGE COMP.
   49 C1140-TEXT PIC X(50).
   EXEC SQL DECLARE :C1140 VARIABLE CCSID 1140 END-EXEC.
01 G1200.
   49 G1200-LEN PIC S9(4) USAGE COMP.
   49 G1200-TEXT PIC N(50) USAGE NATIONAL.
   EXEC SQL DECLARE :G1200 VARIABLE CCSID 1200 END-EXEC.

EXEC SQL FETCH C1 INTO :INT1, :C1140, :G1200 END-EXEC.
```

If you specify EXEC SQL DECLARE *variable-name* VARIABLE CCSID *nnnn* END-EXEC, that specification overrides the implied CCSID. For example, the following code would cause DB2 to treat C1208-TEXT as encoded in UTF-8 (CCSID 1208) rather than as encoded in the CCSID in effect for the COBOL CODEPAGE compiler option:

```
01 C1208.
   49 C1208-LEN PIC S9(4) USAGE COMP.
   49 C1208-TEXT PIC X(50).
   EXEC SQL DECLARE :C1208 VARIABLE CCSID 1208 END-EXEC.
```

The NSYMBOL compiler option has no effect on a character literal inside an EXEC SQL statement. Character literals in an EXEC SQL statement follow the SQL rules for character constants.

### related concepts

[“COBOL and DB2 CCSID determination” on page 422](#)

### related tasks

*DB2 Application Programming and SQL Guide* (Coding SQL statements in a COBOL application)

### related references

[“Differences in how the DB2 precompiler and coprocessor behave” on page 424](#)

[“CODEPAGE” on page 295](#)

*DB2 SQL Reference*

## Using national decimal data in SQL statements

You can use national decimal host variables in EXEC SQL statements when you use either the integrated DB2 coprocessor or the DB2 precompiler. You do not need to specify the CCSID in EXEC SQL DECLARE statements in either case. CCSID 1200 is used automatically.

Any national decimal host variable that you specify in an EXEC SQL statement must have the following characteristics:

- It must be signed.
- It must be specified with the SIGN LEADING SEPARATE clause.
- USAGE NATIONAL must be in effect implicitly or explicitly.

### **related concepts**

[“Formats for numeric data” on page 45](#)

### **related tasks**

[“Defining national numeric data items” on page 127](#)

### **related references**

[“Differences in how the DB2 precompiler and coprocessor behave” on page 424](#)

## Using national group items in SQL statements

You can use a national group item as a host variable in an EXEC SQL statement. The national group item is treated with group semantics (that is, as shorthand for the set of host variables that are subordinate to the group item) rather than as an elementary item.

Because all subordinate items in a national group must have USAGE NATIONAL, a national group item cannot describe a variable-length string.

### **related tasks**

[“Using national groups” on page 128](#)

## Using binary items in SQL statements

For binary data items that you specify in an EXEC SQL statement, you can define the data items as either USAGE COMP-5 or as USAGE BINARY, COMP, or COMP-4.

If you define the binary data items as USAGE BINARY, COMP, or COMP-4, use the TRUNC(BIN) option. (This technique might have a larger effect on performance than using USAGE COMP-5 on individual data items.) If instead TRUNC(OPT) or TRUNC(STD) is in effect, the compiler accepts the items but the data might not be valid because of the decimal truncation rules. You need to ensure that truncation does not affect the validity of the data.

### **related concepts**

[“Formats for numeric data” on page 45](#)

### **related references**

[“TRUNC” on page 344](#)

## Determining the success of SQL statements

When DB2 finishes executing an SQL statement, DB2 sends a return code in the SQLCA structure, with one exception, to indicate whether the operation succeeded or failed. In your program, test the return code and take any necessary action.

The exception occurs when a program runs under DSN from one of the alternate entry points of the TSO batch mode module IKJEFT01 (IKJEFT1A or IKJEFT1B). In this case, the return code is passed in register 15.

After execution of SQL statements, the content of the RETURN-CODE special register might not be valid. Therefore, even if your COBOL program terminates normally after successfully using SQL statements, the job step could end with an undefined return code. To ensure that a meaningful return code is given at termination, set the RETURN-CODE special register before terminating your program.

### related tasks

*DB2 Application Programming and SQL Guide* (Coding SQL statements in a COBOL application)

## Compiling with the SQL option

You use the SQL compiler option to enable the DB2 coprocessor and to specify DB2 suboptions.

You can specify the SQL option in any of the compiler option sources: compiler invocation, PROCESS or CBL statements, or installation default. You cannot specify DB2 suboptions when the SQL option is the COBOL installation default, but you can specify default DB2 suboptions by customizing the DB2 product installation defaults.

The DB2 suboption string that you provide in the SQL compiler option is made available to the DB2 coprocessor. Only the DB2 coprocessor views the contents of the string.

You can use standard JCL procedural statements to compile your program with the DB2 coprocessor. In addition to specifying the above compiler options, specify the following items in your JCL:

- DBRMLIB DD statement with the location for the generated database request module (DBRM).
- STEPLIB override for the COBOL step, adding the data set that contains the DB2 coprocessor services, unless these services are in the LNKST. Typically, this data set is xxxxxx.SDSNLOAD. For example, for DB2 9 it might be DSN910.SDSNLOAD, but your installation might have changed the name.

For example, you might have the following lines in your JCL:

```
//DBRMLIB DD DSN=PAYROLL.MONTHLY.DBRMLIB.DATA(MASTER),DISP=SHR
//STEPLIB DD DSN=DSN910.SDSNLOAD,DISP=SHR
```

**Compiling a batch of programs:** If you use the SQL option when compiling a source file that contains a sequence of COBOL programs (a batch compile sequence), SQL must be in effect for only the first program of the sequence. Although you can specify SQL upon compiler invocation, the option will be in effect for only the first program. If you specify SQL in a CBL or PROCESS statement for a program other than the first program in the batch, you will receive a compiler diagnostic message.

### related concepts

[“DB2 coprocessor” on page 417](#)

[“COBOL and DB2 CCSID determination” on page 422](#)

### related tasks

[“Separating DB2 suboptions” on page 422](#)

[“Choosing the DYNAM or NODYNAM compiler option” on page 426](#)

### related references

[“DYNAM” on page 305](#)

[“SQL” on page 335](#)

*DB2 Command Reference*

## Separating DB2 suboptions

Because of the concatenation of multiple SQL option specifications, you can separate DB2 suboptions (which might not fit in one CBL statement) into multiple CBL statements.

The options that you include in the suboption string are cumulative. The compiler concatenates these suboptions from multiple sources in the order that they are specified. For example, suppose that your source file has the following code:

```
//STEP1 EXEC IGYWC, . . .
// PARM.COBOL='SQL("string1")'
//COBOL.SYSIN DD *
  CBL SQL("string2")
  CBL SQL("string3")
  IDENTIFICATION DIVISION.
  PROGRAM-ID. DRIVER1.
```

During compilation, the compiler passes the following suboption string to the DB2 coprocessor:

```
"string1 string2 string3"
```

The concatenated strings are delimited with single spaces. If the compiler finds multiple instances of the same SQL suboption, the last specification of that suboption in the concatenated string takes effect. The compiler limits the length of the concatenated DB2 suboption string to 4 KB.

## COBOL and DB2 CCSID determination

All DB2 string data other than BLOB, BINARY, and VARBINARY data has an associated encoding scheme and a coded character set ID (CCSID). This is true for fixed-length and variable-length character strings, fixed-length and variable-length graphic character strings, CLOB host variables, and DBCLOB host variables.

When you use the integrated DB2 coprocessor, the determination of the code page CCSID that will be associated with the string host variables used in SQL statement processing depends on the setting of the COBOL SQLCCSID option, on the programming techniques used, and on various DB2 configuration options.

When you use the SQL and SQLCCSID COBOL compiler options, the CCSID value *nnnnn* that is specified in the CODEPAGE compiler option, or that is determined from the COBOL data type of a host variable, is communicated automatically from COBOL to DB2. DB2 associates the COBOL CCSID with host variables, overriding the CCSID that would otherwise be implied by DB2 external mechanisms and defaults. This associated CCSID is used for the processing of the SQL statements that reference host variables.

When you use the SQL and NOSQLCCSID compiler options, the CCSID value *nnnnn* that is specified in the CODEPAGE compiler option is used only for processing COBOL statements within the COBOL program; that CCSID is not used for the processing of SQL statements. Instead, DB2 assumes in processing SQL statements that host variable data values are encoded according to the CCSID or CCSIDs that are specified through DB2 external mechanisms and defaults.

### related concepts

[“DB2 coprocessor” on page 417](#)

### related tasks

[“Programming with the SQLCCSID or NOSQLCCSID option” on page 423](#)

### related references

[“Code-page determination for string host variables in SQL statements” on page 423](#)

[“CODEPAGE” on page 295](#)

[“SQL” on page 335](#)

[“SQLCCSID” on page 336](#)

## Code-page determination for string host variables in SQL statements

When you use the integrated DB2 coprocessor (SQL compiler option), the code page for processing string host variables in SQL statements is determined as shown below, in descending order of precedence.

- A host variable that has USAGE NATIONAL is always processed by DB2 using CCSID 1200 (Unicode UTF-16). For example:

```
01 hostvariable pic n(10) usage national.
```

- An alphanumeric host variable that has an explicit FOR BIT DATA declaration is set by DB2 to CCSID 66535, which indicates that the variable does not represent encoded characters. For example:

```
EXEC SQL DECLARE hostvariable VARIABLE FOR BIT DATA END-EXEC
```

- A BLOB, BINARY, or VARBINARY host variable has no CCSID association. These string types do not represent encoded characters.
- A host variable for which you specify an explicit CCSID override in the SQLDA is processed with that CCSID.
- A host variable that you specify in a declaration with an explicit CCSID is processed with that CCSID. For example:

```
EXEC SQL DECLARE hostvariable VARIABLE CCSID nnnnn END-EXEC
```

- An alphanumeric host variable, if the SQLCCSID compiler option is in effect, is processed with the CCSID *nnnnn* from the CODEPAGE compiler option.
- A DBCS host variable, if the SQLCCSID option is in effect, is processed with the mapped value *mmmmm*, which is the pure DBCS CCSID component of the mixed (MBCS) CCSID *nnnnn* from the CODEPAGE(*nnnnn*) compiler option.
- An alphanumeric or DBCS host variable, if the NOSQLCCSID option is in effect, is processed with the CCSID from the DB2 ENCODING bind option, if specified, or from the APPLICATION ENCODING set in DSNHDECP through the DB2 installation panel DSNTIPF.

### related references

[“CODEPAGE” on page 295](#)

[“SQLCCSID” on page 336](#)

## Programming with the SQLCCSID or NOSQLCCSID option

In general, the SQLCCSID option is recommended for new applications that use the integrated DB2 coprocessor, and as a long-term direction for existing applications. The NOSQLCCSID option is recommended as a mechanism for migrating existing precompiler-based applications to use the integrated DB2 coprocessor.

The SQLCCSID option is recommended for COBOL-DB2 applications that have any of these characteristics:

- Use COBOL Unicode support
- Use other COBOL syntax that is indirectly sensitive to CCSID encoding, such as XML support or object-oriented syntax for Java interoperability
- Process character data that is encoded in a CCSID that is different from the default CCSID assumed by DB2

The NOSQLCCSID option is recommended for applications that require the highest compatibility with the behavior of the DB2 precompiler.

For applications that use COBOL alphanumeric data items as host variables interacting with DB2 string data that is defined with the FOR BIT DATA subtype, you must either:

- Use the NOSQLCCSID compiler option
- Specify explicit FOR BIT DATA declarations for those host variables, for example:

```
EXEC SQL DECLARE hostvariable VARIABLE FOR BIT DATA END-EXEC
```

#### Usage notes

- If you use the DB2 DCLGEN command to generate COBOL declarations for a table, you can optionally create FOR BIT DATA declarations automatically. To do so, specify the DCLBIT (YES) option of the DCLGEN command.
- **Performance consideration:** Using the SQLCCSID compiler option could result in some performance overhead in SQL processing, because with SQLCCSID in effect the default DB2 CCSID association mechanism is overridden with a mechanism that works on a per-host-variable basis.

#### related concepts

[“DB2 coprocessor” on page 417](#)

#### related references

[“SQLCCSID” on page 336](#)

## Differences in how the DB2 precompiler and coprocessor behave

The sections that follow enumerate the differences in behavior between the stand-alone COBOL DB2 precompiler and the integrated COBOL DB2 coprocessor.

For details about the CCSID determination under the DB2 precompiler and coprocessor, see [“COBOL and DB2 CCSID determination” on page 422](#).

### Period at the end of EXEC SQL INCLUDE statements

**Precompiler:** The DB2 precompiler does not require that a period end each EXEC SQL INCLUDE statement. If a period is specified, the precompiler processes it as part of the statement. If a period is not specified, the precompiler accepts the statement as if a period had been specified.

**Coprocessor:** The DB2 coprocessor treats each EXEC SQL INCLUDE statement like a COPY statement, and requires that a period end the statement. For example:

```
IF A = B THEN
    EXEC SQL INCLUDE some_code_here END-EXEC.
ELSE
    .
END-IF
```

Note that the period does not terminate the IF statement.

### EXEC SQL and REPLACE or COPY REPLACING

**Precompiler:** With the DB2 precompiler, COBOL REPLACE statements and the REPLACING phrase of the COPY statement act on the expanded source created from the EXEC SQL statement. COBOL rules for REPLACE and REPLACING are used.

**Coprocessor:** With the DB2 coprocessor, REPLACE and COPY . . . REPLACING statements act on the original source program, including EXEC SQL statements.

Different behavior can result, as in the following example:

```
REPLACE == ABC == By == XYZ ==.  
01  G.  
   02  ABC PIC X(10).  
  
EXEC SQL SELECT * INTO :G.ABC FROM TABLE1 END-EXEC
```

With the precompiler, the reference to G.ABC will appear as ABC of G in the expanded source and will be replaced with XYZ of G. With the coprocessor, replacement will not occur, because ABC is not delimited by separators in the original source string G.ABC.

## Source code after an END-EXEC statement

**Precompiler:** The DB2 precompiler ignores any code that follows END-EXEC statements on the same line.

**Coprocessor:** The DB2 coprocessor processes code that follows END-EXEC statements on the same line.

## Multiple definitions of host variables

**Precompiler:** The DB2 precompiler does not require that host variable references be unique. The first definition that maps to a valid DB2 data type is used.

**Coprocessor:** The DB2 coprocessor requires that each host variable reference be unique. The coprocessor diagnoses nonunique references to host variables. You must fully qualify host variable references to make them unique.

## EXEC SQL statement continuation lines

**Precompiler:** The DB2 precompiler requires that EXEC SQL statements start in columns 12 through 72. Continuation lines of the statements can start anywhere in columns 8 through 72.

**Coprocessor:** The DB2 coprocessor requires that all lines of an EXEC SQL statement, including continuation lines, be coded in columns 12 through 72.

## Bit-data host variables

**Precompiler:** With the DB2 precompiler, a COBOL alphanumeric data item can be used as a host variable to hold DB2 character data that has subtype FOR BIT DATA. An explicit EXEC SQL DECLARE VARIABLE statement that declares that host variable as FOR BIT DATA is not required.

**Coprocessor:** With the DB2 coprocessor, a COBOL alphanumeric data item can be used as a host variable to hold DB2 character data that has subtype FOR BIT DATA if an explicit EXEC SQL DECLARE VARIABLE statement for that host variable is specified in the COBOL program. For example:

```
EXEC SQL DECLARE :HV1 VARIABLE FOR BIT DATA END-EXEC.
```

As an alternative to adding EXEC SQL DECLARE . . . FOR BIT DATA statements, you can use the NOSQLCCSID compiler option. For details, see the related reference about code-page determination below.

## SQL-INIT-FLAG

**Precompiler:** With the DB2 precompiler, if you pass host variables that might be located at different addresses when the program is called more than once, the called program must reset SQL-INIT-FLAG. Resetting this flag indicates to DB2 that storage must be initialized when the next SQL statement runs. To reset the flag, insert the statement MOVE ZERO TO SQL-INIT-FLAG in the PROCEDURE DIVISION of the called program ahead of any executable SQL statements that use those host variables.

**Coprocessor:** With the DB2 coprocessor, the called program does not need to reset SQL-INIT-FLAG. An SQL-INIT-FLAG is automatically defined in the program to aid program portability. However, statements

that modify SQL - INIT - FLAG, such as MOVE ZERO TO SQL - INIT - FLAG, have no effect on the SQL processing in the program.

**related concepts**

[“DB2 coprocessor” on page 417](#)

[“COBOL and DB2 CCSID determination” on page 422](#)

**related references**

[“Code-page determination for string host variables in SQL statements” on page 423](#)

[“SQLCCSID” on page 336](#)

## Choosing the DYNAM or NODYNAM compiler option

---

For COBOL programs that have EXEC SQL statements, your choice of the compiler option DYNAM or NODYNAM depends on the operating environment.

When you run under:

- TSO or IMS: You can use either the DYNAM or NODYNAM compiler option.

Note that IMS and DB2 share a common alias name, DSNHLI, for the language interface module. You must concatenate your libraries as follows:

- If you use IMS with the DYNAM option, concatenate the IMS library first.
- If you run your application only under DB2, concatenate the DB2 library first.

- CICS or the DB2 call attach facility (CAF): You must use the NODYNAM compiler option.

Because stored procedures use CAF, you must also compile COBOL stored procedures with the NODYNAM option.

**related tasks**

[“Compiling with the SQL option” on page 421](#)

*DB2 Application Programming and SQL Guide* (Programming for the call attachment facility)

**related references**

[“DYNAM” on page 305](#)

---

## Chapter 22. Developing COBOL programs for IMS

Although much of the coding of a COBOL program will be the same when running under IMS, be aware of the following recommendations and restrictions.

In COBOL, IMS message processing programs (MPPs) do not use non-IMS input or output statements such as READ, WRITE, REWRITE, OPEN, and CLOSE.

With Enterprise COBOL, you can invoke IMS facilities using the following interfaces:

- CBLTDLI call
- Language Environment callable service CEETDLI
- EXEC SQLIMS statements

CEETDLI behaves essentially the same way as CBLTDLI, except that CEETDLI enables LE condition handling to be used. There are some instances when you cannot use Language Environment condition handling when using CBLTDLI under IMS.

You can also run object-oriented COBOL programs in a Java dependent region. You can mix the object-oriented COBOL and Java languages in a single application.

### **related concepts**

[“IMS SQL coprocessor” on page 427](#)

### **related tasks**

[“Coding SQLIMS statements” on page 428](#)

[“Compiling with the SQLIMS option” on page 429](#)

[“Compiling and linking COBOL programs for running under IMS” on page 430](#)

[“Using object-oriented COBOL and Java under IMS” on page 431](#)

[“Calling a COBOL method from a Java application under IMS” on page 431](#)

[“Building a mixed COBOL-Java application that starts with COBOL” on page 432](#)

[“Writing mixed-language IMS applications” on page 432](#)

---

## IMS SQL coprocessor

When you use the IMS SQL coprocessor (called *SQL statement coprocessor* by IMS), the compiler handles your source programs that contain embedded SQL statements.

When the compiler encounters SQLIMS statements in the source program, it interfaces with the IMS SQL coprocessor. All text between EXEC SQLIMS and END-EXEC statements is passed to the coprocessor. The coprocessor takes appropriate actions for the SQLIMS statements and indicates to the compiler what native COBOL statements to generate for them.

### **Notes:**

- The IMS SQL coprocessor processes embedded SQLIMS statements, not embedded SQL statements.
- IMS program might contain EXEC SQL statements for accessing a DB2 SQL database, EXEC SQLIMS statements for accessing an IMS DLI databases, or both. The SQL option enables EXEC SQL statements while the SQLIMS option enables EXEC SQLIMS statements.

With the IMS SQL coprocessor, you can use statements in the following ways:

- Use EXEC SQLIMS statements in any nested program.
- Use EXEC SQLIMS statements in COPYBOOKS.
- REPLACE statements work in SQLIMS statements.

### **related tasks**

[“Coding SQLIMS statements” on page 428](#)

[“Compiling with the SQLIMS option” on page 429](#)

[“Compiling and linking COBOL programs for running under IMS” on page 430](#)

#### **related references**

[“SQLIMS” on page 337](#)

## **Coding SQLIMS statements**

---

Delimit SQLIMS statements with EXEC SQLIMS and END-EXEC. The EXEC SQLIMS and END-EXEC delimiters must each be complete on one line. Do not code COBOL statements within EXEC SQLIMS statements.

Code an EXEC SQLIMS INCLUDE statement to include an SQLIMS communication area (SQLCA) in the WORKING-STORAGE SECTION or LOCAL-STORAGE SECTION of the outermost program. The LOCAL-STORAGE SECTION is recommended for recursive programs and programs that use the THREAD compiler option.

**Restriction:** You cannot use SQLIMS statements in object-oriented classes or methods.

#### **related tasks**

[“Using SQLIMS](#)

[INCLUDE with the IMS SQL coprocessor” on page 428](#)

[“Using character data in SQLIMS statements” on page 428](#)

[“Using binary items in SQLIMS statements” on page 429](#)

[“Determining the success of SQLIMS statements” on page 429](#)

## **Using SQLIMS INCLUDE with the IMS SQL coprocessor**

An SQLIMS INCLUDE statement is treated identically to a native COBOL COPY statement when you use the SQLIMS compiler option.

The following two lines are therefore treated the same way. The period that ends the EXEC SQLIMS INCLUDE statement is required.

```
EXEC SQLIMS INCLUDE name END-EXEC.  
COPY "name".
```

The processing of the *name* in an SQLIMS INCLUDE statement follows the same rules as the literal in a COPY *literal-1* statement that does not have a REPLACING phrase.

The library search order for SQLIMS INCLUDE statements is the same SYSLIB concatenation as the compiler uses to resolve COBOL COPY statements that do not specify a library-name.

#### **related references**

Chapter 18, “Compiler-directing statements,” on page 357

COPY statement (*Enterprise COBOL for z/OS Language Reference*)

## **Using character data in SQLIMS statements**

Alphanumeric host data items for use in EXEC SQLIMS statements (host variables) must be defined as USAGE DISPLAY.

**Note:** Do not use character data items that are defined with USAGE DISPLAY-1 or USAGE NATIONAL as SQLIMS host variables.

#### **related concepts**

[“IMS SQL coprocessor” on page 427](#)

#### **related references**

[“CODEPAGE” on page 295](#)

## Using binary items in SQLIMS statements

For binary data items that you specify in an EXEC SQLIMS statement, you can define the data items as either USAGE COMP-5 or as USAGE BINARY, COMP, or COMP-4.

If you define the binary data items as USAGE BINARY, COMP, or COMP-4, use the TRUNC (BIN) compiler option. Using this option might have a larger effect on performance than using USAGE COMP-5 on individual data items. If instead you use the TRUNC (OPT) or TRUNC (STD) compiler options, the compiler accepts the items but the data might not be valid because of the decimal truncation rules. You must ensure that truncation does not affect the validity of the data.

### related concepts

[“Formats for numeric data” on page 45](#)

### related references

[“TRUNC” on page 344](#)

## Determining the success of SQLIMS statements

When IMS finishes running an SQLIMS statement, IMS sends a return code in the SQLIMSCA structure to indicate whether the operation succeeded or failed. In your program, test the return code and take any necessary action.

After execution of SQLIMS statements, the content of the RETURN-CODE special register might not be valid. Therefore, even if a program terminates normally after successfully using SQLIMS statements, the job step might end with an undefined return code. To ensure that a meaningful return code is given at termination, set the RETURN-CODE special register before you end the program.

### related tasks

*IMS Application Programming Guide*

## Compiling with the SQLIMS option

---

Use the SQLIMS compiler option to enable the IMS SQL coprocessor and to specify IMS suboptions.

You can specify the SQLIMS option in any of the compiler option sources: compiler invocation, PROCESS or CBL statements, or installation default. However, you cannot specify IMS suboptions when the SQLIMS option is the COBOL installation default. The IMS suboption string in the SQLIMS compiler option is only available to the IMS SQL coprocessor.

To use the IMS SQL coprocessor, you must compile with the SQLIMS option and IMS must be available on the system on which you compile.

You can use standard JCL procedural statements to compile your program with the IMS SQL coprocessor. In addition to specifying the above compiler options, specify the following item in your JCL:

STEPLIB override for the COBOL step, adding the data set that contains the IMS SQL coprocessor services, unless these services are in the LNKLIST. Typically, the data set is IMS.SDFSRESL but your installation might have changed the name.

For example, you might have the following lines in your JCL:

```
//STEPLIB DD DSN=IMS.SDFSRESL,DISP=SHR
```

### Compiling a batch of programs:

If you use the SQLIMS option when you compile a source file that contains a sequence of COBOL programs (a batch compile sequence), SQLIMS is in effect for only the first program of the sequence. Although you can specify SQLIMS upon compiler invocation, the option is in effect for only the first program. If you specify SQLIMS in a CBL or PROCESS statement for a program other than the first program in the batch, a compiler diagnostic message is issued.

**related concepts**

[“IMS SQL coprocessor” on page 427](#)

**related tasks**

[“Separating IMS suboptions” on page 430](#)

**related references**

[“SQL” on page 335](#)

## Separating IMS suboptions

Because of the concatenation of multiple SQLIMS option specifications, you can separate IMS suboptions (which might not fit in one CBL statement) into multiple CBL statements.

The options that you include in the suboption string are cumulative. The compiler concatenates these suboptions from multiple sources in the order that they are specified. For example, suppose that your source file contains the following code:

```
//STEP1 EXEC IGYWC, . . .  
// PARM.COBOL='SQLIMS("string1")'  
//COBOL.SYSIN DD *  
CBL SQLIMS("string2")  
CBL SQLIMS("string3")  
IDENTIFICATION DIVISION.  
PROGRAM-ID. DRIVER1.
```

During compilation, the compiler passes the following suboption string to the IMS SQL coprocessor:

```
"string1 string2 string3"
```

The concatenated strings are delimited with single spaces. If the compiler finds multiple instances of the same SQLIMS suboption, the last specification of that suboption in the concatenated string takes effect. The compiler limits the length of the concatenated IMS suboption string to 4 KB.

**related concepts**

[“IMS SQL coprocessor” on page 427](#)

**related tasks**

[“Compiling with the SQLIMS option” on page 429](#)

## Compiling and linking COBOL programs for running under IMS

For best performance in the IMS environment, use the RENT compiler option. RENT causes COBOL to generate reentrant code. You can then run your application programs in either *preloaded* mode (the programs are always resident in storage) or *nonpreload* mode without having to recompile using different options.

Preloading can boost performance because subsequent requests for a program can be handled faster when the program is already in storage (rather than being fetched from a library each time it is needed).

For IMS programs, using the RENT compiler option is recommended. You must use the RENT compiler option for a program that is to be run preloaded or both preloaded and nonpreloaded. When you preload a program object that contains COBOL programs, all of the COBOL programs in that program object must be compiled using the RENT option.

You can place programs compiled with the RENT option in the z/OS link pack area. There they can be shared among the IMS dependent regions.

To run above the 16 MB line, an application program must be compiled with RENT. The data for IMS application programs can reside above the 16 MB line, and you can use DATA(31) RENT for programs that use IMS services.

For proper execution of COBOL programs under IMS, observe the following guidelines for the link-edit attributes:

- To link program objects that contain only COBOL programs compiled with the RENT compiler option, link as RENT.
- To link program objects that contain a mixture of COBOL RENT programs and other programs, use the link-edit attributes recommended for the other programs.

#### **related concepts**

[“Storage and its addressability” on page 37](#)

#### **related tasks**

[“Choosing the DYNAM or NODYNAM compiler option” on page 426](#)

*Language Environment Programming Guide* (Condition handling under IMS)

#### **related references**

[“DATA” on page 300](#)

[“RENT” on page 330](#)

*Enterprise COBOL Migration Guide* (IMS considerations)

## **Using object-oriented COBOL and Java under IMS**

---

You can mix object-oriented COBOL and Java in an application that runs in a Java dependent region.

For example, you can:

- Call a COBOL method from a Java application. You can build the messaging portion of your application in Java and call COBOL methods to access IMS databases.
- Build a mixed COBOL and Java application that starts with the main method of a COBOL class and that invokes Java routines.

You must run these applications in either a Java message processing (JMP) dependent region or a Java batch processing (JBP) dependent region. A program that reads from the message queue (regardless of the language) must run in a JMP dependent region.

#### **related tasks**

[“Defining a factory section” on page 590](#)

[Chapter 33, “Writing object-oriented programs,” on page 561](#)

[Chapter 34, “Communicating with Java methods,” on page 601](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

*IMS Application Programming Guide*

## **Calling a COBOL method from a Java application under IMS**

You can use the object-oriented language support in Enterprise COBOL to write COBOL methods that a Java program can call under IMS.

When you define a COBOL class and compile it using Enterprise COBOL, the compiler generates a Java class definition with native methods and the object code that implements those native methods. You can then create an instance and invoke the methods of this class from a Java program that runs in a Java dependent region, just as you would use any other class.

For example, you can define a COBOL class that uses the appropriate DL/I calls to access an IMS database. To make the implementation of this class available to a Java program, do the following steps:

1. Compile the COBOL class using Enterprise COBOL.  
The compiler generates a Java source file (.java) that contains the class definition, and an object module (.o) that contains the implementation of the native methods.
2. Compile the generated Java source file using the Java compiler.  
The Java compiler creates a class file (.class).

3. Link the object code into a dynamic link library (DLL) in the z/OS UNIX file system (.so). The directory that contains the COBOL DLLs must be listed in the LIBPATH, as specified in the IMS.PROCLIB member that is indicated by the ENVIRON= parameter of the IMS region procedure.
4. Update the sharable application class path in the master JVM options member (ibm.jvm.sharable.application.class.path in the IMS.PROCLIB member that is specified by the JVMOPMAS= parameter of the IMS region procedure) to enable the JVM to access the Java class file.

A Java program cannot call procedural COBOL programs directly. To reuse existing COBOL IMS code, use one of the following techniques:

- Restructure the COBOL code as a method in a COBOL class.
- Write a COBOL class definition and method that serves as a wrapper for the existing procedural code. The wrapper code can use COBOL CALL statements to access procedural COBOL programs.

#### **related tasks**

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[“Structuring OO applications” on page 598](#)

[“Wrapping procedure-oriented COBOL programs” on page 598](#)

[IMS Application Programming Guide](#)

## **Building a mixed COBOL-Java application that starts with COBOL**

An application that runs in a Java dependent region must start with the main method of a class.

A COBOL class definition that has a main factory method meets this requirement; therefore, you can use a main factory method as the first routine of a mixed COBOL and Java application under IMS.

Enterprise COBOL generates a Java class with a main method, which the Java dependent region can find, instantiate, and invoke. Although you can code the entire application in COBOL, you would probably build this type of application to call a Java routine. When the COBOL run time runs within the JVM of a Java dependent region, it automatically finds and uses this JVM to invoke methods on Java classes.

The COBOL application should use DL/I calls for processing messages (GU and GN) and synchronizing transactions (CHKP).

#### **related tasks**

[“Structuring OO applications” on page 598](#)

[IMS Application Programming Guide](#)

[IBM SDK for Java - Tools Documentation](#)

## **Writing mixed-language IMS applications**

When you write mixed-language IMS applications, you need to be aware of the effects of the STOP RUN statement. You also need to understand how to process messages and synchronize transactions, access databases, and use the application interface block (AIB).

#### **related tasks**

[“Using the STOP RUN statement” on page 432](#)

[“Processing messages and synchronizing transactions” on page 433](#)

[“Accessing databases” on page 433](#)

[“Using the application interface block” on page 433](#)

## **Using the STOP RUN statement**

If you use the STOP RUN statement in the COBOL portion of your application, the statement terminates all COBOL and Java routines (including the JVM).

Control is returned immediately to IMS. The program and the transaction are left in a stopped state.

## Processing messages and synchronizing transactions

IMS message-processing applications must do all message processing and transaction synchronization either in COBOL or Java, rather than distributing this logic between application components written in both languages.

COBOL components use CALL statements to DL/I services to process messages (GU and GN) and synchronize transactions (CHKP). Java components use Java classes for IMS to do these functions. You can use object instances of classes derived from `IMSFieldMessage` to communicate entire IMS messages between the COBOL and Java components of the application.

### related tasks

*IMS Application Programming Guide*

### related references

*IMS Application Programming API Reference*

## Accessing databases

You can use either Java, COBOL, or a mixture of the two languages to access IMS databases.

**Limitation:** EXEC SQL statements for DB2 database access are not supported in COBOL routines that run in a Java dependent region.

**Recommendation:** Do not access the same database program communication block (PCB) from both Java and COBOL. The Java and COBOL parts of the application share the same database position. Changes in database position from calls in one part of the application affect the database position in another part of the application. (This problem occurs whether the affected parts of an application are written in the same language or in different languages.)

Suppose that a Java component of a mixed application builds an SQL `SELECT` clause and uses Java Database Connectivity (JDBC) to query and retrieve results from an IMS database. The Java class libraries for IMS construct the appropriate request to IMS to establish the correct position in the database. If you then invoke a COBOL method that builds a segment search argument (SSA) and issues a GU (Get Unique) request to IMS against the same database PCB, the request probably altered the position in the database for that PCB. If so, subsequent JDBC requests to retrieve more records by using the initial SQL `SELECT` clause are incorrect because the database position changed. If you must access the same PCB from multiple languages, reestablish the database position after an interlanguage call before you access more records in the database.

### related tasks

*IMS Application Programming Guide*

## Using the application interface block

COBOL applications that run in a Java dependent region normally must use the AIB interface because the Java dependent region does not provide PCB addresses to its application.

To use the AIB interface, specify the PCB requested for the call by placing the PCB name (which must be defined as part of the PSBGEN) in the resource name field of the AIB. (The AIB requires that all PCBs in a program specification block (PSB) definition have a name.) You do not specify the PCB address directly, and your application does not need to know the relative PCB position in the PCB list. Upon the completion of the call, the AIB returns the PCB address that corresponds to the PCB name that the application passed.

Alternatively, you can obtain PCB addresses by making an IMS INQY call using subfunction FIND, and the PCB name as the resource name. The call returns the address of the PCB, which you can then pass to a COBOL program. (This approach still requires that the PCB name be defined as part of the PSBGEN, but the application does not have to use the AIB interface.)

[“Example: using the application interface block” on page 434](#)

## related tasks

*IMS Application Programming Guide*

### **Example: using the application interface block**

The following example shows how you can use the AIB interface in a COBOL application.

```
Local-storage section.  
  copy AIB.  
  .  
  .  
  .  
Linkage section.  
01 IOPCB.  
  05 logtterm      pic x(08).  
  05              pic x(02).  
  05 tpstat        pic x(02).  
  05 iodate        pic s9(7)   comp-3.  
  05 iotime        pic s9(7)   comp-3.  
  05              pic x(02).  
  05 seqnum        pic x(02).  
  05 mod           pic x(08).  
Procedure division.  
  Move spaces to input-area  
  Move spaces to AIB  
  Move "DFS AIB" to AIBRID  
  Move length of AIB to AIBRLEN  
  Move "IOPCB" to AIBRSNM1  
  Move length of input-area to AIBOALEN  
  Call "CEETDLI" using GU, AIB, input-area  
  Set address of IOPCB to AIBRESA1  
  If tpstat = spaces  
* . . process input message
```

---

## Chapter 23. Running COBOL programs under z/OS UNIX

To run COBOL programs in the z/OS UNIX environment, compile them using Enterprise COBOL or COBOL for OS/390 & VM. The programs must be reentrant, so use the compiler and linker option RENT.

If you are going to run the programs from the z/OS UNIX file system, use the linker option AMODE 31. Any AMODE 24 program that you call from within a z/OS UNIX application must reside in an MVS PDSE.

**Restrictions:** The following restrictions apply to running under z/OS UNIX:

- SORT and MERGE statements are not supported.
- You cannot use the old COBOL interfaces for preinitialization (runtime option RTEREUS) to establish a reusable environment.
- You cannot run a COBOL program compiled with the NOTHREAD option in more than one thread. If you start a COBOL application in a second thread, you get a software condition from the COBOL run time. You can run NOTHREAD COBOL programs in the initial process thread (IPT) or in one non-IPT that you create from a C or PL/I routine.

You can run a COBOL program in more than one thread if you compile all the COBOL programs in the application with the THREAD option.

You can use Debug Tool to debug z/OS UNIX programs in remote debug mode, for example, by using the Debug Perspective of IBM Developer for z/OS, or in full-screen mode (MFI) using a VTAM® terminal.

### related tasks

Chapter 15, “Compiling under z/OS UNIX,” on page 265

“Running OO applications under z/OS UNIX” on page 275

“Running in z/OS UNIX environments” on page 435

“Setting and accessing environment variables” on page 436

“Calling UNIX/POSIX APIs” on page 438

“Accessing main program parameters under z/OS UNIX” on page 440

*Language Environment Programming Guide*

### related references

“RENT” on page 330

---

## Running in z/OS UNIX environments

You can run COBOL programs in any of the z/OS UNIX execution environments, either from within a z/OS UNIX shell or from outside a shell.

- You can run programs in either the OMVS shell (OMVS) or the ISPF shell (ISHELL).

Enter the program-name at the shell prompt. The program must be in the current directory or in your search path.

You can specify runtime options only by setting the environment variable \_CEE\_RUNOPTS before starting the program.

You can run programs that reside in a cataloged MVS data set from a shell by using the tso utility. For example:

```
tso "call 'my.loadlib(myprog)'"
```

The ISPF shell can direct stdout and stderr only to a z/OS UNIX file, not to your terminal.

- From outside a shell, you can run programs either under TSO/E or in batch.

To call a COBOL program that resides in a z/OS UNIX file from the TSO/E prompt, use the BPXBATCH utility or a spawn() syscall in a REXX exec.

To call a COBOL program that resides in a z/OS UNIX file with the EXEC JCL statement, use the BPXBATCH utility.

#### **related tasks**

[“Running OO applications under z/OS UNIX” on page 275](#)

[“Setting and accessing environment variables” on page 436](#)

[“Calling UNIX/POSIX APIs” on page 438](#)

[“Accessing main program parameters under z/OS UNIX” on page 440](#)

[“Defining and allocating QSAM files” on page 164](#)

[“Allocating line-sequential files” on page 200](#)

[“Allocating VSAM files” on page 192](#)

[“Displaying values on a screen or in a file \(DISPLAY\)” on page 33](#)

*Language Environment Programming Guide* (Running POSIX-enabled programs)

#### **related references**

[“TEST” on page 340](#)

*UNIX System Services User's Guide* (The BPXBATCH utility)

*Language Environment Programming Reference*

## **Setting and accessing environment variables**

---

You can set environment variables for z/OS UNIX COBOL programs either from the shell with commands `export` and `set`, or from the program.

Although setting and resetting environment variables from the shell before you begin to run a program is a typical procedure, you can set, reset, and access environment variables from the program while it is running.

If you are running a program with BPXBATCH, you can set environment variables by using an `STDENV DD` statement.

To reset an environment variable as if it had not been set, use the z/OS UNIX shell command `unset`. To reset an environment variable from a COBOL program, call the `setenv()` function.

To see the values of all environment variables, use the `export` command with no parameters. To access the value of an environment variable from a COBOL program, call the `getenv()` function.

[“Example: setting and accessing environment variables” on page 438](#)

#### **related tasks**

[“Running in z/OS UNIX environments” on page 435](#)

[“Setting environment variables that affect execution” on page 437](#)

[“Accessing main program parameters under z/OS UNIX” on page 440](#)

[“Running OO applications under z/OS UNIX” on page 275](#)

[“Setting environment variables under z/OS UNIX” on page 265](#)

#### **related references**

[“Runtime environment variables” on page 437](#)

*Language Environment Programming Reference*

*MVS Program Management: User's Guide and Reference*

## Setting environment variables that affect execution

To set environment variables for z/OS UNIX COBOL programs from a shell, use the `export` or `set` command. To set environment variables from within the program, call POSIX functions `setenv()` or `putenv()`.

For example, to set the environment variable `MYFILE`:

```
export MYFILE=/usr/mystuff/notes.txt
```

[“Example: setting and accessing environment variables” on page 438](#)

### related tasks

[“Calling UNIX/POSIX APIs” on page 438](#)

[“Setting environment variables under z/OS UNIX” on page 265](#)

### related references

[“Runtime environment variables” on page 437](#)

## Runtime environment variables

Several runtime variables are of interest for COBOL programs.

These are the runtime environment variables:

### **`_CEE_ENVFILE`**

Specifies a file from which to read environment variables.

### **`_CEE_RUNOPTS`**

Specifies runtime options.

### **`CLASSPATH`**

Specifies directory paths of Java .class files required for an OO application.

### **`COBJVMINITOPTIONS`**

Specifies Java virtual machine (JVM) options to be used when COBOL initializes a JVM.

### **`_IGZ_SYSOUT`**

Specifies where to direct DISPLAY output. `stdout` and `stderr` are the only allowable values.

### **`LIBPATH`**

Specifies directory paths of dynamic link libraries.

### **`PATH`**

Specifies directory paths of executable programs.

### **`STEPLIB`**

Specifies location of programs that are not in the LNKLIST.

### related tasks

[“Displaying data on the system logical output device” on page 34](#)

### related references

*XL C/C++ Programming Guide* (`_CEE_ENVFILE`)

*Language Environment Programming Reference*

## Example: setting and accessing environment variables

The following example shows how you can access and set environment variables from a COBOL program by calling the standard POSIX functions `getenv()` and `putenv()`.

Because `getenv()` and `putenv()` are C functions, you must pass arguments BY VALUE. Pass character strings as BY VALUE pointers that point to null-terminated strings. Compile programs that call these functions with the `NODYNAM` and `PGMNAME(LONGMIXED)` options.

```
CBL pgmname(longmixed),nodynam
Identification division.
Program-id. "envdemo".
Data division.
Working-storage section.
01 P pointer.
01 PATH pic x(5) value Z"PATH".
01 var-ptr pointer.
01 var-len pic 9(4) binary.
01 putenv-arg pic x(14) value Z"MYVAR=ABCDEFGH".
01 rc pic 9(9) binary.
Linkage section.
01 var pic x(5000).
Procedure division.
* Retrieve and display the PATH environment variable
  Set P to address of PATH
  Call "getenv" using by value P returning var-ptr
  If var-ptr = null then
    Display "PATH not set"
  Else
    Set address of var to var-ptr
    Move 0 to var-len
    Inspect var tallying var-len
      for characters before initial X"00"
    Display "PATH = " var(1:var-len)
  End-if
* Set environment variable MYVAR to ABCDEFGH
  Set P to address of putenv-arg
  Call "putenv" using by value P returning rc
  If rc not = 0 then
    Display "putenv failed"
  Stop run
End-if
Goback.
```

## Calling UNIX/POSIX APIs

You can call standard UNIX/POSIX functions from z/OS UNIX COBOL programs and from traditional z/OS COBOL programs by using the `CALL literal` statement. These functions are part of Language Environment.

Because these are C functions, you must pass arguments BY VALUE. Pass character strings as BY VALUE pointers that point to null-terminated strings. You must use the compiler options `NODYNAM` and `PGMNAME(LONGMIXED)` when you compile programs that call these functions.

You can call the `fork()`, `exec()`, and `spawn()` functions from a COBOL program or from a non-COBOL program in the same process as COBOL programs. However, be aware of these restrictions:

- From a forked process you cannot access any COBOL sequential, indexed, or relative files that were open when you issued the `fork`. File status code 92 is returned if you attempt such access (`CLOSE`, `READ`, `WRITE`, `REWRITE`, `DELETE`, or `START`). You can access line-sequential files that were open at the time of a `fork`.
- You cannot use the `fork()` function in a process in which any of the following conditions are true:
  - A COBOL `SORT` or `MERGE` is running.
  - A declarative is running.
  - The process has more than one Language Environment enclave (COBOL run unit).
  - The process has used any of the COBOL reusable environment interfaces.
  - The process has ever run a VS COBOL II program.

- With one exception, DD allocations are not inherited from a parent process to a child process. The exception is the local spawn, which creates a child process in the same address space as the parent process. You request a local spawn by setting the environment variable `_BPX_ SHAREAS=YES` before you invoke the `spawn()` function.

The `exec()` and `spawn()` functions start a new Language Environment enclave in the new UNIX process. Therefore the target program of the `exec()` or `spawn()` function is a main program, and all COBOL programs in the process start in initial state with all files closed.

Sample code for calling some of the POSIX routines is provided in the SIGYSAMP data set.

<i>Table 60. Samples with POSIX function calls</i>		
<b>Purpose</b>	<b>Sample</b>	<b>Functions used</b>
Shows how to use some of the file and directory routines	IGYTFL1	<ul style="list-style-type: none"> <li>• <code>getcwd()</code></li> <li>• <code>mkdir()</code></li> <li>• <code>rmdir()</code></li> <li>• <code>access()</code></li> </ul>
Shows how to use the <code>iconv</code> routines to convert data	IGYTCNV	<ul style="list-style-type: none"> <li>• <code>iconv_open()</code></li> <li>• <code>iconv()</code></li> <li>• <code>iconv_close()</code></li> </ul>
Shows the use of the <code>exec()</code> routine to run a new program along with other process-related routines	IGYTEXC, IGYTEXC1	<ul style="list-style-type: none"> <li>• <code>fork()</code></li> <li>• <code>getpid()</code></li> <li>• <code>getppid()</code></li> <li>• <code>execl()</code></li> <li>• <code>perror()</code></li> <li>• <code>wait()</code></li> </ul>
Shows how to get the <code>errno</code> value	IGYTERNO, IGYTGETE	<ul style="list-style-type: none"> <li>• <code>perror()</code></li> <li>• <code>fopen()</code></li> </ul>
Shows the use of the interprocess communication message routines	IGYTMSQ, IGYTMSQ2	<ul style="list-style-type: none"> <li>• <code>ftok()</code></li> <li>• <code>msgget()</code></li> <li>• <code>msgsnd()</code></li> <li>• <code>perror()</code></li> <li>• <code>fopen()</code></li> <li>• <code>fclose()</code></li> <li>• <code>msgrcv()</code></li> <li>• <code>msgctl()</code></li> <li>• <code>perror()</code></li> </ul>

#### **related tasks**

[“Running in z/OS UNIX environments” on page 435](#)

[“Setting and accessing environment variables” on page 436](#)

[“Accessing main program parameters under z/OS UNIX” on page 440](#)

*Language Environment Programming Guide*

## related references

*XL C/C++ Run-Time Library Reference*

*UNIX System Services Programming: Assembler Callable Services Reference*

## Accessing main program parameters under z/OS UNIX

When you run a COBOL program from the z/OS UNIX shell command line or with an `exec()` or `spawn()` function, the parameter list consists of three parameters passed by reference. You can access these parameters with standard COBOL coding.

### argument count

A binary fullword integer that contains the number of elements in each of the arrays that are passed in the second and third parameters.

### argument length list

An array of pointers. The *n*th entry in the array is the address of a fullword binary integer that contains the length of the *n*th entry in the argument list.

### argument list

An array of pointers. The *n*th entry in the array is the address of the *n*th character string passed as an argument in the `spawn()` or `exec()` function or in the command invocation. Each character string is null-terminated.

This array is never empty. The first argument is the character string that represents the name of the file associated with the process being started.

[“Example: accessing main program parameters under z/OS UNIX” on page 440](#)

## related tasks

[“Running in z/OS UNIX environments” on page 435](#)

[“Setting and accessing environment variables” on page 436](#)

[“Calling UNIX/POSIX APIs” on page 438](#)

[“Accessing main program parameters under z/OS” on page 478](#)

## Example: accessing main program parameters under z/OS UNIX

The following example shows the three parameters that are passed by reference, and shows the coding that you can use to access them.

```
Identification division.
Program-id. "EXECED".
*****
* This sample program displays arguments received via exec() *
* function of z/OS UNIX                                     *
*****
Data division.
Working-storage section.
01 curr-arg-count pic 9(9) binary value zero.
Linkage section.
01 arg-count pic 9(9) binary.                (1)
01 arg-length-list.                          (2)
    05 arg-length-addr pointer occurs 1 to 99999
        depending on curr-arg-count.
01 arg-list.                                (3)
    05 arg-addr pointer occurs 1 to 99999
        depending on curr-arg-count.
01 arg-length pic 9(9) binary.
01 arg pic X(65536).
Procedure division using arg-count arg-length-list arg-list.
*****
* Display number of arguments received                      *
*****
    Display "Number of arguments received: " arg-count
*****
* Display each argument passed to this program             *
*****
    Perform arg-count times
        Add 1 to curr-arg-count
* *****
```

```

* * Set address of arg-length to address of current      *
* * argument length and display                          *
* *****
  Set Address of arg-length
    to arg-length-addr(curr-arg-count)
  Display
    "Length of Arg " curr-arg-count " = " arg-length
* *****
* * Set address of arg to address of current argument    *
* * and display                                          *
* *****
  Set Address of arg to arg-addr(curr-arg-count)
  Display "Arg " curr-arg-count " = " arg (1:arg-length - 1)
End-Perform
Display "Display of arguments complete."
Goback.

```

- (1) This count contains the number of elements in the arrays that are passed in the second and third parameters.
- (2) This array contains a pointer to the length of the  $n$ th entry in the argument list.
- (3) This array contains a pointer to the  $n$ th character string passed as an argument in the `spawn()` or `exec()` function or in the command invocation.



## Chapter 24. Developing COBOL programs in the mixed AMODE Language Environment

This chapter describes developing programs in the mixed AMODE Language Environment.

### COBOL programs in AMODE 31 interacting with Java programs in AMODE 64

This topic describes writing COBOL programs running in AMODE 31 to interact with Java programs in AMODE 64.

**Note:** This topic does not apply to COBOL programs that contain OO features. Examples are programs that contain `INVOKE` statements, `OBJECT-REFERENCE` data items, and class definitions. An exception is `JNIEnvPtr`, a COBOL special register that is used in OO programs but can be used by non-OO COBOL programs to make Java Native Interface (JNI) calls.

**Note:** IBM SDK, Java Technology Edition V8.0.6.35 (JVM) is needed for this enhancement.

### Application calls between COBOL programs in AMODE 31 and Java programs in AMODE 64

This section describes how to configure and enable COBOL/Java program calls in a mixed 31/64-bit environment.

#### Applications initiated from COBOL in AMODE 31 calling Java methods in AMODE 64

For applications that start from COBOL and need to make JNI calls, it is necessary to get the JNI environment pointer through the COBOL special register `JNIEnvPtr`. This special register can be used to establish addressability to the `JNIEnv` and `JNINativeInterface` structures defined in copybook `JNI.cpy`. `JNIEnvPtr` can also be passed to JNI calls as the JNI environment pointer parameter.

Since the COBOL program will start the Java Virtual Machine (JVM), you can set the environment variable `COBJVMINITOPTIONS` to the desired JVM initialization options. To leverage the mixed AMODE JVM support, you must specify the JVM option `-XX:+Enable3164Interoperability`.

For example:

```
export COBJVMINITOPTIONS="-XX:+Enable3164Interoperability -Djava.library.path=."
```

Also set the `CLASSPATH` environment variable appropriately.

#### Applications initiated from Java in AMODE 64 calling COBOL native methods in AMODE 31

For applications that start from Java, the JNI environment pointer is passed as a parameter to COBOL native programs, so there is no need to use the `JNIEnvPtr` special register. For coding convenience, the `JNIEnvPtr` special register is still available. The JVM option `XX:+Enable3164Interoperability` is required to invoke native functions (COBOL programs) in AMODE 31.

#### Programming considerations:

In the mixed 31/64-bit environment, references to Java types must be declared as `PIC 9(18) COMP-5` in COBOL, that is, as an 8-byte data item. The `OBJECT-REFERENCE` type cannot be used as this data item maps to an incorrect 4-byte size in AMODE 31 COBOL programs. This applies to COBOL data items that are used to interact with JNI types such as `jobject`, `jclass`, `jfieldID`, `jmethodID`, `jarray`, `jarray<type>`, etc., when using them as parameters in JNI calls.

**Note:** Accesses to `EXTERNAL` data items and `EXTERNAL` files are not serialized.

## Building the mixed AMODE COBOL/Java interoperability application

This section describes how to build the mixed AMODE COBOL/Java interoperability application.

It is recommended that you build and run COBOL JNI applications in z/OS UNIX.

### Compiling

To compile the COBOL program, use the `cob2` command in a z/OS UNIX shell. Specify the `RENT`, `DLL` and `PGMNAME (LONGMIXED)` compiler options. The `THREAD` option is not mandatory, provided that there is only one COBOL program active in the run-unit at any time.

If the COBOL program includes the file `JNI.cpy` by using a `COPY` statement, specify the include subdirectory of the COBOL install directory, typically `/usr/lpp/cobol/include`, in the search order for copybooks. You can specify the include subdirectory by using the `-I` option of the `cob2` command or by setting the `SYSLIB` environment variable.

### Linking

To prepare the COBOL program for execution, link the object file with the following two DLL side files to create an executable module:

- `libjvm31.x`, which is provided with your 64-bit IBM Java Software Development Kit:  
`$JAVA_HOME/lib/s390x/j9vm`.
- `igzjni2.x`, which is provided in the `lib` subdirectory of the `cobol` directory in the z/OS UNIX file system, typically `/usr/lpp/cobol/lib`. This DLL side file is also available as the member `IGZXJNI2` in the `SCEELIB` PDS.

Do not link with the sidedeck `igzcjava.x`. This is used only by OO features, which is not supported in the mixed AMODE environment. Linking both `igzjni2.x` and `igzcjava.x` in the same program can lead to ABENDs.

**Note:** `$JAVA_HOME` is the home directory of the 64-bit IBM Java Software Development Kit.

## Running the mixed AMODE COBOL/Java interoperability program

This section lists the steps to run the program under z/OS UNIX.

To run the program under z/OS UNIX, set up your environment variables as follows:

- **STEPLIB:** Include the Language Environment datasets `SCEERUN` and `SCERUN2` in the `STEPLIB` concatenation.

For example:

```
export STEPLIB=CEE.SCEERUN2:CEE.SCEERUN
```

or use the default Language Environment installed on your system.

- **Java environment variables:** set the `LIBPATH` and `CLASSPATH` environment variables. `$JAVAHOME` is the home directory of the installed Java JDK.

For example:

```
export LIBPATH=${$JAVAHOME}/lib/s390x/j9vm:./  
export CLASSPATH=.
```

- **COBJVMINITOPTIONS:** Set this environment variable to Java JDK initialization options. The JVM option `-XX:+Enable3164Interoperability` is needed to initialize the mixed AMODE environment.

For example:

```
export COBJVMINITOPTIONS="-Djava.library.path=. -XX:+Enable3164Interoperability"
```

## Examples for mixed AMODE COBOL/Java interoperability application

This section provides examples for mixed AMODE COBOL/Java interoperability application.

Below is an example of a COBOL program starting in AMODE 31 and calling the main method in Java in AMODE 64.

### COBOL program example:

Compile and link the program below with cob2, where the program text is in source file prog.cbl.

```
cob2 -o prog.cbl -I/usr/lpp/cobol/include -q"dll" -q"pgmname(longmixed)" prog.cbl
/usr/lpp/cobol/lib/igzxjni2.x $JAVA_HOME/lib/s390x/j9vm/libjvm31.x
```

```
IDENTIFICATION DIVISION.
PROGRAM-ID. "PROG" recursive.

*
ENVIRONMENT DIVISION.
*
DATA DIVISION.
WORKING-STORAGE SECTION.

01 WS-CLASS-NAME      PIC X(50) VALUE LOW-VALUES.
01 WS-METHOD-NAME    PIC X(50).
01 WS-METHOD-SX      PIC X(50).

01 WS-MAIN-METHOD-ID PIC S9(18) COMP-5.
01 WS-CLASS-ID        PIC S9(18) COMP-5.
01 WS-NULL            PIC S9(18) COMP-5 VALUE ZERO.

01 WS-JNI-ENV         USAGE POINTER.

*
LINKAGE SECTION.

COPY JNI.

PROCEDURE DIVISION.
0010-MAIN.

    SET ADDRESS OF JNIEnv TO JNIEnvPtr.
    SET ADDRESS OF JNINativeInterface TO JNIEnv.

    DISPLAY "set class name".
    MOVE z"Greetings" TO WS-CLASS-NAME.
    CALL "__etoa" USING WS-CLASS-NAME.

* *****
* FIND CLASS
* *****
CALL FindClass USING BY VALUE
                JNIEnvPtr
                ADDRESS OF WS-CLASS-NAME
                RETURNING WS-CLASS-ID .

    IF WS-CLASS-ID = ZERO
        DISPLAY "CANT LOAD CLASS " WS-CLASS-NAME
        GOBACK
    END-IF.

* *****
* FIND METHOD (main)
* *****

    MOVE z"main" TO WS-METHOD-NAME.
    CALL "__etoa" USING WS-METHOD-NAME.

    MOVE z"([Ljava/lang/String;)V" TO WS-METHOD-SX.
    CALL "__etoa" USING WS-METHOD-SX.

    CALL GetStaticMethodId USING BY VALUE
                            JNIEnvPtr
                            WS-CLASS-ID
                            ADDRESS OF WS-METHOD-NAME
                            ADDRESS OF WS-METHOD-SX
                            RETURNING
                                WS-MAIN-METHOD-ID.

* *****
```

```

*      CALL METHOD (main)
*      *****
      CALL CallStaticVoidMethod USING BY VALUE
                                   JNIEnvPTR
                                   WS-CLASS-ID
                                   WS-MAIN-METHOD-ID.

      GOBACK.
0100-INIT.
      EXIT.

```

### Java program example:

Create a Java Class Hello World instance, with static main method.

```

public class Greetings {
    public static void main(String[] args){
        System.out.println("Greetings from AMODE 64");
    }
}

```

---

## Part 4. Structuring complex applications



---

## Chapter 25. Using subprograms

Many applications consist of several separately compiled programs linked together. A *run unit* (the COBOL term that is synonymous with the Language Environment term *enclave*) includes one or more object programs and can include object programs written in other Language Environment member languages.

Language Environment provides interlanguage support that lets your Enterprise COBOL programs call and be called by programs that meet the requirements of Language Environment.

**Name prefix alert:** Do not use program-names that start with prefixes used by IBM products. If you use programs whose names start with such prefixes, CALL statements might resolve to IBM library or compiler routines rather than to the intended program. For a list of prefixes to avoid, see the related task about identifying a program.

### related concepts

[“Main programs, subprograms, and calls” on page 449](#)

### related tasks

[“Identifying a program” on page 3](#)

[“Ending and reentering main programs or subprograms” on page 450](#)

[“Transferring control to another program” on page 451](#)

[“Making recursive calls” on page 461](#)

[“Calling to and from object-oriented programs” on page 461](#)

[“Using procedure and function](#)

[pointers” on page 461](#)

[“Making programs reentrant” on page 464](#)

[“Handling COBOL limitations with multithreading” on page 496](#)

[Language Environment Writing ILC Communication Applications](#)

### related references

[Language Environment Programming Guide](#) (Register conventions)

---

## Main programs, subprograms, and calls

If a COBOL program is the first program in a run unit, that COBOL program is the *main program*. Otherwise, it and all other COBOL programs in the run unit are *subprograms*. No specific source-code statements or options identify a COBOL program as a main program or subprogram.

Whether a COBOL program is a main program or subprogram can be significant for either of two reasons:

- Effect of program termination statements
- State of the program when it is reentered after returning

In the PROCEDURE DIVISION, a program can call another program (generally called a *subprogram*), and this called program can itself call other programs. The program that calls another program is referred to as the *calling* program, and the program it calls is referred to as the *called* program. When the processing of the called program is completed, the called program can either transfer control back to the calling program or end the run unit.

The called COBOL program starts running at the top of the PROCEDURE DIVISION.

### related tasks

[“Ending and reentering main programs or subprograms” on page 450](#)

[“Transferring control to another program” on page 451](#)

[“Making recursive calls” on page 461](#)

### related references

[Language Environment Programming Guide](#)

## Ending and reentering main programs or subprograms

Whether a program is left in its last-used state or its initial state, and to which caller it returns, can depend on the termination statements that you use.

You can use any of three termination statements in a program, but they have different effects as shown in the following table.

<i>Table 61. Effects of termination statements</i>		
<b>Termination statement</b>	<b>Main program</b>	<b>Subprogram</b>
EXIT PROGRAM	No action taken	Return to calling program without ending the run unit. An implicit EXIT PROGRAM statement is generated if the called program has no next executable statement.  In a threaded environment, the thread is not terminated unless the program is the first (oldest) one in the thread.
STOP RUN	Return to calling program. <sup>1</sup> (Might be the operating system, and application will end.)  STOP RUN terminates the run unit (also called an enclave in Language Environment terms), and deletes all dynamically called programs in the run unit and all programs link-edited with them. (It does not delete the main program.)  In a threaded environment, the entire Language Environment enclave is terminated, including all threads running within the enclave.  In a CICS environment, the entire transaction is terminated, including all programs running within the transaction.	Return directly to the program that called the main program. <sup>1</sup> (Might be the operating system, and application will end.)  STOP RUN terminates the run unit, and deletes all dynamically called programs in the run unit and all programs link-edited with them. (It does not delete the main program.)  In a threaded environment, the entire Language Environment enclave is terminated, including all threads running within the enclave.  In a CICS environment, the entire transaction is terminated, including all programs running within the transaction.
GOBACK	Return to calling program. <sup>1</sup> (Might be the operating system, and application will end.)  GOBACK terminates the run unit, and deletes all dynamically called programs in the run unit and all programs link-edited with them. (It does not delete the main program.)  In a threaded environment, the thread is terminated. <sup>2</sup>	Return to calling program.  In a threaded environment, if the program is the first program in a thread, the thread is terminated. <sup>2</sup>
<p>1. If the main program is called by a program written in another language that does not follow Language Environment linkage conventions, return is to this calling program.</p> <p>2. If the thread is the initial thread of execution in an enclave, the enclave is terminated.</p>		

A subprogram is usually left in its *last-used state* when it terminates with EXIT PROGRAM or GOBACK. The next time the subprogram is called in the run unit, its internal values are as they were left, except that return points for PERFORMed paragraphs and sections are reset to their initial values. (In contrast, a main program is initialized each time it is called.)

There are some cases in which programs will be in their initial state:

- A subprogram that is dynamically called and then canceled will be in the initial state the next time it is called.
- A program that has the INITIAL clause in the PROGRAM-ID paragraph will be in the initial state each time it is called.
- Data items defined in the LOCAL-STORAGE SECTION will be reset to the initial state specified by their VALUE clauses each time the program is called.

#### **related concepts**

[“Comparison of WORKING-STORAGE and LOCAL-STORAGE” on page 13](#)

*Language Environment Programming Guide* (What happens during termination: thread termination)

#### **related tasks**

[“Calling nested COBOL programs” on page 458](#)

[“Making recursive calls” on page 461](#)

## **Transferring control to another program**

---

You can use several different methods to transfer control to another program: static calls, dynamic calls, calls to nested programs, and calls to dynamic link libraries (DLLs).

In addition to making calls between Enterprise COBOL programs, you can also make static and dynamic calls between Enterprise COBOL and programs compiled with older compilers in all environments including CICS.

For restrictions about making calls with older levels of programs, see *Interoperability with older levels of IBM COBOL programs* in the *Enterprise COBOL for z/OS Migration Guide*.

Calling nested programs lets you create applications using structured programming techniques. You can use nested programs in place of PERFORM procedures to prevent unintentional modification of data items. Call nested programs using either the CALL *literal* or CALL *identifier* statement.

Calls to dynamic link libraries (DLLs) are an alternative to COBOL dynamic CALL, and are well suited to object-oriented COBOL applications, z/OS UNIX programs, and applications that interoperate with C/C++.

Under z/OS, linking two program objects together results logically in a single program with a primary entry point and an alternate entry point, each with its own name. Each name by which a subprogram is to be dynamically called must be known to the system. You must specify each such name in binder (linkage-editor) control statements as either a NAME or an ALIAS of the program object that contains the subprogram.

#### **related concepts**

[“AMODE switching” on page 454](#)

[“Performance considerations of static and dynamic calls” on page 456](#)

[“Nested programs” on page 459](#)

#### **related tasks**

[“Making static calls” on page 452](#)

[“Making dynamic calls” on page 452](#)

[“Making both static and dynamic calls” on page 456](#)

[“Calling nested COBOL programs” on page 458](#)

### related references

*Enterprise COBOL for z/OS Migration Guide*

(Interoperability with older levels of IBM COBOL programs)

## Making static calls

When you use the *CALL literal* statement in a program that is compiled using the NODYNAM and NODLL compiler options, a static call occurs. With these options, all *CALL literal* calls are handled as static calls.

With static calls statement, the COBOL program and all called programs are part of the same program object. When control is transferred, the called program already resides in storage, and a branch to it takes place. Subsequent executions of the *CALL* statement make the called program available in its last-used state unless the called program has the INITIAL attribute. In that case, the called program and each program directly or indirectly contained within it are placed into their initial state each time the called program is called within a run unit.

If you specify alternate entry points, a static *CALL* statement can use any alternate entry point to enter the called subprogram.

[“Examples: static and dynamic CALL statements” on page 456](#)

### related concepts

[“Performance considerations of static and dynamic calls” on page 456](#)

### related tasks

[“Making dynamic calls” on page 452](#)

[“Making both static and dynamic calls” on page 456](#)

[“Calling to and from object-oriented programs” on page 461](#)

### related references

[“DLL” on page 303](#)

[“DYNAM” on page 305](#)

*CALL* statement (*Enterprise COBOL for z/OS Language Reference*)

## Making dynamic calls

When you use a *CALL literal* statement in a program that is compiled using the DYNAM and the NODLL compiler options, or when you use the *CALL identifier* statement in a program that is compiled using the NODLL compiler option, a dynamic call occurs.

In these forms of the *CALL* statement, the called COBOL subprogram is not link-edited with the main program. Instead, it is link-edited into a separate program object, and is loaded at run time only when it is required (that is, when called). The program-name in the PROGRAM-ID paragraph or ENTRY statement must be identical to the corresponding program object name or program object alias of the program object that contains the program.

Each subprogram that you call with a dynamic *CALL* statement can be part of a different program object that is a member of either the system link library or a private library that you supply. In either case it must be in an MVS load library; it cannot reside in the z/OS UNIX file system. When a dynamic *CALL* statement calls a subprogram that is not resident in storage, the subprogram is loaded from secondary storage into the region or partition that contains the main program, and a branch to the subprogram is performed.

The first dynamic call to a subprogram within a run unit obtains a fresh copy of the subprogram. Subsequent calls to the same subprogram (by either the original caller or any other subprogram within the same run unit) result in a branch to the same copy of the subprogram in its last-used state, provided the subprogram does not possess the INITIAL attribute. Therefore, the reinitialization of either of the following items is your responsibility:

- GO TO statements that have been altered
- Data items

If you call the same COBOL program in different run units, a separate copy of WORKING-STORAGE is allocated for each run unit.

**Restrictions:** You cannot make dynamic calls to:

- COBOL DLL programs
- COBOL programs compiled with the PGMNAME (LONGMIXED) option, unless the program-name is less than or equal to eight characters in length and is all uppercase
- COBOL programs compiled with the PGMNAME (LONGUPPER) option, unless the program-name is less than or equal to eight characters in length
- More than one entry point in the same COBOL program (unless an intervening CANCEL statement was executed)

[“Examples: static and dynamic CALL statements” on page 456](#)

#### **related concepts**

[“When to use a dynamic](#)

[call with subprograms” on page 453](#)

[“Performance considerations of static and dynamic calls” on page 456](#)

#### **related tasks**

[“Canceling a subprogram” on page 453](#)

[“Making static calls” on page 452](#)

[“Making both static and dynamic calls” on page 456](#)

#### **related references**

[“DLL” on page 303](#)

[“DYNAM” on page 305](#)

ENTRY statement (*Enterprise COBOL for z/OS Language Reference*)

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

*Language Environment Programming Reference*

## **Canceling a subprogram**

When you issue a CANCEL statement for a subprogram, the storage that is occupied by the subprogram is freed. A subsequent call to the subprogram functions as though it were the first call. You can cancel a subprogram from a program other than the original caller.

If the called subprogram has more than one entry point, ensure that an intervening CANCEL statement is executed before you specify different entry points in a dynamic CALL statement to that subprogram.

After a CANCEL statement is processed for a dynamically called contained program, the program will be in its first-used state. However, the program is not loaded with the initial call, and storage is not freed after the program is canceled.

[“Examples: static and dynamic CALL statements” on page 456](#)

#### **related concepts**

[“Performance considerations of static and dynamic calls” on page 456](#)

## **When to use a dynamic call with subprograms**

Your decision to use dynamic calls with subprograms depends on factors such as location of the program object, frequency of calls to the subprograms, size of the subprograms, ease of maintenance, the need to call subprograms in their unused state, the need for AMODE switching, and when the program-names are known.

The program object that you want to dynamically call must be in an MVS load library rather than in the z/OS UNIX file system.

If subprograms are called in only a few conditions, you can use dynamic calls to bring in the subprograms only when needed.

If the subprograms are very large or there are many of them, using static calls might require too much main storage. Less total storage might be required to call and cancel one, then call and cancel another, than to statically call both.

If you are concerned about ease of maintenance, dynamic calls can help. Applications do not have to be link-edited again when dynamically called subprograms are changed.

When you cannot use the INITIAL attribute to ensure that a subprogram is placed in its unused state each time that it is called, you can set the unused state by using a combination of dynamic CALL and CANCEL statements. When you cancel a subprogram that was first called by a COBOL program, the next call causes the subprogram to be reinitialized to its unused state.

Using the CANCEL statement to explicitly cancel a subprogram that was dynamically loaded and branched to by a non-COBOL program does not result in any action being taken to release the subprogram's storage or to delete the subprogram.

Suppose you have an AMODE 24 program in the same run unit with Enterprise COBOL programs that you want to run in 31-bit addressing mode. COBOL dynamic call processing includes AMODE switching for AMODE 24 programs that call AMODE 31 programs, and vice versa. To have this implicit AMODE switching done, the Language Environment runtime options ALL31(OFF) and STACK(, , BELOW) must be in effect.

When dynamic call is performed, control is passed from the caller to a Language Environment library routine. After the switching is performed, control passes to the called program; the save area for the library routine will be positioned between the save area for the caller program and the save area for the called program.

If you do not know the program-name to be called until run time, use the format CALL *identifier*, where *identifier* is a data item that will contain the name of the called program at run time. For example, you could use CALL *identifier* when the program to be called varies depending on conditional processing in your program. CALL *identifier* is always dynamic, even if you use the NODYNAM compiler option.

[“Examples: static and dynamic CALL statements” on page 456](#)

#### **related concepts**

[“AMODE switching” on page 454](#)

[“Performance considerations of static and dynamic calls” on page 456](#)

#### **related tasks**

[“Making dynamic calls” on page 452](#)

#### **related references**

[“DYNAM” on page 305](#)

CALL statement (*Enterprise COBOL for z/OS Language Reference*)  
*Language Environment Programming Reference*


## **AMODE switching**

When you have an application that has COBOL subprograms, some of the COBOL subprograms can be AMODE 31 and some can be AMODE 24. To have this mixed AMODE support, the calls must be dynamic and the Language Environment runtime options ALL31(OFF) and STACK(, , BELOW) must be in effect.

If your application consists of only COBOL programs, and you are using dynamic calls, each COBOL subprogram will always be entered in the proper AMODE. For example, if you are using a dynamic call from an AMODE 31 COBOL program to an AMODE 24 COBOL program, the AMODE is automatically switched.


However, if you are using procedure pointers, function pointers, or other languages that call COBOL subprograms, you must ensure that when a COBOL program is called more than once in an enclave, it is entered in the same AMODE each time that it is called. The AMODE is not automatically switched in this case.

The following scenario shows that AMODE problems can arise when procedure pointers are used to call COBOL subprograms. This scenario is not supported because the COBOL program COBOLY is not entered in the same AMODE each time that it is called.



1. COBOLX is AMODE 31. It uses the SET statement to set a procedure pointer to COBOLZ. COBOLZ is a reentrant program object and is AMODE 31 and RMODE 24. COBOLX calls COBOLZ using the procedure pointer. COBOLZ is entered in AMODE 31.
2. COBOLZ returns to COBOLX.
3. COBOLX dynamically calls COBOLY, passing the procedure pointer for COBOLZ. COBOLY is a reentrant program object, and is AMODE 24 and RMODE 24. COBOLY is entered in AMODE 24.
4. COBOLY calls COBOLZ using the procedure pointer. This call causes COBOLZ to be entered in AMODE 24, which is not the same AMODE in which COBOLZ was entered when it was called the first time.

The following scenario uses a mix of COBOL and assembler language. This scenario is not supported because the COBOL program COBOLB is not entered in the same AMODE each time that it is called.



1. COBOLA is AMODE 31. COBOLA dynamically calls COBOLB. COBOLB is a reentrant program object and is AMODE 31 and RMODE 24. COBOLB is entered in AMODE 31.
2. COBOLB returns to COBOLA.
3. COBOLA dynamically calls ASSEM10, which is in assembler language. ASSEM10 is a reentrant program object, and is AMODE 24 and RMODE 24. ASSEM10 is entered in AMODE 24.
4. ASSEM10 loads COBOLB. ASSEM10 does a BALR instruction to COBOLB. COBOLB is entered in AMODE 24, which is not the same AMODE in which COBOLB was entered when it was called the first time.

#### related concepts

[“Storage and its addressability” on page 37](#)

[“When to use a dynamic call with subprograms” on page 453](#)

**related tasks**

[“Making dynamic calls” on page 452](#)

**related references**

*Language Environment Programming Reference* (ALL31)

## Performance considerations of static and dynamic calls

Because a statically called program is link-edited into the same program object as the calling program, a static call is faster than a dynamic call. A static call is the preferred method if your application does not require the services of the dynamic call.

Statically called programs cannot be deleted using CANCEL, so static calls might take more main storage. If storage is a concern, think about using dynamic calls. Storage usage of calls depends on whether:

- The subprogram is called only a few times. Regardless of whether it is called, a statically called program is loaded into storage; a dynamically called program is loaded only when it is called.
- You subsequently delete the dynamically called subprogram with a CANCEL statement.

You cannot delete a statically called program, but you can delete a dynamically called program. Using a dynamic call and then a CANCEL statement to delete the dynamically called program after it is no longer needed in the application (and not after each call to it) might require less storage than using a static call.

**related concepts**

[“When to use a dynamic call with subprograms” on page 453](#)

**related tasks**

[“Making static calls” on page 452](#)

[“Making dynamic calls” on page 452](#)

## Making both static and dynamic calls

You can use both static and dynamic CALL statements in the same program if you compile the program with the NODYNAM compiler option.

In this case, with the CALL *literal* statement, the called subprogram will be link-edited with the main program into one program object. The CALL *identifier* statement results in the dynamic invocation of a separate program object.

When a dynamic CALL statement and a static CALL statement to the same subprogram are issued within one program, a second copy of the subprogram is loaded into storage. Because this arrangement does not guarantee that the subprogram will be left in its last-used state, results can be unpredictable.

**related references**

[“DYNAM” on page 305](#)

## Examples: static and dynamic CALL statements

This example shows how you can code static and dynamic calls.

The example has three parts:

- Code that uses a static call to call a subprogram
- Code that uses a dynamic call to call the same subprogram
- The subprogram that is called by the two types of calls

The following example shows how you would code static calls:

```
PROCESS NODYNAM NODLL
IDENTIFICATION DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 RECORD-2          PIC X.          (6)
01 RECORD-1.         (2)
   05 PAY            PICTURE S9(5)V99.
   05 HOURLY-RATE    PICTURE S9V99.
   05 HOURS          PICTURE S99V9.
. . .
PROCEDURE DIVISION.
CALL "SUBPROG" USING RECORD-1.        (1)
CALL "PAYMASTR" USING RECORD-1 RECORD-2. (5)
STOP RUN.
```

The following example shows how you would code dynamic calls:

```
DATA DIVISION.
WORKING-STORAGE SECTION.
77 PGM-NAME          PICTURE X(8).
01 RECORD-2          PIC x.          (6)
01 RECORD-1.         (2)
   05 PAY            PICTURE S9(5)V99.
   05 HOURLY-RATE    PICTURE S9V99.
   05 HOURS          PICTURE S99V9.
. . .
PROCEDURE DIVISION.
. . .
MOVE "SUBPROG" TO PGM-NAME.
CALL PGM-NAME USING RECORD-1.        (1)
CANCEL PGM-NAME.
MOVE "PAYMASTR" TO PGM-NAME.        (4)
CALL PGM-NAME USING RECORD-1 RECORD-2. (5)
STOP RUN.
```

The following example shows a called subprogram that is called by each of the two preceding calling programs:

```
IDENTIFICATION DIVISION.
PROGRAM-ID. SUBPROG.
DATA DIVISION.
LINKAGE SECTION.
01 PAYREC.          (2)
   10 PAY           PICTURE S9(5)V99.
   10 HOURLY-RATE   PICTURE S9V99.
   10 HOURS         PICTURE S99V9.
77 PAY-CODE         PICTURE 9.        (6)
PROCEDURE DIVISION USING PAYREC.      (1)
. . .
EXIT PROGRAM.          (3)
ENTRY "PAYMASTR" USING PAYREC PAY-CODE. (5)
. . .
GOBACK.               (7)
```

**(1)**

Processing begins in the calling program. When the first CALL statement is executed, control is transferred to the first statement of the PROCEDURE DIVISION in SUBPROG, which is the called program.

In each of the CALL statements, the operand of the first USING option is identified as RECORD-1.

**(2)**

When SUBPROG receives control, the values within RECORD-1 are made available to SUBPROG; however, in SUBPROG they are referred to as PAYREC.

The PICTURE character-strings within PAYREC and PAY-CODE contain the same number of characters as RECORD-1 and RECORD-2, although the descriptions are not identical.

(3)

When processing within SUBPROG reaches the EXIT PROGRAM statement, control is returned to the calling program. Processing continues in that program until the second CALL statement is executed.

(4)

In the example of a dynamically called program, because the second CALL statement refers to another entry point within SUBPROG, a CANCEL statement is executed before the second CALL statement.

(5)

With the second CALL statement in the calling program, control is again transferred to SUBPROG, but this time processing begins at the statement following the ENTRY statement in SUBPROG.

(6)

The values within RECORD-1 are again made available to PAYREC. In addition, the value in RECORD-2 is now made available to SUBPROG through the corresponding USING operand, PAY-CODE.

When control is transferred the second time from the statically linked program, SUBPROG is made available in its last-used state (that is, if any values in SUBPROG storage were changed during the first execution, those changed values are still in effect). When control is transferred from the dynamically linked program, however, SUBPROG is made available in its initial state, because of the CANCEL statement that has been executed.

(7)

When processing reaches the GOBACK statement, control is returned to the calling program at the statement immediately after the second CALL statement.

In any given execution of the called program and either of the two calling programs, if the values within RECORD-1 are changed between the time of the first CALL and the second, the values passed at the time of the second CALL statement will be the changed, not the original, values. If you want to use the original values, you must save them.

## Calling nested COBOL programs

By calling nested programs, you can create applications that use structured programming techniques. You can also call nested programs instead of PERFORM procedures to prevent unintentional modification of data items.

Use either CALL *literal* or CALL *identifier* statements to make calls to nested programs.

You can call a contained program only from its directly containing program unless you identify the contained program as COMMON in its PROGRAM-ID paragraph. In that case, you can call the *common program* from any program that is contained (directly or indirectly) in the same program as the common program. Only contained programs can be identified as COMMON. Recursive calls are not allowed.

Follow these guidelines when using nested program structures:

- Code an IDENTIFICATION DIVISION in each program. All other divisions are optional.
- Optionally make the name of each contained program unique. Although the names of contained programs are not required to be unique (as described in the related reference about scope of names), making the names unique could help make your application more maintainable. You can use any valid user-defined word or an alphanumeric literal as the name of a contained program.
- In the outermost program, code any CONFIGURATION SECTION entries that might be required. Contained programs cannot have a CONFIGURATION SECTION.
- Include each contained program in the containing program immediately before the END PROGRAM marker of the containing program.
- Use an END PROGRAM marker to terminate contained and containing programs.

You cannot use the THREAD option when compiling programs that contain nested programs.

### related concepts

[“Nested programs” on page 459](#)

## related references

[“Scope of names” on page 460](#)


## Nested programs

A COBOL program can *nest*, or contain, other COBOL programs. The nested programs can themselves contain other programs. A nested program can be directly or indirectly contained in a program.

There are four main advantages to nesting called programs:

- Nested programs provide a method for creating modular functions and maintaining structured programming techniques. They can be used analogously to perform procedures (using the PERFORM statement), but with more structured control flow and with the ability to protect local data items.
- Nested programs let you debug a program before including it in an application.
- Nested programs enable you to compile an application with a single invocation of the compiler.
- Calls to nested programs have the best performance of all the forms of COBOL CALL statements.

The following example describes a nested structure that has directly and indirectly contained programs:



[“Example: structure of nested programs” on page 460](#)

## related tasks


[“Calling nested COBOL programs” on page 458](#)

## related references

[“Scope of names” on page 460](#)

## Example: structure of nested programs

The following example shows a nested structure with some contained programs that are identified as COMMON.



The following table describes the calling hierarchy for the structure that is shown in the example above. Programs A12, A2, and A3 are identified as COMMON, and the calls associated with them differ.

This program	Can call these programs	And can be called by these programs
A	A1, A2, A3	None
A1	A11, A12, A2, A3	A
A11	A111, A12, A2, A3	A1
A111	A12, A2, A3	A11
A12	A2, A3	A1, A11, A111
A2	A3	A, A1, A11, A111, A12, A3
A3	A2	A, A1, A11, A111, A12, A2

In this example, note that:

- A2 cannot call A1 because A1 is not common and is not contained in A2.
- A1 can call A2 because A2 is common.

## Scope of names

Names in nested structures are divided into two classes: local and global. The class determines whether a name is known beyond the scope of the program that declares it. A specific search sequence locates the declaration of a name after it is referenced in a program.

### Local names

Names (except the program-name) are local unless declared to be otherwise. Local names are visible or accessible only within the program in which they are declared. They are not visible or accessible to contained and containing programs.

### Global names

A name that is global (indicated by using the GLOBAL clause) is visible and accessible to the program in which it is declared and to all the programs that are directly and indirectly contained in that program. Therefore, the contained programs can share common data and files from the containing program simply by referencing the names of the items.

Any item that is subordinate to a global item (including condition-names and indexes) is automatically global.

You can declare the same name with the GLOBAL clause more than one time, provided that each declaration occurs in a different program. Be aware that you can mask, or hide, a name in a nested structure by having the same name occur in different programs in the same containing structure. However, such masking could cause problems during a search for a name declaration.

#### *Searches for name declarations*

When a name is referenced in a program, a search is made to locate the declaration for that name. The search begins in the program that contains the reference and continues outward to the containing programs until a match is found. The search follows this process:

1. Declarations in the program are searched.
2. If no match is found, only global declarations are searched in successive outer containing programs.
3. The search ends when the first matching name is found. If no match is found, an error exists.

The search is for a global name, not for a particular type of object associated with the name such as a data item or file connector. The search stops when any match is found, regardless of the type of object. If the object declared is of a different type than that expected, an error condition exists.

## Making recursive calls

---

A called program can directly or indirectly execute its caller. For example, program X calls program Y, program Y calls program Z, and program Z then calls program X. This type of call is *recursive*.

To make a recursive call, you must code the RECURSIVE clause in the PROGRAM-ID paragraph of the recursively called program. If you try to recursively call a COBOL program that does not have the RECURSIVE clause in the PROGRAM-ID paragraph, a condition is signaled. If the condition remains unhandled, the run unit will end.

#### **related tasks**

[“Identifying a program as recursive” on page 4](#)

#### **related references**

PROGRAM-ID paragraph (*Enterprise COBOL for z/OS Language Reference*)

## Calling to and from object-oriented programs

---

When you create applications that contain object-oriented (OO) programs, the OO COBOL programs are DLL programs and can be in one or more dynamic link libraries (DLLs). Each class definition must be in a separate DLL, however.

Calls to or from COBOL DLL programs must either use DLL linkage or be static calls. COBOL dynamic calls to or from COBOL DLL programs are not supported.

If you must call a COBOL DLL program from a COBOL non-DLL program, other means to ensure that the DLL linkage mechanism is followed are available.

## Using procedure and function pointers

---

You can set procedure-pointer and function-pointer data items only by using format 6 of the SET statement.

*Procedure pointers* are data items defined with the USAGE IS PROCEDURE-POINTER clause. *Function pointers* are data items defined with the USAGE IS FUNCTION-POINTER clause. In this information, "pointer" refers to either a procedure-pointer data item or a function-pointer data item. You can set either of these data items to contain entry addresses of, or pointers to, these entry points:

- Another COBOL program that is not nested. For example, to have a user-written error-handling routine take control when an exception condition occurs, you must first pass the entry address of the routine to CEEHDLR, a condition-management Language Environment callable service, so that the routine is registered.
- A program written in another language. For example, to receive the entry address of a C function, call the function with the CALL RETURNING statement. It will return a pointer that you can either use as a function pointer or convert to a procedure pointer by using a form of the SET statement.
- An alternate entry point in another COBOL program (as defined in an ENTRY statement).

The SET statement sets the pointer to refer either to an entry point in the same program object as your program, to a separate program object, or to an entry point that is exported from a DLL, depending on the DYNAM | NODYNAM and DLL | NODLL compiler options. Therefore, consider these factors when using these pointer data items:

- If you compile a program with the NODYNAM and NODLL options and set a pointer item to a literal value (to an actual name of an entry point), the value must refer to an entry point in the same program object. Otherwise the reference cannot be resolved.
- If you compile a program with the NODLL option and either set a pointer item to an identifier that will contain the name of the entry point at run time or set the pointer item to a literal and compile with the DYNAM option, then the pointer item, whether a literal or variable, must point to an entry point in a separate program objectlink. The entry point can be either the primary entry point or an alternate entry point named in an ALIAS binder (linkage-editor) statement.
- If you compile with the NODYNAM and DLL options and set a pointer item to a literal value (the actual name of an entry point), the value must refer to an entry point in the same program object or to an entry-point name that is exported from a DLL module. In the latter case you must include the DLL side file for the target DLL module in the link-edit of your program object.
- If you compile with the NODYNAM and DLL options and set a pointer item to an identifier (a data item that contains the entry point name at run time), the identifier value must refer to the entry-point name that is exported from a DLL module. In this case the DLL module name must match the name of the exported entry point.

If you set a pointer item to an entry address in a dynamically called program object, and your program subsequently cancels that dynamically called module, then that pointer item becomes undefined. Reference to it thereafter is not reliable.

Procedure pointer and function pointer calls are supported for AMODE 24 applications. However, the addressing mode cannot be switched for these calls, so the called and calling programs must have the same addressing mode at execution time.

COBOL entry points with the AMODE ANY attribute can be entered in either AMODE 31 or AMODE 24. However, the AMODE value that is in effect when the program is entered for the first time must also be in effect for all subsequent reentries of the program during the current Language Environment enclave.

For COBOL V5 and later, procedure and function pointers point to a function descriptor rather than directly to the entry point. If you have a data-only module, a table for example, you can no longer use the technique:

```
77 DATA-FUNCTION-PTR USAGE FUNCTION-POINTER.
77 DATA-PTR REDEFINES DATA-FUNCTION-PTR USAGE POINTER.

SET DATA-FUNCTION-PTR TO ENTRY "DATAONLY"
SET ADDRESS OF DATA TO DATA_PTR
```

However, you need to do the following change:

```
77 DATA-PTR USAGE POINTER.

CALL "DATAONLY" RETURNING DATA-PTR
SET ADDRESS OF DATA TO DATA_PTR
```

with the data-only module revised to return the address of the data, and below is the LP(32) example:

```
DATAONLY CSECT
          USING  *,15
          LA     15,DATA
          BR     14
*
DATA      DC     ...
...
          END
```

The revised method also works with earlier COBOLs.

Calls to procedure and function pointers must be from a module with a Language Environment stack frame, as will be the case for any high-level programming language. If such a call is to be made from an assembler module, an LE stack frame must be provided by using the CEEENTRY and CEETERM macros, along with the associated register content requirements.

#### **related tasks**

[“Deciding which type of pointer to use” on page 463](#)

[“Calling alternate entry points” on page 464](#)

[“Using procedure or function pointers with DLLs” on page 486](#)

#### **related references**

[“DLL” on page 303](#)

[“DYNAM” on page 305](#)

CANCEL statement (*Enterprise COBOL for z/OS Language Reference*)

Format 6: SET for procedure-pointer and function-pointer data items  
(*Enterprise COBOL for z/OS Language Reference*)

ENTRY statement (*Enterprise COBOL for z/OS Language Reference*)  
[MVS Program Management: User's Guide and Reference](#)

## **Deciding which type of pointer to use**

Use procedure pointers to call other COBOL programs and to call Language Environment callable services. Use function pointers to communicate with C/C++ programs or with services provided by the Java Native Interface.

Procedure pointers are more efficient than function pointers for COBOL-to-COBOL calls, and are required for calls to Language Environment condition-handling services.

Many callable services written in C return function pointers. You can call such a C function pointer from your COBOL program by using COBOL function pointers as shown below.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. DEMO.
ENVIRONMENT DIVISION.
DATA DIVISION.
*
WORKING-STORAGE SECTION.
01 FP USAGE FUNCTION-POINTER.
*
PROCEDURE DIVISION.
CALL "c-function" RETURNING FP.
CALL FP.
```

#### **related tasks**

[“Using procedure or function pointers with DLLs” on page 486](#)

[“Accessing JNI services” on page 601](#)

## Calling alternate entry points

You can specify another entry point at which a program will begin running by using the ENTRY label in the called program.

Static calls to alternate entry points work without restriction.

Dynamic calls to alternate entry points require either explicitly specified NAME and/or ALIAS binder (linkage-editor) control statements, or use of the NAME compiler option, which generates them automatically.

Dynamically calling a compile unit at more than one entry point, including the primary entry point will produce a unique instance of WORKING-STRAGE for each such entry, as if separate compile units were being called.

If you share one WORKING-STRAGE instance among several entry points without statically linking the compile unit with its caller, you must make it a DLL and use EXPORTALL to expose the secondary entry points, and call the compile unit using a DLL call rather than a dynamic call.

[“Examples: static and dynamic CALL statements” on page 456](#)

### related references

[“NAME” on page 319](#)

CANCEL statement (*Enterprise COBOL for z/OS Language Reference*)

ENTRY statement (*Enterprise COBOL for z/OS Language Reference*)

[MVS Program Management: User's Guide and Reference](#)

## Making programs reentrant

---

If more than one user will run an application program at the same time (for example, users in different address spaces accessing a program that resides in the link pack area), you must make the program *reentrant* by compiling with the RENT option.

You do not need to worry about multiple copies of variables. The compiler creates the necessary reentrancy controls in the object module.

The following Enterprise COBOL programs must be reentrant:

- Programs to be used with CICS
- Programs to be preloaded with IMS
- Programs to be used as DB2 stored procedures
- Programs to be run in the z/OS UNIX environment
- Programs that are enabled for DLL support
- Programs that use object-oriented syntax

For reentrant programs, use the DATA compiler option and the HEAP and ALL31 runtime options to control whether dynamic data areas, such as WORKING-STORAGE, are obtained from storage below or above the 16 MB line.

### related concepts

[“Storage and its addressability” on page 37](#)

### related tasks

[“Compiling programs to create DLLs” on page 482](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

### related references

[“RENT” on page 330](#)

[“DATA” on page 300](#)

[Language Environment Programming Reference \(ALL31, HEAP\)](#)

---

## Chapter 26. Sharing data

If a run unit consists of several separately compiled programs that call each other, the programs must be able to communicate with each other. They also usually need access to common data.

This information describes how you can write programs that share data with other programs. In this information, a *subprogram* is any program that is called by another program.

### related tasks

[“Using data from another program” on page 15](#)

[“Sharing data with Java” on page 605](#)

[“Passing data” on page 465](#)

[“Coding the LINKAGE SECTION” on page 469](#)

[“Coding the PROCEDURE DIVISION](#)

[for passing arguments” on page 470](#)

[“Passing return-code information” on page 474](#)

[“Sharing data by using the EXTERNAL clause” on page 475](#)

[“Sharing files between programs](#)

[\(external files\)” on page 475](#)

[“Accessing main program parameters under z/OS” on page 478](#)

---

## Passing data

You can choose among three ways of passing data between programs: BY REFERENCE, BY CONTENT, or BY VALUE.

### BY REFERENCE

The subprogram refers to and processes the data items in the storage of the calling program rather than working on a copy of the data. BY REFERENCE is the assumed passing mechanism for a parameter if none of the three ways is specified or implied for the parameter.

### BY CONTENT

The calling program passes only the contents of the *literal* or *identifier*. The called program cannot change the value of the *literal* or *identifier* in the calling program, even if it modifies the data item in which it received the *literal* or *identifier*.

### BY VALUE


The calling program or method passes the value of the *literal* or *identifier*, not a reference to the sending data item. The called program or invoked method can change the parameter. However, because the subprogram or method has access only to a temporary copy of the sending data item, any change does not affect the argument in the calling program.

The following figure shows the differences in values passed BY REFERENCE, BY CONTENT, and BY VALUE:

```

MOVE 16 TO X.
CALL ABC USING
  BY REFERENCE X
  BY CONTENT X
  BY VALUE X
  BY CONTENT ADDRESS OF X

```



Determine which of these data-passing methods to use based on what you want your program to do with the data.

Table 62. <i>Methods for passing data in the CALL statement</i>		
Code	Purpose	Comments
CALL . . . BY REFERENCE <i>identifier</i>	To have the definition of the argument of the CALL statement in the calling program and the definition of the parameter in the called program share the same memory	Any changes made by the subprogram to the parameter affect the argument in the calling program.
CALL . . . BY REFERENCE ADDRESS OF <i>identifier</i>	To pass the address of <i>identifier</i> to a called program, where <i>identifier</i> is an item in the LINKAGE SECTION	Any changes made by the subprogram to the address affect the address in the calling program.
CALL . . . BY REFERENCE <i>file-name</i>	To pass a data control block (DCB) to assembler programs	The file-name must reference a QSAM sequential file. <sup>1</sup>
CALL . . . BY CONTENT ADDRESS OF <i>identifier</i>	To pass a copy of the address of <i>identifier</i> to a called program	Any changes to the copy of the address will not affect the address of <i>identifier</i> , but changes to <i>identifier</i> using the copy of the address will cause changes to <i>identifier</i> .
CALL . . . BY CONTENT <i>identifier</i>	To pass a copy of the identifier to the subprogram	Changes to the parameter by the subprogram will not affect the caller's identifier.
CALL . . . BY CONTENT <i>literal</i>	To pass a copy of a literal value to a called program	
CALL . . . BY CONTENT LENGTH OF <i>identifier</i>	To pass a copy of the length of a data item	The calling program passes the length of the <i>identifier</i> from its LENGTH special register.

Table 62. <i>Methods for passing data in the CALL statement (continued)</i>		
Code	Purpose	Comments
A combination of BY REFERENCE and BY CONTENT such as:  <pre>CALL 'ERRPROC'   USING BY REFERENCE A   BY CONTENT LENGTH OF A.</pre>	To pass both a data item and a copy of its length to a subprogram	
CALL . . . BY VALUE <i>identifier</i>	To pass data to a program, such as a C/C++ program, that uses BY VALUE parameter linkage conventions	A copy of the identifier is passed directly in the parameter list.
CALL . . . BY VALUE <i>literal</i>	To pass data to a program, such as a C/C++ program, that uses BY VALUE parameter linkage conventions	A copy of the literal is passed directly in the parameter list.
CALL . . . BY VALUE ADDRESS OF <i>identifier</i>	To pass the address of <i>identifier</i> to a called program. This is the recommended way to pass data to a C/C++ program that expects a pointer to the data.	Any changes to the copy of the address will not affect the address of <i>identifier</i> , but changes to <i>identifier</i> using the copy of the address will cause changes to <i>identifier</i> .
CALL . . . RETURNING	To call a C/C++ function with a function return value	
1. File-names as CALL operands are allowed as an IBM extension to COBOL. Any use of the extension generally depends on the specific internal implementation of the compiler. Control block field settings might change in future releases. Any changes made to the control block are the user's responsibility and are not supported by IBM.		

#### related concepts

[“Storage and its addressability” on page 37](#)

#### related tasks

[“Describing arguments in](#)

[the calling program” on page 468](#)

[“Describing parameters](#)

[in the called program” on page 468](#)

[“Testing for OMITTED arguments” on page 469](#)

[“Specifying CALL . . . RETURNING” on page 475](#)

[“Sharing data by using the EXTERNAL clause” on page 475](#)

[“Sharing files between programs](#)

[\(external files\)” on page 475](#)

[“Sharing data with Java” on page 605](#)

#### related references

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

The USING phrase (*Enterprise COBOL for z/OS Language Reference*)

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## Describing arguments in the calling program

In the calling program, describe arguments in the DATA DIVISION in the same manner as other data items in the DATA DIVISION.

Storage for arguments is allocated only in the outermost program. For example, program A calls program B, which calls program C. Data items are allocated in program A. They are described in the LINKAGE SECTION of programs B and C, making the one set of data available to all three programs.

If you reference data in a file, the file must be open when the data is referenced.

Code the USING phrase of the CALL statement to pass the arguments. If you pass a data item BY VALUE, it must be an elementary item.

To pass CALL arguments from AMODE 31 programs to AMODE 24 programs, you must ensure that the arguments are in storage below the 16 MB line to be addressed by the AMODE 24 subprogram.

- For reentrant AMODE 31 programs, compile the program with the DATA(24) option, or specify the Language Environment runtime option HEAP( , , BELOW) if WORKING-STORAGE is allocated from HEAP storage. For more information about when WORKING-STORAGE is allocated from HEAP storage, see [“Storage and its addressability” on page 37](#).
- For nonreentrant programs that are compiled with the NORENT option, compile with the RMODE(24) or RMODE(AUTO) option. Consequently, the following items are allocated below the 16 MB line, and can be passed as arguments to AMODE 24 programs:
  - WORKING-STORAGE data items without the EXTERNAL clause
  - FD record areas
  - QSAM buffers
- For mixed AMODE applications, the Language Environment runtime options ALL31(OFF) and STACK( , , BELOW) are required. Consequently, the LOCAL-STORAGE SECTION data items and data items with the EXTERNAL attributes will be allocated below the 16 MB line, and can be passed as arguments to AMODE 24 programs.

### related concepts

[“Storage and its addressability” on page 37](#)

### related tasks

[“Coding the LINKAGE SECTION” on page 469](#)

[“Coding the PROCEDURE DIVISION for passing arguments” on page 470](#)

### related references

The USING phrase (*Enterprise COBOL for z/OS Language Reference*)

## Describing parameters in the called program

You must know what data is being passed from the calling program and describe it in the LINKAGE SECTION of each program that is called directly or indirectly by the calling program.

Code the USING phrase after the PROCEDURE DIVISION header to name the parameters that receive the data that is passed from the calling program.

When arguments are passed to the subprogram BY REFERENCE, it is invalid for the subprogram to specify any relationship between its parameters and any fields other than those that are passed and defined in the main program. The subprogram must not:

- Define a parameter to be larger in total number of bytes than the corresponding argument.
- Use subscript references to refer to elements beyond the limits of tables that are passed as arguments by the calling program.
- Use reference modification to access data beyond the length of defined parameters.

- Manipulate the address of a parameter in order to access other data items that are defined in the calling program.

If any of the rules above are violated, unexpected results might occur.

#### related tasks

[“Coding the LINKAGE SECTION” on page 469](#)

#### related references

The USING phrase (*Enterprise COBOL for z/OS Language Reference*)

## Testing for OMITTED arguments

You can specify that one or more BY REFERENCE arguments are not to be passed to a called program by coding the OMITTED keyword in place of those arguments in the CALL statement.

For example, to omit the second argument when calling program sub1, code this statement:

```
Call 'sub1' Using PARM1, OMITTED, PARM3
```

The arguments in the USING phrase of the CALL statement must match the parameters of the called program in number and position.

In a called program, you can test whether an argument was passed as OMITTED by comparing the address of the corresponding parameter to NULL. For example:

```
Program-ID. sub1.
.
.
Procedure Division Using RPARM1, RPARM2, RPARM3.
  If Address Of RPARM2 = Null Then
    Display 'No 2nd argument was passed this time'
  Else
    Perform Process-Param-2
  End-If
```

#### related references

CALL statement (*Enterprise COBOL for z/OS Language Reference*)


The USING phrase (*Enterprise COBOL for z/OS Language Reference*)

## Coding the LINKAGE SECTION

Code the same number of data-names in the identifier list of the called program as the number of arguments in the calling program. Synchronize by position, because the compiler passes the first argument from the calling program to the first identifier of the called program, and so on.

You will introduce errors if the number of data-names in the identifier list of a called program is greater than the number of arguments passed from the calling program. The compiler does not try to match arguments and parameters.

The following figure shows a data item being passed from one program to another (implicitly BY REFERENCE):



In the calling program, the code for parts (PARTCODE) and the part number (PARTNO) are distinct data items. In the called program, by contrast, the code for parts and the part number are combined into one data item (PART-ID). In the called program, a reference to PART-ID is the only valid reference to these items.

#### related tasks

[“Accessing main program parameters under z/OS” on page 478](#)

## Coding the PROCEDURE DIVISION for passing arguments

If you pass an argument BY VALUE, code the USING BY VALUE clause in the PROCEDURE DIVISION header of the subprogram. If you pass an argument BY REFERENCE or BY CONTENT, you do not need to indicate in the header how the argument was passed.

```

PROCEDURE DIVISION USING BY VALUE. . .
PROCEDURE DIVISION USING. . .
PROCEDURE DIVISION USING BY REFERENCE. . .
  
```

The first header above indicates that the data items are passed BY VALUE; the second or third headers indicate that the items are passed BY REFERENCE or BY CONTENT.

#### related references

The procedure division header (*Enterprise COBOL for z/OS Language Reference*)

The USING phrase (*Enterprise COBOL for z/OS Language Reference*)

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

## Grouping data to be passed

Consider grouping all the data items that you need to pass between programs and putting them under one level-01 item. If you do so, you can pass a single level-01 record.

Note that if you pass a data item BY VALUE, it must be an elementary item.

To lessen the possibility of mismatched records, put the level-01 record into a copy library and copy it into both programs. That is, copy it in the WORKING-STORAGE SECTION of the calling program and in the LINKAGE SECTION of the called program.

#### related tasks

[“Coding the LINKAGE SECTION” on page 469](#)

#### related references

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

## Handling null-terminated strings

COBOL supports null-terminated strings when you use string-handling statements together with null-terminated literals and the hexadecimal literal X'00'.

You can manipulate null-terminated strings (passed from a C program, for example) by using string-handling mechanisms such as those in the following code:

```
01 L      pic X(20) value z'ab'.
01 M      pic X(20) value z'cd'.
01 N      pic X(20).
01 N-Length pic 99 value zero.
01 Y      pic X(13) value 'Hello, World!'.
```

To determine the length of a null-terminated string, and display the value of the string and its length, code:

```
Inspect N tallying N-length for characters before initial X'00'
Display 'N: ' N(1:N-length) ' Length: ' N-length
```

To move a null-terminated string to an alphanumeric string, but delete the null, code:

```
Unstring N delimited by X'00' into X
```

To create a null-terminated string, code:

```
String Y      delimited by size
X'00'         delimited by size
into N.
```

To concatenate two null-terminated strings, code:

```
String L      delimited by x'00'
M             delimited by x'00'
X'00'         delimited by size
into N.
```

### related tasks

[“Manipulating null-terminated strings” on page 106](#)

### related references

Null-terminated alphanumeric literals  
(*Enterprise COBOL for z/OS Language Reference*)

## Using pointers to process a chained list

When you need to pass and receive addresses of record areas, you can use pointer data items, which are either data items that are defined with the USAGE IS POINTER clause or are ADDRESS OF special registers.

A typical application for using pointer data items is in processing a *chained list*, a series of records in which each record points to the next.

When you pass addresses between programs in a chained list, you can use NULL to assign the value of an address that is not valid (nonnumeric 0) to a pointer item in either of two ways:

- Use a VALUE IS NULL clause in its data definition.
- Use NULL as the sending field in a SET statement.

In the case of a chained list in which the pointer data item in the last record contains a null value, you can use this code to check for the end of the list:

```
IF PTR-NEXT-REC = NULL
  '(logic for end of chain)
```

If the program has not reached the end of the list, the program can process the record and move on to the next record.

The data passed from a calling program might contain header information that you want to ignore. Because pointer data items are not numeric, you cannot directly perform arithmetic on them. However, to bypass header information, you can use the SET statement to increment the passed address.

[“Example: using pointers to process a chained list” on page 472](#)

#### related tasks

[“Coding the LINKAGE SECTION” on page 469](#)

[“Coding the PROCEDURE DIVISION for passing arguments” on page 470](#)


#### related references

SET statement (*Enterprise COBOL for z/OS Language Reference*)

### Example: using pointers to process a chained list

The following example shows how you might process a linked list, that is, a chained list of data items.

For this example, picture a chained list of data that consists of individual salary records. The following figure shows one way to visualize how the records are linked in storage. The first item in each record except the last points to the next record. The first item in the last record contains a null value (instead of a valid address) to indicate that it is the last record.



The high-level pseudocode for an application that processes these records might be:

```
Obtain address of first record in chained list from routine
Check for end of the list
Do until end of the list
  Process record
  Traverse to the next record
End
```

The following code contains an outline of the calling program, LISTS, used in this example of processing a chained list.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. LISTS.
ENVIRONMENT DIVISION.
DATA DIVISION.
*****
WORKING-STORAGE SECTION.
77 PTR-FIRST          POINTER VALUE IS NULL.          (1)
77 DEPT-TOTAL         PIC 9(4) VALUE IS 0.
*****
LINKAGE SECTION.
01 SALARY-REC.
```

```

02 PTR-NEXT-REC    POINTER.                                (2)
02 NAME            PIC X(20).
02 DEPT            PIC 9(4).
02 SALARY          PIC 9(6).
01 DEPT-X          PIC 9(4).
*****
PROCEDURE DIVISION USING DEPT-X.
*****
* FOR EVERYONE IN THE DEPARTMENT RECEIVED AS DEPT-X,
* GO THROUGH ALL THE RECORDS IN THE CHAINED LIST BASED ON THE
* ADDRESS OBTAINED FROM THE PROGRAM CHAIN-ANCH
* AND ACCUMULATE THE SALARIES.
* IN EACH RECORD, PTR-NEXT-REC IS A POINTER TO THE NEXT RECORD
* IN THE LIST; IN THE LAST RECORD, PTR-NEXT-REC IS NULL.
* DISPLAY THE TOTAL.
*****
CALL "CHAIN-ANCH" USING PTR-FIRST                          (3)
SET ADDRESS OF SALARY-REC TO PTR-FIRST                      (4)
*****
PERFORM WITH TEST BEFORE UNTIL ADDRESS OF SALARY-REC = NULL (5)

    IF DEPT = DEPT-X
        THEN ADD SALARY TO DEPT-TOTAL
        ELSE CONTINUE
    END-IF
    SET ADDRESS OF SALARY-REC TO PTR-NEXT-REC                (6)

END-PERFORM
*****
DISPLAY DEPT-TOTAL
GOBACK.

```

(1)

PTR-FIRST is defined as a pointer data item with an initial value of NULL. On a successful return from the call to CHAIN-ANCH, PTR-FIRST contains the address of the first record in the chained list. If something goes wrong with the call, and PTR-FIRST never receives the value of the address of the first record in the chain, a null value remains in PTR-FIRST and, according to the logic of the program, the records will not be processed.

(2)

The LINKAGE SECTION of the calling program contains the description of the records in the chained list. It also contains the description of the department code that is passed in the USING clause of the CALL statement.

(3)

To obtain the address of the first SALARY-REC record area, the LISTS program calls the program CHAIN-ANCH.

(4)

The SET statement bases the record description SALARY-REC on the address contained in PTR-FIRST.

(5)

The chained list in this example is set up so that the last record contains an address that is not valid. This check for the end of the chained list is accomplished with a do-while structure where the value NULL is assigned to the pointer data item in the last record.

(6)

The address of the record in the LINKAGE-SECTION is set equal to the address of the next record by means of the pointer data item sent as the first field in SALARY-REC. The record-processing routine repeats, processing the next record in the chained list.

To increment addresses received from another program, you could set up the LINKAGE SECTION and PROCEDURE DIVISION like this:

```

LINKAGE SECTION.
01 RECORD-A.
   02 HEADER          PIC X(12).
   02 REAL-SALARY-REC PIC X(30).
.
.
.
01 SALARY-REC.
   02 PTR-NEXT-REC    POINTER.

```

```

02  NAME          PIC X(20) .
02  DEPT          PIC 9(4) .
02  SALARY        PIC 9(6) .

. . .
PROCEDURE DIVISION USING DEPT-X.
. . .
SET ADDRESS OF SALARY-REC TO ADDRESS OF REAL-SALARY-REC

```

The address of SALARY-REC is now based on the address of REAL-SALARY-REC, or RECORD-A + 12.

#### related tasks

“Using pointers to process  
a chained list” on page 471

## Passing return-code information

Use the RETURN-CODE special register to pass return codes between programs. (Methods do not return information in the RETURN-CODE special register, but they can check the register after a call to a program.)

You can also use the RETURNING phrase in the PROCEDURE DIVISION header of a method to return information to an invoking program or method. If you use PROCEDURE DIVISION . . . RETURNING with CALL . . . RETURNING, the RETURN-CODE register will not be set.

## Using the RETURN-CODE special register

When a COBOL program returns to its caller, the contents of the RETURN-CODE special register are stored into register 15.

When control is returned to a COBOL program or method from a call, the contents of register 15 are stored into the RETURN-CODE special register of the calling program or method. When control is returned from a COBOL program to the operating system, the special register contents are returned as a user return code.

You might need to think about this handling of the RETURN-CODE special register when control is returned to a COBOL program from a non-COBOL program. If the non-COBOL program does not use register 15 to pass back the return code, the RETURN-CODE special register of the COBOL program might be updated with an invalid value. Unless you set this special register to a meaningful value before your Enterprise COBOL program returns to the operating system, a return code that is invalid will be passed to the system.

For equivalent function between COBOL and C programs, have your COBOL program call the C program with the RETURNING phrase. If the C program (function) correctly declares a function value, the RETURNING value of the calling COBOL program will be set.

You cannot set the RETURN-CODE special register by using the INVOKE statement.

## Using PROCEDURE DIVISION RETURNING . . .

Use the RETURNING phrase in the PROCEDURE DIVISION header of a program to return information to the calling program.

```
PROCEDURE DIVISION RETURNING dataname2
```

When the called program in the example above successfully returns to its caller, the value in *dataname2* is stored into the identifier that was specified in the RETURNING phrase of the CALL statement:

```
CALL . . . RETURNING dataname2
```

**CEEPIPI:** The results of specifying PROCEDURE DIVISION RETURNING in programs that are called with the Language Environment preinitialization service (CEEPIPI) are undefined.

## Specifying CALL . . . RETURNING

You can specify the RETURNING phrase of the CALL statement for calls to C/C++ functions or to COBOL subroutines.

The RETURNING phrase has the following format.

```
CALL . . . RETURNING dataname2
```

The return value of the called program is stored into *dataname2*. You must define *dataname2* in the DATA DIVISION of the calling program. The data type of the return value that is declared in the target function must be identical to the data type of *dataname2*.

## Sharing data by using the EXTERNAL clause

Use the EXTERNAL clause to enable separately compiled programs and methods (including programs in a batch sequence) to share data items. Code EXTERNAL in the level-01 data description in the WORKING-STORAGE SECTION.

The following rules apply:

- Items that are subordinate to an EXTERNAL group item are themselves EXTERNAL.
- You cannot use the name of an EXTERNAL data item as the name for another EXTERNAL item in the same program.
- You cannot code the VALUE clause for any group item or subordinate item that is EXTERNAL.

In the run unit, any COBOL program or method that has the same data description for the item as the program that contains the item can access and process that item. For example, suppose program A has the following data description:

```
01 EXT-ITEM1      EXTERNAL      PIC 99.
```

Program B can access that data item if B has the identical data description in its WORKING-STORAGE SECTION.

Any program that has access to an EXTERNAL data item can change the value of that item. Therefore do not use this clause for data items that you need to protect.

## Sharing files between programs (external files)

To enable separately compiled programs or methods in a run unit to access a file as a common file, use the EXTERNAL clause for the file.

It is recommended that you follow these guidelines:

- Use the same data-name in the FILE STATUS clause of all the programs that check the file status code.
- For each program that checks the same file status field, code the EXTERNAL clause in the level-01 data definition for the file status field.

Using an external file has these benefits:

- Even if the main program does not contain any input or output statements, it can reference the record area of the file.
- Each subprogram can control a single input or output function, such as OPEN or READ.
- Each program has access to the file.

[“Example: using external files” on page 476](#)

## related tasks

[“Using data in input and output operations” on page 11](#)

## related references

EXTERNAL clause (*Enterprise COBOL for z/OS Language Reference*)

## Example: using external files

The following example shows the use of an external file in several programs. COPY statements ensure that each subprogram contains an identical description of the file.

The following table describes the main program and subprograms.

Name	Function
ef1	The main program, which calls all the subprograms and then verifies the contents of a record area
ef1openo	Opens the external file for output and checks the file status code
ef1write	Writes a record to the external file and checks the file status code
ef1openi	Opens the external file for input and checks the file status code
ef1read	Reads a record from the external file and checks the file status code
ef1close	Closes the external file and checks the file status code

Each program uses three copybooks:

- efselect is placed in the FILE-CONTROL paragraph:

```
Select ef1
Assign To ef1
File Status Is efs1
Organization Is Sequential.
```

- effile is placed in the FILE SECTION:

```
Fd ef1 Is External
   Record Contains 80 Characters
   Recording Mode F.
01 ef-record-1.
   02 ef-item-1 Pic X(80).
```

- efwrkstg is placed in the WORKING-STORAGE SECTION:

```
01 efs1          Pic 99 External.
```

## Input/output using external files

```
IDENTIFICATION DIVISION.
Program-Id.
    ef1.
*
* This main program controls external file processing.
*
ENVIRONMENT DIVISION.
Input-Output Section.
File-Control.
    Copy efselect.
DATA DIVISION.
FILE SECTION.
    Copy effile.
WORKING-STORAGE SECTION.
    Copy efwrkstg.
PROCEDURE DIVISION.
```

```

    Call "eflopeno"
    Call "eflwrite"
    Call "eflclose"
    Call "eflopeni"
    Call "eflread"
    If ef-record-1 = "First record" Then
        Display "First record correct"
    Else
        Display "First record incorrect"
        Display "Expected: " "First record"
        Display "Found   : " ef-record-1
    End-If
    Call "eflclose"
    Goback.
End Program efl.
IDENTIFICATION DIVISION.
Program-Id.
    efllopeno.
*
* This program opens the external file for output.
*
ENVIRONMENT DIVISION.
Input-Output Section.
File-Control.
    Copy efselect.
DATA DIVISION.
FILE SECTION.
    Copy effile.
WORKING-STORAGE SECTION.
    Copy efwrkstg.
PROCEDURE DIVISION.
    Open Output efl
    If efs1 Not = 0
        Display "file status " efs1 " on open output"
    Stop Run
    End-If
    Goback.
End Program efllopeno.
IDENTIFICATION DIVISION.
Program-Id.
    eflwrite.
*
* This program writes a record to the external file.
*
ENVIRONMENT DIVISION.
Input-Output Section.
File-Control.
    Copy efselect.
DATA DIVISION.
FILE SECTION.
    Copy effile.
WORKING-STORAGE SECTION.
    Copy efwrkstg.
PROCEDURE DIVISION.
    Move "First record" to ef-record-1
    Write ef-record-1
    If efs1 Not = 0
        Display "file status " efs1 " on write"
    Stop Run
    End-If
    Goback.
End Program eflwrite.
Identification Division.
Program-Id.
    efllopeni.
*
* This program opens the external file for input.
*
ENVIRONMENT DIVISION.
Input-Output Section.
File-Control.
    Copy efselect.
DATA DIVISION.
FILE SECTION.
    Copy effile.
WORKING-STORAGE SECTION.
    Copy efwrkstg.
PROCEDURE DIVISION.
    Open Input efl
    If efs1 Not = 0
        Display "file status " efs1 " on open input"
    Stop Run

```

```

        End-If
        Goback.
    End Program eflopeni.
Identification Division.
Program-Id.
    eflread.
*
* This program reads a record from the external file.
*
ENVIRONMENT DIVISION.
Input-Output Section.
File-Control.
    Copy efselect.
DATA DIVISION.
FILE SECTION.
    Copy effile.
WORKING-STORAGE SECTION.
    Copy efwrkstg.
PROCEDURE DIVISION.
    Read ef1
    If efs1 Not = 0
        Display "file status " efs1 " on read"
        Stop Run
    End-If
    Goback.
End Program eflread.
Identification Division.
Program-Id.
    eflclose.
*
* This program closes the external file.
*
ENVIRONMENT DIVISION.
Input-Output Section.
File-Control.
    Copy efselect.
DATA DIVISION.
FILE SECTION.
    Copy effile.
WORKING-STORAGE SECTION.
    Copy efwrkstg.
PROCEDURE DIVISION.
    Close ef1
    If efs1 Not = 0
        Display "file status " efs1 " on close"
        Stop Run
    End-If
    Goback.
End Program eflclose.

```

## Accessing main program parameters under z/OS

When you run an Enterprise COBOL program under z/OS and pass the program a parameter string, for example, by using JCL or a TSO command, the parameter list consists of a character string that has a halfword prefix that contains the string length.

You can access the parameter string by using a LINKAGE SECTION and standard COBOL coding as shown in the example referenced below:

[“Example: accessing main program parameters under z/OS” on page 479](#)

Alternatively, you can obtain the parameter string by calling either of the following Language Environment callable services, which are described in the related references below:

- CEE3PRM (query parameter string): obtain the parameter string (if not longer than 80 characters)
- CEE3PR2 (query parameter string long): obtain the parameter string and its length

In either case, the parameter string might contain program arguments, runtime options, or both. The setting of the CBLOPTS runtime option determines the relative order in which program arguments and runtime options are expected. If CBLOPTS (ON) (the default) is in effect, and program arguments and

runtime options are both passed in the parameter string, they must appear in the following order, separated by a forward slash:

```
program_arguments/runtime_options
```

For further details, see the related information referenced below.

#### related tasks

[“Coding the LINKAGE SECTION” on page 469](#)

[“Accessing main program parameters under z/OS UNIX” on page 440](#)

[Appendix I, “Accessing JCL parameters,” on page 825](#)

*Language Environment Programming Guide* (Specifying runtime options and program arguments, Preparing your main routine to receive parameters)

#### related references

*Language Environment Customization* (CBLOPTS (COBOL only))

*Language Environment Programming Reference* (CEE3PRM, CEE3PR2)

## Example: accessing main program parameters under z/OS

The following example shows how to receive a parameter string that is passed to a COBOL program that runs under z/OS, and shows the coding that you can use to access the parameter string.

```
IDENTIFICATION DIVISION.  
PROGRAM-ID. "testarg".  
*  
ENVIRONMENT DIVISION.  
CONFIGURATION SECTION.  
*  
DATA DIVISION.  
WORKING-STORAGE SECTION.  
*  
linkage section.  
01 os-parm.  
   05 parm-len          pic s999 comp.  
   05 parm-string.  
       10 parm-char      pic x occurs 0 to 100 times  
                           depending on parm-len.  
*  
PROCEDURE DIVISION using os-parm.  
   display "parm-len=" parm-len  
   display "parm-string='" parm-string "'"  
   evaluate parm-string  
       when "01" display "case one"  
       when "02" display "case two"  
       when "95" display "case ninety-five"  
       when other display "case unknown"  
   end-evaluate  
   GOBACK.
```

Suppose that the CBLOPTS (ON) runtime option is in effect, and that you pass the following argument in the JCL or TSO command that you use to run the program:

```
'95/'
```

Then the resulting output is:

```
parm-len=002  
parm-string='95'  
case ninety-five
```



---

## Chapter 27. Creating a DLL or a DLL application

Creating a dynamic link library (DLL) or a DLL application is similar to creating a regular COBOL application. It involves writing, compiling, and linking your source code.

Special considerations when writing a DLL or a DLL application include:

- Determining how the parts of the program object or the application relate to each other or to other DLLs
- Deciding what linking or calling mechanisms to use

Depending on whether you want to create a DLL program object or a program object that references a separate DLL, you need to use slightly different compiler and binder (linkage-editor) options.

### related concepts

[“Dynamic link libraries \(DLLs\)” on page 481](#)

### related tasks

[“Creating a DLL under z/OS UNIX” on page 268](#)

[“Compiling programs to create DLLs” on page 482](#)

[“Linking DLLs” on page 482](#)

[“Using CALL identifier with DLLs” on page 484](#)

[“Using DLL linkage and dynamic calls together” on page 485](#)

[“Using COBOL DLLs with C/C++ programs” on page 488](#)

[“Using DLLs in OO COBOL applications” on page 488](#)


[“Using procedure or function pointers with DLLs” on page 486](#)

---

## Dynamic link libraries (DLLs)

A DLL is a program object that can be accessed from other separate program objects.

A DLL differs from a traditional program object in that it *exports* definitions of programs, functions, or variables to DLLs, DLL applications, or non-DLLs. Therefore, you do not need to link the target routines into the same program object as the referencing routine. When an application references a separate DLL for the first time, the system automatically loads the DLL into memory. In other words, calling a program in a DLL is similar to calling a program object with a dynamic CALL.



A DLL application is an application that references imported definitions of programs, functions, or variables.

Although some functions of z/OS DLLs overlap the functions provided by COBOL dynamic CALL statements, DLLs have several advantages over regular z/OS program objects and dynamic calls:

- DLLs are common across COBOL and C/C++, thus providing better interoperability for applications that use multiple programming languages. Reentrant COBOL and C/C++ DLLs can also interoperate smoothly.
- You can make calls to programs in separate DLL modules that have long program-names. (Dynamic call resolution truncates program-names to eight characters.) Using the COBOL option PGMNAME (LONGUPPER) or PGMNAME (LONGMIXED) and the COBOL DLL support, you can make calls between program objects with names of up to 160 characters.

DLLs are supported by IBM z/OS Language Environment, based on function provided by the z/OS program management binder. DLL support is available for applications running under z/OS in batch or in TSO, CICS, z/OS UNIX, or IMS environments.

#### related references

[“PGMNAME” on page 328](#)

[MVS Program Management: User's Guide and Reference](#) (Binder support for DLLs)

## Compiling programs to create DLLs

When you compile a COBOL program with the DLL option, it becomes enabled for DLL support. Applications that use DLL support must be reentrant. Therefore, you must compile them with the RENT compiler option and link them with the RENT binder option.

In an application with DLL support, use the following compiler options depending on where the programs or classes are:

Table 63. <b>Compiler options for DLL applications</b>	
Programs or classes in:	Compile with:
Root program object	DLL, RENT, NOEXPORTALL
DLL program objects used by other program objects	DLL, RENT, EXPORTALL

If a DLL program object includes some programs that are used only from within the DLL module, you can hide these routines by compiling them with NOEXPORTALL.

[“Example: sample JCL for a procedural DLL application” on page 483](#)

#### related tasks

[“Creating a DLL under z/OS UNIX” on page 268](#)

[“Linking DLLs” on page 482](#)

[Chapter 27, “Creating a DLL or a DLL application,” on page 481](#)

#### related references

[“DLL” on page 303](#)

[“EXPORTALL” on page 307](#)

[“RENT” on page 330](#)

## Linking DLLs

You can link DLL-enabled object modules into separate DLL program objects, or you can link them together statically. You can decide whether to package the application as one module or as several DLL modules at link time.

The DLL support in the z/OS binder is recommended for linking DLL applications. The binder can directly receive the output of COBOL compilers.

A binder-based DLL must reside in a PDSE or in a z/OS UNIX file.

When using the binder to link a DLL application, use the following options:

Table 64. <i>Binder options for DLL applications</i>	
Type of code	Link using binder parameters:
DLL applications	DYNAM(DLL), RENT
Applications that use mixed-case exported program-names	CASE(MIXED)
Class definitions or INVOKE statements	

You must specify a SYSDEFSD DD statement to indicate the data set in which the binder should create a DLL definition side file. This side file contains IMPORT control statements for each symbol exported by a DLL. The binder SYSLIN input (the binding code that references the DLL code) must include the DLL definition side files for DLLs that are to be referenced from the module being linked.

If there are programs in the module that you do not want to make available with DLL linkage, you can edit the definition side file to remove these programs.

[“Example: sample JCL for a procedural DLL application” on page 483](#)

#### related tasks

[“Creating a DLL under z/OS UNIX” on page 268](#)

[Chapter 27, “Creating a DLL or a DLL application,” on page 481](#)

[“Compiling programs to create DLLs” on page 482](#)

#### related references

[MVS Program Management: User's Guide and Reference](#) (Binder support for DLLs)

## Example: sample JCL for a procedural DLL application

The following example shows how to create an application that consists of a main program that calls a DLL subprogram.

The first step creates the DLL program object that contains the subprogram DemoDLLSubprogram. The second step creates the main program object that contains the program MainProgram. The third step runs the application.

```
//DILLSAMP JOB ,
// TIME=(1),MSGLEVEL=(1,1),MSGCLASS=H,CLASS=A,
// NOTIFY=&SYSUID,USER=&SYSUID
// SET LEPMFX='SYS1'
//*-----
//* Compile COBOL subprogram, bind to form a DLL.
//*-----
//STEP1 EXEC IGYWCL,REGION=80M,GOPGM=DEMOLL,
// PARM.COBL='RENT,PGMN(LM),DLL,EXPORTALL',
// PARM.LKED='RENT,LIST,XREF,LET,MAP,DYNAM(DLL),CASE(MIXED)'
//COBOL.SYSIN DD *
Identification division.
Program-id. "DemoDLLSubprogram".
Procedure division.
Display "Hello from DemoDLLSubprogram!".
End program "DemoDLLSubprogram".
/*
//LKED.SYSDEFSD DD DSN=&SIDECK,UNIT=SYSDA,DISP=(NEW,PASS),
// SPACE=(TRK,(1,1))
//LKED.SYSLMOD DD DSN=&GOSSET(&GOPGM),DSNTYPE=LIBRARY,DISP=(MOD,PASS)
//LKED.SYSIN DD DUMMY
//*-----
//* Compile and bind COBOL main program
//*-----
//STEP2 EXEC IGYWCL,REGION=80M,GOPGM=MAINPGM,
// PARM.COBL='RENT,PGMNAME(LM),DLL',
// PARM.LKED='RENT,LIST,XREF,LET,MAP,DYNAM(DLL),CASE(MIXED)'
//COBOL.SYSIN DD *
```

```

Identification division.
Program-id. "MainProgram".
Procedure division.
    Call "DemoDLLSubprogram"
    Stop Run.
End program "MainProgram".

/*
//LKED.SYSIN DD DSN=&&SIDEDECK,DISP=(OLD,DELETE)
//*-----
//* Execute the main program, calling the subprogram DLL.
//*-----
//STEP3 EXEC PGM=MAINPGM,REGION=80M
//STEPLIB DD DSN=&&GOSET,DISP=(OLD,DELETE)
// DD DSN=&LEPFX..SCEERUN,DISP=SHR
// DD DSN=&LEPFX..SCEERUN2,DISP=SHR
//SYSOUT DD SYSOUT=*
//CEEDUMP DD SYSOUT=*

```

## Using CALL identifier with DLLs

In a COBOL program that has been compiled with the DLL option, you can use `CALL identifier` and `CALL literal` statements to make calls to DLLs. However, there are a few additional considerations for the `CALL identifier` case.

For the content of the *identifier* or for the *literal*, use the name of either of the following programs:

- A nested program in the same compilation unit that is eligible to be called from the program that contains the `CALL identifier` statement.
- A program in a separately bound DLL module. The target program-name must be exported from the DLL, and the DLL module name must match the exported name of the target program.

In the nonnested case, the runtime environment interprets the program-name in the *identifier* according to the setting of the PGMNAME compiler option of the program that contains the `CALL` statement, and interprets the program-name that is exported from the target DLL according to the setting of the PGMNAME option used when the target program was compiled.

The search for the target DLL in the z/OS UNIX file system is case sensitive. If the target DLL is a PDSE member, the DLL member name must be eight characters or less. For the purpose of the search for the DLL as a PDSE member, the run time automatically converts the name to uppercase.

If the runtime environment cannot resolve the `CALL` statement in either of these cases, control is transferred to the `ON EXCEPTION` or `ON OVERFLOW` phrase of the `CALL` statement. If the `CALL` statement does not specify one of these phrases in this situation, Language Environment raises a severity-3 condition.

### related tasks

[“Using DLL linkage and dynamic calls together” on page 485](#)

[“Compiling programs to create DLLs” on page 482](#)

[“Linking DLLs” on page 482](#)

### related references

[“DLL” on page 303](#)

[“PGMNAME” on page 328](#)

[CALL statement \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

[“Search order for DLLs in the z/OS UNIX file system” on page 484](#)

## Search order for DLLs in the z/OS UNIX file system

When you use the z/OS UNIX file system, the search order for resolving a DLL reference in a `CALL` statement depends on the setting of the Language Environment POSIX runtime option.

If the POSIX runtime option is `ON`, the search order is as follows:

1. The runtime environment looks for the DLL in the z/OS UNIX file system. If the LIBPATH environment variable is set, the run time searches each directory listed. Otherwise, it searches just the current directory. The search for the DLL in the z/OS UNIX file system is case sensitive.
2. If the runtime environment does not find the DLL in the z/OS UNIX file system, it tries to load the DLL from the MVS load library search order of the caller. In this case, the DLL name must be eight characters or less. The run time automatically converts the DLL name to uppercase for this search.

If the POSIX runtime option is set to OFF, the search order is reversed:

1. The runtime environment tries to load the DLL from the search order for the load library of the caller.
2. If the runtime environment cannot load the DLL from this load library, it tries to load the DLL from the z/OS UNIX file system.

#### **related tasks**

[“Using CALL identifier with DLLs” on page 484](#)

#### **related references**

*Language Environment Programming Reference (POSIX)*

## **Using DLL linkage and dynamic calls together**

---

For applications (that is, Language Environment enclaves) that are structured as multiple separately bound modules, each module can be invoked by using dynamic call linkage or DLL linkage. For a certain module, use exclusively one form of linkage to enter it. However, the caller can contain CALL statements with both linkage types, calling out to different modules.

*DLL linkage* refers to a call in a program that is compiled with the DLL and NODYNAM options, or a call with the CALLINTERFACE compiler directive that specifies DLL. In such calls, the called subprogram is resolved to an exported name in a separate module. DLL linkage can also refer to an invocation of a method that is defined in a separate module.

Within a compilation unit you can call a specific program with only one of the calling conventions: Dynamic, DLL or Static. If a program is called by using different calling conventions, the compiler diagnoses this case and force all the calls to have the same convention as the first call statement that is encountered for that program.

A program can contain CALL statements with both dynamic call linkage and DLL linkage. It can do so by using the CALLINTERFACE compiler directive to specify the linkage type of a particular call. All components of a DLL application must have the same AMODE. The automatic AMODE switching normally provided by COBOL dynamic calls is not available for DLL linkages. You cannot cancel programs that are called by using DLL linkage.

All components of a DLL application must have the same AMODE. The automatic AMODE switching normally provided by COBOL dynamic calls is not available for DLL linkages.

#### **related concepts**

[“Dynamic link libraries \(DLLs\)” on page 481](#)

#### **related tasks**

[“Compiling programs to create DLLs” on page 482](#)

[“Linking DLLs” on page 482](#)

[“Using procedure or function pointers with DLLs” on page 486](#)

[“Calling DLLs from non-DLLs” on page 486](#)

#### **related references**

[“DLL” on page 303](#)

[“EXPORTALL” on page 307](#)

[CALLINTERFACE](#) (*Enterprise COBOL for z/OS Language Reference*)

## Using procedure or function pointers with DLLs

In run units that contain both DLLs and non-DLLs, use procedure- and function-pointer data items with care.

The `SET procedure-pointer-1 TO ENTRY entry-name` statement, `SET function-pointer-1 TO ENTRY entry-name` statement, and the `CALL` statement have a call linkage type that associates with them. The call linkage type is determined by the compiler options and the `CALLINTERFACE` directive that are in effect on that statement. In a program that is compiled with the `DLL` option, the default call linkage type is `DLL`. Otherwise, the linkage type is `non-DLL`. This default can be overridden by the `CALLINTERFACE` directive.

For a procedure-pointer or function-pointer data item that is set by a `SET` statement with linkage type `non-DLL`, it must not be used by a `CALL` statement with linkage type `DLL`. For a `SET` statement with linkage type `DLL` and the *entry-name* is an identifier, and if the `NODYNAM` option is in effect, the *entry-name* identifier value must refer to the entry-point name that is exported from a DLL module. The DLL module name must match the name of the exported entry point. In this case, note also that:

- The program-name that is contained in the identifier is interpreted according to the setting of the `PGMNAME` (`COMPAT` | `LONGUPPER` | `LONGMIXED`) compiler option of the program that contains the `CALL` statement.
- The program-name that is exported from the target DLL is interpreted according to the setting of the `PGMNAME` option used when compiling the target program.
- The search for the target DLL in the z/OS UNIX file system is case sensitive.
- If the target DLL is a PDSE member, the DLL member name must have eight characters or less. For the purpose of the search for the DLL as a PDSE member, the name is automatically converted to uppercase.

### related tasks

[“Using CALL identifier with DLLs” on page 484](#)

[“Using procedure and function pointers” on page 461](#)

[“Compiling programs to create DLLs” on page 482](#)

[“Linking DLLs” on page 482](#)

### related references

[“DLL” on page 303](#)

[“EXPORTALL” on page 307](#)

[CALLINTERFACE \(Enterprise COBOL for z/OS Language Reference\)](#)

## Calling DLLs from non-DLLs

It is possible to call a DLL from a COBOL program that is compiled with the `NODLL` option, but there are restrictions.

You can use the following methods to ensure that the DLL linkage is followed:

- Put the COBOL DLL programs that you want to call from the COBOL non-DLL programs in the program object that contains the main program. Use static calls from the COBOL non-DLL programs to call the COBOL DLL programs.

The COBOL DLL programs in the program object that contains the main program can call COBOL DLL programs in other DLLs.

- Put the COBOL DLL programs in DLLs and call them from COBOL non-DLL programs with `CALL function-pointer`, where *function-pointer* is set to a function descriptor of the target program. You can obtain the address of the function descriptor for the program in the DLL by calling a C routine that uses `dllload` and `dllqueryfn`.

[“Example: calling DLLs from non-DLLs” on page 487](#)

## related tasks

[“Using procedure and function pointers” on page 461](#)

## Example: calling DLLs from non-DLLs

The following example shows how a COBOL program that is not in a DLL (COBOL1) can call a COBOL program that is in a DLL (program ooc05R in DLL OOC05R).

```
CBL NODYNAM
  IDENTIFICATION DIVISION.
  PROGRAM-ID. 'COBOL1'.
  ENVIRONMENT DIVISION.
  CONFIGURATION SECTION.
  INPUT-OUTPUT SECTION.
  FILE-CONTROL.
  DATA DIVISION.
  FILE SECTION.
  WORKING-STORAGE SECTION.
  01 DLL-INFO.
      03 DLL-LOADMOD-NAME PIC X(12).
      03 DLL-PROGRAM-NAME PIC X(160).
      03 DLL-PROGRAM-HANDLE FUNCTION-POINTER.
  77 DLL-RC PIC S9(9) BINARY.
  77 DLL-STATUS PIC X(1) VALUE 'N'.
      88 DLL-LOADED VALUE 'Y'.
      88 DLL-NOT-LOADED VALUE 'N'.

  PROCEDURE DIVISION.

      IF DLL-NOT-LOADED
      THEN
      *      Move the names in. They must be null terminated.
        MOVE Z'OOC05R' TO DLL-LOADMOD-NAME
        MOVE Z'ooc05r' TO DLL-PROGRAM-NAME

      *      Call the C routine to load the DLL and to get the
      *      function descriptor address.
        CALL 'A1CCDLGT' USING BY REFERENCE DLL-INFO
                              BY REFERENCE DLL-RC

        IF DLL-RC = 0
        THEN
          SET DLL-LOADED TO TRUE
        ELSE
          DISPLAY 'A1CCDLGT failed with rc = '
            DLL-RC
          MOVE 16 TO RETURN-CODE
          STOP RUN
        END-IF
      END-IF

      *      Use the function pointer on the call statement to call the
      *      program in the DLL.
      *      Call the program in the DLL.
        CALL DLL-PROGRAM-HANDLE

      GOBACK.

#include <stdio.h>
#include <dll.h>
#pragma linkage (A1CCDLGT,COBOL)

typedef struct dll_lm {
  char      dll_loadmod_name[(12)];
  char      dll_func_name[(160)];
  void      (*fptr)(void); /* function pointer */
} dll_lm;

void A1CCDLGT (dll_lm *dll, int *rc)
{
  dllhandle *handle;
  void (*fptr1)(void);
  *rc = 0;
  /* Load the DLL */
  handle = dllload(dll->dll_loadmod_name);
  if (handle == NULL) {
    /*
```

```

        perror("A1CCDLGT failed on call to load DLL./n");
        *rc = 1;
        return;
    }

    /* Get the address of the function */
    fptr1 = (void (*)(void))
        dllqueryfn(handle,dll->dll_func_name);
    if (fptr1 == NULL) {
        perror("A1CCDLGT failed on retrieving function./n");
        *rc = 2;
        return;
    }
    /* Return the function pointer */
    dll->fptr = fptr1;
    return;
}

```

## Using COBOL DLLs with C/C++ programs

COBOL support for DLLs interoperates with the DLL support in the z/OS C/C++ products, except for COBOL EXTERNAL data. In particular, COBOL applications can call functions that are exported from C/C++ DLLs, and C/C++ applications can call COBOL programs that are exported from COBOL DLLs.

COBOL data items that are declared with the EXTERNAL attribute are independent of DLL support. These data items are accessible by name from any COBOL program in the run unit that declares them, regardless of whether the programs are in DLLs.

The COBOL options DLL, RENT, and EXPORTALL work much the same way as the C/C++ DLL, RENT, and EXPORTALL options. (The DLL option applies only to C.) However, the C/C++ compiler produces DLL-enabled code by default.

You can pass a C/C++ DLL function pointer to COBOL and use it within COBOL, receiving the C/C++ function pointer as a function-pointer data item. The following example shows a COBOL call to a C function that returns a function pointer to a service, followed by a COBOL call to the service.

```

Identification Division.
Program-id. Demo.
Data Division.
Working-Storage section.
01 fp usage function-pointer.
Procedure Division.
    Call "c-function" returning fp.
    Call fp.

```

### related tasks

[“Compiling programs to create DLLs” on page 482](#)

[“Linking DLLs” on page 482](#)

### related references

[“DLL” on page 303](#)

[“EXPORTALL” on page 307](#)

[“RENT” on page 330](#)

EXTERNAL clause (*Enterprise COBOL for z/OS Language Reference*)

CALLINTERFACE (*Enterprise COBOL for z/OS Language Reference*)

## Using DLLs in OO COBOL applications

You must compile each COBOL class definition using the DLL, THREAD, RENT, and DBCS compiler options, and link-edit it into a separate DLL module using the RENT binder option.

### related tasks

Chapter 16, “Compiling, linking, and running OO applications,” on page 273

[“Compiling programs to create DLLs” on page 482](#)

[“Linking DLLs” on page 482](#)

**related references**

[“DLL” on page 303](#)

[“THREAD” on page 343](#)

[“RENT” on page 330](#)

[“DBCS” on page 301](#)



---

## Chapter 28. Preparing COBOL programs for multithreading

You can run COBOL programs in multiple threads within a process under batch, TSO, IMS, or z/OS UNIX.

There is no explicit COBOL language to use for multithreaded execution; rather, you compile with the `THREAD` compiler option.

COBOL does not directly support managing program threads. However, you can run COBOL programs that you compile with the `THREAD` compiler option in multithreaded application servers, in applications that use a C/C++ driver program to create the threads, in programs that interoperate with Java and use Java threads, and in applications that use PL/I tasking. In other words, other programs can call COBOL programs in such a way that the COBOL programs run in multiple threads within a process or as multiple program invocation instances within a thread. Your threaded application must run within a single Language Environment enclave.

**Choosing LOCAL-STORAGE or WORKING-STORAGE:** Because you must code your multithreaded programs as recursive, the persistence of data is that of any recursive program:

- Data items in the `LOCAL-STORAGE SECTION` are automatically allocated for each instance of a program invocation. When a program runs in multiple threads simultaneously, each invocation has a separate copy of `LOCAL-STORAGE` data.
- Data items in the `WORKING-STORAGE SECTION` are allocated once for each program and are thus available in their last-used state to all invocations of the program.

For the data that you want to isolate to an individual program invocation instance, define the data in the `LOCAL-STORAGE SECTION`. In general, this choice is appropriate for working data in threaded programs. If you define data in `WORKING-STORAGE` and your program changes the contents of the data, you must take one of the following actions:

- Structure your application so that you do not access data in `WORKING-STORAGE` simultaneously from multiple threads.
- If you do access data simultaneously from separate threads, write appropriate serialization code.

### related concepts

[“Multithreading” on page 491](#)

### related tasks

[“Choosing THREAD to support multithreading” on page 492](#)

[“Transferring control to multithreaded programs” on page 493](#)

[“Ending multithreaded programs” on page 493](#)

[“Processing files with multithreading” on page 494](#)

[“Handling COBOL limitations with multithreading” on page 496](#)

### related references

[“THREAD” on page 343](#)

`PROGRAM-ID` paragraph (*Enterprise COBOL for z/OS Language Reference*)

---

## Multithreading

To use COBOL support for multithreading, you need to understand how processes, threads, run units, and program invocation instances relate to each other.


The operating system and multithreaded applications can handle execution flow within a *process*, which is the course of events when all or part of a program runs. Programs that run within a process can share resources. Processes can be manipulated. For example, they can have a high or low priority in terms of the amount of time that the system devotes to running the process.

Within a process, an application can initiate one or more *threads*, each of which is a stream of computer instructions that controls that thread. A multithreaded process begins with one stream of instructions (one thread) and can later create other instruction streams to perform tasks. These multiple threads can run concurrently. Within a thread, control is transferred between executing programs.

In a multithreaded environment, a COBOL *run unit* is the portion of the process that includes threads that have actively executing COBOL programs. The COBOL run unit continues until no COBOL program is active in the execution stack for any of the threads. For example, a called COBOL program contains a GOMAIN statement and returns control to a C program. Within the run unit, COBOL programs can call non-COBOL programs, and vice versa.

Within a thread, control is transferred between separate COBOL and non-COBOL programs. For example, a COBOL program can call another COBOL program or a C program. Each separately called program is a *program invocation instance*. Program invocation instances of a particular program can exist in multiple threads within a given process.

The following illustration shows these relationships between processes, threads, run units, and program invocation instances.



### related concepts

*Language Environment Programming Guide* (Program management model, Understanding the basics: threads)

### related tasks

[“Choosing THREAD to support multithreading” on page 492](#)

[“Transferring control to multithreaded programs” on page 493](#)

[“Ending multithreaded programs” on page 493](#)

[“Processing files with multithreading” on page 494](#)

[“Handling COBOL limitations with multithreading” on page 496](#)

### related references

[“THREAD” on page 343](#)

## Choosing THREAD to support multithreading

Use the THREAD compiler option for multithreading support. Use THREAD if your program will be called in more than one thread in a single process by an application. However, THREAD might adversely affect performance because of the serialization logic that is automatically generated.

In order to run COBOL programs in more than one thread, you must compile all of the COBOL programs in the application using the THREAD compiler option. You must also compile them with the RENT compiler option and link them with the RENT option of the binder (linkage-editor).

Use the `THREAD` option when you compile object-oriented (OO) clients and classes.

**Language restrictions:** When you use the `THREAD` option, you cannot use certain language elements. For details, see the related reference below.

**Recursion:** Before you compile a program using the `THREAD` compiler option, you must specify the `RECURSIVE` phrase in the `PROGRAM-ID` paragraph. If you do not do so, an error will occur.

**related tasks**

[“Sharing data in recursive or multithreaded programs” on page 15](#)  
[“Compiling OO applications under z/OS UNIX” on page 273](#)

**related references**

[“THREAD” on page 343](#)

## Transferring control to multithreaded programs

---

When you write COBOL programs for a multithreaded environment, choose appropriate program linkage statements.

As in single-threaded environments, a called program is in its initial state when it is first called within a run unit and when it is first called after a `CANCEL` to the called program. Ensure that the program that you name on a `CANCEL` statement is not active on any thread. If you try to cancel an active program, a severity-3 Language Environment condition occurs.

If your threaded application requires preinitialization, use the Language Environment services (CEEPIPI interface). You cannot use the COBOL-specific interfaces for preinitialization (runtime option `RTEREUS`) to establish a reusable environment from any program that has been compiled with the `THREAD` option.

**related concepts**

*Language Environment Programming Guide* (What happens during termination: enclave termination)

**related tasks**

[“Ending multithreaded programs” on page 493](#)  
[“Ending and reentering main programs or subprograms” on page 450](#)

## Ending multithreaded programs

---

You can end a multithreaded program by using `GOBACK`, `EXIT PROGRAM`, or `STOP RUN`.

Use `GOBACK` to return to the caller of the program. When you use `GOBACK` from the first program in a thread, the thread is terminated. If that thread is the initial thread in an enclave, the entire enclave is terminated.

Use `EXIT PROGRAM` as you would `GOBACK`, except from a main program where it has no effect.

Use `STOP RUN` to terminate the entire Language Environment enclave and to return control to the caller of the main program (which might be the operating system). All threads that are executing within the enclave are terminated.

**related concepts**

*Language Environment Programming Guide* (What happens during termination: enclave termination)

**related tasks**

[“Ending and reentering main programs or subprograms” on page 450](#)

## Processing files with multithreading

---

In threaded applications, you can code COBOL statements for input and output in QSAM, VSAM, and line-sequential files.

Each file definition (FD) has an implicit serialization lock. This lock is used with automatic serialization logic during the input or output operation that is associated with the execution of the following statements:

- OPEN
- CLOSE
- READ
- WRITE
- REWRITE
- START
- DELETE

Automatic serialization also occurs for the implicit MOVE that is associated with the following statements:

```
WRITE record-name FROM identifier  
READ  file-name  INTO identifier
```

Automatic serialization is not applied to any statements specified within the following conditional phrases:

- AT END
- NOT AT END
- INVALID KEY
- NOT INVALID KEY
- AT END-OF-PAGE
- NOT AT END-OF-PAGE

### **related concepts**

[“File-definition \(FD\) storage” on page 494](#)

### **related tasks**

[“Closing QSAM files” on page 162](#)

[“Closing VSAM files” on page 187](#)

[“Coding ERROR declaratives” on page 228](#)

[“Serializing file access with multithreading” on page 495](#)

## File-definition (FD) storage

On all program invocations, the storage that is associated with a file definition (such as FD records and the record area that is associated with the SAME RECORD AREA clause) is allocated and available in its last-used state.

All threads of execution share this storage. You can depend on automatic serialization for this storage during the execution of the OPEN, CLOSE, READ, WRITE, REWRITE, START, and DELETE statements, but not between uses of these statements.

### **related tasks**

[“Serializing file access with multithreading” on page 495](#)

## Serializing file access with multithreading

To take full advantage of automatic serialization and to avoid explicitly writing your own serialization logic, use one of the recommended file organizations and usage patterns when you access files in threaded programs.

Use one of the following file organizations:

- Sequential organization
- Line-sequential organization
- Relative organization with sequential access
- Indexed organization with sequential access

Use the following pattern for input:

```
OPEN INPUT fn
READ fn INTO local-storage-item
* Process the record from the local-storage item
CLOSE fn
```

Use the following pattern for output:

```
OPEN OUTPUT fn
* Construct output record in local-storage item
WRITE rec FROM local-storage-item
CLOSE fn
```

With other usage patterns, you must take one of the following actions:

- Verify the safety of your application logic. Ensure that two instances of the program are never simultaneously active on different threads.
- Code explicit serialization logic by using calls to POSIX services.

To avoid serialization problems when you access a file from multiple threads, define the data items that are associated with the file (such as file-status data items and key arguments) in the LOCAL-STORAGE SECTION.

[“Example: usage patterns of file input and output with multithreading” on page 495](#)

### related tasks

[“Calling UNIX/POSIX APIs” on page 438](#)

## Example: usage patterns of file input and output with multithreading

The following examples show the need for explicit serialization logic when you deviate from the recommended usage pattern for file input and output in your multithreaded applications. These examples also explain the unexpected behavior that might result if you fail to handle serialization properly.

In each example, two instances of a program that contains the sample operations are running within one run unit on two different threads.

```
READ F1
REWRITE R1
```

In the example above, the second thread might execute the READ statement after the READ statement is executed on the first thread but before the REWRITE statement is executed on the first thread. The

REWRITE statement might not update the record that you intended. To ensure the results that you want, write explicit serialization logic.

```
READ F1
. . .
* Process the data in the FD record description entry for F1
. . .
```

In the example above, the second thread might execute the READ statement while the first thread is still processing a record in the FD record description entry. The second READ statement would overlay the record that the first thread is processing. To avoid this problem, use the recommended technique:

```
READ F1 INTO LOCAL-STORAGE-item
```

**Other cases:** You must give similar consideration to other usage patterns that involve a sequence of related input and output operations, such as START followed by READ NEXT, or READ followed by DELETE. Take appropriate steps to ensure the correct processing of file input and output.

## Handling COBOL limitations with multithreading

Some COBOL applications depend on subsystems or other applications. In a multithreaded environment, these dependencies and others result in some limitations on COBOL programs.

In general, you must synchronize access to resources that are visible to the application within a run unit. Exceptions to this requirement are DISPLAY and ACCEPT, which you can use from multiple threads, and supported COBOL file I/O statements that have the recommended usage pattern; all synchronization is provided for these by the runtime environment.

**CICS:** You cannot run multithreaded applications in CICS. In CICS, you can run a COBOL program that has been compiled with the THREAD option and that is part of an application that has no multiple threads or PL/I tasks.

**Recursive:** Because you must code the programs in a multithreaded application as recursive, you must adhere to all the restrictions and programming considerations that apply to recursive programs, such as not coding nested programs.

**Reentrancy:** You must compile your multithreading programs with the RENT compiler option and link them with the RENT option of the binder (linkage-editor).

**POSIX and PL/I:** If you use POSIX threads in your multithreaded application, you must specify the Language Environment runtime option POSIX(ON). If the application uses PL/I tasking, you must specify POSIX(OFF). You cannot mix POSIX threads and PL/I tasks in the same application.

**PL/I tasking:** To include COBOL programs in applications that contain multiple PL/I tasks, follow these guidelines:

- Compile all COBOL programs that you run in multiple PL/I tasks with the THREAD option. If you compile any COBOL program with the NTHREAD option, all of the COBOL programs must run in one PL/I task.
- You can call COBOL programs compiled with the THREAD option from one or more PL/I tasks. However, calls from PL/I programs to COBOL programs cannot include the TASK or EVENT option. The PL/I tasking call must first call a PL/I program or function that in turn calls the COBOL program. This indirection is required because you cannot specify the COBOL program directly as the target of a PL/I CALL statement that includes the TASK or EVENT option.
- Be aware that issuing a STOP RUN statement from a COBOL program or a STOP statement from a PL/I program terminates the entire Language Environment enclave, including all the tasks of execution.
- Do not code explicit POSIX threading (calls to pthread\_create()) in any run unit that includes PL/I tasking.

**C and Language Environment conforming assembler:** You can combine your multithreaded COBOL programs with C programs and Language Environment conforming assembler programs in the same run unit when those programs are also appropriately coded for multithreaded execution.

**AMODE:** You must run your multithreaded applications with AMODE 31. You can run a COBOL program that has been compiled with the THREAD option with AMODE 24 as part of an application that does not have multiple threads or PL/I tasks.

**Asynchronous signals:** In a threaded application your COBOL program might be interrupted by an asynchronous signal or interrupt. If your program contains logic that cannot tolerate such an interrupt, you must disable the interrupts for the duration of that logic. Call a C/C++ function to set the signal mask appropriately.

**Older COBOL programs:** To run your COBOL programs on multiple threads of a multithreaded application, you must compile them with Enterprise COBOL and use the THREAD option. Run applications that contain programs compiled by older compilers only on one thread.

**IGZETUN and IGZEOPT:** Do not use the modules IGZETUN (for storage tuning) or IGZEOPT (for runtime options) for applications in which the main program has been compiled with the THREAD option; these CSECTs are ignored.

**UPSI switches:** All programs and all threads in an application share a single copy of UPSI switches. If you modify switches in a threaded application, you must code appropriate serialization logic.

#### **related tasks**

[“Making recursive calls” on page 461](#)

[“Serializing file access with multithreading” on page 495](#)

*XL C/C++ Programming Guide* (Using threads in z/OS UNIX System Services applications)

*Language Environment Writing ILC Communication Applications*



---

## Part 5. Using COBOL for Web Services



---

## Chapter 29. Web Services interface

COBOL can provide or request Web Services, using architectures based on SOAP (Simple Object Access Protocol) or REST (REpresentational State Transfer). Data in the interface to such services is typically represented in JSON (JavaScript Object Notation) or XML (eXtensible Markup Language). The following information describes COBOL and other facilities that can be used to generate and consume JSON and XML.

### Processing JSON input

The z/OS Client Web Enablement Toolkit enables applications to participate in the client/server space by providing a built-in z/OS JSON parser (provided with z/OS V2.2, or z/OS V2.1 with the PTF for APAR OA46575 installed) to consume JSON text from any source. Be aware that this parser supports JSON texts in EBCDIC codepage 1047 only, thus JSON text received by the application in another encoding format must first be converted to EBCDIC 1047 before it can be input into the parser. For details, see the description of the z/OS JSON parser in *z/OS MVS Programming: Callable Services for High-Level Languages*.

### related tasks

[Chapter 30, “Producing JSON output,” on page 503](#)

[Chapter 31, “Processing XML input,” on page 505](#)

[Chapter 32, “Producing XML output,” on page 545](#)



## Chapter 30. Producing JSON output

You can express COBOL data items as JSON text by using the JSON GENERATE statement, which identifies the source and output data items.

You can optionally also specify:

- A data item to receive the count of characters generated.
- Alternative names for the input data items
- Data items to be excluded from the output JSON text
- A statement to receive control if an exception occurs

The JSON text can be used to represent a resource for the interface to a Web service, and is encoded in UTF-8 if the output data item is alphanumeric, or UTF-16 if the output data item is national.

### Using the JSON GENERATE statement

Consider the following example:

```
01 Greeting.  
 02 Msg pic x(80) value 'Hello, World!'.  
01 Jtext national pic n(80).  
01 i binary pic 99.  
...  
  JSON generate Jtext from Greeting count in i  
    on exception  
      display 'JSON generation error: ' json-code  
    not on exception  
      display function display-of(Jtext(1:i))  
End-JSON
```

The above code sequence produces the following output:

```
{"Greeting":{"msg":"Hello, World!"}}
```

The following example is more complex which illustrates optional phrases that:

- Provide alternative JSON names for the included data items (NAME)
- Allow you to exclude sensitive or unwanted information from the output (SUPPRESS)

```
01 GRP.  
 05 Ac-No PIC AA9999 value 'SX1234'.  
 05 More.  
 10 Stuff PIC S99V9 OCCURS 2.  
 05 SSN PIC 999/99/9999 value '987-65-4321'.  
01 d pic x(80).  
01 i binary pic 99.  
...  
  move 7.8 to stuff(1), move -9 to stuff(2)  
  JSON generate d from grp count i  
  NAME of stuff is 'Value' SUPPRESS ssn  
  display function display-of(function national-of(  
    d(1:i) 1208))
```

The example produces the following output:

```
{"GRP":{"Ac-No":"SX1234","More":{"Value":[7.8,-9.0]}}}
```



---

## Chapter 31. Processing XML input

You can process XML input in a COBOL program by using the XML PARSE statement.

The XML PARSE statement is the COBOL language interface to either of two high-speed XML parsers. You use the XMLPARSE compiler option to select the appropriate parser for your application:

- XMLPARSE (XMLSS) selects the z/OS XML System Services parser.

This option provides enhanced features such as namespace processing, validation of XML documents with respect to an XML schema, and conversion of text fragments to national character representation (Unicode UTF-16).

- XMLPARSE (COMPAT) selects the XML parser that is built into the COBOL library.

This option provides compatibility with XML parsing in Enterprise COBOL Version 3 and Version 4.

Processing XML input involves passing control between the XML parser and a processing procedure in which you handle parser events.

Use the following COBOL facilities to process XML input:

- The XML PARSE statement to begin XML parsing and to identify the source XML document and the processing procedure.

You can also use the following optional phrases of the XML PARSE statement:

- ENCODING to specify the encoding of the XML document
- VALIDATING to identify an XML schema against which the XML document is to be validated
- The processing procedure to control the parsing, that is, receive and process XML events and associated document fragments, and return to the parser for continued processing
- Special registers to exchange information between the parser and the processing procedure:
  - XML - CODE to receive the status of XML parsing and, in some cases, to return information to the parser
  - XML - EVENT to receive the name of each XML event from the parser
  - XML - INFORMATION provides a mechanism to easily determine whether an XML event is complete
  - XML - NTEXT to receive XML document fragments that are returned as national character data
  - XML - TEXT to receive document fragments that are returned as alphanumeric data
  - XML - NAMESPACE or XML - NNAMESPACE to receive a namespace identifier for a NAMESPACE-DECLARATION XML event, or for an element name or attribute name that is in a namespace
  - XML - NAMESPACE - PREFIX or XML - NNAMESPACE - PREFIX to receive a namespace prefix for a NAMESPACE-DECLARATION XML event, or for an element name or attribute name that is prefixed
- The optional RETURNING NATIONAL phrase of the XML PARSE statement to indicate that the fragments of an XML document in an alphanumeric data item are to be converted to UTF-16 and returned to the processing procedure in the national special registers XML - NTEXT, XML - NNAMESPACE, and XML - NNAMESPACE - PREFIX

You can use the ENCODING, VALIDATING, and RETURNING NATIONAL phrases of the XML PARSE statement only if XMLPARSE (XMLSS) is in effect.

**Link-edit consideration:** COBOL programs that contain the XML PARSE statement must be link-edited with AMODE 31.

### related concepts

[“XML parser in COBOL” on page 506](#)

### related tasks

[“Accessing XML documents” on page 507](#)

[“Parsing XML documents” on page 508](#)  
[“Handling XML PARSE exceptions” on page 527](#)  
[“Terminating XML parsing” on page 531](#)

#### related references

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“The encoding of XML documents” on page 522](#)  
[Appendix C, “XML reference material,” on page 671](#)  
[Extensible Markup Language \(XML\)](#)

## XML parser in COBOL


Enterprise COBOL provides an event-based interface that lets you parse XML documents and transform them to COBOL data structures.

The XML parser finds fragments within the source XML document, and your processing procedure acts on those fragments. The fragments are associated with XML events; you code the processing procedure to handle each XML event.

Execution of the XML PARSE statement begins the parsing and establishes the processing procedure with the parser. The parser transfers control to the processing procedure for each XML event that it detects while processing the document. After processing the event, the processing procedure automatically returns control to the parser. Each normal return from the processing procedure causes the parser to continue analyzing the XML document to report the next event. Throughout this operation, control passes back and forth between the parser and the processing procedure.

In the XML PARSE statement, you can also specify two imperative statements to which you want control to be passed at the end of the parsing: one if a normal end occurs, and the other if an exception condition exists.

The following figure shows a high-level overview of the basic exchange of control between the parser and your COBOL program:



Normally, parsing continues until the entire XML document has been parsed.

The XML parser checks XML documents for most aspects of well formedness. A document is *well formed* if it adheres to the XML syntax in the *XML specification* and follows some additional rules such as proper use of end tags and uniqueness of attribute names.

When you parse an XML document with validation against an XML schema, the z/OS XML System Services parser additionally verifies that the XML document adheres to the content and structure prescribed in the schema. For example, the parser checks that there are no unexpected elements or attributes, that no required elements or attributes are missing, and that any values of elements or attributes are legal.

**related concepts**

[“XML schemas” on page 518](#)

[“XML input document encoding” on page 523](#)

**related tasks**

[“Parsing XML documents” on page 508](#)

[“Parsing XML](#)

[documents with validation” on page 516](#)

[“Handling XML PARSE exceptions” on page 527](#)

[“Terminating XML parsing” on page 531](#)

**related references**

[“The encoding of XML documents” on page 522](#)

[XML specification](#)

## Accessing XML documents

---

Before you can parse an XML document using an XML PARSE statement, you must make the document available to your program. Common methods of acquiring an XML document are by retrieval from a WebSphere MQ message, a CICS transient queue or communication area, or an IMS message processing queue; or by reading the document from a file.

If the XML document that you want to parse is held in a file, use ordinary COBOL facilities to place the document into a data item in your program:

- A FILE-CONTROL entry to define the file to your program.
- An OPEN statement to open the file.
- READ statements to read all the records from the file into a data item (either an elementary item of category alphanumeric or national, or an alphanumeric or national group). You can define the data item in the WORKING-STORAGE SECTION or the LOCAL-STORAGE SECTION.
- Optionally, the STRING statement to string all of the separate records together into one continuous stream, to remove extraneous blanks, and to handle variable-length records.

If the XMLPARSE (XMLSS) option is in effect, you can parse an XML document that is in a file by passing the parser one record (or *segment*) of text from the file at a time. This capability is useful for parsing very large XML documents.

**related tasks**

[“Coding COBOL programs to run under CICS” on page 407](#)

[Chapter 22, “Developing COBOL programs for IMS,” on page 427](#)

[“Parsing XML documents one segment at a time” on page 519](#)

**related references**

[“XMLPARSE” on page 350](#) (compiler option)

## Parsing XML documents

To parse XML documents, use the XML PARSE statement, specifying the XML document that is to be parsed and the processing procedure for handling XML events that occur during parsing, as shown in the following code fragment.

```
XML PARSE xml-document
  PROCESSING PROCEDURE xml-event-handler
  ON EXCEPTION
    DISPLAY 'XML document error ' XML-CODE
    STOP RUN
  NOT ON EXCEPTION
    DISPLAY 'XML document was successfully parsed.'
END-XML
```

In the XML PARSE statement, you first identify the *parse data item* (xml-document in the example above) that contains the XML document character stream. In the DATA DIVISION, define the parse data item as an elementary data item of category national or as a national group item if the encoding of the document is Unicode UTF-16; otherwise, define the parse data item as an elementary alphanumeric data item or an alphanumeric group item:

- If the parse data item is national, the XML document must be encoded in UTF-16, CCSID 1200.
- If the parse data item is alphanumeric, its content must be encoded in one of the supported code pages described in the related reference about the encoding of XML documents.

Next, specify the name of the processing procedure (xml-event-handler in the example above) that is to handle the XML events that occur during parsing of the document.

If the XMLPARSE (XMLSS) compiler option is in effect, you can also use any of these optional phrases of the XML PARSE statement:

- ENCODING, to specify the CCSID of the document
- RETURNING NATIONAL, to cause the parser to automatically convert UTF-8 or single-byte characters to national characters for return to the processing procedure
- VALIDATING, to cause the parser to validate the document against an XML schema

In addition, you can specify either or both of the following optional phrases (as shown in the fragment above) to indicate the action to be taken after parsing finishes:

- ON EXCEPTION, to receive control if an unhandled exception occurs during parsing
- NOT ON EXCEPTION, to receive control otherwise

You can end the XML PARSE statement with the explicit scope terminator END-XML. Use END-XML to nest an XML PARSE statement that uses the ON EXCEPTION or NOT ON EXCEPTION phrase in a conditional statement.

The parser passes control to the processing procedure for each XML event. Control returns to the parser at the end of the processing procedure. This exchange of control between the XML parser and the processing procedure continues until one of the following events occurs:

- The entire XML document was parsed, as indicated by the END-OF-DOCUMENT event.
- If XMLPARSE (XMLSS) is in effect, either:
  - The parser detects an error in the document and signals an EXCEPTION event (regardless of the kind of exception).
  - The parser signals an END-OF-INPUT event, and the processing procedure returns to the parser with special register XML-CODE still set to zero, which indicates that no further XML data will be provided to the parser.
- If XMLPARSE (COMPAT) is in effect, either:
  - The parser signals an encoding conflict EXCEPTION event, and the processing procedure does not reset special register XML-CODE to zero or to the correct CCSID before returning to the parser.

- The parser detects an error in the document and signals an EXCEPTION event (other than an encoding conflict), and the processing procedure does not reset special register XML - CODE to zero before returning to the parser.
- The parsing process is terminated deliberately by the user's code in the processing procedure that sets the XML-CODE special register to -1 before it returns to the parser.

#### related concepts

[“XML events” on page 511](#)

[“XML-CODE” on page 512](#)

[“XML schemas” on page 518](#)

[“XML-INFORMATION” on page 514](#)

#### related tasks

[“Writing procedures to process](#)

[XML” on page 509](#)

[“Parsing XML](#)

[documents with validation” on page 516](#)

[“Parsing XML documents one segment at a time” on page 519](#)

[“Parsing XML documents](#)

[encoded in UTF-8” on page 526](#)

#### related references

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“The encoding of XML documents” on page 522](#)

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

XML PARSE statement (*Enterprise COBOL for z/OS Language Reference*)

## Writing procedures to process XML

In your processing procedure, code statements to handle XML events.

For each event that the parser encounters, the parser passes information to the processing procedure in several special registers. Use the content of those special registers to populate COBOL data structures and to control the processing.

Examine the XML - EVENT special register to determine which event the parser passed to the processing procedure. XML - EVENT contains an event name, such as 'START-OF-ELEMENT'. Obtain the text associated with the event from the XML - TEXT or XML - NTEXT special register.

If the XMLPARSE (XMLSS) option is in effect, you can use special register XML - NAMESPACE or XML - NNAMESPACE to determine the namespace identifier, if any, that is associated with the XML event, and examine the XML - NAMESPACE - PREFIX or XML - NNAMESPACE - PREFIX special register to determine the associated prefix, if any.

When used in nested programs, the XML special registers are implicitly defined as GLOBAL in the outermost program.

For additional details about the XML special registers, see the following table.

Table 65. <i>Special registers used by the XML parser</i>		
Special register	Implicit definition and usage	Content
XML - EVENT <sup>1</sup>	PICTURE X(30) USAGE DISPLAY VALUE SPACE	The name of the XML event

Table 65. <i>Special registers used by the XML parser (continued)</i>		
Special register	Implicit definition and usage	Content
XML - CODE <sup>2</sup>	PICTURE S9(9) USAGE BINARY VALUE ZERO	An exception code or zero for each XML event
XML - INFORMATION <sup>1</sup>	PICTURE S9(9) USAGE BINARY VALUE 0	A mechanism to easily determine whether an XML EVENT is complete
XML - TEXT <sup>1</sup>	Variable-length elementary category alphanumeric item	Text (corresponding to the event that the parser encountered) from the XML document if you specify an alphanumeric item for the XML PARSE identifier <sup>3</sup>
XML - NTEXT <sup>1</sup>	Variable-length elementary category national item	Text (corresponding to the event that the parser encountered) from the XML document if you specify a national item for the XML PARSE identifier <sup>3</sup>
XML - NAMESPACE <sup>1, 4</sup>	Variable-length elementary category alphanumeric item	The namespace identifier for a NAMESPACE - DECLARATION XML event or for an element or attribute name that is in a namespace, if the XML document is in an alphanumeric data item <sup>3</sup>
XML - NNAMESPACE <sup>1, 4</sup>	Variable-length elementary category national item	The namespace identifier for a NAMESPACE - DECLARATION XML event or for an element or attribute name that is in a namespace, if the XML document is in a national data item or the RETURNING NATIONAL phrase is specified in the XML PARSE statement
XML - NAMESPACE - PREFIX <sup>1, 4</sup>	Variable-length elementary category national item	The prefix, if any, for a NAMESPACE - DECLARATION XML event or for an element or attribute name that is in a nondefault namespace, if the XML document is in an alphanumeric data item <sup>3</sup>
XML - NNAMESPACE - PREFIX <sup>1, 4</sup>	Variable-length elementary category national item	The prefix, if any, for a NAMESPACE - DECLARATION XML event or for an element or attribute name that is in a nondefault namespace, if the XML document is in a national data item or the RETURNING NATIONAL phrase is specified in the XML PARSE statement
<ol style="list-style-type: none"> <li>1. You cannot use this special register as a receiving data item.</li> <li>2. The XML GENERATE statement also uses XML - CODE. Therefore, if you have an XML GENERATE statement in the processing procedure, save the value of XML - CODE before the XML GENERATE statement, and restore the saved value after the XML GENERATE statement.</li> <li>3. If you specify the RETURNING NATIONAL phrase in the XML PARSE statement for an alphanumeric data item, text is returned in the corresponding national special register. You can specify the RETURNING NATIONAL phrase only if the XMLPARSE (XMLSS) option is in effect.</li> <li>4. The parser sets the namespace special registers only if the XMLPARSE (XMLSS) option is in effect.</li> </ol>		

### Restrictions:

- A processing procedure must not directly execute an XML PARSE statement. However, if a processing procedure passes control to a method or outermost program by using an INVOKE or CALL statement, the target method or program can execute the same or a different XML PARSE statement. You can also execute the same XML statement or different XML statements simultaneously from a program that is running on multiple threads.
- The range of the processing procedure must not cause the execution of any GOBACK or EXIT PROGRAM statement, except to return control from a method or program to which control was passed by an INVOKE or CALL statement, respectively, that is executed in the range of the processing procedure.

You can code a STOP RUN statement in a processing procedure to end the run unit.

The compiler inserts a return mechanism after the last statement in each processing procedure.

[“Example: program for processing XML” on page 532](#)

**related concepts**

[“XML events” on page 511](#)

[“XML-CODE” on page 512](#)

[“XML-TEXT and XML-NTEXT” on page 514](#)

[“XML-NAMESPACE and XML-NNAMESPACE” on page 515](#)

[“XML-NAMESPACE-PREFIX and XML-NNAMESPACE-PREFIX” on page 515](#)

**related tasks**

[“Parsing XML documents one segment at a time” on page 519](#)

[“Parsing XML](#)

[documents with validation” on page 516](#)

[“Terminating XML parsing” on page 531](#)

**related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

[XML-EVENT \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## XML events

An *XML event* results when the XML parser detects various conditions (such as END-OF-INPUT or EXCEPTION) or encounters document fragments (such as CONTENT-CHARACTERS or START-OF-CDATA-SECTION) while processing an XML document.

For each event that occurs during XML parsing, the parser sets the associated event name in the XML - EVENT special register, and passes the XML - EVENT special register to the processing procedure. Depending on the event, the parser sets other special registers to contain additional information about the event.

In most cases, the parser sets the XML - TEXT or XML - NTEXT special register to the XML fragment that caused the event:

- If the XMLPARSE (COMPAT) compiler option is in effect, the parser sets XML - NTEXT if the XML document is in a national data item, or if the parser finds a character reference; otherwise, the parser sets XML - TEXT.
- If XMLPARSE (XMLSS) is in effect, the parser sets XML - NTEXT if the RETURNING NATIONAL phrase is specified in the XML PARSE statement, or if the XML document is in a national data item; otherwise, the parser sets XML - TEXT.

If XMLPARSE (XMLSS) is in effect, the parser sets the namespace special registers for a NAMESPACE-DECLARATION event, or if it encounters a name that is in a namespace.

When the parser detects an encoding conflict or a well-formedness or validation error in the document, it sets XML - EVENT to 'EXCEPTION' and provides additional information about the exception in the XML - CODE special register. You can parse with validation only if XMLPARSE (XMLSS) is in effect. For further details, see the related task about parsing with validation.

For a detailed description of the set of XML events, see the related reference about XML - EVENT.

[“Example: parsing a simple document” on page 532](#)

**related concepts**

[“XML parser in COBOL” on page 506](#)

[“XML-CODE” on page 512](#)

[“XML-INFORMATION” on page 514](#)

[“XML-TEXT and XML-NTEXT” on page 514](#)

[“XML-NAMESPACE and XML-NNAMESPACE” on page 515](#)

[“XML-NAMESPACE-PREFIX and XML-NNAMESPACE-PREFIX” on page 515](#)

**related tasks**

[“Writing procedures to process](#)

[XML” on page 509](#)

[“Parsing XML documents with validation” on page 516](#)

## related references

[“XMLPARSE” on page 350](#) (compiler option)

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

XML-EVENT (*Enterprise COBOL for z/OS Language Reference*)

## XML-CODE

For each XML event except an EXCEPTION event, the parser sets the value of the XML - CODE special register to zero. For an EXCEPTION event, the parser sets XML - CODE to a value that identifies the specific exception.

For information about the possible exception codes, see the related references.

When the parser returns control to the XML PARSE statement from your processing procedure, XML - CODE generally contains the most recent value that was set by the parser. However, for any event other than EXCEPTION, if you set XML - CODE to -1 in your processing procedure, parsing terminates with a user-initiated exception condition when control returns to the parser, and XML - CODE retains the value -1.

For an EXCEPTION XML event when XMLPARSE (COMPAT) is in effect, your processing procedure can, in some cases, set XML - CODE to a meaningful value before control returns to the parser. (For details, see the related tasks about handling XML PARSE exceptions and handling encoding conflicts.) If you set XML - CODE to any other nonzero value or set it for any other exception, the parser resets XML - CODE to the original exception code.

For a START-OF-DOCUMENT XML event when compiler option XMLPARSE (COMPAT) is in effect, your processing procedure can set XML - CODE to 1 before control returns to the parser. This action instructs the parser to release (at the end of parsing) any Language Environment resources acquired during parsing.

The following table shows the results of setting XML - CODE to various values. The leftmost column shows the type of XML event passed to the processing procedure; the other column headings show the XML - CODE value set by the processing procedure. The cell at the intersection of each row and column shows the action that the parser takes upon return from the processing procedure for a given combination of XML event and XML - CODE value.

<i>Table 66. Results of processing-procedure changes to XML - CODE with XMLPARSE (XMLSS) in effect</i>				
XML event type	XML-CODE set to -1	XML-CODE set to 0	XML-CODE set to 1	XML-CODE set to other nonzero values
<b>Fatal EXCEPTION</b>	Ignores setting; keeps original XML - CODE value	Ignores setting; keeps original XML - CODE value	Ignores setting; keeps original XML - CODE value	Ignores setting; keeps original XML - CODE value
<b>Warning EXCEPTION (Reason code 800 or 801)</b>	Ignores setting; keeps original XML - CODE value	Next event is ATTRIBUTE - NAME or START-OF - ELEMENT	Ignores setting; keeps original XML - CODE value	Ignores setting; keeps original XML - CODE value
<b>END-OF-INPUT</b>	Ends immediately; XML - CODE = -1 <sup>1</sup>	Next event is END-OF-DOCUMENT <sup>2</sup>	Next event depends on input <sup>2</sup>	Fatal runtime error (message 230S)
<b>Normal event</b>	Ends immediately; XML - CODE = -1 <sup>1</sup>	XML - CODE already 0, no change	Fatal runtime error (message 230S)	Fatal runtime error (message 230S)

*Table 66. Results of processing-procedure changes to XML - CODE with XMLPARSE (XMLSS) in effect (continued)*

XML event type	XML-CODE set to -1	XML-CODE set to 0	XML-CODE set to 1	XML-CODE set to other nonzero values
<p>1. See the related task about terminating XML parsing.</p> <p>2. See the related task about parsing documents one segment at a time.</p>				

*Table 67. Results of processing-procedure changes to XML - CODE with XMLPARSE (COMPAT) in effect*

XML event type	-1	0	XML - CODE-100,000	Other nonzero value
<b>Encoding-conflict exception</b> (exception codes 50 - 99)	Ignores setting; keeps original XML - CODE value	Chooses encoding depending on the specific exception code <sup>1</sup>	Ignores setting; keeps original XML - CODE value	Ignores setting; keeps original XML - CODE value
<b>Encoding-choice exception</b> (exception codes > 100,000)	Ignores setting; keeps original XML - CODE value	Parses using the CODEPAGE value <sup>2</sup>	Parses using the difference (shown above) as the encoding value <sup>2</sup>	Ignores setting; keeps original XML - CODE value
<b>Other exception</b>	Ignores setting; keeps original XML - CODE value	Limited continuation only for exception codes 1 - 49 <sup>3</sup>	Ignores setting; keeps original XML - CODE value	Ignores setting; keeps original XML - CODE value
<b>Normal event</b> (except START-OF-DOCUMENT)	Ends immediately; XML - CODE = -1 <sup>4</sup>	[No apparent change to XML - CODE]	Ends immediately; XML - CODE = -1	Ends immediately; XML - CODE = -1
<b>START-OF-DOCUMENT</b>	Ends immediately; XML - CODE = -1 <sup>4</sup>	[No apparent change to XML - CODE]	Ends immediately; XML - CODE = -1	<ul style="list-style-type: none"> <li>• XML - CODE = 1</li> <li>• Else ends immediately; XML - CODE = -1</li> </ul>
<p>1. See the exception codes in the related reference about XML PARSE exceptions with XMLPARSE (COMPAT) in effect.</p> <p>2. See the related task about handling encoding conflicts.</p> <p>3. See the related task about handling XML PARSE exceptions.</p> <p>4. See the related task about terminating XML parsing.</p>				

XML generation also uses the XML - CODE special register. For details, see the related task about handling XML GENERATE exceptions.

#### **related concepts**

[“How the XML parser handles errors” on page 529](#)

#### **related tasks**

[“Writing procedures to process](#)

[XML” on page 509](#)

[“Parsing XML documents one segment at a time” on page 519](#)

[“Handling XML PARSE exceptions” on page 527](#)

[“Terminating XML parsing” on page 531](#)

[“Handling XML GENERATE exceptions” on page 550](#)

#### **related references**

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

[“XML GENERATE exceptions” on page 679](#)

XML-CODE (*Enterprise COBOL for z/OS Language Reference*)

XML-EVENT (*Enterprise COBOL for z/OS Language Reference*)

## **XML-INFORMATION**

For most XML events, the parser sets XML - INFORMATION to indicate whether an XML EVENT is complete or whether the XML content spans multiple events.

The application program logic can use the XML - INFORMATION special register to concatenate pieces of parsed XML content together.

#### **related concepts**

[“XML events” on page 511](#)

[“XML-CODE” on page 512](#)

#### **related tasks**

[“Writing procedures to process](#)

[XML” on page 509](#)

#### **related references**

XML-TEXT (*Enterprise COBOL for z/OS Language Reference*)

XML-NTEXT (*Enterprise COBOL for z/OS Language Reference*)

## **XML-TEXT and XML-NTEXT**

For most XML events, the parser sets XML - TEXT or XML - NTEXT to an associated document fragment.

Typically, the parser sets XML - TEXT if the XML document is in an alphanumeric data item. The parser sets XML - NTEXT if:

- The XML document is in a national data item.
- The XMLPARSE (XMLSS) option is in effect and the RETURNING NATIONAL phrase is specified in the XML PARSE statement.
- The ATTRIBUTE - NATIONAL - CHARACTER or CONTENT - NATIONAL - CHARACTER event occurs.

The special registers XML - TEXT and XML - NTEXT are mutually exclusive. When the parser sets XML - TEXT, XML - NTEXT is empty with length zero. When the parser sets XML - NTEXT, XML - TEXT is empty with length zero.

To determine the number of character encoding units in XML - NTEXT, use the LENGTH intrinsic function; for example `FUNCTION LENGTH(XML - NTEXT)`. To determine the number of bytes in XML - NTEXT, use special register `LENGTH OF XML - NTEXT`. The number of character encoding units differs from the number of bytes.

To determine the number of bytes in XML - TEXT, use either special register `LENGTH OF XML - TEXT` or the LENGTH intrinsic function; each returns the number of bytes.

The XML - TEXT and XML - NTEXT special registers are undefined outside the processing procedure.

#### **related concepts**

[“XML events” on page 511](#)

[“XML-CODE” on page 512](#)

### **related tasks**

[“Writing procedures to process XML” on page 509](#)

### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)  
[XML-TEXT \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)  
[XML-NTEXT \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## **XML-NAMESPACE and XML-NNAMESPACE**

If the XMLPARSE (XMLSS) option is in effect, the XML parser sets the XML - NAMESPACE or XML - NNAMESPACE special register to the namespace identifier for a NAMESPACE - DECLARATION XML event, or if it encounters an element name or attribute name that is in a namespace.

The parser sets XML - NNAMESPACE if the XML document is in a national data item, or if the RETURNING NATIONAL phrase is specified in the XML PARSE statement. Otherwise, the parser sets XML - NAMESPACE.

The special registers XML - NAMESPACE and XML - NNAMESPACE are mutually exclusive: If the parser sets XML - NAMESPACE, XML - NNAMESPACE is empty with length zero. If the parser sets XML - NNAMESPACE, XML - NAMESPACE is empty with length zero.

To determine the number of character encoding units in XML - NNAMESPACE, use the LENGTH intrinsic function; for example: FUNCTION LENGTH (XML - NNAMESPACE). To determine the number of bytes in XML - NNAMESPACE, use special register LENGTH OF XML - NNAMESPACE. The number of character encoding units differs from the number of bytes.

To determine the number of bytes in XML - NAMESPACE, use either special register LENGTH OF XML - NAMESPACE or the LENGTH intrinsic function; each returns the number of bytes.

The XML namespace special registers are undefined outside the processing procedure.

### **related concepts**

[“XML events” on page 511](#)  
[“XML-CODE” on page 512](#)  
[“XML-NAMESPACE-PREFIX and XML-NNAMESPACE-PREFIX” on page 515](#)  
[“XML-TEXT and XML-NTEXT” on page 514](#)

### **related tasks**

[“Writing procedures to process XML” on page 509](#)

### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

## **XML-NAMESPACE-PREFIX and XML-NNAMESPACE-PREFIX**

If the XMLPARSE (XMLSS) option is in effect, the XML parser sets the XML - NAMESPACE - PREFIX special register or the XML - NNAMESPACE - PREFIX special register for a NAMESPACE - DECLARATION XML event that also defines a namespace prefix, or if an element name or attribute name in a namespace is prefixed.

The parser sets XML - NNAMESPACE - PREFIX if the XML document is in a national data item, or the RETURNING NATIONAL phrase is specified in the XML PARSE statement. Otherwise, the parser sets XML - NAMESPACE - PREFIX.

The special registers XML - NAMESPACE - PREFIX and XML - NNAMESPACE - PREFIX are mutually exclusive: If the parser sets XML - NAMESPACE - PREFIX, XML - NNAMESPACE - PREFIX is empty with length zero. If the parser sets XML - NNAMESPACE - PREFIX, XML - NAMESPACE - PREFIX is empty with length zero.

To determine the number of character encoding units in XML - NNAMESPACE - PREFIX, use the LENGTH intrinsic function; for example: FUNCTION LENGTH (XML - NNAMESPACE - PREFIX). To determine the number of bytes in XML - NNAMESPACE - PREFIX, use special register LENGTH OF XML - NNAMESPACE - PREFIX. The number of character encoding units differs from the number of bytes.

To determine the number of bytes in XML-NAMESPACE-PREFIX, use either special register LENGTH OF XML-NAMESPACE-PREFIX or the LENGTH intrinsic function; each returns the number of bytes.

The XML namespace-prefix special registers are undefined outside the processing procedure.

#### **related concepts**

[“XML events” on page 511](#)

[“XML-NAMESPACE and XML-NNAMESPACE” on page 515](#)

#### **related tasks**

[“Writing procedures to process XML” on page 509](#)

#### **related references**

[“XMLPARSE” on page 350](#) (compiler option)

## **Transforming XML text to COBOL data items**

Because XML data is neither fixed length nor fixed format, you need to use special techniques when you move XML data to a COBOL data item.

For alphanumeric items, decide whether the XML data should go at the left (default) end, or at the right end, of the COBOL data item. If the data should go at the right end, specify the JUSTIFIED RIGHT clause in the definition of the item.

Give special consideration to numeric XML values, particularly "decorated" monetary values such as '\$1,234.00' or '\$1234'. These two strings might mean the same thing in XML, but need quite different definitions if used as COBOL sending fields.

Use one of the following techniques when you move XML data to COBOL data items:

- If the format is reasonably regular, code a MOVE to an alphanumeric item that you redefine appropriately as a numeric-edited item. Then do the final move to a numeric (operational) item by moving from, and thus de-editing, the numeric-edited item. (A regular format would have the same number of digits after the decimal point, a comma separator for values greater than 999, and so on.)
- For simplicity and vastly increased flexibility, use the following intrinsic functions for alphanumeric XML data:
  - NUMVAL to extract and decode simple numeric values from XML data that represents plain numbers
  - NUMVAL-C to extract and decode numeric values from XML data that represents monetary quantities

However, using these functions is at the expense of performance.

#### **related tasks**

[“Converting to numbers \(NUMVAL, NUMVAL-C\)” on page 113](#)

[“Using national data \(Unicode\) in COBOL” on page 124](#)

[“Writing procedures to process XML” on page 509](#)

## **Parsing XML documents with validation**

Validating an XML document determines whether the structure and content of the document conform to a set of rules. In Enterprise COBOL, the rules are expressed in an *XML schema*, which is essentially a blueprint for a class of documents.

To validate XML documents while parsing, use the VALIDATING phrase of the XML PARSE statement. To do so, you must compile your program using the XMLPARSE (XMLSS) compiler option.

You can validate XML documents only against an XML schema.

In Enterprise COBOL, a schema used for XML validation must be in a preprocessed format known as *Optimized Schema Representation*, or *OSR*. To generate a schema in OSR format from a text-form schema,

use the z/OS UNIX command `xsdosrg`, which invokes the OSR generator provided by z/OS System Services. (Alternatively, you can call the OSR generator programmatically. For details, see the related reference about z/OS XML System Services.)

For example, to convert the text-form schema in file `item.xsd` to a schema in preprocessed format in file `item.osr`, you can use the following z/OS UNIX command:

```
xsdosrg -v -o /u/HLQ/xml/item.osr /u/HLQ/xml/item.xsd
```

Use one of two forms of the `VALIDATING` phrase, depending on the location of the preprocessed schema:

- In one form, you use the `FILE` keyword and specify an XML schema name. In this case, the schema must be in an MVS data set or a z/OS UNIX file.
- In the other form, you specify the identifier of a data item that contains the schema.

If you use the `FILE` keyword and specify an XML schema name, the COBOL runtime library automatically retrieves the schema during execution of the `XML PARSE` statement. The following code fragment shows this method of specifying validation:

```
XML PARSE document-item
  VALIDATING WITH FILE schema-name
  PROCESSING PROCEDURE xml-event-handler
ON EXCEPTION
  DISPLAY 'Document has an error.'
  GOBACK
NOT ON EXCEPTION
  DISPLAY 'Document is valid.'
END-XML
```

To associate an XML schema name with the external file that contains the schema, code the `XML - SCHEMA` clause in the `SPECIAL - NAMES` paragraph, specifying either a literal or a user-defined word to identify the file.

For example, you can associate the XML schema name `schema-name` shown in the fragment above with the ddname `DDSCHEMA` by coding the ddname as a literal in the `XML - SCHEMA` clause as follows:

```
ENVIRONMENT DIVISION.
CONFIGURATION SECTION.
SPECIAL-NAMES.
  XML-SCHEMA schema-name IS 'DDSCHEMA'.
```

For running the program, you can associate ddname `DDSCHEMA` with the z/OS UNIX file `item.osr` by coding a `DD` statement as follows:

```
//GO.DDSCHEMA DD PATH='/u/HLQ/xml/item.osr'
```

Or you can use an analogous TSO `ALLOCATE` command.

Alternatively, `DDSCHEMA` in the example above could be the name of an environment variable that identifies the external file by means of a `DSN` option that specifies an MVS data set or a `PATH` option that specifies a z/OS UNIX file.

If your schema is in an MVS data set, the data set can be any sequential data set (for example, QSAM fixed blocked or variable blocked, or VSAM ESDS).

For further details about how to associate an XML schema name with the external file that contains the schema, see the related reference about the `XML - SCHEMA` clause.

**Restriction:** XML validation using the `FILE` keyword is not supported under CICS.

The automatic retrieval that occurs when you use the `FILE` keyword is convenient. But if you have several XML documents of the same type to validate, reading the schema into memory once and then reusing the schema for each of the documents provides better performance than automatic retrieval. In this case,

you use the other form of the VALIDATING phrase, in which you specify an identifier that references an alphanumeric data item that contains the XML schema. For example:

```
XML PARSE document-item
  VALIDATING WITH xmlschema
  PROCESSING PROCEDURE xml-event-handler
ON EXCEPTION
  DISPLAY 'Document has an error.'
  GOBACK
NOT ON EXCEPTION
  DISPLAY 'Document is valid.'
END-XML
```

Read the preprocessed schema into the data item, for example by using normal COBOL statements.

For more information about this form of the VALIDATING phrase, see the related reference about the XML PARSE statement.

During parsing with validation, normal XML events are returned until an exception occurs due to a validation error or well-formedness error. If an XML document is not valid, the parser signals an XML exception and passes control to the processing procedure with special register XML - EVENT containing 'EXCEPTION' and special register XML - CODE containing return code 24 in the high-order halfword and a specific validation reason code in the low-order halfword.

For information about the return code and reason code for exceptions that might occur when parsing XML documents with validation, see the related reference about exceptions with XMLPARSE (XMLSS) in effect.

[“Example: parsing XML documents with validation” on page 542](#)

#### **related concepts**

[“XML-CODE” on page 512](#)

[“XML schemas” on page 518](#)

#### **related tasks**

[“Handling XML PARSE exceptions” on page 527](#)

#### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

XML PARSE statement (*Enterprise COBOL for z/OS Language Reference*)

XML-SCHEMA clause (*Enterprise COBOL for z/OS Language Reference*)

*z/OS XML System Services User's Guide and Reference*

## **XML schemas**

An *XML schema* is a mechanism, defined by the W3C, for describing and constraining the structure and content of XML documents. An XML schema, which is itself expressed in XML, effectively defines a class of XML documents of a given type, for example, purchase orders.

For Enterprise COBOL, XML schemas used for validating XML documents must be in a preprocessed format known as *Optimized Schema Representation (OSR)*. For information about this format, see the related reference about z/OS XML System Services.

Consider an XML document that describes an item for stock-keeping purposes:

```
<stockItem itemNumber="453-SR">
  <itemName>Stainless steel rope thimbles</itemName>
  <quantityOnHand>23</quantityOnHand>
</stockItem>
```

The example document above is both well formed and valid according to the following schema. (The numbers that precede each line are not part of the schema, but are used in the explanations after the schema.)

```
1. <xsd:schema xmlns:xsd="http://www.w3.org/2001/XMLSchema">
2.
3. <xsd:element name="stockItem" type="stockItemType"/>
4.
5. <xsd:complexType name="stockItemType">
6.   <xsd:sequence>
7.     <xsd:element name="itemName" type="xsd:string" minOccurs="0"/>
8.     <xsd:element name="quantityOnHand">
9.       <xsd:simpleType>
10.        <xsd:restriction base="xsd:nonNegativeInteger">
11.          <xsd:maxExclusive value="100"/>
12.        </xsd:restriction>
13.      </xsd:simpleType>
14.    </xsd:element>
15.  </xsd:sequence>
16.  <xsd:attribute name="itemNumber" type="SKU" use="required"/>
17. </xsd:complexType>
18.
19. <xsd:simpleType name="SKU">
20.   <xsd:restriction base="xsd:string">
21.     <xsd:pattern value="\d{3}-[A-Z]{2}"/>
22.   </xsd:restriction>
23. </xsd:simpleType>
24.
25. </xsd:schema>
```

The schema declares (line 3) that the root element is `stockItem`, which has a mandatory `itemNumber` attribute (line 16) of type `SKU`, and includes a sequence (lines 6 - 15) of other elements:

- An optional `itemName` element of type `string` (line 7)
- A required `quantityOnHand` element that has a constrained range of 1 - 99 based on the type `nonNegativeInteger` (lines 8 - 14)

Type declarations can be inline and unnamed, as in lines 9 - 13, which include the `maxExclusive` facet to specify the legal values for the `quantityOnHand` element.

For the `itemNumber` attribute, by contrast, the named type `SKU` is declared separately in lines 19 - 23, which include a pattern facet that uses regular expression syntax to specify that the legal values for that type consist of (in order): 3 digits, a hyphen-minus, then two uppercase letters.

The example referenced below shows a program that parses documents against this schema.

[“Example: parsing XML documents with validation” on page 542](#)

#### **related tasks**

[“Parsing XML documents with validation” on page 516](#)

#### **related references**

*z/OS XML System Services User's Guide and Reference*

## **Parsing XML documents one segment at a time**

You can parse XML documents by passing the parser one *segment* (or record) of XML text at a time. Processing very large documents, or processing XML documents that reside in a data set, are two possible major applications of this technique.

To use this feature, compile your program with the `XMLPARSE (XMLSS)` compiler option in effect.

You parse an XML document a segment at a time by initializing the parse data item to the first segment of the XML document, and then executing the `XML PARSE` statement. The parser processes the XML text and returns XML events to your processing procedure as usual.

At the end of the text segment, the parser signals an `END-OF-INPUT XML` event, with `XML - CODE` set to zero. If there is another segment of the document to process, in your processing procedure move the next

segment of XML data to the parse data item, set XML - CODE to one, and return to the parser. To signal the end of XML segments to the parser, return to the parser with XML - CODE still set to zero.

The length of the parse data item is evaluated for each segment, and determines the segment length.

**Variable-length segments:** If the XML document segments are variable length, specify a variable-length item for the parse data item. For example, for variable-length XML segments, you can define the parse data item as one of the following items:

- A variable-length group item that contains an OCCURS DEPENDING ON clause
- A reference-modified item
- An FD record that specifies the RECORD IS VARYING DEPENDING ON clause, where the depending-on data item is used as the length in a reference modifier or ODO object for the FD record

When you send an XML document to the parser in multiple segments, document content is in some cases returned to the processing procedure in multiple fragments by means of multiple events, rather than as one large fragment in a single event.

For example, if the document is split into two segments with the split point in the middle of a string of content characters, the parser returns the content in two separate CONTENT-CHARACTERS events. In the processing procedure, you must reassemble the string of content as needed by the application.

Starting element tags, attribute names, namespace declarations, and ending element tags are always delivered to the processing procedure in a single event, even if those items are split between two segments of a document.

If a segment split occurs between the bytes of a multibyte character, the parser detects the split and reassembles the character for delivery in a single event.

If you are parsing an XML document with an unknown number of repetitive elements to be processed, use unbounded tables. For more information on unbounded tables, see [“Working with unbounded tables and groups” on page 86](#).

For each such element in a given document, manage the table size using one of the following methods:

- Calculating number of elements:
  1. Count the number of elements in the document during an initial parse.
  2. Set the OCCURS DEPENDING ON object for the table to that size
  3. Allocate storage for the table
  4. Parse the document a second time to process the XML
- Incremental expansion:
  1. Set an initial size in the OCCURS DEPENDING ON object for the unbounded table
  2. Parse the document normally. For each element
    - a. Check the limit and expand the unbounded table if necessary.
  3. Allocate a new, larger storage area:
  4. Copy the data from the smaller area
  5. Free the smaller area
  6. Set the table pointer to the address of the larger storage area.

**QSAM and VSAM files:** You can process XML documents stored in a QSAM or VSAM file as follows:

1. Open the file and read the first record of the XML document.
2. Execute the XML PARSE statement with the FD record as the parse data item.
3. In the processing-procedure logic for handling the END-OF-INPUT event, read the next record of the XML document into the parse data item. If not end-of-file (file status code 10), set XML - CODE to one and return to the parser. If end-of-file, return to the parser with XML - CODE still set to zero.
4. In your processing procedure logic for the END-OF-DOCUMENT event, close the file.

### Miscellaneous information after the root element:

The root element of an XML document might be followed by zero or more occurrences of a comment or processing instruction, in any order. If you parse the document one segment at a time, the parser signals an END-OF-INPUT XML event after processing the end tag of the root element only if the last item in the segment is incomplete. If the segment ends with a complete XML item (such as the root element end tag, or after that tag, a complete comment or processing instruction), the next XML event after the event for the item itself is the END-OF-DOCUMENT XML event.

**Tip:** To provide successive segments of XML data after the end of the root element, include at least the first nonspace character of an XML item at the end of each segment. Include a complete item only on the last segment that you want the parser to process.

For instance, in the following example, in which each line represents a segment of an XML document, the segment that includes the text `This comment ends this segment` is the last segment to be parsed:

```
<Tagline>
COBOL is the language of the future!
</Tagline> <
!--First comment--
> <?pi data?> <!--
-This comment ends this segment-->
<!-- This segment is not included in the parse-->
```

[“Example: parsing an XML document one segment at a time” on page 540](#)

#### related concepts

[“XML events” on page 511](#)

[“XML-CODE” on page 512](#)

#### related tasks

[“Parsing XML documents one segment at a time” on page 519](#)

[“XML-CODE” on page 512](#)

#### related references

[“XMLPARSE” on page 350 \(compiler option\)](#)

## Handling splits using the XML-INFORMATION special register

You can parse large XML documents by using the XML - INFORMATION special register.

To use this feature, compile your program with the XMLPARSE (XMLSS) compiler option in effect.

Splits in character content might occur at arbitrary points in the XML data stream, even with unsegmented input. The XML - INFORMATION special register simplifies the reassembly of content. This register may be required for any and all attribute values and element character content.

The length of the parse data item is evaluated for each segment, and determines the segment length.

The example, [“Example: program for processing XML” on page 532](#), demonstrates various ways of assigning values obtained from the XML document to program data items for later processing.

The XML data is provided to the parser in 40-byte records, imitating the way an XML document might be acquired from an external source such as a data file. The record boundaries are designed so that all data splits but one are accommodated by the parser. For example, the sample treats as an error a split in any content except the content of the “filling” element.

In the example, the XML - INFORMATION special register is only used to simplify the reassembly of content for the “filling” element. This register could be used for any attribute values and element character content. An XML - INFORMATION value of 2 indicates that the character data for an ATTRIBUTE-CHARACTERS or CONTENT-CHARACTERS XML event is continued in a subsequent XML event, and should thus be buffered in order to accumulate the complete character string. A subsequent XML event of the same type with an XML - INFORMATION value of 1 indicates that XML - TEXT or XML - NTEXT contains the final piece of the character content, and that the complete string can be moved to the appropriate data item.

In the example, the `STRING ... WITH POINTER` statement accumulates and describes properly the complete character value for assignment to the "filling" identifier.

```
String xml-text delimited by size into
content-buffer with pointer tally
On overflow
  Display 'content buffer ('
    length of content-buffer
    ' bytes) is too small'
  Move -1 to xml-code
End-string
```

#### related concepts

["XML events" on page 511](#)

["XML-CODE" on page 512](#)

#### related references

["XMLPARSE" on page 350 \(compiler option\)](#)

["Example: program for processing XML" on page 532](#)

## The encoding of XML documents

XML documents must be encoded in a supported code page.

XML documents generated in or parsed from national data items must be encoded in Unicode UTF-16 in big-endian format, CCSID 1200.

For XML `GENERATE` statements, documents generated in alphanumeric data items must be encoded in Unicode UTF-8 (CCSID 1208) or one of the single-byte EBCDIC encodings listed in the table below. You can use any CCSID from that table in the `ENCODING` phrase of the XML `GENERATE` statement.

For XML `PARSE` statements, documents in alphanumeric data items must be encoded as follows:

- If XMLPARSE (XMLSS) is in effect:
  - If the `RETURNING NATIONAL` phrase is specified in the XML `PARSE` statement, in any EBCDIC or ASCII encoding that is supported by z/OS Unicode Services for conversion to UTF-16
  - If the `RETURNING NATIONAL` phrase is not specified in the XML `PARSE` statement, in UTF-8 (CCSID 1208) or one of the single-byte EBCDIC encodings listed in the table below
- If XMLPARSE (COMPAT) is in effect: in one of the single-byte EBCDIC encodings listed in the table below

If XMLPARSE (XMLSS) is in effect, you can use any supported CCSID (as described above for XML `PARSE`) in the `ENCODING` phrase of the XML `PARSE` statement.

Table 68. Coded character sets for XML documents	
CCSID	Description
1208	UTF-8 <sup>1</sup>
1047	Latin 1 / Open Systems
1140, 37	USA, Canada, . . . Euro Country Extended Code Page (ECECP), Country Extended Code Page (CECP)
1141, 273	Austria, Germany ECECP, CECP
1142, 277	Denmark, Norway ECECP, CECP
1143, 278	Finland, Sweden ECECP, CECP
1144, 280	Italy ECECP, CECP
1145, 284	Spain, Latin America (Spanish) ECECP, CECP
1146, 285	UK ECECP, CECP

Table 68. <b>Coded character sets for XML documents</b> (continued)	
CCSID	Description
1147, 297	France ECECP, CECP
1148, 500	International ECECP, CECP
1149, 871	Iceland ECECP, CECP
1. Supported for the XML PARSE statement in the ENCODING phrase if XMLPARSE (XMLSS) is in effect	

#### related concepts

[“XML input document encoding” on page 523](#)

#### related tasks

[“Specifying the encoding” on page 525](#)

[“Parsing XML documents](#)

[encoded in UTF-8” on page 526](#)

[Chapter 32, “Producing XML output,” on page 545](#)

#### related references

[“CODEPAGE” on page 295](#)

[“XMLPARSE” on page 350](#) (compiler option)

## XML input document encoding

To parse an XML document using the XML PARSE statement, the document must be encoded in a supported encoding.

The supported encodings for a given parse operation depend on:

- The category of the data item that contains the XML document
- The setting of the XMLPARSE compiler option
- The optional phrases that are specified in the XML PARSE statement

For XML documents that are contained in a national data item, the supported encoding is Unicode UTF-16 in big-endian format, CCSID 1200.

For XML documents that are contained in an alphanumeric data item, the supported encodings if the XMLPARSE (XMLSS) compiler option is in effect are as follows:

- If the RETURNING NATIONAL phrase is specified in the XML PARSE statement: UTF-8 or any EBCDIC or ASCII encoding that is supported by the z/OS Unicode Services for conversion to UTF-16
- If the RETURNING NATIONAL phrase is not specified: UTF-8 or any of the single-byte EBCDIC CCSIDs listed in the related reference about the encoding of XML documents

For XML documents that are contained in an alphanumeric data item, the supported CCSIDs if XMLPARSE (COMPAT) is in effect are those specified in the related reference about the encoding of XML documents.

To parse an XML document that is encoded in an unsupported code page, first convert the document to national character data (UTF-16) by using the NATIONAL -OF intrinsic function. You can convert the individual pieces of document text that are passed to the processing procedure in special register XML -NTEXT back to the original code page by using the DISPLAY -OF intrinsic function.

#### XML declaration and white space:

XML documents can begin with *white space* only if they do not have an XML declaration:

- If an XML document begins with an XML declaration, the first angle bracket (<) in the document must be the first character in the document.

- If an XML document does not begin with an XML declaration, the first angle bracket in the document can be preceded only by white space.

White-space characters have the hexadecimal values shown in the following table.

<i>Table 69. Hexadecimal values of white-space characters</i>		
<b>White-space character</b>	<b>EBCDIC</b>	<b>Unicode</b>
Space	X'40'	X'0020'
Horizontal tabulation	X'05'	X'0009'
Carriage return	X'0D'	X'000D'
Line feed	X'25'	X'000A'
New line / next line	X'15'	X'0085'

### ***Determining the encoding of an input XML document***

The parser must know the encoding of an XML document in order to process the document correctly.

If the specified encoding is not one of the supported coded character sets, the parser signals an XML exception event before beginning the parse operation. If the *actual document encoding* does not match the specified encoding, the parser signals an appropriate XML exception after beginning the parse operation.

Several sources are used in determining the encoding of an XML document:

- If the XMLPARSE (XMLSS) option is in effect:
  - The data type of the data item that contains the XML document
  - The ENCODING phrase (if used) of the XML PARSE statement
  - The CCSID specified in the CODEPAGE compiler option
- If the XMLPARSE (COMPAT) option is in effect:
  - The data type of the data item that contains the XML document
  - The actual encoding determined when the parser examines the first few bytes of the document
  - The *encoding declaration* specified within the XML document
  - The CCSID specified in the CODEPAGE compiler option

If XMLPARSE (XMLSS) is in effect:

- Any encoding declaration specified within the XML document is ignored.
- For XML documents that are contained in a national data item, the ENCODING phrase of the XML PARSE statement must be omitted or must specify CCSID 1200. The CCSID specified in the CODEPAGE compiler option is ignored. The parser signals an XML exception event if the actual document encoding is not UTF-16 in big-endian format.
- For XML documents that are contained in an alphanumeric data item, the CCSID specified in the ENCODING phrase overrides the CODEPAGE compiler option. The parser raises an XML exception event at the beginning of the parse operation if the actual document encoding is not consistent with the specified CCSID.

#### **related tasks**

[“Converting to or from national \(Unicode\) representation” on page 131](#)

[“Specifying the encoding” on page 525](#)

[“Parsing XML documents](#)

[encoded in UTF-8” on page 526](#)

[“Handling XML PARSE exceptions” on page 527](#)

## related references

[“XMLPARSE” on page 350](#) (compiler option)

[“The encoding of XML documents” on page 522](#)

[“EBCDIC code-page-sensitive characters in XML markup” on page 526](#)

## Specifying the encoding

You can choose how to specify the encoding for parsing an XML document that is in an alphanumeric data item.

The preferred way is to omit the encoding declaration from the document and to specify the encoding using one of the following means:

- If XMLPARSE (XMLSS) is in effect: the ENCODING phrase of the XML PARSE statement, or the CODEPAGE compiler option
- If XMLPARSE (COMPAT) is in effect: the CODEPAGE compiler option

Omitting the encoding declaration makes it possible to more easily transmit an XML document between heterogeneous systems. (If you included an encoding declaration, you would need to update it to reflect any code-page translation imposed by the transmission process.)

### For XMLPARSE (COMPAT):

You can instead specify an encoding declaration in the XML declaration with which most XML documents begin. For example:

```
<?xml version="1.0" encoding="ibm-1140"?>
```

Note that the XML parser generates an exception if it encounters an XML declaration that does not begin in the first byte of an XML document.

If you specify an encoding declaration, do so in one of the following ways:

- Specify the CCSID number (with or without any number of leading zeros) prefixed by one of the following strings in any mixture of uppercase and lowercase letters:
  - IBM-
  - IBM\_
  - CCSID-
  - CCSID\_
- Use one of the aliases listed in the following table. You can code the aliases in any mixture of uppercase and lowercase letters.

Table 70. <i>Aliases for XML encoding declarations</i>	
CCSID	Supported aliases
037	EBCDIC-CP-US, EBCDIC-CP-CA, EBCDIC-CP-WT, EBCDIC-CP-NL
500	EBCDIC-CP-BE, EBCDIC-CP-CH
1200	UTF-16
1208	UTF-8

For more information about the CCSIDs that are supported for XML parsing, see the related reference about the encoding of XML documents.

## related concepts

[“XML input document encoding” on page 523](#)

## related tasks

[“Parsing XML documents](#)

[encoded in UTF-8” on page 526](#)

[“Handling encoding conflicts” on page 530](#)

## related references

[“The encoding of XML documents” on page 522](#)

## EBCDIC code-page-sensitive characters in XML markup

Several special characters that are used in XML markup have different hexadecimal representations in different EBCDIC code pages.

The following table shows those special characters and their hexadecimal values for various EBCDIC CCSIDs.

Table 71. <i>Hexadecimal values of special characters for various EBCDIC CCSIDs</i>											
Character	1047	1140	1141	1142	1143	1144	1145	1146	1147	1148	1149
[	X'AD'	X'BA'	X'63'	X'9E'	X'B5'	X'90'	X'4A'	X'B1'	X'90'	X'4A'	X'AE'
]	X'BD'	X'BB'	X'FC'	X'9F'	X'9F'	X'51'	X'5A'	X'BB'	X'B5'	X'5A'	X'9E'
!	X'5A'	X'5A'	X'4F'	X'4F'	X'4F'	X'4F'	X'BB'	X'5A'	X'4F'	X'4F'	X'4F'
	X'4F'	X'4F'	X'BB'	X'BB'	X'BB'	X'BB'	X'4F'	X'4F'	X'BB'	X'BB'	X'BB'
#	X'7B'	X'7B'	X'7B'	X'4A'	X'63'	X'B1'	X'69'	X'7B'	X'B1'	X'7B'	X'7B'

## Parsing XML documents encoded in UTF-8

If the XMLPARSE (XMLSS) compiler option is in effect, you can parse XML documents that are encoded in Unicode UTF-8 in a manner similar to parsing other XML documents. However, some additional requirements apply.

To parse a UTF-8 XML document, you must specify CCSID 1208 in the ENCODING phrase of the XML PARSE statement, as shown in the following code fragment:

```
XML PARSE xml-document
      WITH ENCODING 1208
      PROCESSING PROCEDURE xml-event-handler
END-XML
```

You define `xml-document` as an alphanumeric data item or alphanumeric group item in `WORKING-STORAGE` or `LOCAL-STORAGE`.

If you do not code the `RETURNING NATIONAL` phrase in the `XML PARSE` statement, the parser returns the XML document fragments in the alphanumeric special registers `XML-TEXT`, `XML-NAMESPACE`, and `XML-NAMESPACE-PREFIX`.

UTF-8 characters are encoded using a variable number of bytes per character. Most COBOL operations on alphanumeric data assume a single-byte encoding, in which each character is encoded in 1 byte. When you operate on UTF-8 characters as alphanumeric data, you must ensure that the data is processed correctly. Avoid operations (such as reference modification and moves that involve truncation) that can split a multibyte character between bytes. You cannot reliably use statements such as `INSPECT` to process multibyte characters in alphanumeric data.

You can more reliably process UTF-8 document fragments by specifying the `RETURNING NATIONAL` phrase in the `XML PARSE` statement. If you use the `RETURNING NATIONAL` phrase, XML document fragments are efficiently converted to UTF-16 encoding and are returned to the application in the national special registers `XML-NTEXT`, `XML-NNAMESPACE`, and `XMLNNAMESPACE-PREFIX`. Then you can process

the XML text fragments in national data items. (The UTF-16 encoding in national data items greatly facilitates Unicode processing in COBOL.)

The following code fragment illustrates the use of both the ENCODING phrase and the RETURNING NATIONAL phrase for parsing a UTF-8 XML document:

```
XML PARSE xml-document
  WITH ENCODING 1208 RETURNING NATIONAL
  PROCESSING PROCEDURE xml-event-handler
ON EXCEPTION
  DISPLAY 'XML document error ' XML-CODE
  STOP RUN
NOT ON EXCEPTION
  DISPLAY 'XML document was successfully parsed.'
END-XML
```

#### related concepts

[“XML-TEXT and XML-NTEXT” on page 514](#)

[“XML-NAMESPACE and XML-NNAMESPACE” on page 515](#)

[“XML-NAMESPACE-PREFIX and XML-NNAMESPACE-PREFIX” on page 515](#)

#### related tasks

[“Processing UTF-8 data” on page 134](#)

[“Parsing XML documents” on page 508](#)

[“Specifying the encoding” on page 525](#)

#### related references

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“The encoding of XML documents” on page 522](#)

XML PARSE statement (*Enterprise COBOL for z/OS Language Reference*)

## Handling XML PARSE exceptions

If the XML parser encounters an anomaly or error during parsing, it sets an exception code in the XML - CODE special register and signals an XML exception event. The specific exception codes that can occur and the subsequent actions that you can take differ depending on the setting of the XMLPARSE compiler option.

#### For XMLPARSE (XMLSS):

**Return code and reason code:** The exception code is formed from the return code and the reason code that the parser generates. The return code and the reason code are each a halfword binary value. The value in XML - CODE is a concatenation of these two values.

As an example, the following XML document is not well formed because the element end tag mmsg does not match the element start tag msg:

```
<msg>Hello</mmsg>
```

The return code is hexadecimal 000C (XRC\_NOT\_WELL\_FORMED), and the reason code is hexadecimal 3035 (XRSN\_ENDTAG\_NAME\_MISMATCH), if you parse the document without validation. The concatenation of these two values, hexadecimal 000C3035, is returned to the processing procedure in the XML - CODE special register.

If you parse a document with validation, the values returned in XML - CODE for any well-formedness errors differ from the values returned for the same errors when you parse without validation. The return code generated by the z/OS XML System Services parser for any validation error is 24 (hexadecimal 0018).

For more information about the return codes and reason codes that can be generated, see the related reference about exceptions with XMLPARSE (XMLSS) in effect.

If XMLPARSE (XMLSS) is in effect, processing procedures cannot handle exception events and cannot cause parsing to resume. When a processing procedure returns to the parser from an exception event, the

parser does not signal any further events. The parser transfers control to the statement that is specified in the ON EXCEPTION phrase of the XML PARSE statement. If you did not code an ON EXCEPTION phrase, control is passed to the end of the XML PARSE statement. XML -CODE contains the original exception code set by the parser.

If no exception occurs during parsing, control is passed to the statement specified in the NOT ON EXCEPTION phrase. If you did not code a NOT ON EXCEPTION phrase, control is passed to the end of the XML PARSE statement. XML -CODE contains zero.

#### **For XMLPARSE (COMPAT):**

If the exception code is within a certain range, you might be able to handle the exception event within your processing procedure, and resume parsing.

To handle an exception in the processing procedure, follow these steps:

1. Check the contents of XML -CODE.
2. Handle the exception appropriately.
3. Set XML -CODE to zero to indicate that you handled the exception.
4. Return control to the parser.

The exception condition no longer exists.

You can handle exceptions in this way only if the exception code that is passed in XML -CODE is within one of the following ranges, which indicates that an encoding conflict was detected:

- 50 - 99
- 100,001 - 165,535

**Exception codes 1 - 49:** In the processing procedure, you can do limited handling of exceptions for which the exception code is within the range 1 - 49. After an exception in this range occurs, the parser does not signal any further normal events, except the END-OF-DOCUMENT event, even if you set XML -CODE to zero before returning. If you set XML -CODE to zero, the parser continues parsing the document and signals any exceptions that it finds. (Doing so can provide a useful way to discover multiple errors in the document.)

**Restriction:** The compatibility-mode COBOL XML parser might not signal all additional exception events. The number of exceptions is limited to the remaining space in the XML PARSE event token array, probably 8192 events.

At the end of parsing after an exception that has an exception code in the range 1 - 49, control is passed to the statement specified in the ON EXCEPTION phrase. If you did not code an ON EXCEPTION phrase, control is passed to the end of the XML PARSE statement. XML -CODE contains the code set by the parser for the most recent exception.

For all exceptions other than those having an exception code within one of the ranges described above, the parser does not signal any further events, but passes control to the statement specified in the ON EXCEPTION phrase. XML -CODE contains the original exception code even if you set XML -CODE in the processing procedure before returning control to the parser.

If you do not want to handle an exception, return control to the parser without changing the value of XML -CODE. The parser transfers control to the statement specified in the ON EXCEPTION phrase. If you did not code an ON EXCEPTION phrase, control is transferred to the end of the XML PARSE statement.

If no unhandled exceptions occur before the end of parsing, control is passed to the statement specified in the NOT ON EXCEPTION phrase. If you did not code a NOT ON EXCEPTION phrase, control is transferred to the end of the XML PARSE statement. XML -CODE contains zero.

#### **related concepts**

[“XML-CODE” on page 512](#)

[“XML input document encoding” on page 523](#)

[“How the XML parser handles errors” on page 529](#)

#### **related tasks**

[“Writing procedures to process](#)

[XML” on page 509](#)

[“Parsing XML](#)

[documents with validation” on page 516](#)

[“Handling encoding conflicts” on page 530](#)

#### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“The encoding of XML documents” on page 522](#)

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

*z/OS XML System Services User's Guide and Reference*

## **How the XML parser handles errors**

When the XML parser detects an error in an XML document, it generates an XML exception event and passes control to your processing procedure.

The parser passes the following information in special registers to the processing procedure:

- XML - EVENT contains 'EXCEPTION'.
- XML - CODE contains a numeric exception code.

The exception codes are described in the related references about XML PARSE exceptions.

- For fatal exceptions, XML - TEXT or XML - NTEXT contains the document text up to and including the point where the exception was detected.
- For the warning exceptions issued for using an undeclared prefix, XML - TEXT or XML - NTEXT contains the fully qualified attribute name or element name. That is, the name includes the undeclared prefix and the separator colon (:).
- If XMLPARSE (COMPAT) is in effect, XML - TEXT or XML - NTEXT contains the document text up to and including the point where the exception was detected.
- If XMLPARSE (XMLSS) is in effect, XML - TEXT or XML - NTEXT contains the document text up to the point where the error or anomaly was detected. If you process the XML document one segment at a time, the applicable special register contains only the current segment.

All other XML special registers are empty with length zero.

#### **For XMLPARSE (XMLSS):**

Parsing cannot continue after a fatal exception even if you set XML - CODE to zero in the processing procedure. Upon return to the parser from the processing procedure, the parser transfers control to the ON EXCEPTION phrase, if specified; otherwise the parser transfers control to the end of the XML PARSE statement. XML - CODE contains the original exception code set by the parser.

#### **For XMLPARSE (COMPAT):**

The processing procedure might be able to handle an exception so that parsing continues if the exception code is within one of the following ranges:

- 1 - 99
- 100,001 - 165,535

If the exception code has any other nonzero value, parsing cannot continue.

**Encoding conflicts:** The exceptions for encoding conflicts (50 - 99 and 300 - 399) are signaled before the parsing of the document begins. For these exceptions, XML - TEXT or XML - NTEXT is either length zero or contains only the encoding declaration value from the document.

**Exception codes 1 - 49:** An exception for which the exception code is in the range 1 - 49 is a fatal error according to the *XML specification*. Therefore, the parser does not continue normal parsing even if the processing procedure handles the exception. However, the parser does continue scanning for further

errors until it reaches the end of the document, or until the existing XML EVENT token array is exhausted. For these exceptions, the parser does not signal any further normal events except the END-OF-DOCUMENT event.

#### **related concepts**

[“XML events” on page 511](#)

[“XML-CODE” on page 512](#)

[“XML input document encoding” on page 523](#)

#### **related tasks**

[“Parsing XML documents one segment at a time” on page 519](#)

[“Handling XML PARSE exceptions” on page 527](#)

[“Handling encoding conflicts” on page 530](#)

[“Terminating XML parsing” on page 531](#)

#### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“The encoding of XML documents” on page 522](#)

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

*z/OS XML System Services User's Guide and Reference*  
*XML specification*

## **Handling encoding conflicts**

The way that you handle encoding-conflict exceptions depends on the setting of the XMLPARSE compiler option.

#### **For XMLPARSE (XMLSS):**

The parser does not continue after an encoding-conflict exception or after any other type of exception. Any changes that you make in the processing procedure to the value of XML - CODE are ignored. The value in XML - CODE when the parser returns to the XML PARSE statement is the original exception code that the parser set.

#### **For XMLPARSE (COMPAT):**

Your processing procedure might be able to handle exceptions for document encoding conflicts. Exception events in which the parse data item is alphanumeric and the exception code in XML - CODE is within the range 100,001 - 165,535 indicate that the code page of the document (as specified by its encoding declaration) conflicts with the external code-page information.

In this special case, you can choose to parse using the code page of the document by subtracting 100,000 from the value in XML - CODE. For instance, if XML - CODE contains 101,140, the code page of the document is 1140. Alternatively, you can choose to parse using the *external code page* by setting XML - CODE to zero before returning to the parser.

The parser takes one of three actions after returning from a processing procedure for an encoding-conflict exception event:

- If you set XML - CODE to zero, the parser uses the external code page: the value of the CODEPAGE compiler option.
- If you set XML - CODE to the code page of the document (that is, the original XML - CODE value minus 100,000), the parser uses the code page of the document.

This is the only case in which the parser continues when XML - CODE has a nonzero value upon returning from a processing procedure.

- Otherwise, the parser stops processing the document and returns control to the XML PARSE statement with an exception condition. XML - CODE contains the exception code that was originally passed with the exception event.

#### **related concepts**

[“XML-CODE” on page 512](#)

[“XML input document encoding” on page 523](#)

[“How the XML parser handles errors” on page 529](#)

#### **related tasks**

[“Handling XML PARSE exceptions” on page 527](#)

#### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

[“The encoding of XML documents” on page 522](#)

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

*z/OS XML System Services User's Guide and Reference*

## Terminating XML parsing

---

You can terminate parsing immediately, without processing any remaining XML text, by setting XML - CODE to -1 in your processing procedure before the procedure returns to the parser from any normal XML event (that is, any event other than EXCEPTION).

You can use this technique when the processing procedure has examined enough of the document or has detected some irregularity in the document that precludes further meaningful processing.

If you terminate parsing in this way, the parser does not signal any further XML events, including the exception event. Control transfers to the ON EXCEPTION phrase of the XML PARSE statement, if that phrase was specified.

In the imperative statement of the ON EXCEPTION phrase, you can determine whether parsing was deliberately terminated by testing whether XML - CODE contains -1. If you do not specify the ON EXCEPTION phrase, control transfers to the end of the XML PARSE statement.

If the XMLPARSE (COMPAT) compiler option is in effect, you can also terminate parsing after any XML EXCEPTION event by returning to the parser from the processing procedure without changing the value in XML - CODE. The result is similar to the result of deliberate termination, except that the parser returns to the XML PARSE statement with XML - CODE containing the original exception code.

If the XMLPARSE (XMLSS) option is in effect, parsing always terminates after any exception event.

#### **related concepts**

[“XML-CODE” on page 512](#)

[“How the XML parser handles errors” on page 529](#)

#### **related tasks**

[“Writing procedures to process](#)

[XML” on page 509](#)

[“Handling XML PARSE exceptions” on page 527](#)

## XML PARSE examples

---

The examples that are referenced below illustrate various uses of the XML PARSE statement.

Use these examples to understand the basic use of XML PARSE and for XMLPARSE (XMLSS), specialized uses such as parsing documents that include namespaces, parsing documents one segment at a time, and parsing documents with validation against a schema.

[“Example: parsing a simple document” on page 532](#)

[“Example: program for processing XML” on page 532](#)

[“Example: parsing an XML document that uses namespaces” on page 537](#)

[“Example: parsing an XML document one segment at a time” on page 540](#)

[“Example: parsing XML documents with validation” on page 542](#)

## Example: parsing a simple document

This example shows the flow of events and the contents of special register XML - TEXT that result from the parsing of a simple XML document.

Assume that the COBOL program contains the following XML document in data item Doc:

```
<?xml version="1.0"?><msg type="short">Hello, World!</msg>
```

The following code fragment shows an XML PARSE statement for parsing Doc, and a processing procedure, P, for handling the XML events:

```
XML Parse Doc
  Processing procedure P
P. Display XML-Event XML-Text.
```

The processing procedure displays the content of XML - EVENT and XML - TEXT for each event that the parser signals during parsing. The following table shows the events and the text.

Table 72. XML events and special registers	
XML - EVENT	XML - TEXT
START-OF-DOCUMENT	
VERSION-INFORMATION	1.0
START-OF-ELEMENT	msg
ATTRIBUTE-NAME	type
ATTRIBUTE-CHARACTERS	short
CONTENT-CHARACTERS	Hello, World!
END-OF-ELEMENT	msg
END-OF-DOCUMENT	

### related concepts

[“XML events” on page 511](#)

[“XML-TEXT and XML-NTEXT” on page 514](#)

## Example: program for processing XML

This example shows the parsing of an XML document, and a processing procedure that reports the various XML events and their associated text fragments.

The XML document is shown in the program source to make it easier to follow the flow of the parsing. The output of the program with XMLPARSE (XMLSS) and with XMLPARSE (COMPAT) in effect is shown after the example.

To understand the interaction of the parser and the processing procedure, and to match events to document fragments, compare the XML document to the output of the program.

```
Process codepage(1047)
  Identification division.
```

```

Program-id. XMLSAMPL.
Data division.
Working-storage section.
*****
* XML document data, encoded as initial values of data items. *
*****
1 xml-document-data.
2 pic x(39) value '<?xml version="1.0" encoding="IBM-1047"'.
2 pic x(19) value ' standalone="yes"?>'.
2 pic x(39) value '<!--This document is just an example-->'.
2 pic x(10) value '<sandwich>'.
2 pic x(33) value '<bread type="baker&apos;s best"/>'.
2 pic x(36) value '<?spread We'll use real mayonnaise?>'.
2 pic x(29) value '<meat>Ham & turkey</meat>'.
2 pic x(34) value '<filling>Cheese, lettuce, tomato, '.
2 pic x(32) value 'and that's all, Folks!</filling>'.
2 pic x(25) value '<![CDATA[We should add a '.
2 pic x(20) value '<relish> element!]]>'.
2 pic x(28) value '<listprice>$4.99</listprice>'.
2 pic x(25) value '<discount>0.10</discount>'.
2 pic x(31) value '</sandwich>'.
*****
* XML document, represented as fixed-length records. *
*****
1 xml-document redefines xml-document-data.
2 xml-segment pic x(40) occurs 10 times.
1 xml-segment-no comp pic s9(4).
1 content-buffer pic x(100).
1 current-element-stack.
2 current-element pic x(30) occurs 10 times.
*****
* Sample data definitions for processing numeric XML content. *
*****
1 element-depth comp pic s9(4).
1 discount computational pic 9v99 value 0.
1 display-price pic $$$9.99.
1 filling pic x(4095).
1 list-price computational pic 9v99 value 0.
1 ofr-ed pic x(9) justified.
1 ofr-ed-1 redefines ofr-ed pic 999999.99.
Procedure division.
Mainline section.
Move 1 to xml-segment-no
Display 'Initial segment {' xml-segment(xml-segment-no) '}'
Display ' '
XML parse xml-segment(xml-segment-no)
processing procedure XML-handler
On exception
Display 'XML processing error, XML-Code=' XML-Code ' .'
Move 16 to return-code
Goback
Not on exception
Display 'XML document successfully parsed.'
End-XML
*****
* Process the transformed content and calculate promo price. *
*****
Display ' '
Display '-----***** Using information from XML '
Display ' '
Move list-price to Display-price
Display ' Sandwich list price: ' Display-price
Compute Display-price = list-price * (1 - discount)
Display ' Promotional price: ' Display-price
Display ' Get one today!'
Goback.
XML-handler section.
Evaluate XML-Event
* ==> Order XML events most frequent first
When 'START-OF-ELEMENT'
Display 'Start element tag: {' XML-Text '}'
Add 1 to element-depth
Move XML-Text to current-element(element-depth)
When 'CONTENT-CHARACTERS'
Display 'Content characters: {' XML-Text '}'
* ==> In general, a split can occur for any element or attribute
* ==> data, but in this sample, it only occurs for "filling"...
If xml-information = 2 and
current-element(element-depth) not = 'filling'
Display 'Unexpected split in content for element '
current-element(element-depth)

```

```

        Move -1 to xml-code
      End-if
    * ==> Transform XML content to operational COBOL data item...
      Evaluate current-element(element-depth)
      When 'filling'
    * ==> After reassembling separate pieces of character content...
      String xml-text delimited by size into
        content-buffer with pointer tally
      On overflow
        Display 'content buffer ('
          length of content-buffer
          ' bytes) is too small'
        Move -1 to xml-code
      End-string
      Evaluate xml-information
      When 2
        Display ' Character data for element "filling" '
          'is incomplete.'
        Display ' The partial data was buffered for '
          'content assembly.'
      When 1
        subtract 1 from tally
        move content-buffer(1:tally) to filling
        Display ' Element "filling" data (' tally
          ' bytes) is now complete:'
        Display ' {' filling(1:tally) '}'
      End-evaluate
      When 'listprice'
    * ==> Using function NUMVAL-C...
        Move XML-Text to content-buffer
        Compute list-price =
          function numval-c(content-buffer)
      When 'discount'
    * ==> Using de-editing of a numeric edited item...
        Move XML-Text to ofr-ed
        Move ofr-ed-1 to discount
      End-evaluate
      When 'END-OF-ELEMENT'
        Display 'End element tag: {' XML-Text '}'
        Subtract 1 from element-depth
      When 'END-OF-INPUT'
        Display 'End of input'
        Add 1 to xml-segment-no
        Display ' Next segment: {' xml-segment(xml-segment-no)
          '}'
        Display ' '
        Move 1 to xml-code
      When 'START-OF-DOCUMENT'
        Display 'Start of document'
        Move 0 to element-depth
        Move 1 to tally
      When 'END-OF-DOCUMENT'
        Display 'End of document.'
      When 'VERSION-INFORMATION'
        Display 'Version: {' XML-Text '}'
      When 'ENCODING-DECLARATION'
        Display 'Encoding: {' XML-Text '}'
      When 'STANDALONE-DECLARATION'
        Display 'Standalone: {' XML-Text '}'
      When 'ATTRIBUTE-NAME'
        Display 'Attribute name: {' XML-Text '}'
      When 'ATTRIBUTE-CHARACTERS'
        Display 'Attribute value characters: {' XML-Text '}'
      When 'ATTRIBUTE-CHARACTER'
        Display 'Attribute value character: {' XML-Text '}'
      When 'START-OF-CDATA-SECTION'
        Display 'Start of CData section'
      When 'END-OF-CDATA-SECTION'
        Display 'End of CData section'
      When 'CONTENT-CHARACTER'
        Display 'Content character: {' XML-Text '}'
      When 'PROCESSING-INSTRUCTION-TARGET'
        Display 'PI target: {' XML-Text '}'
      When 'PROCESSING-INSTRUCTION-DATA'
        Display 'PI data: {' XML-Text '}'
      When 'COMMENT'
        Display 'Comment: {' XML-Text '}'
      When 'EXCEPTION'
        Compute tally = function length (XML-Text)
        Display 'Exception ' XML-Code ' at offset ' tally '.'
      When other
        Display 'Unexpected XML event: ' XML-Event '.'

```

```
End-evaluate
.
End program XMLSAMPL.
```

## Output from parsing with XMLPARSE (XMLSS)

From the following output you can see which fragments of the document were associated with the events that occurred during parsing:

```
Initial segment {<?xml version="1.0" encoding="ibm-1047" }

Start of document
End of input
  Next segment: {standalone="yes"?><!--This document is j}

Version: {1.0}
Encoding: {ibm-1047}
Standalone: {yes}
Comment: {This document is j}
End of input
  Next segment: {ust an example--><sandwich><bread type="}

Comment: {ust an example}
Start element tag: {sandwich}
End of input
  Next segment: {baker&apos;s best"/><?spread We'll use r}

Start element tag: {bread}
Attribute name: {type}
Attribute value characters: {baker's best}
End element tag: {bread}
PI target: {spread}
PI data: {We'll use r}
End of input
  Next segment: {eal mayonnaise?><meat>Ham &amp; turkey</}

PI target: {spread}
PI data: {eal mayonnaise}
Start element tag: {meat}
Content characters: {Ham & turkey}
End of input
  Next segment: {meat}<filling>Cheese, lettuce, tomato, a}

End element tag: {meat}
Start element tag: {filling}
Content characters: {Cheese, lettuce, tomato, a}
  Character data for element "filling" is incomplete.
  The partial data was buffered for content assembly.
End of input
  Next segment: {nd that's all, Folks!</filling><![CDATA[}

Content characters: {nd that's all, Folks!}
  Element "filling" data (00047 bytes) is now complete:
  {Cheese, lettuce, tomato, and that's all, Folks!}
End element tag: {filling}
End of input
  Next segment: {We should add a <relish> element!]]><lis}

Start of CData section
Content characters: {We should add a <relish> element!}
End of CData section
End of input
  Next segment: {tprice>$4.99</listprice><discount>0.10</}

Start element tag: {listprice}
Content characters: {$4.99}
End element tag: {listprice}
Start element tag: {discount}
Content characters: {0.10}
End of input
  Next segment: {discount}></sandwich>                                }

End element tag: {discount}
End element tag: {sandwich}
End of document.
XML document successfully parsed.

-----+***** Using information from XML *****-----
```

```
Sandwich list price: $4.99
Promotional price: $4.49
Get one today!
```

## ***Output from parsing with XMLPARSE (COMPAT)***

From the following output you can see which fragments of the document were associated with the events that occurred during parsing:

```
Start of document
Version: {1.0}
Encoding: {IBM-1047}
Standalone: {yes}
Comment: {This document is just an example}
Start element tag: {sandwich}
Content characters: { }
Start element tag: {bread}
Attribute name: {type}
Attribute value characters: {baker}
Attribute value character: {'}
Attribute value characters: {s best}
End element tag: {bread}
Content characters: { }
PI target: {spread}
PI data: {please use real mayonnaise }
Content characters: { }
Start element tag: {meat}
Content characters: {Ham }
Content character: {&}
Content characters: { turkey}
End element tag: {meat}
Content characters: { }
Start element tag: {filling}
Content characters: {Cheese, lettuce, tomato, etc.}
End element tag: {filling}
Content characters: { }
Start of CData: {<![CDATA[}
Content characters: {We should add a <relish> element in future!}
End of CData: {]]>}
Content characters: { }
Start element tag: {listprice}
Content characters: {$4.99 }
End element tag: {listprice}
Content characters: { }
Start element tag: {discount}
Content characters: {0.10}
End element tag: {discount}
End element tag: {sandwich}
End of document.
XML document successfully parsed

-----***** Using information from XML *****-----

Sandwich list price: $4.99
Promotional price: $4.49
Get one today!
```

### **related concepts**

[“XML events” on page 511](#)

### **related tasks**

[“Handling splits using the XML-INFORMATION special register” on page 521](#)

### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

[XML-EVENT \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

# Example: parsing an XML document that uses namespaces

This example shows the parsing of a document that uses namespaces and namespace prefixes. The program must be compiled using the XMLPARSE (XMLSS) compiler option.

Namespace identifiers and namespace prefixes are used in the program to qualify element names and attribute names. This qualification makes it possible to use the same name in more than one context: title is used both as an author's title (Mr) and as a book title (Writing COBOL for Fun and Profit).

## Sample XML document

The following XML document contains several namespace declarations: a default namespace; then three namespace identifiers with prefixes (bk, pi, and isbn). Notice that the default namespace is set to the empty string for the element comment (xmlns= ' '). This setting "undeclares" the default namespace, with the result that there is no default namespace.

```
<section
xmlns="http://www.ibm.com/events"
xmlns:bk="urn:loc.gov:books"
xmlns:pi="urn:personalInformation"
xmlns:isbn="urn:ISBN:0-395-36341-6">
  <title>Book-Signing Event</title>
  <signing>
    <bk:author pi:title="Mr" pi:name="Jim Ross"/>
    <book bk:title="Writing COBOL for Fun and Profit" isbn:number="0426070806"/>
    <comment xmlns=' '>What a great issue!</comment>
  </signing>
</section>
```

## Results from parsing

The following table shows the sequence of events that the processing procedure receives from the parser, and shows the content of the associated XML special registers.

Table 73. XML events and special registers			
XML - EVENT	XML - TEXT	XML - NAMESPACE - PREFIX	XML - NAMESPACE
START-OF-DOCUMENT			
START-OF-ELEMENT	section		http://www.ibm.com/ events
NAMESPACE- DECLARATION			http://www.ibm.com/ events
NAMESPACE- DECLARATION		bk	urn:loc.gov:books
NAMESPACE- DECLARATION		pi	urn:personalInformatio n
NAMESPACE- DECLARATION		isbn	urn:ISBN:0-395-36341-6
START-OF-ELEMENT	title		http://www.ibm.com/ events
CONTENT-CHARACTERS	Book-Signing Event		
END-OF-ELEMENT	title		http://www.ibm.com/ events

Table 73. XML events and special registers (continued)			
XML - EVENT	XML - TEXT	XML - NAMESPACE - PREFIX	XML - NAMESPACE
START-OF-ELEMENT	signing		http://www.ibm.com/events
START-OF-ELEMENT	author	bk	urn:loc.gov:books
ATTRIBUTE-NAME	title	pi	urn:personalInformation
ATTRIBUTE-CHARACTERS	Mr		
ATTRIBUTE-NAME	name	pi	urn:personalInformation
ATTRIBUTE-CHARACTERS	Jim Ross		
END-OF-ELEMENT	author	bk	urn:loc.gov:books
START-OF-ELEMENT	book		http://www.ibm.com/events
ATTRIBUTE-NAME	title	bk	urn:loc.gov:books
ATTRIBUTE-CHARACTERS	Writing COBOL for Fun and Profit		
ATTRIBUTE-NAME	number	isbn	urn:ISBN:0-395-36341-6
ATTRIBUTE-CHARACTERS	0426070806		
END-OF-ELEMENT	book		http://www.ibm.com/events
START-OF-ELEMENT	comment		
NAMESPACE-DECLARATION			
CONTENT-CHARACTERS	What a great issue!		
END-OF-ELEMENT	comment		
END-OF-ELEMENT	signing		http://www.ibm.com/events
END-OF-ELEMENT	section		http://www.ibm.com/events
END-OF-DOCUMENT			

### **XML PARSE example with an undeclared namespace prefix**

The following XML document contains undeclared namespace prefixes:

```

Identification division.
  Program-id. XMLup.
  Data division.
    Working-storage section.
      1 d.

```

```

2 pic x(40) value '<pfx0:root xmlns:pfx1="http://whatever">'.
2 pic x(19) value '<pfx1:localElName1>'.
2 pic x(20) value '<pfx2:localElName2/>'.
2 pic x(40) value '<pfx3:localElName3 pfx4:localAtName4="">'.
2 pic x(02) value 'c1'.
2 pic x(41) value '<pfx5:localElName5 pfx6:localAtName6=""/>'.
2 pic x(24) value 'c2</pfx3:localElName3>c3'.
2 pic x(32) value '</pfx1:localElName1></pfx0:root>'.
Procedure division.
main.
display 'XML document: ' d
display ' '
xml parse d processing procedure h
goback.
h.
if xml-event = 'EXCEPTION'
display ' '
end-if
display xml-event xml-code '|' xml-text '|'
xml-namespace-prefix '|'
xml-namespace '|'
if xml-event = 'EXCEPTION' and xml-code = 264192 or 264193
move 0 to xml-code
end-if
.
End program XMLUp.

```

## Results from parsing XML document with an undeclared namespace prefix

The following table lists the sequence of events that the processing procedure receives from the parser, and shows the content of the associated XML special registers.

*Table 74. XML events and special registers from parsing XML document with an undeclared namespace prefix*

XML - EVENT	XML - CODE	XML - TEXT	XML - NAMESPACE - PREFIX	XML - NAMESPACE
START-OF-DOCUMENT	000000000			
EXCEPTION	000264193	pfx0:root		
START-OF-ELEMENT	000000000	root	pfx0	
NAMESPACE-DECLARATION	000000000		pfx1	http://whatever
START-OF-ELEMENT	000000000	localElName1	pfx1	http://whatever
EXCEPTION	000264193	pfx2:localElName2		
START-OF-ELEMENT	000000000	localElName2	pfx2	
END-OF-ELEMENT	000000000	localElName2	pfx2	
EXCEPTION	000264193	pfx3:localElName3		
START-OF-ELEMENT	000000000	localElName3	pfx3	
EXCEPTION	000264192	pfx4:localAtName4		
ATTRIBUTE-NAME	000000000	localAtName4	pfx4	
ATTRIBUTE-CHARACTERS	000000000			

Table 74. **XML events and special registers from parsing XML document with an undeclared namespace prefix**  
(continued)

XML - EVENT	XML - CODE	XML - TEXT	XML - NAMESPACE - PREFIX	XML - NAMESPACE
CONTENT - CHARACTERS	000000000	c1		
EXCEPTION	000264193	pfx5:localElName5		
START-OF - ELEMENT	000000000	localElName5	pfx5	
EXCEPTION	000264192	pfx6:localAtName6		
ATTRIBUTE - NAME	000000000	localAtName6	pfx6	
ATTRIBUTE - CHARACTERS	000000000			
END-OF - ELEMENT	000000000	localElName5	pfx5	
CONTENT - CHARACTERS	000000000	c2		
END-OF - ELEMENT	000000000	localElName3	pfx3	
CONTENT - CHARACTERS	000000000	c3		
END-OF - ELEMENT	000000000	localElName1	pfx1	http:// whatever
END-OF - ELEMENT	000000000	root	pfx0	
END-OF - DOCUMENT	000000000			

For a detailed description of the set of XML events, see the related reference about XML - EVENT.

#### **related concepts**

“XML events” on page 511

“XML-TEXT and XML-NTEXT” on page 514

“XML-NAMESPACE and XML-NNAMESPACE” on page 515

“XML-NAMESPACE-PREFIX and XML-NNAMESPACE-PREFIX” on page 515

#### **related references**

“XMLPARSE” on page 350 (compiler option)

XML-EVENT (*Enterprise COBOL for z/OS Language Reference*)

## **Example: parsing an XML document one segment at a time**

This example shows the parsing of a document one segment at a time. The program must be compiled using the XMLPARSE (XMLSS) compiler option.

The example shows the XML content of a file, the program that reads and submits XML text to the parser, and the sequence of events that results from parsing the input records.

### ***Content of infile***

The XML document that will be parsed a segment at a time is contained in file `infile`, shown below.

```
<?xml version='1.0'?>
<Tagline>
```

COBOL is the language of the future!  
</Tagline>

## Program PARSESEG

Program PARSESEG reads a segment (a record) of the XML document from file infile, then passes the record to the parser using the XML PARSE statement. The parser processes the XML text and transfers control to the processing procedure for each XML event. The processing procedure handles each event and returns to the parser.

At the end of the segment, the parser sets XML - EVENT to END-OF-INPUT, sets XML - CODE to zero, and transfers control to the processing procedure. The processing procedure reads the next XML record into the parse data item, sets XML - CODE to one, and returns to the parser.

The exchange between the processing procedure and the parser continues until the READ statement returns the end-of-file status code. The processing procedure returns to the parser with XML - CODE still set to zero to indicate the end of segment processing.

```
Identification division.
Program-id. PARSESEG.
Environment division.
Input-output section.
File-control.
    Select Input-XML
    Assign to infile
    File status is Input-XML-status.
Data division.
File section.
FD Input-XML
    Record is varying from 1 to 255 depending on Rec-length
    Recording mode V.
1 fdrec.
    2 pic X occurs 1 to 255 depending on Rec-length .
Working-storage section.
1 Event-number comp pic 99.
1 Rec-length comp-5 pic 9(4).
1 Input-XML-status pic 99.
Procedure division.
    Open input Input-XML
    If Input-XML-status not = 0
        Display 'Open failed, file status: ' Input-XML-status
        Goback
    End-if
    Read Input-XML
    If Input-XML-status not = 0
        Display 'Read failed, file status: ' Input-XML-status
        Goback
    End-if
    Move 0 to Event-number
    Display 'Starting with: ' fdrec
    Display 'Event number and name      Content of XML-text'
    XML parse fdrec processing procedure Handle-parse-events
    Close Input-XML
    Goback
.
Handle-parse-events.
    Add 1 to Event-number
    Display ' ' Event-number ': ' XML-event '{' XML-text '}'
    Evaluate XML-event
        When 'END-OF-INPUT'
            Read Input-XML
            Evaluate Input-XML-status
                When 0
                    Move 1 to XML-code
                    Display 'Continuing with: ' fdrec
                When 10
                    Display 'At EOF; no more input.'
                When other
                    Display 'Read failed, file status:' Input-XML-status
                    Goback
            End-evaluate
        When other
            Continue
    End-evaluate
.
```

```
End program PARSESEG.
```

## Results from parsing

To show parsing results, the processing procedure displayed each record of input, followed by the sequence of XML events and any associated text fragments in XML - TEXT. The content of XML - TEXT is displayed in braces ({ }); empty braces signify that XML - TEXT is empty.

Notice the extra zero-length CONTENT - CHARACTERS XML event at event number 08. (Such anomalies are typical when supplying XML text piecemeal.)

```
Starting with:  <?xml version='1.0'?>
Event number and name      Content of XML-TEXT
01: START-OF-DOCUMENT      {}
02: VERSION-INFORMATION    {1.0}
03: END-OF-INPUT           {}
Continuing with:  <Tagline>
04: START-OF-ELEMENT       {Tagline}
05: END-OF-INPUT           {}
Continuing with:  COBOL is the language of the future!
06: CONTENT-CHARACTERS     {COBOL is the language of the future!}
07: END-OF-INPUT           {}
Continuing with:  </Tagline>
08: CONTENT-CHARACTERS     {}
09: END-OF-ELEMENT         {Tagline}
10: END-OF-DOCUMENT        {}
```

For a detailed description of the XML events that were detected, see the related reference about XML - EVENT.

### related references

[“XMLPARSE” on page 350](#) (compiler option)

XML-EVENT (*Enterprise COBOL for z/OS Language Reference*)

## Example: parsing XML documents with validation

This example shows the parsing of several XML documents with validation against a schema, and a processing procedure that captures the return code and reason code that the parser generates after parsing each document. All of the XML documents are well formed but not necessarily valid.

The program must be compiled using the XMLPARSE (XMLSS) compiler option.

The example uses the schema that was described in the related concept about XML schemas.

Assume that file `item.xsd` contains the schema in text format, and that the preprocessed schema was generated in file `item.osr` by means of the following z/OS UNIX command:

```
xsdosrg -v -o /u/HLQ/xml/item.osr /u/HLQ/xml/item.xsd
```

The example uses the XML - SCHEMA clause to associate the XML schema name `schema` with the ddname `ddschema`. The following DD statement associates the ddname with the external z/OS UNIX file that contains the schema:

```
//GO.DDSHEMA DD PATH='/u/HLQ/xml/item.osr'
```

## Program ValidCk

```
Identification division.
Program-id. ValidCk.
Environment division.
Configuration section.
Special-names.
    xml-schema schema is 'ddschema'.
```

```

Data division.
Working-storage section.
1 xml-decode.
  2 rtn comp Pic 9(2).
  2 rsn comp-5 Pic 9(4).
1 hv pic x(16) value '0123456789ABCDEF'.
1 T Pic 999 COMP.
1 xml-document-1.
  2 pic x(52) value
    '<!--Valid: the "itemName" element can be omitted-->'.
  2 pic x(31) value '<stockItem itemNumber="123-AB">'.
  2 pic x(36) value ' <quantityOnHand>1</quantityOnHand>'.
  2 pic x(12) value '</stockItem>'.
1 xml-document-2.
  2 pic x(44)
    value '<!--Invalid: missing attribute itemNumber-->'.
  2 pic x(11) value '<stockItem>'.
  2 pic x(30) value ' <itemName>No name</itemName>'.
  2 pic x(36) value ' <quantityOnHand>1</quantityOnHand>'.
  2 pic x(12) value '</stockItem>'.
1 xml-document-3.
  2 pic x(47)
    value '<!--Invalid: unexpected attribute warehouse-->'.
  2 pic x(46) value
    '<stockItem itemNumber="074-UN" warehouse="NJ">'.
  2 pic x(37) value ' <quantityOnHand>10</quantityOnHand>'.
  2 pic x(32) value ' <itemName>Not here!</itemName>'.
  2 pic x(12) value '</stockItem>'.
1 xml-document-4.
  2 pic x(46)
    value '<!--Invalid: illegal attribute value 123-Ab-->'.
  2 pic x(31) value '<stockItem itemNumber="123-Ab">'.
  2 pic x(33) value ' <itemName>Paintbrush</itemName>'.
  2 pic x(37) value ' <quantityOnHand>10</quantityOnHand>'.
  2 pic x(12) value '</stockItem>'.
1 xml-document-5.
  2 pic x(46)
    value '<!--Invalid: missing element quantityOnHand-->'.
  2 pic x(31) value '<stockItem itemNumber="074-UN">'.
  2 pic x(32) value ' <itemName>Not here!</itemName>'.
  2 pic x(12) value '</stockItem>'.
1 xml-document-6.
  2 pic x(42)
    value '<!--Invalid: unexpected element comment-->'.
  2 pic x(31) value '<stockItem itemNumber="123-AB">'.
  2 pic x(33) value ' <itemName>Paintbrush</itemName>'.
  2 pic x(36) value ' <quantityOnHand>1</quantityOnHand>'.
  2 pic x(35) value ' <comment>Nylon bristles</comment>'.
  2 pic x(12) value '</stockItem>'.
1 xml-document-7.
  2 pic x(46) value
    '<!--Invalid: out-of-range element value 100-->'.
  2 pic x(31) value '<stockItem itemNumber="123-AB">'.
  2 pic x(33) value ' <itemName>Paintbrush</itemName>'.
  2 pic x(38) value ' <quantityOnHand>100</quantityOnHand>'.
  2 pic x(12) value '</stockItem>'.
Procedure division.
m.
  xml parse xml-document-1 validating with file schema
  processing procedure p
  xml parse xml-document-2 validating with file schema
  processing procedure p
  xml parse xml-document-3 validating with file schema
  processing procedure p
  xml parse xml-document-4 validating with file schema
  processing procedure p
  xml parse xml-document-5 validating with file schema
  processing procedure p
  xml parse xml-document-6 validating with file schema
  processing procedure p
  xml parse xml-document-7 validating with file schema
  processing procedure p
  goback
.
p.
  evaluate xml-event
  when 'COMMENT'
    display ' '
    display xml-text
  when 'END-OF-DOCUMENT'
    display ' Document successfully parsed.'
  when 'EXCEPTION'

```

```

        move xml-code to xml-decode
        Divide rsn by 16 giving tally remainder T
        display ' RC=' rtn ', reason=x'''
            hv(function mod(rsn / 4096 16) + 1:1)
            hv(function mod(rsn / 256 16) + 1:1)
            hv(function mod(rsn / 16 16) + 1:1)
            hv(T + 1:1) '''
        end-evaluate
    .
End program ValidCk.

```

## ***Output from program ValidCk***

In the following output, you can see which XML documents in the source program failed validation against the schema.

For those documents that were not valid, the parser signaled an XML exception and passed control to the processing procedure with special register XML - EVENT containing 'EXCEPTION' and special-register XML - CODE containing the return code and a specific reason code.

```

Valid: the "itemName" element can be omitted
Document successfully parsed.

Invalid: missing attribute itemNumber
RC=24, reason=x'8613'

Invalid: unexpected attribute warehouse
RC=24, reason=x'8612'

Invalid: illegal attribute value 123-Ab
RC=24, reason=x'8809'

Invalid: missing element quantityOnHand
RC=24, reason=x'8611'

Invalid: unexpected element comment
RC=24, reason=x'8607'

Invalid: out-of-range element value 100
RC=24, reason=x'8803'

```

### **related concepts**

[“XML-CODE” on page 512](#)

[“XML schemas” on page 518](#)

### **related tasks**

[“Parsing XML](#)

[documents with validation” on page 516](#)

[“Handling XML PARSE exceptions” on page 527](#)

### **related references**

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

---

## Chapter 32. Producing XML output

You can produce XML output from a COBOL program by using the XML GENERATE statement.

In the XML GENERATE statement, you identify the source and the output data items. You can optionally also identify:

- A field to receive a count of the XML characters generated
- A code page in which the generated XML document is to be encoded
- A *namespace* for the generated document
- A namespace prefix to qualify the start and end tag of each element, if you specify a namespace
- A user-defined element or attribute name in the generated XML document
- Attributes or elements to be suppressed according to some specified conditions
- Particular items to be specified as attributes, elements or content in the generated XML output.
- A statement to receive control if an exception occurs

Optionally, you can generate an XML declaration for the document, and can cause eligible source data items to be expressed as attributes in the output rather than as elements.

You can use the XML - CODE special register to determine the status of XML generation.

After you transform COBOL data items to XML, you can use the resulting XML output in various ways, such as deploying it in a web service, passing it as a message to WebSphere MQ, or transmitting it for subsequent conversion to a CICS communication area.

**Link-edit considerations:** COBOL programs that contain the XML GENERATE statement must be link-edited with AMODE 31.

### related tasks

[“Generating XML output” on page 545](#)

[“Controlling the encoding of generated XML output” on page 550](#)

[“Handling XML GENERATE exceptions” on page 550](#)

[“Enhancing XML output” on page 555](#)

### related references

*Extensible Markup Language (XML)*

XML GENERATE statement (*Enterprise COBOL for z/OS Language Reference*)

---

## Generating XML output

To transform COBOL data to XML, use the XML GENERATE statement as in the example below.

```
XML GENERATE XML-OUTPUT FROM SOURCE-REC
COUNT IN XML-CHAR-COUNT
ON EXCEPTION
  DISPLAY 'XML generation error ' XML-CODE
  STOP RUN
NOT ON EXCEPTION
  DISPLAY 'XML document was successfully generated.'
END-XML
```

In the XML GENERATE statement, you first identify the data item (XML - OUTPUT in the example above) that is to receive the XML output. Define the data item to be large enough to contain the generated XML output, typically five to 10 times the size of the COBOL source data depending on the length of its data-name or data-names.

In the DATA DIVISION, you can define the receiving identifier as alphanumeric (either an alphanumeric group item or an elementary item of category alphanumeric) or as national (either a national group item or an elementary item of category national).

Next you identify the source data item that is to be transformed to XML format (SOURCE-REC in the example). The source data item can be an alphanumeric group item, national group item, or elementary data item of class alphanumeric or national.

Some COBOL data items are not transformed to XML, but are ignored. Subordinate data items of an alphanumeric group item or national group item that you transform to XML are ignored if they:

- Specify the REDEFINES clause, or are subordinate to such a redefining item
- Specify the RENAMES clause

These items in the source data item are also ignored when you generate XML:

- Elementary FILLER (or unnamed) data items
- Slack bytes inserted for SYNCHRONIZED data items

No extra white space (for example, new lines or indentation) is inserted to make the generated XML more readable.

Optionally, you can code the COUNT IN phrase to obtain the number of XML character encoding units that are filled during generation of the XML output. If the receiving identifier has category national, the count is in UTF-16 character encoding units. For all other encodings (including UTF-8), the count is in bytes.

You can use the count field as a reference modification length to obtain only that portion of the receiving data item that contains the generated XML output. For example, XML-OUTPUT (1:XML-CHAR-COUNT) references the first XML-CHAR-COUNT character positions of XML-OUTPUT.

Consider the following program excerpt:

```
01 doc pic x(512).
01 docSize pic 9(9) binary.
01 G.
   05 A pic x(3) value "aaa".
   05 B.
       10 C pic x(3) value "ccc".
       10 D pic x(3) value "ddd".
   05 E pic x(3) value "eee".
XML Generate Doc from G
```

The code above generates the following XML document, in which A, B, and E are expressed as child elements of element G, and C and D become child elements of element B:

```
<G><A>aaa</A><B><C>ccc</C><D>ddd</D></B><E>eee</E></G>
```

Alternatively, you can specify the ATTRIBUTES phrase of the XML GENERATE statement. The ATTRIBUTES phrase causes every eligible data item included in the generated XML document to be expressed as an attribute of the containing XML element, rather than as a child element of the containing XML element. To be eligible, the data item must be elementary, must have a name other than FILLER, and must not have an OCCURS clause in its data description entry. The containing XML element corresponds to the group data item that is immediately superordinate to the elementary data item. Optionally, you can specify more precise control of which data items should be expressed as attributes or elements by using the TYPE OF phrase.

For example, suppose that the XML GENERATE statement in the program excerpt above had instead been coded as follows:

```
XML Generate Doc from G with attributes
```

The code would then generate the following XML document, in which A and E are expressed as attributes of element G, and C and D become attributes of element B:

```
<G A="aaa" E="eee"><B C="ccc" D="ddd"></B></G>
```

Optionally, you can code the `ENCODING` phrase of the `XML GENERATE` statement to specify the CCSID of the generated XML document. If you do not use the `ENCODING` phrase, the document encoding is determined by the category of the receiving data item and by the `CODEPAGE` compiler option. For further details, see the related task below about controlling the encoding of generated XML output.

Optionally, you can code the `XML-DECLARATION` phrase to cause the generated XML document to have an XML declaration that includes version information and an encoding declaration. If the receiving data item is of category:

- **National:** The encoding declaration has the value `UTF-16` (`encoding="UTF-16"`).
- **Alphanumeric:** The encoding declaration is derived from the `ENCODING` phrase, if specified, or from the `CODEPAGE` compiler option in effect for the program if the `ENCODING` phrase is not specified.

For example, the program excerpt below specifies the `XML-DECLARATION` phrase of `XML GENERATE`, and specifies encoding with CCSID 1208 (UTF-8):

```
01 Greeting.  
   05 msg pic x(80) value 'Hello, world!'.  
   .  
   . XML Generate Doc from Greeting  
     with Encoding 1208  
     with XML-declaration  
   End-XML
```

The code above generates the following XML document:

```
<?xml version="1.0" encoding="UTF-8"?><Greeting><msg>Hello, world!</msg></Greeting>
```

If you do not code the `XML-DECLARATION` phrase, an XML declaration is not generated.

Optionally, you can code the `NAMESPACE` phrase to specify a *namespace* for the generated XML document. The namespace value must be a valid *Uniform Resource Identifier (URI)*, for example, a URL (Uniform Resource Locator); for further details, see the related concept about URI syntax below.

Specify the namespace in an identifier or literal of either category national or alphanumeric.

If you specify a namespace, but do not specify a namespace prefix (described below), the namespace becomes the *default namespace* for the document. That is, the namespace define on the root element applies by default to each element name in the document, including the root element.

For example, consider the following data definitions and `XML GENERATE` statement:

```
01 Greeting.  
   05 msg pic x(80) value 'Hello, world!'.  
01 NS pic x(20) value 'http://example'.  
   .  
   . XML Generate Doc from Greeting  
     namespace is NS
```

The resulting XML document has a default namespace (`http://example`), as follows:

```
<Greeting xmlns="http://example"><msg>Hello, world!</msg></Greeting>
```

If you do not specify a namespace, the element names in the generated XML document are not in any namespace.

Optionally, you can code the `NAMESPACE-PREFIX` phrase to specify a prefix to be applied to the start and end tag of each element in the generated document. You can specify a prefix only if you have specified a namespace as described above.

When the XML GENERATE statement is executed, the prefix value must be a valid XML name, but without the colon (:); see the related reference below about namespaces for details. The value can have trailing spaces, which are removed before the prefix is used.

Specify the namespace prefix in an identifier or literal of either category national or alphanumeric.

It is recommended that the prefix be short, because it qualifies the start and end tag of each element.

For example, consider the following data definitions and XML GENERATE statement:

```
01 Greeting.  
   05 msg pic x(80) value 'Hello, world!'.  
01 NS pic x(20) value 'http://example'.  
01 NP pic x(5) value 'pre'.  
  
XML Generate Doc from Greeting  
   namespace is NS  
   namespace-prefix is NP
```

The resulting XML document has an explicit namespace (http://example), and the prefix pre is applied to the start and end tag of the elements Greeting and msg, as follows:

```
<pre:Greeting xmlns:pre="http://example"><pre:msg>Hello, world!</pre:msg></pre:Greeting>
```

Optionally, you can code the NAME phrase to specify attribute and element names in the generated XML document. The attribute and element names must be alphanumeric or national literals and must be legal names according to the XML 1.0 standard.

For example, consider the following data structure and XML GENERATE statement:

```
01 Msg.  
   02 Msg-Severity pic 9 value 1.  
   02 Msg-Date pic 9999/99/99 value "2012/04/12".  
   02 Msg-Text pic X(50) value "Sell everything!".  
01 Doc pic X(500).
```

```
XML Generate Doc from Msg  
With attributes  
   Name of Msg is "Message"  
   Msg-Severity is "Severity"  
   Msg-Date is "Date"  
   Msg-Text is "Text"  
End-XML
```

The resulting XML document is as follows:

```
<Message Severity="1" Date="2012/04/12" Text="Sell everything!"></Message>
```

Optionally, you can code the SUPPRESS phrase to specify whether individual data items are generated based on whether or not they meet certain criteria.

For example, consider the following data structure and XML GENERATE statement to suppress spaces and zeros:

```
01 G.  
   02 SensitiveInfo.  
       03 SSN pic x(11) value '123-45-6789'.  
       03 HomeAddress pic x(50) value '123 Main St, Anytown, USA'.  
   02 Aarray value spaces.  
       03 A pic AAA occurs 5.  
   02 Barray value spaces.  
       03 B pic XXX occurs 5.  
   02 Carray value zeros.  
       03 C pic 999 occurs 5.  
   Move 'abc' to A(1)  
   Move 123 to C(3)  
   XML Generate Doc from G  
       Suppress SensitiveInfo  
           every nonnumeric element when space
```

```
End-XML          every numeric element when zero
```

The resulting XML document is as follows:

```
<G>
  <Aarray><A>abc</A></Aarray>
  <Carray><C>123</C></Carray>
</G>
```

Optionally, you can use the TYPE OF phrase to specify whether individual data items are expressed as attributes, elements or content.

For example, consider the following data structure and XML GENERATE statement:

```
01 Msg.
  02 Msg-Severity pic 9 value 1.
  02 Msg-Date pic 9999/99/99 value "2012/04/12".
  02 Msg-Text pic X(50) value "Sell everything!".
01 Doc pic X(500).
  XML Generate Doc from Msg
  With attributes
    Type of Msg-Severity is attribute
    Msg-Date is attribute
    Msg-Text is element
End-XML
```

The resulting XML document is as follows:

```
<Msg Msg-Severity="1" Msg-Date="2012/04/12">
  <Msg-Text>Sell everything!</Msg-Text></Msg>
```

In addition, you can specify either or both of the following phrases to receive control after generation of the XML document:

- ON EXCEPTION, to receive control if an error occurs during XML generation
- NOT ON EXCEPTION, to receive control if no error occurs

You can end the XML GENERATE statement with the explicit scope terminator END-XML. Code END-XML to nest an XML GENERATE statement that has the ON EXCEPTION or NOT ON EXCEPTION phrase in a conditional statement.

XML generation continues until either the COBOL source record has been transformed to XML or an error occurs. If an error occurs, the results are as follows:

- The XML-CODE special register contains a nonzero exception code.
- Control is passed to the ON EXCEPTION phrase, if specified, otherwise to the end of the XML GENERATE statement.

If no error occurs during XML generation, the XML-CODE special register contains zero, and control is passed to the NOT ON EXCEPTION phrase if specified or to the end of the XML GENERATE statement otherwise.

[“Example: generating XML” on page 551](#)

### **related concepts**

[Uniform Resource Identifier \(URI\): Generic Syntax](#)

### **related tasks**

[“Controlling the encoding](#)

[of generated XML output” on page 550](#)

[“Handling XML GENERATE exceptions” on page 550](#)

[“Processing UTF-8 data” on page 134](#)

### **related references**

XML GENERATE statement (*Enterprise COBOL for z/OS Language Reference*)

## Controlling the encoding of generated XML output

When you generate XML output by using the XML GENERATE statement, you can control the encoding of the output by the category of the data item that receives the output, and by identifying the code page using the WITH ENCODING phrase of the XML GENERATE statement.

If you specify the WITH ENCODING *codepage* phrase to designate the coded character set identifier (CCSID) of the output document, *codepage* must specify an unsigned integer data item or unsigned integer literal that identifies one of the code pages supported for COBOL XML processing as described in the related reference below about the encoding of XML documents:

- If the data item that receives the generated XML is of category national, the WITH ENCODING phrase must specify 1200, the CCSID for Unicode UTF-16.
- If the receiving identifier is of category alphanumeric, the WITH ENCODING phrase must specify CCSID 1208 or the CCSID of a supported EBCDIC code page.

If you do not code the WITH ENCODING phrase, the generated XML output is encoded as shown in the table below.

Table 75. <i>Encoding of generated XML if the ENCODING phrase is omitted</i>	
If you define the receiving XML identifier as:	The generated XML output is encoded in:
Alphanumeric	The code page specified by the CODEPAGE compiler option in effect when the source was compiled
National	UTF-16 big-endian (UTF-16BE, CCSID 1200)

A byte order mark is not generated.

For details about how data items are converted to XML and how the XML element names and attributes names are formed from the COBOL data-names, see the related reference below about the operation of the XML GENERATE statement.

### related references

[“CODEPAGE” on page 295](#)

[“The encoding of XML documents” on page 522](#)

XML GENERATE statement (*Enterprise COBOL for z/OS Language Reference*)

Operation of XML GENERATE (*Enterprise COBOL for z/OS Language Reference*)

## Handling XML GENERATE exceptions

When an error is detected during generation of XML output, an exception condition exists. You can write code to check the XML-CODE special register, which contains a numeric exception code that indicates the error type.

To handle errors, use either or both of the following phrases of the XML GENERATE statement:

- ON EXCEPTION
- COUNT IN

If you code the ON EXCEPTION phrase in the XML GENERATE statement, control is transferred to the imperative statement that you specify. You might code an imperative statement, for example, to display the XML-CODE value. If you do not code an ON EXCEPTION phrase, control is transferred to the end of the XML GENERATE statement.

When an error occurs, one problem might be that the data item that receives the XML output is not large enough. In that case, the XML output is not complete, and the XML - CODE special register contains error code 400®.

You can examine the generated XML output by doing these steps:

1. Code the COUNT IN phrase in the XML GENERATE statement.

The count field that you specify holds a count of the XML character encoding units that are filled during XML generation. If you define the XML output as national, the count is in UTF-16 character encoding units; for all other encodings (including for UTF-8), the count is in bytes.

2. Use the count field as a reference modification length to refer to the substring of the receiving data item that contains the XML characters that were generated until the point when the error occurred.

For example, if XML - OUTPUT is the data item that receives the XML output, and XML - CHAR - COUNT is the count field, then XML - OUTPUT (1 : XML - CHAR - COUNT) references the XML output.

Use the contents of XML - CODE to determine what corrective action to take. For a list of the exceptions that can occur during XML generation, see the related reference below.

#### **related tasks**

[“Referring to substrings of data items” on page 107](#)

#### **related references**

[“XML GENERATE exceptions” on page 679](#)

[XML-CODE \(Enterprise COBOL for z/OS Language Reference\)](#)

## **Example: generating XML**

---

The following example simulates the building of a purchase order in a group data item, and generates an XML version of that purchase order.

Program XGFX uses XML GENERATE to produce XML output in elementary data item xmlPO from the source record, group data item purchaseOrder. Elementary data items in the source record are converted to character format as necessary, and the characters are inserted as the values of XML attributes whose names are derived from the data-names in the source record.

XGFX calls program Pretty, which uses the XML PARSE statement with processing procedure p to format the XML output with new lines and indentation so that the XML content can more easily be verified.

### **Program XGFX**

```
Identification division.
  Program-id. XGFX.
Data division.
  Working-storage section.
    01 numItems pic 99 global.
    01 purchaseOrder global.
      05 orderDate pic x(10).
      05 shipTo.
        10 country pic xx value 'US'.
        10 name pic x(30).
        10 street pic x(30).
        10 city pic x(30).
        10 state pic xx.
        10 zip pic x(10).
      05 billTo.
        10 country pic xx value 'US'.
        10 name pic x(30).
        10 street pic x(30).
        10 city pic x(30).
        10 state pic xx.
        10 zip pic x(10).
      05 orderComment pic x(80).
    05 items occurs 0 to 20 times depending on numItems.
      10 item.
        15 partNum pic x(6).
```

```

        15 productName pic x(50).
        15 quantity pic 99.
        15 USPrice pic 999v99.
        15 shipDate pic x(10).
        15 itemComment pic x(40).
    01 numChars comp pic 999.
    01 xmlPO pic x(999).
Procedure division.
m.
    Move 20 to numItems
    Move spaces to purchaseOrder

    Move '1999-10-20' to orderDate

    Move 'US' to country of shipTo
    Move 'Alice Smith' to name of shipTo
    Move '123 Maple Street' to street of shipTo
    Move 'Mill Valley' to city of shipTo
    Move 'CA' to state of shipTo
    Move '90952' to zip of shipTo

    Move 'US' to country of billTo
    Move 'Robert Smith' to name of billTo
    Move '8 Oak Avenue' to street of billTo
    Move 'Old Town' to city of billTo
    Move 'PA' to state of billTo
    Move '95819' to zip of billTo
    Move 'Hurry, my lawn is going wild!' to orderComment

    Move 0 to numItems
    Call 'addFirstItem'
    Call 'addSecondItem'
    Move space to xmlPO
    Xml generate xmlPO from purchaseOrder count in numChars
        with xml-declaration with attributes
            namespace 'http://www.example.com' namespace-prefix 'po'
    Call 'pretty' using xmlPO value numChars
    Goback
.

Identification division.
    Program-id. 'addFirstItem'.
Procedure division.
    Add 1 to numItems
    Move '872-AA' to partNum(numItems)
    Move 'Lawnmower' to productName(numItems)
    Move 1 to quantity(numItems)
    Move 148.95 to USPrice(numItems)
    Move 'Confirm this is electric' to itemComment(numItems)
    Goback.
End program 'addFirstItem'.

Identification division.
    Program-id. 'addSecondItem'.
Procedure division.
    Add 1 to numItems
    Move '926-AA' to partNum(numItems)
    Move 'Baby Monitor' to productName(numItems)
    Move 1 to quantity(numItems)
    Move 39.98 to USPrice(numItems)
    Move '1999-05-21' to shipDate(numItems)
    Goback.
End program 'addSecondItem'.

End program XGFX.

```

## Program Pretty

```

Process xmlparse(xmlss), codepage(37)
Identification division.
    Program-id. Pretty.
Data division.
Working-storage section.
    01 prettyPrint.
        05 pose pic 999.
        05 posd pic 999.
        05 depth pic 99.
        05 inx pic 999.

```

```

05 elementName pic x(30).
05 indent pic x(40).
05 buffer pic x(998).
05 lastitem pic 9.
88 unknown value 0.
88 xml-declaration value 1.
88 element value 2.
88 attribute value 3.
88 charcontent value 4.
Linkage section.
1 doc.
2 pic x occurs 16384 times depending on len.
1 len comp-5 pic 9(9).
Procedure division using doc value len.
m.
  Move space to prettyPrint
  Move 0 to depth
  Move 1 to posd pose
  Xml parse doc processing procedure p
  Goback
.
p.
  Evaluate xml-event
  When 'VERSION-INFORMATION'
    String '<?xml version="' xml-text '"' delimited by size
      into buffer with pointer posd
    Set xml-declaration to true
  When 'ENCODING-DECLARATION'
    String ' encoding="' xml-text '"' delimited by size
      into buffer with pointer posd
  When 'STANDALONE-DECLARATION'
    String ' standalone="' xml-text '"' delimited by size
      into buffer with pointer posd
  When 'START-OF-ELEMENT'
    Evaluate true
    When xml-declaration
      String '?>' delimited by size into buffer
        with pointer posd
      Set unknown to true
      Perform printline
      Move 1 to posd
    When element
      String '>' delimited by size into buffer
        with pointer posd
    When attribute
      String '>' delimited by size into buffer
        with pointer posd
    End-evaluate
    If elementName not = space
      Perform printline
    End-if
    Move xml-text to elementName
    Add 1 to depth
    Move 1 to pose
    Set element to true
    If xml-namespace-prefix = space
      String '<' xml-text delimited by size
        into buffer with pointer pose
    Else
      String '<' xml-namespace-prefix ':' xml-text
        delimited by size into buffer with pointer pose
    End-if
    Move pose to posd
  When 'ATTRIBUTE-NAME'
    If element
      String ' ' delimited by size into buffer
        with pointer posd
    Else
      String '" ' delimited by size into buffer
        with pointer posd
    End-if
    If xml-namespace-prefix = space
      String xml-text '=' delimited by size into buffer
        with pointer posd
    Else
      String xml-namespace-prefix ':' xml-text '='
        delimited by size into buffer with pointer posd
    End-if
    Set attribute to true
  When 'NAMESPACE-DECLARATION'
    If element
      String ' ' delimited by size into buffer

```

```

        with pointer posd
    Else
        String ' ' delimited by size into buffer
        with pointer posd
    End-if
    If xml-namespace-prefix = space
        String 'xmlns=' xml-namespace delimited by size
        into buffer with pointer posd
    Else
        String 'xmlns:' xml-namespace-prefix '=' xml-namespace
        delimited by size into buffer with pointer posd
    End-if
    Set attribute to true
    When 'ATTRIBUTE-CHARACTERS'
        String xml-text delimited by size into buffer
        with pointer posd
    When 'ATTRIBUTE-CHARACTER'
        String xml-text delimited by size into buffer
        with pointer posd
    When 'CONTENT-CHARACTERS'
        Evaluate true
        When element
            String '>' delimited by size into buffer
            with pointer posd
        When attribute
            String '>' delimited by size into buffer
            with pointer posd
        End-evaluate
        String xml-text delimited by size into buffer
        with pointer posd
        Set charcontent to true
    When 'CONTENT-CHARACTER'
        Evaluate true
        When element
            String '>' delimited by size into buffer
            with pointer posd
        When attribute
            String '>' delimited by size into buffer
            with pointer posd
        End-evaluate
        String xml-text delimited by size into buffer
        with pointer posd
        Set charcontent to true
    When 'END-OF-ELEMENT'
        Move space to elementName
        Evaluate true
        When element
            String '/>' delimited by size into buffer
            with pointer posd
        When attribute
            String '>' delimited by size into buffer
            with pointer posd
        When other
            If xml-namespace-prefix = space
                String '</' xml-text '>' delimited by size
                into buffer with pointer posd
            Else
                String '</' xml-namespace-prefix ':' xml-text '>'
                delimited by size into buffer with pointer posd
            End-if
        End-evaluate
        Set unknown to true
        Perform printline
        Subtract 1 from depth
        Move 1 to posd
    When other
        Continue
    End-evaluate
.
printline.
Compute inx = function max(0 2 * depth - 2) + posd - 1
If inx > 120
    compute inx = 117 - function max(0 2 * depth - 2)
    If depth > 1
        Display indent(1:2 * depth - 2) buffer(1:inx) '...'
    Else
        Display buffer(1:inx) '...'
    End-if
Else
    If depth > 1
        Display indent(1:2 * depth - 2) buffer(1:posd - 1)
    Else

```

```

        Display buffer(1:posd - 1)
      End-if
    End-if
  .
End program Pretty.

```

## Output from program XGFX

```

<?xml version="1.0" encoding="IBM-037"?>
<po:purchaseOrder xmlns:po="http://www.example.com" orderDate="1999-10-20" orderComment="Hurry, my lawn
is going wild!">
  <po:shipTo country="US" name="Alice Smith" street="123 Maple Street" city="Mill Valley" state="CA"
zip="90952"/>
  <po:billTo country="US" name="Robert Smith" street="8 Oak Avenue" city="Old Town" state="PA"
zip="95819"/>
  <po:items>
    <po:item partNum="872-AA" productName="Lawnmower" quantity="1" USPrice="148.95" shipDate=" "
itemComment="Confirm..."
  </po:item>
  </po:items>
  <po:items>
    <po:item partNum="926-AA" productName="Baby Monitor" quantity="1" USPrice="39.98"
shipDate="1999-05-21" itemComme...
  </po:item>
  </po:items>
</po:purchaseOrder>

```

### related tasks

[Chapter 31, "Processing XML input," on page 505](#)

### related references

["XMLPARSE" on page 350 \(compiler option\)](#)

[Operation of XML GENERATE \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## Enhancing XML output

It might happen that the information that you want to express in XML format already exists in a group item in the DATA DIVISION, but you are unable to use that item directly to generate an XML document because of one or more factors.

For example:

- In addition to the required data, the item has subordinate data items that contain values that are irrelevant to the XML output document.
- The names of the required data items are unsuitable for external presentation, and are possibly meaningful only to programmers.
- The required data items are broken up into too many components, and should be output as the content of the containing group.

There are various ways that you can deal with such situations. One possible technique is to define a new data item that has the appropriate characteristics, and move the required data to the appropriate fields of this new data item. However, this approach is somewhat laborious and requires careful maintenance to keep the original and new data items synchronized.

A superior approach that addresses most such problems is to use the new optional phrases of the XML GENERATE statement in order to:

- Provide more meaningful and appropriate names for the selected elementary items and for the group items that contain them.
- Exclude irrelevant data items from the generated XML by suppressing them based on their values.

The example that is referenced below shows a way to do so.

["Example: enhancing XML output" on page 556](#)

### related references

[Operation of XML GENERATE \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## Example: enhancing XML output

The following example shows how you can modify XML output.

Consider the following data structure. The XML that is generated from the structure suffers from several problems that can be corrected.

```
01  CDR-LIFE-BASE-VALUES-BOX.
    15  CDR-LIFE-BASE-VAL-DATE      PIC X(08).
    15  CDR-LIFE-BASE-VALUE-LINE    OCCURS 2 TIMES.
        20  CDR-LIFE-BASE-DESC.
            25  CDR-LIFE-BASE-DESC1 PIC X(15).
            25  FILLER                PIC X(01).
            25  CDR-LIFE-BASE-LIT     PIC X(08).
            25  CDR-LIFE-BASE-DTE     PIC X(08).
        20  CDR-LIFE-BASE-PRICE.
            25  CDR-LIFE-BP-SPACE     PIC 9(08).
            25  CDR-LIFE-BP-DASH      PIC X.
            25  CDR-LIFE-BP-SPACE1    PIC X(02).
        20  CDR-LIFE-BASE-PRICE-ED   REDEFINES
            CDR-LIFE-BASE-PRICE      PIC $$$.$$.
        20  CDR-LIFE-BASE-QTY.
            25  CDR-LIFE-QTY-SPACE    PIC X(08).
            25  CDR-LIFE-QTY-DASH     PIC X.
            25  CDR-LIFE-QTY-SPACE1   PIC X(03).
            25  FILLER                PIC X(02).
        20  CDR-LIFE-BASE-VALUE      PIC $$$9.99
            BLANK WHEN ZERO.
    15  CDR-LIFE-BASE-TOT-VALUE      PIC X(15)
```

When this data structure is populated with some sample values, and XML is generated directly from it and then formatted using program Pretty (shown in [“Example: generating XML”](#) on page 551), the result is as follows:

```
<CDR-LIFE-BASE-VALUES-BOX>
<CDR-LIFE-BASE-VAL-DATE>01/02/03</CDR-LIFE-BASE-VAL-DATE>
<CDR-LIFE-BASE-VALUE-LINE>
  <CDR-LIFE-BASE-DESC>
    <CDR-LIFE-BASE-DESC1>First</CDR-LIFE-BASE-DESC1>
    <CDR-LIFE-BASE-LIT> </CDR-LIFE-BASE-LIT>
    <CDR-LIFE-BASE-DTE>01/01/01</CDR-LIFE-BASE-DTE>
  </CDR-LIFE-BASE-DESC>
  <CDR-LIFE-BASE-PRICE>
    <CDR-LIFE-BP-SPACE>23</CDR-LIFE-BP-SPACE>
    <CDR-LIFE-BP-DASH>.</CDR-LIFE-BP-DASH>
    <CDR-LIFE-BP-SPACE1>00</CDR-LIFE-BP-SPACE1>
  </CDR-LIFE-BASE-PRICE>
  <CDR-LIFE-BASE-QTY>
    <CDR-LIFE-QTY-SPACE>123</CDR-LIFE-QTY-SPACE>
    <CDR-LIFE-QTY-DASH>.</CDR-LIFE-QTY-DASH>
    <CDR-LIFE-QTY-SPACE1>000</CDR-LIFE-QTY-SPACE1>
  </CDR-LIFE-BASE-QTY>
  <CDR-LIFE-BASE-VALUE>$765.00</CDR-LIFE-BASE-VALUE>
</CDR-LIFE-BASE-VALUE-LINE>
<CDR-LIFE-BASE-VALUE-LINE>
  <CDR-LIFE-BASE-DESC>
    <CDR-LIFE-BASE-DESC1>Second</CDR-LIFE-BASE-DESC1>
    <CDR-LIFE-BASE-LIT> </CDR-LIFE-BASE-LIT>
    <CDR-LIFE-BASE-DTE>02/02/02</CDR-LIFE-BASE-DTE>
  </CDR-LIFE-BASE-DESC>
  <CDR-LIFE-BASE-PRICE>
    <CDR-LIFE-BP-SPACE>34</CDR-LIFE-BP-SPACE>
    <CDR-LIFE-BP-DASH>.</CDR-LIFE-BP-DASH>
    <CDR-LIFE-BP-SPACE1>00</CDR-LIFE-BP-SPACE1>
  </CDR-LIFE-BASE-PRICE>
  <CDR-LIFE-BASE-QTY>
    <CDR-LIFE-QTY-SPACE>234</CDR-LIFE-QTY-SPACE>
    <CDR-LIFE-QTY-DASH>.</CDR-LIFE-QTY-DASH>
    <CDR-LIFE-QTY-SPACE1>000</CDR-LIFE-QTY-SPACE1>
  </CDR-LIFE-BASE-QTY>
  <CDR-LIFE-BASE-VALUE>$654.00</CDR-LIFE-BASE-VALUE>
</CDR-LIFE-BASE-VALUE-LINE>
<CDR-LIFE-BASE-TOT-VALUE>Very high!</CDR-LIFE-BASE-TOT-VALUE>
</CDR-LIFE-BASE-VALUES-BOX>
```

This generated XML suffers from several problems:

- The element names are long and not very meaningful. There may also be an XML schema that specifies required tag names.
- The XML schema may require some tag names that are COBOL reserved words such as DATE/TIME
- Some fields that are elements should be attributes such as, CDR-LIFE-BASE-VAL-DATE and CDR-LIFE-BASE-DESC1.
- There is unwanted data, for example, CDR-LIFE-BASE-LIT and CDR-LIFE-BASE-DTE.
- Other required fields are split into too many subcomponents. For example, CDR-LIFE-BASE-PRICE has three subcomponents for one amount.

These and other characteristics of the XML output can be remedied by using additional phrases of the XML GENERATE statement as follows:

- Use the NAME OF phrase to provide appropriate tag or attribute names.
- Use the TYPE OF ... IS ATTRIBUTE phrase to select the fields which should be XML attributes rather than elements.
- Use the TYPE OF ... IS CONTENT phrase to suppress tags for excessive subcomponents.
- Use the SUPPRESS ... WHEN phrase to exclude fields that contain uninteresting values.

Here is an example of the XML GENERATE statement to address those problems:

```
XML generate Doc from CDR-LIFE-BASE-VALUES-BOX
Count in tally
Name of
    CDR-LIFE-BASE-VALUES-BOX
    is 'Base_Values'
    CDR-LIFE-BASE-VAL-DATE
    is 'Date'
    CDR-LIFE-BASE-DTE
    is 'Date'
    CDR-LIFE-BASE-VALUE-LINE
    is 'BaseValueLine'
    CDR-LIFE-BASE-DESC1
    is 'Description'
    CDR-LIFE-BASE-PRICE
    is 'BasePrice'
    CDR-LIFE-BASE-QTY
    is 'BaseQuantity'
    CDR-LIFE-BASE-VALUE
    is 'BaseValue'
    CDR-LIFE-BASE-TOT-VALUE
    is 'TotalValue'
Type of
    CDR-LIFE-BASE-VAL-DATE is attribute
    CDR-LIFE-BASE-DESC1 is attribute
    CDR-LIFE-BP-SPACE is content
    CDR-LIFE-BP-DASH is content
    CDR-LIFE-BP-SPACE1 is content
    CDR-LIFE-QTY-SPACE is content
    CDR-LIFE-QTY-DASH is content
    CDR-LIFE-QTY-SPACE1 is content
Suppress every nonnumeric when space
        every numeric when zero
```

The result of generating and formatting XML from the statement shown above is more usable:

```
<Base_Values Date="01/02/03">
  <BaseValueLine Description="First">
    <Date>01/01/01</Date>
    <BasePrice>23.00</BasePrice>
    <BaseQuantity>123.000</BaseQuantity>
    <BaseValue>$765.00</BaseValue>
  </BaseValueLine>
  <BaseValueLine Description="Second">
    <Date>02/02/02</Date>
    <BasePrice>34.00</BasePrice>
    <BaseQuantity>234.000</BaseQuantity>
    <BaseValue>$654.00</BaseValue>
  </BaseValueLine>
  <TotalValue>Very high!</TotalValue>
```

```
</Base_Values>
```

Note that the COBOL reserved word DATE can now be used as an XML tag name in the output. Characters such as accented letters and period . that are illegal in single-byte data names can also be used.

**related references**

Operation of XML GENERATE (*Enterprise COBOL for z/OS Language Reference*)

REPLACE statement (*Enterprise COBOL for z/OS Language Reference*)

---

## Part 6. Developing object-oriented programs



---

## Chapter 33. Writing object-oriented programs

When you write an object-oriented (OO) program, you have to determine what classes you need and the methods and data that the classes need to do their work.

OO programs are based on *objects* (entities that encapsulate state and behavior) and their classes, methods, and data. A *class* is a template that defines the state and the capabilities of an object. Usually a program creates and works with multiple *object instances* (or simply, *instances*) of a class, that is, multiple objects that are members of that class. The state of each instance is stored in data known as *instance data*, and the capabilities of each instance are called *instance methods*. A class can define data that is shared by all instances of the class, known as *factory* or *static* data, and methods that are supported independently of any object instance, known as *factory* or *static* methods.

Using Enterprise COBOL, you can:

- Define classes, with methods and data implemented in COBOL.
- Create instances of Java and COBOL classes.
- Invoke methods on Java and COBOL objects.
- Write classes that inherit from Java classes or other COBOL classes.
- Define and invoke overloaded methods.

In Enterprise COBOL programs, you can call the services provided by the Java Native Interface (JNI) to obtain Java-oriented capabilities in addition to the basic OO capabilities available directly in the COBOL language.

In Enterprise COBOL classes, you can code CALL statements to interface with procedural COBOL programs. Thus COBOL class definition syntax can be especially useful for writing *wrapper* classes for procedural COBOL logic, enabling existing COBOL code to be accessed from Java.

Java code can create instances of COBOL classes, invoke methods of these classes, and can extend COBOL classes.

It is recommended that you develop and run OO COBOL programs and Java programs in the z/OS UNIX environment.

### Restrictions:

- COBOL class definitions and methods cannot contain EXEC SQL statements and cannot be compiled using the SQL compiler option.
- COBOL class definitions and methods cannot contain EXEC SQLIMS statements and cannot be compiled using the SQLIMS compiler option.
- COBOL programs that use object-oriented syntax for Java interoperability cannot contain EXEC CICS statements, and cannot be run in CICS. They cannot be compiled using the CICS compiler option.

[“Example: accounts” on page 562](#)

### related tasks

[“Defining a class” on page 564](#)

[“Defining a class instance method” on page 568](#)

[“Defining a client” on page 576](#)

[“Defining a subclass” on page 586](#)

[“Defining a factory section” on page 590](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[Upgrading IBM COBOL source programs  
\(Enterprise COBOL Migration Guide\)](#)

### related references

[The Java Language Specification](#)

## Example: accounts

Consider the example of a bank in which customers can open accounts and make deposits to and withdrawals from their accounts. You could represent an account by a general-purpose class, called `Account`. Because there are many customers, multiple instances of the `Account` class could exist simultaneously.

After you determine the classes that you need, the next step is to determine the methods that the classes need to do their work. An `Account` class must provide the following services:

- Open the account.
- Get the current balance.
- Deposit to the account.
- Withdraw from the account.
- Report account status.

The following methods for an `Account` class meet those needs:

### **init**

Open an account and assign it an account number.

### **getBalance**

Return the current balance of the account.

### **credit**

Deposit a given sum to the account.

### **debit**

Withdraw a given sum from the account.

### **print**


Display account number and account balance.

As you design an `Account` class and its methods, you discover the need for the class to keep some instance data. Typically, an `Account` object needs the following instance data:

- Account number
- Account balance
- Customer information: name, address, home phone, work phone, social security number, and so forth


To keep the example simple, however, it is assumed that the account number and account balance are the only instance data that the `Account` class needs.

Diagrams are helpful when you design classes and methods. The following diagram depicts a first attempt at a design of the `Account` class:



The words in parentheses in the diagrams are the names of the instance data, and the words that follow a number and colon are the names of the instance methods.

The structure below shows how the classes relate to each other, and is known as the *inheritance hierarchy*. The `Account` class inherits directly from the class `java.lang.Object`.




## Subclasses

In the account example, Account is a general-purpose class. However, a bank could have many different types of accounts: checking accounts, savings accounts, mortgage loans, and so forth, all of which have all the general characteristics of accounts but could have additional characteristics not shared by all types of accounts.

For example, a CheckingAccount class could have, in addition to the account number and account balance that all accounts have, a check fee that applies to each check written on the account. A CheckingAccount class also needs a method to process checks (that is, to read the amount, debit the payer, credit the payee, and so forth). So it makes sense to define CheckingAccount as a subclass of Account, and to define in the subclass the additional instance data and instance methods that the subclass needs.

As you design the CheckingAccount class, you discover the need for a class that models checks. An instance of class Check needs, at a minimum, instance data for payer, payee, and the check amount.

Many additional classes (and database and transaction-processing logic) would need to be designed in a real-world OO account system, but have been omitted to keep the example simple. The updated inheritance diagram is shown below.



A number and colon with no method-name following them indicate that the method with that number is inherited from the superclass.

**Multiple inheritance:** You cannot use *multiple inheritance* in OO COBOL applications. All classes that you define must have exactly one parent, and java.lang.Object must be at the root of every inheritance hierarchy. The class structure of any object-oriented system defined in an OO COBOL application is thus a tree.

[“Example: defining a method” on page 574](#)

#### related tasks

[“Defining a class” on page 564](#)

[“Defining a class instance method” on page 568](#)

[“Defining a subclass” on page 586](#)

## Defining a class

A COBOL class definition consists of an IDENTIFICATION DIVISION and ENVIRONMENT DIVISION, followed by an optional factory definition and optional object definition, followed by an END CLASS marker.

Table 76. <i>Structure of class definitions</i>		
Section	Purpose	Syntax
IDENTIFICATION DIVISION (required)	Name the class. Provide inheritance information for it.	<a href="#">“CLASS-ID paragraph for defining a class” on page 565</a> (required)  AUTHOR paragraph (optional) INSTALLATION paragraph (optional) DATE-WRITTEN paragraph (optional) DATE-COMPILED paragraph (optional)
ENVIRONMENT DIVISION (required)	Describe the computing environment. Relate class-names used within the class definition to the corresponding external class-names known outside the compilation unit.	CONFIGURATION SECTION (required)  <a href="#">“REPOSITORY paragraph for defining a class” on page 566</a> (required)  SOURCE-COMPUTER paragraph (optional) OBJECT-COMPUTER paragraph (optional) SPECIAL-NAMES paragraph (optional)
Factory definition (optional)	Define data to be shared by all instances of the class, and methods supported independently of any object instance.	<pre> IDENTIFICATION DIVISION. FACTORY.   DATA DIVISION.     WORKING-STORAGE SECTION.       * (Factory data here)   PROCEDURE DIVISION.       * (Factory methods here) END FACTORY.</pre>
Object definition (optional)	Define instance data and instance methods.	<pre> IDENTIFICATION DIVISION. OBJECT.   DATA DIVISION.     WORKING-STORAGE SECTION.       * (Instance data here)   PROCEDURE DIVISION.       * (Instance methods here) END OBJECT.</pre>

If you specify the SOURCE-COMPUTER, OBJECT-COMPUTER, or SPECIAL-NAMES paragraphs in a class CONFIGURATION SECTION, they apply to the entire class definition including all methods that the class introduces.

A class `CONFIGURATION SECTION` can consist of the same entries as a program `CONFIGURATION SECTION`, except that a class `CONFIGURATION SECTION` cannot contain an `INPUT-OUTPUT SECTION`. You define an `INPUT-OUTPUT SECTION` only in the individual methods that require it rather than defining it at the class level.

As shown above, you define instance data and methods in the `DATA DIVISION` and `PROCEDURE DIVISION`, respectively, within the `OBJECT` paragraph of the class definition. In classes that require data and methods that are to be associated with the class itself rather than with individual object instances, define a separate `DATA DIVISION` and `PROCEDURE DIVISION` within the `FACTORY` paragraph of the class definition.

Each COBOL class definition must be in a separate source file.

[“Example: defining a class” on page 568](#)

#### related tasks

[“WORKING-STORAGE SECTION for defining class instance data” on page 567](#)

[“Defining a class instance method” on page 568](#)

[“Defining a subclass” on page 586](#)

[“Defining a factory section” on page 590](#)

[“Describing the computing environment” on page 5](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

#### related references

COBOL class definition structure (*Enterprise COBOL for z/OS Language Reference*)

## CLASS-ID paragraph for defining a class

Use the `CLASS-ID` paragraph in the `IDENTIFICATION DIVISION` to name a class and provide inheritance information for it.

```
Identification Division.      Required
Class-id. Account inherits Base. Required
```

Use the `CLASS-ID` paragraph to identify these classes:

- The class that you are defining (Account in the example above).
- The immediate superclass from which the class that you are defining inherits its characteristics. The superclass can be implemented in Java or COBOL.

In the example above, `inherits Base` indicates that the Account class inherits methods and data from the class known within the class definition as Base. It is recommended that you use the name Base in your OO COBOL programs to refer to `java.lang.Object`.

A class-name must use single-byte characters and must conform to the normal rules of formation for a COBOL user-defined word.

Use the `REPOSITORY` paragraph in the `CONFIGURATION SECTION` of the `ENVIRONMENT DIVISION` to associate the superclass name (Base in the example) with the name of the superclass as it is known externally (`java.lang.Object` for Base). You can optionally also specify the name of the class that you are defining (Account in the example) in the `REPOSITORY` paragraph and associate it with its corresponding external class-name.

You must derive all classes directly or indirectly from the `java.lang.Object` class.

#### related tasks

[“REPOSITORY paragraph for defining a class” on page 566](#)

#### related references

`CLASS-ID` paragraph (*Enterprise COBOL for z/OS Language Reference*)

User-defined words (*Enterprise COBOL for z/OS Language Reference*)

## REPOSITORY paragraph for defining a class

Use the REPOSITORY paragraph to declare to the compiler that the specified words are class-names when you use them within a class definition, and to optionally relate the class-names to the corresponding external class-names (the class-names as they are known outside the compilation unit).

External class-names are case sensitive and must conform to Java rules of formation. For example, in the Account class definition you might code this:

Environment Division.	<b>Required</b>
Configuration Section.	<b>Required</b>
Repository.	<b>Required</b>
Class Base is "java.lang.Object"	<b>Required</b>
Class Account is "Account".	<b>Optional</b>

The REPOSITORY paragraph entries indicate that the external class-names of the classes referred to as Base and Account within the class definition are java.lang.Object and Account, respectively.

In the REPOSITORY paragraph, you must code an entry for each class-name that you explicitly reference in the class definition. For example:

- Base
- A superclass from which the class that you are defining inherits
- The classes that you reference in methods within the class definition

In a REPOSITORY paragraph entry, you must specify the external class-name if the name contains non-COBOL characters. You must also specify the external class-name for any referenced class that is part of a Java *package*. For such a class, specify the external class-name as the fully qualified name of the package, followed by period (.), followed by the simple name of the Java class. For example, the Object class is part of the java.lang package, so specify its external name as java.lang.Object as shown above.

An external class-name that you specify in the REPOSITORY paragraph must be an alphanumeric literal that conforms to the rules of formation for a fully qualified Java class-name.

If you do not include the external class-name in a REPOSITORY paragraph entry, the external class-name is formed from the class-name in the following manner:

- The class-name is converted to uppercase.
- Each hyphen is changed to zero.
- The first character, if a digit, is changed:
  - 1-9 are changed to A-I.
  - 0 is changed to J.
- Underscores are not changed.

In the example above, class Account is known externally as Account (in mixed case) because the external name is spelled using mixed case.

You can optionally include in the REPOSITORY paragraph an entry for the class that you are defining (Account in this example). You must include an entry for the class that you are defining if the external class-name contains non-COBOL characters, or to specify a fully package-qualified class-name if the class is to be part of a Java package.

[“Example: external class-names and Java packages” on page 567](#)

### related tasks

[“Declaring arrays and strings for Java” on page 606](#)

### related references

REPOSITORY paragraph (*Enterprise COBOL for z/OS Language Reference*)

[The Java Language Specification \(Identifiers\)](#)

[The Java Language Specification \(Packages\)](#)

## Example: external class-names and Java packages

The following example shows how external class-names are determined from entries in a REPOSITORY paragraph.

```
Environment division.  
Configuration section.  
Repository.  
    Class Employee is "com.acme.Employee"  
    Class JavaException is "java.lang.Exception"  
    Class Orders.
```

The local class-names (the class-names as used within the class definition), the Java packages that contain the classes, and the associated external class-names are as shown in the table below.

Local class-name	Java package	External class-name
Employee	com.acme	com.acme.Employee
JavaException	java.lang	java.lang.Exception
Orders	(unnamed)	ORDERS

The external class-name (the name after the class-name and optional IS in the REPOSITORY paragraph entry) is composed of the fully qualified name of the package (if any) followed by a period, followed by the simple name of the class.

### related tasks

[“REPOSITORY paragraph for defining a class” on page 566](#)

### related references

REPOSITORY paragraph (*Enterprise COBOL for z/OS Language Reference*)

## WORKING-STORAGE SECTION for defining class instance data

Use the WORKING-STORAGE SECTION in the DATA DIVISION of the OBJECT paragraph to describe the *instance data* that a COBOL class needs, that is, the data to be allocated for each instance of the class.

The OBJECT keyword, which you must immediately precede with an IDENTIFICATION DIVISION declaration, indicates the beginning of the definitions of the instance data and instance methods for the class. For example, the definition of the instance data for the Account class might look like this:

```
IDENTIFICATION DIVISION.  
Object.  
DATA DIVISION.  
    WORKING-STORAGE SECTION.  
        01 AccountNumber pic 9(6).  
        01 AccountBalance pic S9(9) value zero.  
End Object.
```

The instance data is allocated when an object instance is created, and exists until garbage collection of the instance by the Java run time.

You can initialize simple instance data by using VALUE clauses as shown above. You can initialize more complex instance data by coding customized methods to create and initialize instances of classes.

COBOL instance data is equivalent to Java private nonstatic member data. No other class or subclass (nor factory method in the same class, if any) can reference COBOL instance data directly. Instance data is global to all instance methods that the OBJECT paragraph defines. If you want to make instance data accessible from outside the OBJECT paragraph, define attribute (get or set) instance methods for doing so.

The syntax of the WORKING-STORAGE SECTION for instance data definition is generally the same as in a program, with these exceptions:

- You cannot use the EXTERNAL attribute.
- You can use the GLOBAL attribute, but it has no effect.

#### related tasks

[“Creating and initializing](#)

[instances of classes” on page 584](#)

[“Freeing instances of classes” on page 585](#)

[“Defining a factory method” on page 591](#)

[“Coding attribute \(get and set\) methods” on page 573](#)

## Example: defining a class

The following example shows a first attempt at the definition of the Account class, excluding method definitions.

```
cb1 dll,thread,pgmname(longmixed)
IDENTIFICATION DIVISION.
Class-id. Account inherits Base.
ENVIRONMENT DIVISION.
Configuration section.
Repository.
    Class Base      is "java.lang.Object"
    Class Account is "Account".
*
IDENTIFICATION DIVISION.
Object.
DATA DIVISION.
WORKING-STORAGE SECTION.
    01 AccountNumber pic 9(6).
    01 AccountBalance pic S9(9) value zero.
*
PROCEDURE DIVISION.
*
*   (Instance method definitions here)
*
End Object.
*
End class Account.
```

#### related tasks

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[“Defining a client” on page 576](#)

## Defining a class instance method

Define COBOL *instance methods* in the PROCEDURE DIVISION of the OBJECT paragraph of a class definition. An instance method defines an operation that is supported for each object instance of a class.

A COBOL instance method definition consists of four divisions (like a COBOL program), followed by an END METHOD marker.

Table 77. **Structure of instance method definitions**

Division	Purpose	Syntax
IDENTIFICATION (required)	Name a method.	<a href="#">“METHOD-ID paragraph for defining a class instance method” on page 569</a> (required)  AUTHOR paragraph (optional) INSTALLATION paragraph (optional) DATE-WRITTEN paragraph (optional) DATE-COMPILED paragraph (optional)
ENVIRONMENT (optional)	Relate the file-names used in a method to the corresponding file-names known to the operating system.	<a href="#">“INPUT-OUTPUT SECTION for defining a class instance method” on page 570</a> (optional)
DATA (optional)	Define external files. Allocate a copy of the data.	<a href="#">“DATA DIVISION for defining a class instance method” on page 570</a> (optional)
PROCEDURE (optional)	Code the executable statements to complete the service provided by the method.	<a href="#">“PROCEDURE DIVISION for defining a class instance method” on page 571</a> (optional)

**Definition:** The *signature* of a method consists of the name of the method and the number and type of its formal parameters. (You define the formal parameters of a COBOL method in the USING phrase of the method's PROCEDURE DIVISION header.)

Within a class definition, you do not need to make each method-name unique, but you do need to give each method a unique signature. (You *overload* methods by giving them the same name but a different signature.)

COBOL instance methods are equivalent to Java public nonstatic methods.

[“Example: defining a method” on page 574](#)

#### related tasks

[“PROCEDURE DIVISION for defining a class instance method” on page 571](#)  
[“Overloading an instance method” on page 573](#)  
[“Overriding an instance method” on page 572](#)  
[“Invoking methods \(INVOKE\)” on page 580](#)  
[“Defining a subclass instance method” on page 588](#)  
[“Defining a factory method” on page 591](#)

## METHOD-ID paragraph for defining a class instance method

Use the METHOD-ID paragraph to name an instance method. Immediately precede the METHOD-ID paragraph with an IDENTIFICATION DIVISION declaration to indicate the beginning of the method definition.

For example, the definition of the `credit` method in the `Account` class begins like this:

```
Identification Division.
Method-id. "credit".
```

Code the method-name as an alphanumeric or national literal. The method-name is processed in a case-sensitive manner and must conform to the rules of formation for a Java method-name.

Other Java or COBOL methods or programs (that is, clients) use the method-name to invoke a method.

#### **related tasks**

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Using national data \(Unicode\)](#)

[in COBOL” on page 124](#)

#### **related references**

[The Java Language Specification \(Meaning of method names\)](#)

[The Java Language Specification \(Identifiers\)](#)

METHOD-ID paragraph (*Enterprise COBOL for z/OS Language Reference*)

## **INPUT-OUTPUT SECTION for defining a class instance method**

The ENVIRONMENT DIVISION of an instance method can have only one section, the INPUT-OUTPUT SECTION. This section relates the file-names used in a method definition to the corresponding file-names as they are known to the operating system.

For example, if the Account class defined a method that read information from a file, the Account class might have an INPUT-OUTPUT SECTION that is coded like this:

```
Environment Division.  
Input-Output Section.  
File-Control.  
    Select account-file Assign AcctFile.
```

The syntax for the INPUT-OUTPUT SECTION of a method is the same as the syntax for the INPUT-OUTPUT SECTION of a program.

#### **related tasks**

[“Describing the computing environment” on page 5](#)

#### **related references**

INPUT-OUTPUT section (*Enterprise COBOL for z/OS Language Reference*)

## **DATA DIVISION for defining a class instance method**

The DATA DIVISION of an instance method consists of any of the following four sections: FILE SECTION, LOCAL-STORAGE SECTION, WORKING-STORAGE SECTION, and LINKAGE SECTION.

#### **FILE SECTION**

The same as a program FILE SECTION, except that a method FILE SECTION can define EXTERNAL files only.

#### **LOCAL-STORAGE SECTION**

A separate copy of the LOCAL-STORAGE data is allocated for each invocation of the method, and is freed on return from the method. The method LOCAL-STORAGE SECTION is similar to a program LOCAL-STORAGE SECTION.

If you specify the VALUE clause on a data item, the item is initialized to that value on each invocation of the method.

#### **WORKING-STORAGE SECTION**

A single copy of the WORKING-STORAGE data is allocated. The data persists in its last-used state until the run unit ends. The same copy of the data is used whenever the method is invoked, regardless of the invoking object or thread. The method WORKING-STORAGE SECTION is similar to a program WORKING-STORAGE SECTION.

If you specify the VALUE clause on a data item, the item is initialized to that value on the first invocation of the method. You can specify the EXTERNAL clause for the data items.

#### **LINKAGE SECTION**

The same as a program LINKAGE SECTION.

If you define a data item with the same name in both the DATA DIVISION of an instance method and the DATA DIVISION of the OBJECT paragraph, a reference in the method to that data-name refers only to the method data item. The method DATA DIVISION takes precedence.

#### related tasks

[“Describing the data” on page 10](#)

[“Sharing data by using the EXTERNAL clause” on page 475](#)

#### related references

DATA DIVISION overview (*Enterprise COBOL for z/OS Language Reference*)

## PROCEDURE DIVISION for defining a class instance method

Code the executable statements to implement the service that an instance method provides in the PROCEDURE DIVISION of the instance method.

You can code most COBOL statements in the PROCEDURE DIVISION of a method that you can code in the PROCEDURE DIVISION of a program. You cannot, however, code the following statements in a method:

- ENTRY
- EXIT PROGRAM
- The following obsolete elements of the 85 COBOL Standard:
  - ALTER
  - GOTO without a specified procedure-name
  - SEGMENT-LIMIT
  - USE FOR DEBUGGING

Additionally, because you must compile all COBOL class definitions with the THREAD compiler option, you cannot use SORT or MERGE statements in a COBOL method.

You can code the EXIT METHOD or GOBACK statement in an instance method to return control to the invoking client. Both statements have the same effect. If you specify the RETURNING phrase upon invocation of the method, the EXIT METHOD or GOBACK statement returns the value of the data item to the invoking client.

An implicit EXIT METHOD is generated as the last statement in the PROCEDURE DIVISION of each method.

You can specify STOP RUN in a method; doing so terminates the entire run unit including all threads executing within it.

You must terminate a method definition with an END METHOD marker. For example, the following statement marks the end of the credit method:

```
End method "credit".
```

**USING phrase for obtaining passed arguments:** Specify the formal parameters to a method, if any, in the USING phrase of the method's PROCEDURE DIVISION header. You must specify that the arguments are passed BY VALUE. Define each parameter as a level-01 or level-77 item in the method's LINKAGE SECTION. The data type of each parameter must be one of the types that are interoperable with Java.

**RETURNING phrase for returning a value:** Specify the data item to be returned as the method result, if any, in the RETURNING phrase of the method's PROCEDURE DIVISION header. Define the data item as a level-01 or level-77 item in the method's LINKAGE SECTION. The data type of the return value must be one of the types that are interoperable with Java.

#### related tasks

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Overriding an instance method” on page 572](#)

[“Overloading an instance method” on page 573](#)

[“Comparing and setting object references” on page 579](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

#### **related references**

[“THREAD” on page 343](#)

[The procedure division header \(\*Enterprise COBOL for z/OS Language Reference\*\)](#)

## **Overriding an instance method**

An instance method that is defined in a subclass is said to *override* an inherited instance method that would otherwise be accessible in the subclass if the two methods have the same signature.

To override a superclass instance method `m1` in a COBOL subclass, define an instance method `m1` in the subclass that has the same name and whose `PROCEDURE DIVISION USING` phrase (if any) has the same number and type of formal parameters as the superclass method has. (If the superclass method is implemented in Java, you must code formal parameters that are interoperable with the data types of the corresponding Java parameters.) When a client invokes `m1` on an instance of the subclass, the subclass method rather than the superclass method is invoked.

For example, the `Account` class defines a method `debit` whose `LINKAGE SECTION` and `PROCEDURE DIVISION` header look like this:

```
Linkage section.  
01 inDebit      pic S9(9) binary.  
Procedure Division using by value inDebit.
```

If you define a `CheckingAccount` subclass and want it to have a `debit` method that overrides the `debit` method defined in the `Account` superclass, define the subclass method with exactly one input parameter also specified as `pic S9(9) binary`. If a client invokes `debit` using an object reference to a `CheckingAccount` instance, the `CheckingAccount debit` method (rather than the `debit` method in the `Account` superclass) is invoked.

The presence or absence of a method return value and the data type of the return value used in the `PROCEDURE DIVISION RETURNING` phrase (if any) must be identical in the subclass instance method and the overridden superclass instance method.

An instance method must not override a factory method in a COBOL superclass nor a static method in a Java superclass.

[“Example: defining a method” on page 574](#)

#### **related tasks**

[“PROCEDURE DIVISION for defining a class instance method” on page 571](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Invoking overridden superclass methods” on page 583](#)

[“Defining a subclass” on page 586](#)

[“Hiding a factory or static method” on page 592](#)

#### **related references**

[The Java Language Specification \(Inheritance, overriding, and hiding\)](#)

## Overloading an instance method

Two methods that are supported in a class (whether defined in the class or inherited from a superclass) are said to be *overloaded* if they have the same name but different signatures.

You overload methods when you want to enable clients to invoke different versions of a method, for example, to initialize data using different sets of parameters.

To overload a method, define a method whose `PROCEDURE DIVISION USING` phrase (if any) has a different number or type of formal parameters than an identically named method that is supported in the same class. For example, the `Account` class defines an instance method `init` that has exactly one formal parameter. The `LINKAGE SECTION` and `PROCEDURE DIVISION` header of the `init` method look like this:

```
Linkage section.  
01 inAccountNumber pic S9(9) binary.  
Procedure Division using by value inAccountNumber.
```

Clients invoke this method to initialize an `Account` instance with a given account number (and a default account balance of zero) by passing exactly one argument that matches the data type of `inAccountNumber`.

But the `Account` class could define, for example, a second instance method `init` that has an additional formal parameter that allows the opening account balance to also be specified. The `LINKAGE SECTION` and `PROCEDURE DIVISION` header of this `init` method could look like this:

```
Linkage section.  
01 inAccountNumber pic S9(9) binary.  
01 inBalance       pic S9(9) binary.  
Procedure Division using by value inAccountNumber  
                             inBalance.
```

Clients could invoke either `init` method by passing arguments that match the signature of the required method.

The presence or absence of a method return value does not have to be consistent in overloaded methods, and the data type of the return value given in the `PROCEDURE DIVISION RETURNING` phrase (if any) does not have to be identical in overloaded methods.

You can overload factory methods in exactly the same way that you overload instance methods.

The rules for overloaded method definition and resolution of overloaded method invocations are based on the corresponding rules for Java.

### related tasks

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Defining a factory method” on page 591](#)

### related references

[The Java Language Specification \(Overloading\)](#)

## Coding attribute (get and set) methods

You can provide access to an instance variable `X` from outside the class in which `X` is defined by coding accessor (`get`) and mutator (`set`) methods for `X`.

Instance variables in COBOL are *private*: the class that defines instance variables fully encapsulates them, and only the instance methods defined in the same `OBJECT` paragraph can access them directly. Normally a well-designed object-oriented application does not need to access instance variables from outside the class.

COBOL does not directly support the concept of a public instance variable as defined in Java and other object-oriented languages, nor the concept of a class attribute as defined by CORBA. (A CORBA *attribute*

is an instance variable that has an automatically generated get method for accessing the value of the variable, and an automatically generated set method for modifying the value of the variable if the variable is not read-only.)

[“Example: coding a get method” on page 574](#)

#### **related tasks**

[“WORKING-STORAGE SECTION for defining class instance data” on page 567](#)

[“Processing the data” on page 16](#)

### **Example: coding a get method**

The following example shows the definition in the Account class of an instance method, getBalance, to return the value of the instance variable AccountBalance to a client. getBalance and AccountBalance are defined in the OBJECT paragraph of the Account class definition.

```
Identification Division.
Class-id. Account inherits Base.
* (ENVIRONMENT DIVISION not shown)
* (FACTORY paragraph not shown)
*
Identification division.
Object.
Data division.
WORKING-STORAGE SECTION.
01 AccountBalance pic S9(9) value zero.
* (Other instance data not shown)
*
Procedure Division.
*
Identification Division.
Method-id. "getBalance".
Data division.
Linkage section.
01 outBalance pic S9(9) binary.
*
Procedure Division returning outBalance.
Move AccountBalance to outBalance.
End method "getBalance".
*
* (Other instance methods not shown)
End Object.
*
End class Account.
```

### **Example: defining a method**

The following example adds to the previous example the instance method definitions of the Account class, and shows the definition of the Java Check class.

(The previous example was [“Example: defining a class” on page 568.](#))

#### **Account class**

```
cb1 dll,thread,pgmname(longmixed)
Identification Division.
Class-id. Account inherits Base.
Environment Division.
Configuration section.
Repository.
Class Base is "java.lang.Object"
Class Account is "Account".
*
* (FACTORY paragraph not shown)
*
Identification division.
Object.
Data division.
Working-storage section.
```

```

01 AccountNumber pic 9(6).
01 AccountBalance pic S9(9) value zero.
*
* Procedure Division.
*
*   init method to initialize the account:
*   Identification Division.
*   Method-id. "init".
*   Data division.
*   Linkage section.
*   01 inAccountNumber pic S9(9) binary.
*   Procedure Division using by value inAccountNumber.
*       Move inAccountNumber to AccountNumber.
*   End method "init".
*
*   getBalance method to return the account balance:
*   Identification Division.
*   Method-id. "getBalance".
*   Data division.
*   Linkage section.
*   01 outBalance pic S9(9) binary.
*   Procedure Division returning outBalance.
*       Move AccountBalance to outBalance.
*   End method "getBalance".
*
*   credit method to deposit to the account:
*   Identification Division.
*   Method-id. "credit".
*   Data division.
*   Linkage section.
*   01 inCredit pic S9(9) binary.
*   Procedure Division using by value inCredit.
*       Add inCredit to AccountBalance.
*   End method "credit".
*
*   debit method to withdraw from the account:
*   Identification Division.
*   Method-id. "debit".
*   Data division.
*   Linkage section.
*   01 inDebit pic S9(9) binary.
*   Procedure Division using by value inDebit.
*       Subtract inDebit from AccountBalance.
*   End method "debit".
*
*   print method to display formatted account number and balance:
*   Identification Division.
*   Method-id. "print".
*   Data division.
*   Local-storage section.
*   01 PrintableAccountNumber pic ZZZZZZ999999.
*   01 PrintableAccountBalance pic $$$,$$$,$$9CR.
*   Procedure Division.
*       Move AccountNumber to PrintableAccountNumber
*       Move AccountBalance to PrintableAccountBalance
*       Display " Account: " PrintableAccountNumber
*       Display " Balance: " PrintableAccountBalance.
*   End method "print".
*
* End Object.
*
* End class Account.

```

## Check class

```

/**
 * A Java class for check information
 */
public class Check {
    private CheckingAccount payer;
    private Account payee;
    private int amount;

    public Check(CheckingAccount inPayer, Account inPayee, int inAmount) {
        payer=inPayer;
        payee=inPayee;
        amount=inAmount;
    }
}

```

```

    public int getAmount() {
        return amount;
    }

    public Account getPayee() {
        return payee;
    }
}

```

### related tasks

Chapter 16, “Compiling, linking, and running OO applications,” on page 273

## Defining a client

A program or method that requests services from one or more methods in a class is called a *client* of that class.

In a COBOL or Java client, you can:

- Create object instances of Java and COBOL classes.
- Invoke instance methods on Java and COBOL objects.
- Invoke COBOL factory methods and Java static methods.

In a COBOL client, you can also call services provided by the Java Native Interface (JNI).

A COBOL client program consists of the usual four divisions:

Table 78. <b>Structure of COBOL clients</b>		
Division	Purpose	Syntax
IDENTIFICATION (required)	Name a client.	Code as usual, except that a client program must be: <ul style="list-style-type: none"> <li>• Recursive (declared RECURSIVE in the PROGRAM- ID paragraph)</li> <li>• Thread-enabled (compiled with the THREAD option, and conforming to the coding guidelines for threaded applications)</li> </ul>
ENVIRONMENT (required)	Describe the computing environment. Relate class-names used in the client to the corresponding external class-names known outside the compilation unit.	CONFIGURATION SECTION (required)  <a href="#">“REPOSITORY paragraph for defining a client” on page 577</a> (required)
DATA (optional)	Describe the data that the client needs.	<a href="#">“DATA DIVISION for defining a client” on page 578</a> (optional)
PROCEDURE (optional)	Create instances of classes, manipulate object reference data items, and invoke methods.	Code using INVOKE, IF, and SET statements.

Because you must compile all COBOL programs that contain object-oriented syntax or that interoperate with Java with the THREAD compiler option, you cannot use the following language elements in a COBOL client:

- SORT or MERGE statements
- Nested programs

Any programs that you compile with the THREAD compiler option must be recursive. You must specify the RECURSIVE clause in the PROGRAM-ID paragraph of each OO COBOL client program.

[“Example: defining a client” on page 586](#)

#### **related tasks**

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[Chapter 28, “Preparing COBOL programs for multithreading,” on page 491](#)

[Chapter 34, “Communicating with Java methods,” on page 601](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Creating and initializing instances of classes” on page 584](#)

[“Comparing and setting object references” on page 579](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Invoking factory or static methods” on page 593](#)

#### **related references**

[“THREAD” on page 343](#)

## **REPOSITORY paragraph for defining a client**

Use the REPOSITORY paragraph to declare to the compiler that the specified words are class-names when you use them in a COBOL client, and to optionally relate the class-names to the corresponding external class-names (the class-names as they are known outside the compilation unit).

External class-names are case sensitive, and must conform to Java rules of formation. For example, in a client program that uses the Account and Check classes you might code this:

```
Environment division.      Required  
Configuration section.    Required  
  Source-Computer.  IBM-390.  
  Object-Computer.  IBM-390.  
Repository.              Required  
  Class Account is "Account"  
  Class Check  is "Check".
```

The REPOSITORY paragraph entries indicate that the external class-names of the classes referred to as Account and Check within the client are Account and Check, respectively.

In the REPOSITORY paragraph, you must code an entry for each class-name that you explicitly reference in the client. In a REPOSITORY paragraph entry, you must specify the external class-name if the name contains non-COBOL characters.

You must specify the external class-name for any referenced class that is part of a Java package. For such a class, specify the external class-name as the fully qualified name of the package, followed by period (.), followed by the simple name of the Java class.

An external class-name that you specify in the REPOSITORY paragraph must be an alphanumeric literal that conforms to the rules of formation for a fully qualified Java class-name.

If you do not include the external class-name in a REPOSITORY paragraph entry, the external class-name is formed from the class-name in the same manner as it is when an external class-name is not included in a REPOSITORY paragraph entry in a class definition. In the example above, class Account and class Check are known externally as Account and Check (in mixed case), respectively, because the external names are spelled using mixed case.

The SOURCE-COMPUTER, OBJECT-COMPUTER, and SPECIAL-NAMES paragraphs of the CONFIGURATION SECTION are optional.

### related tasks

[“REPOSITORY paragraph for defining a class” on page 566](#)

### related references

REPOSITORY paragraph (*Enterprise COBOL for z/OS Language Reference*)

[The Java Language Specification \(Identifiers\)](#)

[The Java Language Specification \(Packages\)](#)

## DATA DIVISION for defining a client

You can use any of the sections of the DATA DIVISION to describe the data that the client needs.

```
Data Division.  
Local-storage section.  
01  anAccount      usage object reference Account.  
01  aCheckingAccount usage object reference CheckingAccount.  
01  aCheck         usage object reference Check.  
01  payee          usage object reference Account.  
  . . .
```

Because a client references classes, it needs one or more special data items called *object references*, that is, references to instances of those classes. All requests to instance methods require an object reference to an instance of a class in which the method is supported (that is, either defined or available by inheritance). You code object references to refer to instances of Java classes using the same syntax as you use to refer to instances of COBOL classes. In the example above, the phrase `usage object reference` indicates an object reference data item.

All four object references in the code above are called *typed* object references because a class-name appears after the OBJECT REFERENCE phrase. A typed object reference can refer only to an instance of the class named in the OBJECT REFERENCE phrase or to one of its subclasses. Thus `anAccount` can refer to instances of the `Account` class or one of its subclasses, but cannot refer to instances of any other class. Similarly, `aCheck` can refer only to instances of the `Check` class or any subclasses that it might have.

Another type of object reference, not shown above, does not have a class-name after the OBJECT REFERENCE phrase. Such a reference is called a *universal* object reference, which means that it can refer to instances of any class. Avoid coding universal object references, because they are interoperable with Java in only very limited circumstances (when used in the RETURNING phrase of the INVOKE *class-name* NEW . . . statement).

You must define, in the REPOSITORY paragraph of the CONFIGURATION SECTION, class-names that you use in the OBJECT REFERENCE phrase.

### related tasks

[“Choosing LOCAL-STORAGE or WORKING-STORAGE” on page 578](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[“REPOSITORY paragraph for defining a client” on page 577](#)

### related references

RETURNING phrase (*Enterprise COBOL for z/OS Language Reference*)

## Choosing LOCAL-STORAGE or WORKING-STORAGE

You can in general use the WORKING-STORAGE SECTION to define working data that a client program needs. However, if the program could simultaneously run on multiple threads, you might instead want to define the data in the LOCAL-STORAGE SECTION.

Each thread has access to a separate copy of LOCAL-STORAGE data but shares access to a single copy of WORKING-STORAGE data. If you define the data in the WORKING-STORAGE SECTION, you need to synchronize access to the data or ensure that no two threads can access it simultaneously.

## related tasks

Chapter 28, “Preparing COBOL programs for multithreading,” on page 491

## Comparing and setting object references

You can compare object references by coding conditional statements or a call to the JNI service `IsSameObject`, and you can set object references by using the `SET` statement.

For example, code either `IF` statement below to check whether the object reference `anAccount` refers to no object instance:

```
If anAccount = Null . . .  
If anAccount = Nulls . . .
```

You can code a call to `IsSameObject` to check whether two object references, `object1` and `object2`, refer to the same object instance or whether each refers to no object instance. To ensure that the arguments and return value are interoperable with Java and to establish addressability to the callable service, code the following data definitions and statements before the call to `IsSameObject`:

```
Local-storage Section.  
01 is-same Pic X.  
88 is-same-false Value X'00'.  
88 is-same-true Value X'01' Through X'FF'.  
Linkage Section.  
Copy JNI.  
Procedure Division.  
Set Address Of JNIEnv To JNIEnvPtr  
Set Address Of JNINativeInterface To JNIEnv  
Call IsSameObject Using By Value JNIEnvPtr object1 object2  
Returning is-same  
If is-same-true . . .
```

Within a method you can check whether an object reference refers to the object instance on which the method was invoked by coding a call to `IsSameObject` that compares the object reference and `SELF`.

You can instead invoke the Java `equals` method (inherited from `java.lang.Object`) to determine whether two object references refer to the same object instance.

You can make an object reference refer to no object instance by using the `SET` statement. For example:

```
Set anAccount To Null.
```

You can also make one object reference refer to the same instance as another object reference does by using the `SET` statement. For example:

```
Set anotherAccount To anAccount.
```

This `SET` statement causes `anotherAccount` to refer to the same object instance as `anAccount` does. If the receiver (`anotherAccount`) is a universal object reference, the sender (`anAccount`) can be either a universal or a typed object reference. If the receiver is a typed object reference, the sender must be a typed object reference bound to the same class as the receiver or to one of its subclasses.

Within a method you can make an object reference refer to the object instance on which the method was invoked by setting it to `SELF`. For example:

```
Set anAccount To Self.
```

### related tasks

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Accessing JNI services” on page 601](#)

### related references

[The Java Native Interface \(IsSameObject\)](#)

## Invoking methods (INVOKE)

In a Java client, you can create object instances of classes that were implemented in COBOL and invoke methods on those objects using standard Java syntax. In a COBOL client, you can invoke methods that are defined in Java or COBOL classes by coding the INVOKE statement.

```
Invoke Account "createAccount"  
    using by value 123456  
    returning anAccount  
Invoke anAccount "credit" using by value 500.
```

The first example INVOKE statement above uses the class-name Account to invoke a method called createAccount. This method must be either defined or inherited in the Account class, and must be one of the following types:

- A Java static method
- A COBOL factory method

The phrase `using by value 123456` indicates that 123456 is an input argument to the method, and is passed by value. The input argument 123456 and the returned data item anAccount must conform to the definition of the formal parameters and return type, respectively, of the (possibly overloaded) createAccount method.

The second INVOKE statement uses the returned object reference anAccount to invoke the instance method credit, which is defined in the Account class. The input argument 500 must conform to the definition of the formal parameters of the (possibly overloaded) credit method.

Code the name of the method to be invoked either as a literal or as an identifier whose value at run time matches the method-name in the signature of the target method. The method-name must be an alphanumeric or national literal or a category alphabetic, alphanumeric, or national data item, and is interpreted in a case-sensitive manner.

When you code an INVOKE statement using an object reference (as in the second example statement above), the statement begins with one of the following two forms:

```
Invoke objRef "literal-name" . . .  
Invoke objRef identifier-name . . .
```

When the method-name is an identifier, you must define the object reference (objRef) as USAGE OBJECT REFERENCE with no specified type, that is, as a universal object reference.

If an invoked method is not supported in the class to which the object reference refers, a severity-3 Language Environment condition is raised at run time unless you code the ON EXCEPTION phrase in the INVOKE statement.

You can use the optional scope terminator END-INVOKE with the INVOKE statement.

The INVOKE statement does not set the RETURN-CODE special register.

### related tasks

[“USING phrase for passing arguments” on page 581](#)

[“RETURNING phrase for obtaining a returned value” on page 583](#)

[“PROCEDURE DIVISION for](#)

[defining a class instance method” on page 571](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Invoking overridden superclass](#)

[methods” on page 583](#)

[“Invoking factory or static](#)

[methods” on page 593](#)

#### related references

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## USING phrase for passing arguments

If you pass arguments to a method, specify the arguments in the USING phrase of the INVOKE statement. Code the data type of each argument so that it conforms to the type of the corresponding formal parameter in the intended target method.

Table 79. <i>Conformance of arguments in a COBOL client</i>			
Programming language of the target method	Is the argument an object reference?	Then code the DATA DIVISION definition of the argument as:	Restriction
COBOL	No	The same as the definition of the corresponding formal parameter	
Java	No	Interoperable with the corresponding Java parameter	
COBOL or Java	Yes	An object reference that is typed to the same class as the corresponding parameter in the target method	In a COBOL client (unlike in a Java client), the class of an argument cannot be a subclass of the class of the corresponding parameter.

See the example referenced below for a way to make an object-reference argument conform to the type of a corresponding formal parameter by using the SET statement or the REDEFINES clause.

[“Example: passing conforming object-reference arguments from a COBOL client” on page 582](#)

If the target method is overloaded, the data types of the arguments are used to select from among the methods that have the same name.

You must specify that the arguments are passed BY VALUE. In other words, the arguments are not affected by any change to the corresponding formal parameters in the invoked method.

The data type of each argument must be one of the types that are interoperable with Java.

#### related tasks

[“PROCEDURE DIVISION for](#)

[defining a class instance method” on page 571](#)

[“Overloading an instance method” on page 573](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Passing data” on page 465](#)

#### related references

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

SET statement (*Enterprise COBOL for z/OS Language Reference*)

REDEFINES clause (*Enterprise COBOL for z/OS Language Reference*)

## Example: passing conforming object-reference arguments from a COBOL client

The following example shows a way to make an object-reference argument in a COBOL client conform to the expected class of the corresponding formal parameter in an invoked method.

Class C defines a method M that has one parameter, a reference to an object of class `java.lang.Object`:

```
..
Class-id. C inherits Base.
..
Repository.
  Class Base      is "java.lang.Object"
  Class JavaObject is "java.lang.Object".
Identification division.
Factory.
..
Procedure Division.
Identification Division.
Method-id. "M".
Data division.
Linkage section.
01 obj object reference JavaObject.
Procedure Division using by value obj.
..
```

To invoke method M, a COBOL client must pass an argument that is a reference to an object of class `java.lang.Object`. The client below defines a data item `aString`, which cannot be passed as an argument to M because `aString` is a reference to an object of class `java.lang.String`. The client first uses a SET statement to assign `aString` to a data item, `anObj`, that is a reference to an object of class `java.lang.Object`. (This SET statement is legal because `java.lang.String` is a subclass of `java.lang.Object`.) The client then passes `anObj` as the argument to M.

```
..
Repository.
  Class jstring    is "java.lang.String"
  Class JavaObject is "java.lang.Object".
Data division.
Local-storage section.
01 aString object reference jstring.
01 anObj  object reference JavaObject.
*
Procedure division.
  .. (statements here assign a value to aString)
  Set anObj to aString
  Invoke C "M"
  using by value anObj
```

Instead of using a SET statement to obtain `anObj` as a reference to an object of class `java.lang.Object`, the client could define `aString` and `anObj` with the REDEFINES clause as follows:

```
..
01 aString object reference jstring.
01 anObj  redefines aString object reference JavaObject.
```

After the client assigns a value to data item `aString` (that is, a valid reference to an object of class `java.lang.String`), `anObj` can be passed as the argument to M. For an example of the use of the REDEFINES clause to obtain argument conformance, see the example referenced below.

[“Example: J2EE client written in COBOL” on page 613](#)

### related tasks

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“PROCEDURE DIVISION for defining a class instance method” on page 571](#)

### related references

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

SET statement (*Enterprise COBOL for z/OS Language Reference*)

REDEFINES clause (*Enterprise COBOL for z/OS Language Reference*)

## RETURNING phrase for obtaining a returned value

If a data item is to be returned as the method result, specify the item in the RETURNING phrase of the INVOKE statement. Define the returned item in the DATA DIVISION of the client.

The item that you specify in the RETURNING phrase of the INVOKE statement must conform to the type returned by the target method, as shown in the table below.

Table 80. <i>Conformance of the returned data item in a COBOL client</i>		
Programming language of the target method	Is the returned item an object reference?	Then code the DATA DIVISION definition of the returned item as:
COBOL	No	The same as the definition of the RETURNING item in the target method
Java	No	Interoperable with the returned Java data item
COBOL or Java	Yes	An object reference that is typed to the same class as the object reference that is returned by the target method

In all cases, the data type of the returned value must be one of the types that are interoperable with Java.

### related tasks

[“Coding interoperable data types in COBOL and Java” on page 606](#)

### related references

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## Invoking overridden superclass methods

Sometimes within a class you need to invoke an overridden superclass method instead of invoking a method that has the same signature and is defined in the current class.

For example, suppose that the CheckingAccount class overrides the debit instance method defined in its immediate superclass, Account. You could invoke the Account debit method within a method in the CheckingAccount class by coding this statement:

```
Invoke Super "debit" Using By Value amount.
```

You would define amount as PIC S9(9) BINARY to match the signature of the debit methods.

The CheckingAccount class overrides the print method that is defined in the Account class. Because the print method has no formal parameters, a method in the CheckingAccount class could invoke the superclass print method with this statement:

```
Invoke Super "print".
```

The keyword SUPER indicates that you want to invoke a superclass method rather than a method in the current class. (SUPER is an implicit reference to the object used in the invocation of the currently executing method.)

[“Example: accounts” on page 562](#)

#### related tasks

[“Overriding an instance method” on page 572](#)

#### related references

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## Creating and initializing instances of classes

Before you can use the instance methods that are defined in a Java or COBOL class, you must first create an instance of the class.

To create a new instance of class *class-name* and to obtain a reference *object-reference* to the created object, code a statement of the following form, where *object-reference* is defined in the DATA DIVISION of the client:

```
INVOKE class-name NEW . . . RETURNING object-reference
```

When you code the INVOKE . . . NEW statement within a method, and the use of the returned object reference is not limited to the duration of the method invocation, you must convert the returned object reference to a global reference by calling the JNI service NewGlobalRef:

```
Call NewGlobalRef using by value JNIEnvPtr object-reference  
returning object-reference
```

If you do not call NewGlobalRef, the returned object reference is only a local reference, which means that it is automatically freed after the method returns.

#### related tasks

[“Instantiating Java classes” on page 584](#)

[“Instantiating COBOL classes” on page 585](#)

[“Accessing JNI services” on page 601](#)

[“Managing local and global references” on page 603](#)

[“DATA DIVISION for defining  
a client” on page 578](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

#### related references

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## Instantiating Java classes

To instantiate a Java class, invoke any parameterized constructor that the class supports by coding the USING phrase in the INVOKE . . . NEW statement immediately before the RETURNING phrase, passing BY VALUE the number and types of arguments that match the signature of the constructor.

The data type of each argument must be one of the types that are interoperable with Java. To invoke the default (parameterless) constructor, omit the USING phrase.

For example, to create an instance of the Check class, initialize its instance data, and obtain reference aCheck to the Check instance created, you could code this statement in a COBOL client:

```
Invoke Check New  
using by value aCheckingAccount, payee, 125  
returning aCheck
```

#### related tasks

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

### related references

VALUE clause (*Enterprise COBOL for z/OS Language Reference*)

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## Instantiating COBOL classes

To instantiate a COBOL class, you can specify either a typed or universal object reference in the RETURNING phrase of the INVOKE . . . NEW statement. However, you cannot code the USING phrase: the instance data is initialized as specified in the VALUE clauses in the class definition.

Thus the INVOKE . . . NEW statement is useful for instantiating COBOL classes that have only simple instance data. For example, the following statement creates an instance of the Account class, initializes the instance data as specified in VALUE clauses in the WORKING-STORAGE SECTION of the OBJECT paragraph of the Account class definition, and provides reference outAccount to the new instance:

```
Invoke Account New returning outAccount
```

To make it possible to initialize COBOL instance data that cannot be initialized using VALUE clauses alone, when designing a COBOL class you must define a parameterized creation method in the FACTORY paragraph and a parameterized initialization method in the OBJECT paragraph:

1. In the parameterized factory creation method, do these steps:
  - a) Code INVOKE *class-name* NEW RETURNING *objectRef* to create an instance of *class-name* and to give initial values to the instance data items that have VALUE clauses.
  - b) Invoke the parameterized initialization method on the instance (*objectRef*), passing BY VALUE the arguments that were supplied to the factory method.
2. In the initialization method, code logic to complete the instance data initialization using the values supplied through the formal parameters.

To create an instance of the COBOL class and properly initialize it, the client invokes the parameterized factory method, passing BY VALUE the required arguments. The object reference returned to the client is a local reference. If the client code is within a method, and the use of the returned object reference is not limited to the duration of that method, the client code must convert the returned object reference to a global reference by calling the JNI service NewGlobalRef.

[“Example: defining a factory \(with methods\)” on page 593](#)

### related tasks

[“Accessing JNI services” on page 601](#)

[“Managing local and global references” on page 603](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Defining a factory section” on page 590](#)

### related references

VALUE clause (*Enterprise COBOL for z/OS Language Reference*)

INVOKE statement (*Enterprise COBOL for z/OS Language Reference*)

## Freeing instances of classes

You do not need to take any action to free individual object instances of any class. No syntax is available for doing so. The Java runtime system automatically performs *garbage collection*, that is, it reclaims the memory for objects that are no longer in use.

There could be times, however, when you need to explicitly free local or global references to objects within a native COBOL client in order to permit garbage collection of the referenced objects to occur.

### related tasks

[“Managing local and global references” on page 603](#)

## Example: defining a client

The following example shows a small client program of the Account class.

The program does this:

- Invokes a factory method `createAccount` to create an Account instance with a default balance of zero
- Invokes the instance method `credit` to deposit \$500 to the new account
- Invokes the instance method `print` to display the account status

(The Account class was shown in [“Example: defining a method” on page 574.](#))

```
cb1 dll,thread,pgmname(longmixed)
Identification division.
Program-id. "TestAccounts" recursive.
Environment division.
Configuration section.
Repository.
    Class Account is "Account".
Data Division.
* Working data is declared in LOCAL-STORAGE instead of
* WORKING-STORAGE so that each thread has its own copy:
Local-storage section.
01 anAccount usage object reference Account.
*
Procedure division.
Test-Account-section.
    Display "Test Account class"
* Create account 123456 with 0 balance:
    Invoke Account "createAccount"
        using by value 123456
        returning anAccount
* Deposit 500 to the account:
    Invoke anAccount "credit" using by value 500
    Invoke anAccount "print"
    Display space
*
    Stop Run.
End program "TestAccounts".
```

[“Example: defining a factory \(with methods\)” on page 593](#)

### related tasks

[“Defining a factory method” on page 591](#)

[“Invoking factory or static methods” on page 593](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

## Defining a subclass

You can make a class (called a *subclass*, derived class, or child class) a specialization of another class (called a *superclass*, base class, or parent class).

A subclass inherits the methods and instance data of its superclasses, and is related to its superclasses by an *is-a* relationship. For example, if subclass P inherits from superclass Q, and subclass Q inherits from superclass S, then an instance of P is an instance of Q and also (by transitivity) an instance of S. An instance of P inherits the methods and data of Q and S.

Using subclasses has several advantages:

- Reuse of code: Through inheritance, a subclass can reuse methods that already exist in a superclass.
- Specialization: In a subclass you can add new methods to handle cases that the superclass does not handle. You can also add new data items that the superclass does not need.
- Change in action: A subclass can override a method that it inherits from a superclass by defining a method of the same signature as that in the superclass. When you override a method, you might make only a few minor changes or completely change what the method does.

**Restriction:** You cannot use *multiple inheritance* in your COBOL programs. Each COBOL class that you define must have exactly one immediate superclass that is implemented in Java or COBOL, and each class must be derived directly or indirectly from `java.lang.Object`. The semantics of inheritance are as defined by Java.

The structure and syntax of a subclass definition are identical to those of a class definition: Define instance data and methods in the `DATA DIVISION` and `PROCEDURE DIVISION`, respectively, within the `OBJECT` paragraph of the subclass definition. In subclasses that require data and methods that are to be associated with the subclass itself rather than with individual object instances, define a separate `DATA DIVISION` and `PROCEDURE DIVISION` within the `FACTORY` paragraph of the subclass definition.

COBOL instance data is private. A subclass can access the instance data of a COBOL superclass only if the superclass defines attribute (get or set) instance methods for doing so.

[“Example: accounts” on page 562](#)

[“Example: defining a subclass \(with methods\)” on page 589](#)

#### **related tasks**

[“Defining a class” on page 564](#)

[“Overriding an instance method” on page 572](#)

[“Coding attribute \(get and set\) methods” on page 573](#)

[“Defining a subclass instance method” on page 588](#)

[“Defining a factory section” on page 590](#)

#### **related references**

*The Java Language Specification* (Inheritance, overriding, and hiding)

COBOL class definition structure (*Enterprise COBOL for z/OS Language Reference*)

## **CLASS-ID paragraph for defining a subclass**

Use the `CLASS-ID` paragraph to name the subclass and indicate from which immediate Java or COBOL superclass it inherits its characteristics.

```
Identification Division.
Class-id. CheckingAccount inherits Account. Required Required
```

In the example above, `CheckingAccount` is the subclass being defined. `CheckingAccount` inherits all the methods of the class known within the subclass definition as `Account`. `CheckingAccount` methods can access `Account` instance data only if the `Account` class provides attribute (get or set) methods for doing so.

You must specify the name of the immediate superclass in the `REPOSITORY` paragraph in the `CONFIGURATION SECTION` of the `ENVIRONMENT DIVISION`. You can optionally associate the superclass name with the name of the class as it is known externally. You can also specify the name of the subclass that you are defining (here, `CheckingAccount`) in the `REPOSITORY` paragraph and associate it with its corresponding external class-name.

#### **related tasks**

[“CLASS-ID paragraph for defining a class” on page 565](#)

[“Coding attribute \(get and set\) methods” on page 573](#)

[“REPOSITORY paragraph for defining a subclass” on page 588](#)

## REPOSITORY paragraph for defining a subclass

Use the REPOSITORY paragraph to declare to the compiler that the specified words are class-names when you use them within a subclass definition, and to optionally relate the class-names to the corresponding external class-names (the class-names as they are known outside the compilation unit).

For example, in the CheckingAccount subclass definition, these REPOSITORY paragraph entries indicate that the external class-names of the classes referred to as CheckingAccount, Check, and Account within the subclass definition are CheckingAccount, Check, and Account, respectively.

Environment Division.		<b>Required</b>
Configuration Section.		<b>Required</b>
Repository.		<b>Required</b>
Class CheckingAccount	is "CheckingAccount"	<b>Optional</b>
Class Check	is "Check"	<b>Required</b>
Class Account	is "Account".	<b>Required</b>

In the REPOSITORY paragraph, you must code an entry for each class-name that you explicitly reference in the subclass definition. For example:

- A user-defined superclass from which the subclass that you are defining inherits
- The classes that you reference in methods within the subclass definition

The rules for coding REPOSITORY paragraph entries in a subclass are identical to those for coding REPOSITORY paragraph entries in a class.

### related tasks

[“REPOSITORY paragraph for defining a class” on page 566](#)

### related references

REPOSITORY paragraph (*Enterprise COBOL for z/OS Language Reference*)

## WORKING-STORAGE SECTION for defining subclass instance data

Use the WORKING-STORAGE SECTION in the DATA DIVISION of the subclass OBJECT paragraph to describe any instance data that the subclass needs in addition to the instance data defined in its superclasses. Use the same syntax that you use to define instance data in a class.

For example, the definition of the instance data for the CheckingAccount subclass of the Account class might look like this:

```
IDENTIFICATION DIVISION.  
Object.  
DATA DIVISION.  
WORKING-STORAGE SECTION.  
01 CheckFee pic S9(9) value 1.  
End Object.
```

### related tasks

[“WORKING-STORAGE SECTION for defining class instance data” on page 567](#)

## Defining a subclass instance method

A subclass inherits the methods of its superclasses. In a subclass definition, you can override any instance method that the subclass inherits by defining an instance method with the same signature as the inherited method. You can also define new methods that the subclass needs.

The structure and syntax of a subclass instance method are identical to those of a class instance method. Define subclass instance methods in the PROCEDURE DIVISION of the OBJECT paragraph of the subclass definition.

[“Example: defining a subclass \(with methods\)” on page 589](#)

## related tasks

[“Defining a class instance method” on page 568](#)

[“Overriding an instance method” on page 572](#)

[“Overloading an instance method” on page 573](#)

## Example: defining a subclass (with methods)

The following example shows the instance method definitions for the `CheckingAccount` subclass of the `Account` class.

The `processCheck` method invokes the Java instance methods `getAmount` and `getPayee` of the `Check` class to get the check data. It invokes the `credit` and `debit` instance methods inherited from the `Account` class to credit the payee and debit the payer of the check.

The `print` method overrides the `print` instance method defined in the `Account` class. It invokes the overridden `print` method to display account status, and also displays the check fee. `CheckFee` is an instance data item defined in the subclass.

(The `Account` class was shown in [“Example: defining a method” on page 574.](#))

### *CheckingAccount class (subclass of Account)*

```
cb1 dll,thread,pgmname(longmixed)
Identification Division.
Class-id. CheckingAccount inherits Account.
Environment Division.
Configuration section.
Repository.
    Class CheckingAccount is "CheckingAccount"
    Class Check           is "Check"
    Class Account         is "Account".
*
* (FACTORY paragraph not shown)
*
Identification division.
Object.
Data division.
Working-storage section.
01 CheckFee pic S9(9) value 1.
Procedure Division.
*
*   processCheck method to get the check amount and payee,
*   add the check fee, and invoke inherited methods debit
*   to debit the payer and credit to credit the payee:
Identification Division.
Method-id. "processCheck".
Data division.
Local-storage section.
01 amount pic S9(9) binary.
01 payee usage object reference Account.
Linkage section.
01 aCheck usage object reference Check.
*
*   Procedure Division using by value aCheck.
*       Invoke aCheck "getAmount" returning amount
*       Invoke aCheck "getPayee" returning payee
*       Invoke payee "credit" using by value amount
*       Add checkFee to amount
*       Invoke self "debit" using by value amount.
*   End method "processCheck".
*
*   print method override to display account status:
Identification Division.
Method-id. "print".
Data division.
Local-storage section.
01 printableFee pic $,$,$,$,$9.
Procedure Division.
    Invoke super "print"
    Move CheckFee to printableFee
    Display " Check fee: " printableFee.
End method "print".
*
End Object.
```

```
*  
End class CheckingAccount.
```

### related tasks

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Overriding an instance method” on page 572](#)

[“Invoking overridden superclass](#)

[methods” on page 583](#)

## Defining a factory section

Use the FACTORY paragraph in a class definition to define data and methods that are to be associated with the class itself rather than with individual object instances.

COBOL *factory data* is equivalent to Java private static data. A single copy of the data is instantiated for the class and is shared by all object instances of the class. You most commonly use factory data when you want to gather data from all the instances of a class. For example, you could define a factory data item to keep a running total of the number of instances of the class that are created.

COBOL *factory methods* are equivalent to Java public static methods. The methods are supported by the class independently of any object instance. You most commonly use factory methods to customize object creation when you cannot use VALUE clauses alone to initialize instance data.

By contrast, you use the OBJECT paragraph in a class definition to define data that is created for each object instance of the class, and methods that are supported for each object instance of the class.

A factory definition consists of three divisions, followed by an END FACTORY statement:

Table 81. <i>Structure of factory definitions</i>		
Division	Purpose	Syntax
IDENTIFICATION (required)	Identify the start of the factory definition.	IDENTIFICATION DIVISION. FACTORY.
DATA (optional)	Describe data that is allocated once for the class (as opposed to data allocated for each instance of a class).	<a href="#">“WORKING-STORAGE SECTION for defining factory data” on page 591</a> (optional)
PROCEDURE (optional)	Define factory methods.	Factory method definitions: <a href="#">“Defining a factory method” on page 591</a>

[“Example: defining a factory \(with methods\)” on page 593](#)

### related tasks

[“Defining a class” on page 564](#)

[“Instantiating COBOL classes” on page 585](#)

[“Wrapping procedure-oriented COBOL programs” on page 598](#)

[“Structuring OO applications” on page 598](#)

## WORKING-STORAGE SECTION for defining factory data

Use the `WORKING-STORAGE SECTION` in the `DATA DIVISION` of the `FACTORY` paragraph to describe the *factory data* that a COBOL class needs, that is, statically allocated data to be shared by all object instances of the class.

The `FACTORY` keyword, which you must immediately precede with an `IDENTIFICATION DIVISION` declaration, indicates the beginning of the definitions of the factory data and factory methods for the class. For example, the definition of the factory data for the `Account` class might look like this:

```
IDENTIFICATION DIVISION.  
Factory.  
DATA DIVISION.  
WORKING-STORAGE SECTION.  
01 NumberOfAccounts pic 9(6) value zero.  
.  
End Factory.
```

You can initialize simple factory data by using `VALUE` clauses as shown above.

COBOL factory data is equivalent to Java private static data. No other class or subclass (nor instance method in the same class, if any) can reference COBOL factory data directly. Factory data is global to all factory methods that the `FACTORY` paragraph defines. If you want to make factory data accessible from outside the `FACTORY` paragraph, define factory attribute (get or set) methods for doing so.

### related tasks

[“Coding attribute \(get and set\) methods” on page 573](#)

[“Instantiating COBOL classes” on page 585](#)

## Defining a factory method

Define COBOL *factory methods* in the `PROCEDURE DIVISION` of the `FACTORY` paragraph of a class definition. A factory method defines an operation that is supported by a class independently of any object instance of the class. COBOL factory methods are equivalent to Java public static methods.

You typically define factory methods for classes whose instances require complex initialization, that is, to values that you cannot assign by using `VALUE` clauses alone. Within a factory method you can invoke instance methods to initialize the instance data. A factory method cannot directly access instance data.

You can code factory attribute (get and set) methods to make factory data accessible from outside the `FACTORY` paragraph, for example, to make the data accessible from instance methods in the same class or from a client program. For example, the `Account` class could define a factory method `getNumberOfAccounts` to return the current tally of the number of accounts.

You can use factory methods to wrap procedure-oriented COBOL programs so that they are accessible from Java programs. You can code a factory method called `main` to enable you to run an OO application by using the `java` command, and to structure your applications in keeping with standard Java practice. See the related tasks for details.

In defining factory methods, you use the same syntax that you use to define instance methods. A COBOL factory method definition consists of four divisions (like a COBOL program), followed by an `END METHOD` marker:

Table 82. <i>Structure of factory method definitions</i>		
Division	Purpose	Syntax
IDENTIFICATION (required)	Same as for a class instance method	Same as for a class instance method (required)
ENVIRONMENT (optional)	Same as for a class instance method	Same as for a class instance method

Table 82. **Structure of factory method definitions** (continued)

Division	Purpose	Syntax
DATA (optional)	Same as for a class instance method	Same as for a class instance method
PROCEDURE (optional)	Same as for a class instance method	Same as for a class instance method

Within a class definition, you do not need to make each factory method-name unique, but you do need to give each factory method a unique signature. You can overload factory methods in exactly the same way that you overload instance methods. For example, the `CheckingAccount` subclass provides two versions of the factory method `createCheckingAccount`: one that initializes the account to have a default balance of zero, and one that allows the opening balance to be passed in. Clients can invoke either `createCheckingAccount` method by passing arguments that match the signature of the intended method.

If you define a data item with the same name in both the `DATA DIVISION` of a factory method and the `DATA DIVISION` of the `FACTORY` paragraph, a reference in the method to that data-name refers only to the method data item. The method `DATA DIVISION` takes precedence.

[“Example: defining a factory \(with methods\)” on page 593](#)

#### related tasks

[“Structuring OO applications” on page 598](#)

[“Wrapping procedure-oriented COBOL programs” on page 598](#)

[“Instantiating COBOL classes” on page 585](#)

[“Defining a class instance method” on page 568](#)

[“Coding attribute \(get and set\) methods” on page 573](#)

[“Overloading an instance method” on page 573](#)

[“Hiding a factory or static method” on page 592](#)

[“Invoking factory or static methods” on page 593](#)

[“Using object-oriented COBOL and Java under IMS” on page 431](#)

## Hiding a factory or static method

A factory method defined in a subclass is said to *hide* an inherited COBOL or Java method that would otherwise be accessible in the subclass if the two methods have the same signature.

To hide a superclass factory method `f1` in a COBOL subclass, define a factory method `f1` in the subclass that has the same name and whose `PROCEDURE DIVISION USING` phrase (if any) has the same number and type of formal parameters as the superclass method has. (If the superclass method is implemented in Java, you must code formal parameters that are interoperable with the data types of the corresponding Java parameters.) When a client invokes `f1` using the subclass name, the subclass method rather than the superclass method is invoked.

The presence or absence of a method return value and the data type of the return value used in the `PROCEDURE DIVISION RETURNING` phrase (if any) must be identical in the subclass factory method and the hidden superclass method.

A factory method must not hide an instance method in a Java or COBOL superclass.

[“Example: defining a factory \(with methods\)” on page 593](#)

#### related tasks

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Overriding an instance method” on page 572](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

## related references

[The Java Language Specification \(Inheritance, overriding, and hiding\)](#)

The procedure division header ([Enterprise COBOL for z/OS Language Reference](#))

## Invoking factory or static methods

To invoke a COBOL factory method or Java static method in a COBOL method or client program, code the class-name as the first operand of the INVOKE statement.

For example, a client program could invoke one of the overloaded CheckingAccount factory methods called createCheckingAccount to create a checking account with account number 777777 and an opening balance of \$300 by coding this statement:

```
Invoke CheckingAccount "createCheckingAccount"  
  using by value 777777 300  
  returning aCheckingAccount
```

To invoke a factory method from within the same class in which you define the factory method, you also use the class-name as the first operand in the INVOKE statement.

Code the name of the method to be invoked either as a literal or as an identifier whose value at run time is the method-name. The method-name must be an alphanumeric or national literal or a category alphabetic, alphanumeric, or national data item, and is interpreted in a case-sensitive manner.

If an invoked method is not supported in the class that you name in the INVOKE statement, a severity-3 Language Environment condition is raised at run time unless you code the ON EXCEPTION phrase in the INVOKE statement.

The conformance requirements for passing arguments to a COBOL factory method or Java static method in the USING phrase, and receiving a return value in the RETURNING phrase, are the same as those for invoking instance methods.

[“Example: defining a factory \(with methods\)” on page 593](#)

## related tasks

[“Invoking methods \(INVOKE\)” on page 580](#)

[“Using national data \(Unicode\)](#)

[in COBOL” on page 124](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

## related references

INVOKE statement ([Enterprise COBOL for z/OS Language Reference](#))

## Example: defining a factory (with methods)

The following example updates the previous examples to show the definition of factory data and methods.

These updates are shown:

- The Account class adds factory data and a parameterized factory method, createAccount, which allows an Account instance to be created using an account number that is passed in.
- The CheckingAccount subclass adds factory data and an overloaded parameterized factory method, createCheckingAccount. One implementation of createCheckingAccount initializes the account with a default balance of zero, and the other allows the opening balance to be passed in. Clients can invoke either method by passing arguments that match the signature of the required method.
- The TestAccounts client invokes the services provided by the factory methods of the Account and CheckingAccount classes, and instantiates the Java Check class.
- The output from the TestAccounts client program is shown.

(The previous examples were [“Example: defining a method” on page 574](#), [“Example: defining a client” on page 586](#), and [“Example: defining a subclass \(with methods\)” on page 589](#).)

You can also find the complete source code for this example in the `cobol/demo/oosample` subdirectory in the z/OS UNIX file system. Typically the complete path for the source is `/usr/lpp/cobol/demo/oosample`. You can use the makefile there to compile and link the code.

## **Account class**

```

cbl dll,thread,pgmname(longmixed)
Identification Division.
Class-id. Account inherits Base.
Environment Division.
Configuration section.
Repository.
    Class Base    is "java.lang.Object"
    Class Account is "Account".
*
Identification division.
Factory.
Data division.
Working-storage section.
01 NumberOfAccounts pic 9(6) value zero.
*
Procedure Division.
*
*   createAccount method to create a new Account
*   instance, then invoke the OBJECT paragraph's init
*   method on the instance to initialize its instance data:
Identification Division.
Method-id. "createAccount".
Data division.
Linkage section.
01 inAccountNumber pic S9(6) binary.
01 outAccount object reference Account.
*   Facilitate access to JNI services:
    Copy JNI.
    Procedure Division using by value inAccountNumber
        returning outAccount.
*   Establish addressability to JNI environment structure:
    Set address of JNIEnv to JNIEnvPtr
    Set address of JNINativeInterface to JNIEnv
    Invoke Account New returning outAccount
    Invoke outAccount "init" using by value inAccountNumber
    Add 1 to NumberOfAccounts.
    End method "createAccount".
*
End Factory.
*
Identification division.
Object.
Data division.
Working-storage section.
01 AccountNumber pic 9(6).
01 AccountBalance pic S9(9) value zero.
*
Procedure Division.
*
*   init method to initialize the account:
Identification Division.
Method-id. "init".
Data division.
Linkage section.
01 inAccountNumber pic S9(9) binary.
Procedure Division using by value inAccountNumber.
    Move inAccountNumber to AccountNumber.
    End method "init".
*
*   getBalance method to return the account balance:
Identification Division.
Method-id. "getBalance".
Data division.
Linkage section.
01 outBalance pic S9(9) binary.
Procedure Division returning outBalance.
    Move AccountBalance to outBalance.
    End method "getBalance".
*
*   credit method to deposit to the account:
Identification Division.
Method-id. "credit".

```

```

Data division.
Linkage section.
01 inCredit pic S9(9) binary.
Procedure Division using by value inCredit.
    Add inCredit to AccountBalance.
End method "credit".
*
*   debit method to withdraw from the account:
Identification Division.
Method-id. "debit".
Data division.
Linkage section.
01 inDebit pic S9(9) binary.
Procedure Division using by value inDebit.
    Subtract inDebit from AccountBalance.
End method "debit".
*
*   print method to display formatted account number and balance:
Identification Division.
Method-id. "print".
Data division.
Local-storage section.
01 PrintableAccountNumber pic ZZZZZZ999999.
01 PrintableAccountBalance pic $$$,$$$,$$9CR.
Procedure Division.
    Move AccountNumber to PrintableAccountNumber
    Move AccountBalance to PrintableAccountBalance
    Display " Account: " PrintableAccountNumber
    Display " Balance: " PrintableAccountBalance.
End method "print".
*
End Object.
*
End class Account.

```

### ***CheckingAccount class (subclass of Account)***

```

cbl dll,thread,pgmname(longmixed)
Identification Division.
Class-id. CheckingAccount inherits Account.
Environment Division.
Configuration section.
Repository.
    Class CheckingAccount is "CheckingAccount"
    Class Check is "Check"
    Class Account is "Account".
*
Identification division.
Factory.
Data division.
Working-storage section.
01 NumberOfCheckingAccounts pic 9(6) value zero.
*
Procedure Division.
*
*   createCheckingAccount overloaded method to create a new
*   CheckingAccount instance with a default balance, invoke
*   inherited instance method init to initialize the account
*   number, and increment factory data tally of checking accounts:
Identification Division.
Method-id. "createCheckingAccount".
Data division.
Linkage section.
01 inAccountNumber pic S9(6) binary.
01 outCheckingAccount object reference CheckingAccount.
*   Facilitate access to JNI services:
    Copy JNI.
Procedure Division using by value inAccountNumber
    returning outCheckingAccount.
*   Establish addressability to JNI environment structure:
    Set address of JNIEnv to JNIEnvPtr
    Set address of JNINativeInterface to JNIEnv
    Invoke CheckingAccount New returning outCheckingAccount
    Invoke outCheckingAccount "init"
        using by value inAccountNumber
    Add 1 to NumberOfCheckingAccounts.
End method "createCheckingAccount".
*
*   createCheckingAccount overloaded method to create a new

```

```

*   CheckingAccount instance, invoke inherited instance methods
*   init to initialize the account number and credit to set the
*   balance, and increment factory data tally of checking accounts:
Identification Division.
Method-id. "createCheckingAccount".
Data division.
Linkage section.
01 inAccountNumber pic S9(6) binary.
01 inInitialBalance pic S9(9) binary.
01 outCheckingAccount object reference CheckingAccount.
Copy JNI.
Procedure Division using by value inAccountNumber
                                inInitialBalance
    returning outCheckingAccount.
Set address of JNIEnv to JNIEnvPtr
Set address of JNINativeInterface to JNIEnv
Invoke CheckingAccount New returning outCheckingAccount
Invoke outCheckingAccount "init"
    using by value inAccountNumber
Invoke outCheckingAccount "credit"
    using by value inInitialBalance
Add 1 to NumberOfCheckingAccounts.
End method "createCheckingAccount".
*
End Factory.
*
Identification division.
Object.
Data division.
Working-storage section.
01 CheckFee pic S9(9) value 1.
Procedure Division.
*
*   processCheck method to get the check amount and payee,
*   add the check fee, and invoke inherited methods debit
*   to debit the payer and credit to credit the payee:
Identification Division.
Method-id. "processCheck".
Data division.
Local-storage section.
01 amount pic S9(9) binary.
01 payee usage object reference Account.
Linkage section.
01 aCheck usage object reference Check.
Procedure Division using by value aCheck.
    Invoke aCheck "getAmount" returning amount
    Invoke aCheck "getPayee" returning payee
    Invoke payee "credit" using by value amount
    Add checkFee to amount
    Invoke self "debit" using by value amount.
End method "processCheck".
*
*   print method override to display account status:
Identification Division.
Method-id. "print".
Data division.
Local-storage section.
01 printableFee pic $,$,$,$,$9.
Procedure Division.
    Invoke super "print"
    Move CheckFee to printableFee
    Display " Check fee: " printableFee.
End method "print".
*
End Object.
*
End class CheckingAccount.

```

## Check class

```

/**
 * A Java class for check information
 */
public class Check {
    private CheckingAccount payer;
    private Account         payee;
    private int              amount;

    public Check(CheckingAccount inPayer, Account inPayee, int inAmount) {

```

```

        payer=inPayer;
        payee=inPayee;
        amount=inAmount;
    }

    public int getAmount() {
        return amount;
    }

    public Account getPayee() {
        return payee;
    }
}

```

### ***TestAccounts client program***

```

cbl dll,thread,pgmname(longmixed)
Identification division.
Program-id. "TestAccounts" recursive.
Environment division.
Configuration section.
Repository.
    Class Account          is "Account"
    Class CheckingAccount is "CheckingAccount"
    Class Check           is "Check".
Data Division.
* Working data is declared in Local-storage
* so that each thread has its own copy:
Local-storage section.
01 anAccount      usage object reference Account.
01 aCheckingAccount usage object reference CheckingAccount.
01 aCheck        usage object reference Check.
01 payee         usage object reference Account.
*
Procedure division.
Test-Account-section.
    Display "Test Account class"
* Create account 123456 with 0 balance:
    Invoke Account "createAccount"
        using by value 123456
        returning anAccount
* Deposit 500 to the account:
    Invoke anAccount "credit" using by value 500
    Invoke anAccount "print"
    Display space
*
    Display "Test CheckingAccount class"
* Create checking account 777777 with balance of 300:
    Invoke CheckingAccount "createCheckingAccount"
        using by value 777777 300
        returning aCheckingAccount
* Set account 123456 as the payee:
    Set payee to anAccount
* Initialize check for 125 to be paid by account 777777 to payee:
    Invoke Check New
        using by value aCheckingAccount, payee, 125
        returning aCheck
* Debit the payer, and credit the payee:
    Invoke aCheckingAccount "processCheck"
        using by value aCheck
    Invoke aCheckingAccount "print"
    Invoke anAccount "print"
*
    Stop Run.
End program "TestAccounts".

```

### ***Output produced by the TestAccounts client program***

```

Test Account class
Account:      123456
Balance:      $500

Test CheckingAccount class
Account:      777777
Balance:      $174
Check fee:    $1

```

Account:	123456
Balance:	\$625

#### **related tasks**

[“Creating and initializing](#)

[instances of classes” on page 584](#)

[“Defining a factory method” on page 591](#)

[“Invoking factory or static](#)

[methods” on page 593](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

## **Wrapping procedure-oriented COBOL programs**

---

A *wrapper* is a class that provides an interface between object-oriented code and procedure-oriented code. Factory methods provide a convenient means for writing wrappers for existing procedural COBOL code to make it accessible from Java programs.

To wrap COBOL code, do these steps:

1. Create a simple COBOL class that contains a FACTORY paragraph.
2. In the FACTORY paragraph, code a factory method that uses a CALL statement to call the procedural program.

A Java program can invoke the factory method by using a static method invocation expression, thus invoking the COBOL procedural program.

#### **related tasks**

[“Defining a class” on page 564](#)

[“Defining a factory section” on page 590](#)

[“Defining a factory method” on page 591](#)

## **Structuring OO applications**

---

You can structure applications that use object-oriented COBOL syntax in one of three ways.

An OO application can begin with:

- A COBOL program, which can have any name.

Under z/OS UNIX, you can run the application by specifying the name of the linked module (which should match the program name) at the command prompt. You can also bind the program as a module in a PDSE and run it in JCL using the EXEC PGM statement.

- A Java class definition that contains a method called main. Declare main as public, static, and void, with a single parameter of type String[].

You can run the application with the java command, specifying the name of the class that contains main, and zero or more strings as command-line arguments.

- A COBOL class definition that contains a factory method called main. Declare main with no RETURNING phrase and a single USING parameter, an object reference to a class that is an array with elements of type java.lang.String. (Thus main is in effect public, static, and void, with a single parameter of type String[.] )

You can run the application with the java command, specifying the name of the class that contains main, and zero or more strings as command-line arguments.

Structure an OO application this way if you want to:

- Run the application by using the java command.
- Run the application in an environment where applications must start with the main method of a Java class (such as a Java dependent region).
- Follow standard Java programming practice.

#### **related tasks**

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[“Defining a factory method” on page 591](#)

[“Declaring arrays and strings for Java” on page 606](#)

[Chapter 22, “Developing COBOL programs for IMS,” on page 427](#)

## **Examples: COBOL applications that run using the java command**

The following examples show COBOL class definitions that contain a factory method called main.

In each case, main has no RETURNING phrase and has a single USING parameter, an object reference to a class that is an array with elements of type java.lang.String. You can run these applications by using the java command.

### ***Displaying a message***

```
cb1 dll,thread
Identification Division.
Class-id. CBLmain inherits Base.
Environment Division.
Configuration section.
Repository.
    Class Base is "java.lang.Object"
    Class stringArray is "jobjectArray:java.lang.String"
    Class CBLmain is "CBLmain".
*
Identification Division.
Factory.
    Procedure division.
*
    Identification Division.
    Method-id. "main".
    Data division.
    Linkage section.
    01 SA usage object reference stringArray.
    Procedure division using by value SA.
        Display " >> COBOL main method entered"
        .
    End method "main".
End factory.
End class CBLmain.
```

### ***Echoing the input strings***

```
cb1 dll,thread,pgmname(longmixed),ssrange
Identification Division.
Class-id. Echo inherits Base.
Environment Division.
Configuration section.
Repository.
    Class Base is "java.lang.Object"
    Class stringArray is "jobjectArray:java.lang.String"
    Class jstring is "java.lang.String"
    Class Echo is "Echo".
*
Identification Division.
Factory.
    Procedure division.
*
    Identification Division.
    Method-id. "main".
    Data division.
    Local-storage section.
    01 SAlen          pic s9(9) binary.
    01 I              pic s9(9) binary.
    01 SAElement     object reference jstring.
    01 SAElementlen  pic s9(9) binary.
```

```

01 Sbuffer      pic X(65535).
01 P            pointer.
Linkage section.
01 SA          object reference stringArray.
Copy "JNI.cpy" suppress.
Procedure division using by value SA.
  Set address of JNIEnv to JNIEnvPtr
  Set address of JNINativeInterface to JNIEnv
  Call GetArrayLength using by value JNIEnvPtr SA
    returning SAlen
  Display "Input string array length: " SAlen
  Display "Input strings:"
  Perform varying I from 0 by 1 until I = SAlen
    Call GetObjectArrayElement
      using by value JNIEnvPtr SA I
      returning SAelement
    Call "GetStringPlatformLength"
      using by value JNIEnvPtr
        SAelement
        address of SAelementlen
        0
    Call "GetStringPlatform"
      using by value JNIEnvPtr
        SAelement
        address of Sbuffer
        length of Sbuffer
        0
    Display Sbuffer(1:SAelementlen)
  End-perform
.
End method "main".
End factory.
End class Echo.

```

### related tasks

Chapter 16, [“Compiling, linking, and running OO applications,” on page 273](#)

[“Defining a factory method” on page 591](#)

Chapter 34, [“Communicating with Java methods,” on page 601](#)

# Chapter 34. Communicating with Java methods

To achieve interlanguage interoperability with Java, you need to follow certain rules and guidelines for using services in the Java Native Interface (JNI), coding data types, and compiling COBOL programs.

You can invoke methods that are written in Java from COBOL programs, and you can invoke methods that are written in COBOL from Java programs. You need to code COBOL object-oriented language for basic Java object capabilities. For additional Java capabilities, you can call JNI services.

Because Java programs might be multithreaded and use asynchronous signals, compile COBOL programs with the THREAD option.

[“Example: J2EE client written in COBOL” on page 613](#)

## related tasks

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

[“Accessing JNI services” on page 601](#)

[“Sharing data with Java” on page 605](#)

[Chapter 33, “Writing object-oriented programs,” on page 561](#)

[Chapter 28, “Preparing COBOL programs for multithreading,” on page 491](#)

## related references

[JDK 5.0 Documentation](#)


## Accessing JNI services

The Java Native Interface (JNI) provides many callable services that you can use when you develop applications that mix COBOL and Java. To facilitate access to these services, copy JNI .cpy into the LINKAGE SECTION of your COBOL program.

The JNI .cpy copybook contains these definitions:

- COBOL data definitions that correspond to the Java JNI types
- JNIInterface, the JNI environment structure that contains function pointers for accessing the callable service functions

You obtain the JNI environment structure by two levels of indirection from the JNI environment pointer, as the following illustration shows:



Use the special register JNIEnvPtr to reference the JNI environment pointer to obtain the address for the JNI environment structure. JNIEnvPtr is implicitly defined as USAGE POINTER; do not use it as a receiving data item. Before you reference the contents of the JNI environment structure, you must code the following statements to establish its addressability:

```
Linkage section.  
COPY JNI  
...
```

```

Procedure division.
    Set address of JNIEnv to JNIEnvPtr
    Set address of JNINativeInterface to JNIEnv
    . . .

```

The code above sets the addresses of the following items:

- JNIEnv, a pointer data item that JNI.cpy provides. JNIEnvPtr is the COBOL special register that contains the environment pointer.
- JNINativeInterface, the COBOL group structure that JNI.cpy contains. This structure maps the JNI environment structure, which contains an array of function pointers for the JNI callable services.

After you code the statements above, you can access the JNI callable services with CALL statements that reference the function pointers. You can pass the JNIEnvPtr special register as the first argument to the services that require the environment pointer, as shown in the following example:

```

01 InputArrayObj usage object reference jlongArray.
01 ArrayLen pic S9(9) comp-5.
. . .
    Call GetArrayLength using by value JNIEnvPtr InputArrayObj
    returning ArrayLen

```

**Important:** Pass all arguments to the JNI callable services by value.

Some JNI callable services require a Java class-object reference as an argument. To obtain a reference to the class object that is associated with a class, use one of the following JNI callable services:

- GetObjectClass
- FindClass

**Restriction:** The JNI environment pointer is thread specific. Do not pass it from one thread to another.

#### related tasks

[“Managing local and global references” on page 603](#)

[“Handling Java exceptions” on page 602](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Defining a client” on page 576](#)

#### related references

Appendix F, “JNI.cpy copybook,” on page 705

[The Java Native Interface](#)

## Handling Java exceptions

Use JNI services to throw and catch Java exceptions.

**Throwing an exception:** Use one of the following services to throw a Java exception from a COBOL method:

- Throw
- ThrowNew

You must make the thrown object an instance of a subclass of java.lang.Throwable.

The Java virtual machine (JVM) does not recognize and process the thrown exception until the method that contains the call has completed and returned to the JVM.

**Catching an exception:** After you invoke a method that might have thrown a Java exception, you can do these steps:

1. Test whether an exception occurred.
2. If an exception occurred, process the exception.
3. Clear the exception, if clearing is appropriate.

Use the following JNI services:

- ExceptionOccurred
- ExceptionCheck
- ExceptionDescribe
- ExceptionClear

To do error analysis, use the methods supported by the exception object that is returned. This object is an instance of the `java.lang.Throwable` class.

[“Example: handling Java exceptions” on page 603](#)

## Example: handling Java exceptions

The following example shows the use of JNI services for catching an exception from Java and the use of the `printStackTrace` method of `java.lang.Throwable` for error analysis.

```
Repository.  
    Class JavaException is "java.lang.Exception".  
..  
Local-storage section.  
01 ex usage object reference JavaException.  
Linkage section.  
COPY "JNI.cpy".  
..  
Procedure division.  
    Set address of JNIEnv to JNIEnvPtr  
    Set address of JNINativeInterface to JNIEnv  
  
    Invoke anObj "someMethod"  
    Perform ErrorCheck  
..  
ErrorCheck.  
    Call ExceptionOccurred  
        using by value JNIEnvPtr  
        returning ex  
    If ex not = null then  
        Call ExceptionClear using by value JNIEnvPtr  
        Display "Caught an unexpected exception"  
        Invoke ex "printStackTrace"  
        Stop run  
    End-if
```

## Managing local and global references

The Java virtual machine tracks the object references that you use in native methods, such as COBOL methods. This tracking ensures that the objects are not prematurely released during garbage collection.

There are two classes of such references:

### Local references

Local references are valid only while the method that you invoke runs. Automatic freeing of the local references occurs after the native method returns.

### Global references

Global references remain valid until you explicitly delete them. You can create global references from local references by using the JNI service `NewGlobalRef`.

The following object references are always local:

- Object references that are received as method parameters
- Object references that are returned as the method RETURNING value from a method invocation
- Object references that are returned by a call to a JNI function
- Object references that you create by using the `INVOKE . . . NEW` statement

You can pass either a local reference or a global reference as an object reference argument to a JNI service.

You can code methods to return either local or global references as RETURNING values. However, in either case, the reference that is received by the invoking program is a local reference.

You can pass either local or global references as USING arguments in a method invocation. However, in either case, the reference that is received by the invoked method is a local reference.

Local references are valid only in the thread in which you create them. Do not pass them from one thread to another.

#### **related tasks**

[“Accessing JNI services” on page 601](#)

[“Deleting, saving, and freeing local references” on page 604](#)

## **Deleting, saving, and freeing local references**

You can manually delete local references at any point within a method. Save local references only in object references that you define in the LOCAL-STORAGE SECTION of a method.

Use a SET statement to convert a local reference to a global reference if you want to save a reference in any of these data items:

- An object instance variable
- A factory variable
- A data item in the WORKING-STORAGE SECTION of a method

Otherwise, an error occurs. These storage areas persist when a method returns; therefore a local reference is no longer valid.

In most cases you can rely on the automatic freeing of local references that occurs when a method returns. However, in some cases you should explicitly free a local reference within a method by using the JNI service DeleteLocalRef. Here are two situations where explicit freeing is appropriate:

- In a method you access a large object, thereby creating a local reference to the object. After extensive computations, the method returns. Free the large object if you do not need it for the additional computations, because the local reference prevents the object from being released during garbage collection.
- You create a large number of local references in a method, but do not use all of them at the same time. Because the Java virtual machine requires space to keep track of each local reference, you should free those that you no longer need. Freeing the local references helps prevent the system from running out of memory.

For example, in a COBOL method you loop through a large array of objects, retrieve the elements as local references, and operate on one element at each iteration. You can free the local reference to the array element after each iteration.

Use the following callable services to manage local references and global references.

<i>Table 83. JNI services for local and global references</i>			
<b>Service</b>	<b>Input arguments</b>	<b>Return value</b>	<b>Purpose</b>
NewGlobalRef	<ul style="list-style-type: none"><li>• The JNI environment pointer</li><li>• A local or global object reference</li></ul>	The global reference, or NULL if the system is out of memory	To create a new global reference to the object that the input object reference refers to

Table 83. <i>JNI services for local and global references</i> (continued)			
Service	Input arguments	Return value	Purpose
DeleteGlobalRef	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>A global object reference</li> </ul>	None	To delete a global reference to the object that the input object reference refers to
DeleteLocalRef	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>A local object reference</li> </ul>	None	To delete a local reference to the object that the input object reference refers to

#### related tasks

[“Accessing JNI services” on page 601](#)

## Java access controls

The Java access modifiers `protected` and `private` are not enforced when you use the Java Native Interface. Therefore a COBOL program could invoke a `protected` or `private` Java method that is not invocable from a Java client. This usage is not recommended.

## Sharing data with Java

You can share the COBOL data types that have Java equivalents. (Some COBOL data types have Java equivalents, but others do not.)

Share data items with Java in these ways:

- Pass them as arguments in the `USING` phrase of an `INVOKE` statement.
- Receive them as parameters in the `USING` phrase from a Java method.
- Receive them as the `RETURNING` value in an `INVOKE` statement.
- Return them as the value in the `RETURNING` phrase of the `PROCEDURE DIVISION` header in a COBOL method.

To pass or receive arrays and strings, declare them as object references:

- Declare an array as an object reference that contains an instance of one of the special array classes.
- Declare a string as an object reference that contains an instance of the `jstring` class.

#### related tasks

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Declaring arrays and strings for Java” on page 606](#)

[“Manipulating Java arrays” on page 608](#)

[“Manipulating Java strings” on page 610](#)

[“Invoking methods \(INVOKE\)” on page 580](#)

[Chapter 26, “Sharing data,” on page 465](#)

## Coding interoperable data types in COBOL and Java

Your COBOL program can use only certain data types when communicating with Java.

Table 84. <i>Interoperable data types in COBOL and Java</i>	
Primitive Java data type	Corresponding COBOL data type
boolean <sup>1</sup>	PIC X followed by exactly two condition-names of this form:  <pre>level-number data-name PIC X. 88          data-name-false value X'00'. 88          data-name-true  value X'01' through X'FF'.</pre>
byte <sup>1</sup>	Single-byte alphanumeric: PIC X or PIC A
short	USAGE BINARY, COMP, COMP-4, or COMP-5, with PICTURE clause of the form S9(n), where 1<=n<=4
int	USAGE BINARY, COMP, COMP-4, or COMP-5, with PICTURE clause of the form S9(n), where 5<=n<=9
long	USAGE BINARY, COMP, COMP-4, or COMP-5, with PICTURE clause of the form S9(n), where 10<=n<=18
float <sup>2</sup>	USAGE COMP-1
double <sup>2</sup>	USAGE COMP-2
char	Single-character elementary national: PIC N USAGE NATIONAL. (Cannot be a national group.)
class types (object references)	USAGE OBJECT REFERENCE <i>class-name</i>
<p>1. You must distinguish boolean from byte, because they each correspond to PIC X. PIC X is interpreted as boolean only if you define an argument or a parameter with the two condition-names as shown. Otherwise, a PIC X data item is interpreted as the Java byte type.</p> <p>2. Java floating-point data is formatted according to the <i>IEEE Standard for Binary Floating Point Arithmetic</i>. Enterprise COBOL, however, uses hexadecimal floating-point representation. When you pass floating-point arguments by using an INVOKE statement, or you receive floating-point data from a Java method, the arguments and data are automatically converted as needed.</p>	

### related tasks

[“Using national data \(Unicode\) in COBOL” on page 124](#)

## Declaring arrays and strings for Java

When you communicate with Java, declare arrays by using the special array classes, and declare strings by using jstring. Code the COBOL data types shown in the table below.

Table 85. <i>Interoperable arrays and strings in COBOL and Java</i>	
Java data type	Corresponding COBOL data type
boolean[ ]	object reference jbooleanArray
byte[ ]	object reference jbyteArray
short[ ]	object reference jshortArray
int[ ]	object reference jintArray

Table 85. <i>Interoperable arrays and strings in COBOL and Java</i> (continued)	
Java data type	Corresponding COBOL data type
long[ ]	object reference jlongArray
char[ ]	object reference jcharArray
Object[ ]	object reference jobjectArray
String	object reference jstring

To use one of these classes for interoperability with Java, you must code an entry in the REPOSITORY paragraph. For example:

```
Configuration section.
Repository.
    Class jbooleanArray is "jbooleanArray".
```

The REPOSITORY paragraph entry for an object array type must specify an external class-name in one of these forms:

```
"jobjectArray"
"jobjectArray:external-classname-2"
```

In the first case, the REPOSITORY entry specifies an array class in which the elements of the array are objects of type `java.lang.Object`. In the second case, the REPOSITORY entry specifies an array class in which the elements of the array are objects of type `external-classname-2`. Code a colon as the separator between the specification of the `jobjectArray` type and the external class-name of the array elements.

The following example shows both cases. In the example, `oa` defines an array of elements that are objects of type `java.lang.Object`. `aDepartment` defines an array of elements that are objects of type `com.acme.Employee`.

```
Environment Division.
Configuration Section.
Repository.
    Class jobjectArray is "jobjectArray"
    Class Employee    is "com.acme.Employee"
    Class Department  is "jobjectArray:com.acme.Employee".
. . .
Linkage section.
01 oa                usage object reference jobjectArray.
01 aDepartment        usage object reference Department.
. . .
Procedure division using by value aDepartment.
. . .
```

[“Examples: COBOL applications that run using the java command” on page 599](#)

The following Java array types are currently not supported for interoperation with COBOL programs.

Table 86. <i>Noninteroperable array types in COBOL and Java</i>	
Java data type	Corresponding COBOL data type
float[ ]	object reference jfloatArray
double[ ]	object reference jdoubleArray

#### related tasks

[“REPOSITORY paragraph for defining a class” on page 566](#)

## Manipulating Java arrays

To represent an array in a COBOL program, code a group item that contains a single elementary item that is of the data type that corresponds to the Java type of the array. Specify an OCCURS or OCCURS DEPENDING ON clause that is appropriate for the array.

For example, the following code specifies a structure to receive 500 or fewer integer values from a jlongArray object:

```
01  jlongArray.
02  X pic S9(10) comp-5 occurs 1 to 500 times depending on N.
```

To operate on objects of the special Java-array classes, call the services that the JNI provides. You can use services to access and set individual elements of an array and for the following purposes, using the services cited:

Table 87. <b>JNI array services</b>			
Service	Input arguments	Return value	Purpose
GetArrayLength	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The array object reference</li> </ul>	The array length as a binary fullword integer	To get the number of elements in a Java array object
NewBooleanArray, NewByteArray, NewCharArray, NewShortArray, NewIntArray, NewLongArray	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The number of elements in the array, as a binary fullword integer</li> </ul>	The array object reference, or NULL if the array cannot be constructed	To create a new Java array object
GetBooleanArrayElements, GetByteArrayElements, GetCharArrayElements, GetShortArrayElements, GetIntArrayElements, GetLongArrayElements	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The array object reference</li> <li>A pointer to a boolean item. If the pointer is not null, the boolean item is set to true if a copy of the array elements was made. If a copy was made, the corresponding ReleasexxxArrayElements service must be called if changes are to be written back to the array object.</li> </ul>	A pointer to the storage buffer	To extract the array elements from a Java array into a storage buffer. The services return a pointer to the storage buffer, which you can use as the address of a COBOL group data item defined in the LINKAGE SECTION.
ReleaseBooleanArrayElements, ReleaseByteArrayElements, ReleaseCharArrayElements, ReleaseShortArrayElements, ReleaseIntArrayElements, ReleaseLongArrayElements	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The array object reference</li> <li>A pointer to the storage buffer</li> <li>The release mode, as a binary fullword integer. See Java JNI documentation for details. (Recommendation: Specify 0 to copy back the array content and free the storage buffer.)</li> </ul>	None; the storage for the array is released.	To release the storage buffer that contains elements that have been extracted from a Java array, and conditionally map the updated array values back into the array object

Table 87. <b>JNI array services</b> (continued)			
Service	Input arguments	Return value	Purpose
NewObjectArray	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The number of elements in the array, as a binary fullword integer</li> <li>An object reference for the array element class</li> <li>An object reference for the initial element value. All array elements are set to this value.</li> </ul>	The array object reference, or NULL if the array cannot be constructed <sup>1</sup>	To create a new Java object array
GetObjectArrayElement	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The array object reference</li> <li>An array element index, as a binary fullword integer using origin zero</li> </ul>	An object reference <sup>2</sup>	To return the element at a given index within an object array
SetObjectArrayElement	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>The array object reference</li> <li>The array element index, as a binary fullword integer using origin zero</li> <li>The object reference for the new value</li> </ul>	None <sup>3</sup>	To set an element within an object array
<p>1. NewObjectArray throws an exception if the system runs out of memory.</p> <p>2. GetObjectArrayElement throws an exception if the index is not valid.</p> <p>3. SetObjectArrayElement throws an exception if the index is not valid or if the new value is not a subclass of the element class of the array.</p>			

[“Examples: COBOL applications that run using the java command” on page 599](#)

[“Example: processing a Java integer array” on page 609](#)

#### **related tasks**

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Declaring arrays and strings for Java” on page 606](#)

[“Accessing JNI services” on page 601](#)

### **Example: processing a Java integer array**

The following example shows the use of the Java-array classes and JNI services to process a Java integer array in COBOL.

```

cbl thread,dll
Identification division.
Class-id. OOARRAY inherits Base.
Environment division.
Configuration section.
Repository.
    Class Base is "java.lang.Object"
    Class jintArray is "jintArray".

```

```

Identification division.
Object.
Procedure division.
  Identification division.
  Method-id. "ProcessArray".
  Data Division.
  Local-storage section.
  01 intArrayPtr pointer.
  01 intArrayLen pic S9(9) comp-5.
  Linkage section.
  COPY JNI.
  01 inIntArrayObj usage object reference jintArray.
  01 intArrayGroup.
    02 X pic S9(9) comp-5
      occurs 1 to 1000 times depending on intArrayLen.
  Procedure division using by value inIntArrayObj.
    Set address of JNIEnv to JNIEnvPtr
    Set address of JNINativeInterface to JNIEnv

    Call GetArrayLength
      using by value JNIEnvPtr inIntArrayObj
      returning intArrayLen
    Call GetIntArrayElements
      using by value JNIEnvPtr inIntArrayObj 0
      returning IntArrayPtr
    Set address of intArrayGroup to intArrayPtr

*   . . . process the array elements X(I) . . .

    Call ReleaseIntArrayElements
      using by value JNIEnvPtr inIntArrayObj intArrayPtr 0.
  End method "ProcessArray".
End Object.
End class OOARRAY.

```

## Manipulating Java strings

COBOL represents Java String data in Unicode. To represent a Java String in a COBOL program, declare the string as an object reference of the `jstring` class. Then use JNI services to set or extract COBOL alphanumeric or national (Unicode) data from the object.

**Services for Unicode:** Use the following standard services to convert between `jstring` object references and COBOL USAGE NATIONAL data items. Use these services for applications that you intend to be portable between the workstation and the mainframe. Access these services by using function pointers in the `JNINativeInterface` environment structure.

Table 88. <i>Services that convert between jstring references and national data</i>		
Service	Input arguments	Return value
NewString <sup>1</sup>	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>A pointer to a Unicode string, such as a COBOL national data item</li> <li>The number of characters in the string; binary fullword</li> </ul>	jstring object reference
GetStringLength	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>A jstring object reference</li> </ul>	The number of Unicode characters in the jstring object reference; binary fullword

Table 88. <i>Services that convert between jstring references and national data (continued)</i>		
Service	Input arguments	Return value
GetStringChars <sup>1</sup>	<ul style="list-style-type: none"> <li>• The JNI environment pointer</li> <li>• A jstring object reference</li> <li>• A pointer to a boolean data item, or NULL</li> </ul>	<ul style="list-style-type: none"> <li>• A pointer to the array of Unicode characters extracted from the jstring object, or NULL if the operation fails. The pointer is valid until it is released with ReleaseStringChars.</li> <li>• If the pointer to the boolean data item is not null, the boolean value is set to true if a copy is made of the string and to false if no copy is made.</li> </ul>
ReleaseStringChars	<ul style="list-style-type: none"> <li>• The JNI environment pointer</li> <li>• A jstring object reference</li> <li>• A pointer to the array of Unicode characters that was returned from GetStringChars</li> </ul>	None; the storage for the array is released.
1. This service throws an exception if the system runs out of memory.		

**Services for EBCDIC:** Use the following z/OS services, an extension of the JNI, to convert between jstring object references and COBOL alphanumeric data (PIC X(*n*)).

Table 89. <i>Services that convert between jstring references and alphanumeric data</i>		
Service	Input arguments	Return value
NewStringPlatform	<ul style="list-style-type: none"> <li>• The JNI environment pointer</li> <li>• Pointer to the null-terminated EBCDIC character string that you want to convert to a jstring object</li> <li>• Pointer to the jstring object reference in which you want the result</li> <li>• Pointer to the Java encoding name for the string, represented as a null-terminated EBCDIC character string<sup>1</sup></li> </ul>	Return code as a binary fullword integer: <b>0</b> Success. <b>-1</b> Malformed input or illegal input character. <b>-2</b> Unsupported encoding; the jstring object reference pointer is set to NULL.

Table 89. <i>Services that convert between jstring references and alphanumeric data</i> (continued)		
Service	Input arguments	Return value
GetStringPlatformLength	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>jstring object reference for which you want the length</li> <li>Pointer to a binary fullword integer for the result</li> <li>Pointer to the Java encoding name for the string, represented as a null-terminated EBCDIC character string<sup>1</sup></li> </ul>	Return code as a binary fullword integer: <b>0</b> Success. <b>-1</b> Malformed input or illegal input character. <b>-2</b> Unsupported encoding; the jstring object reference pointer is set to NULL. Returns, in the third argument, the needed length in bytes of the output buffer to hold the converted Java string, including the terminating null byte referenced by the second argument.
GetStringPlatform	<ul style="list-style-type: none"> <li>The JNI environment pointer</li> <li>jstring object reference that you want to convert to a null-terminated string</li> <li>Pointer to the output buffer in which you want the converted string</li> <li>Length of the output buffer as a binary fullword integer</li> <li>Pointer to the Java encoding name for the string, represented as a null-terminated EBCDIC character string<sup>1</sup></li> </ul>	Return code as a binary fullword integer: <b>0</b> Success. <b>-1</b> Malformed input or illegal input character. <b>-2</b> Unsupported encoding; the output string is set to a null string. <b>-3</b> Conversion buffer is full.
1. If the pointer is NULL, the encoding from the Java file.encoding property is used.		

These EBCDIC services are packaged as a DLL that is part of your IBM Java Software Development Kit. For details about the services, see `jni_convert.h` in the IBM Java Software Development Kit.

Use CALL *literal* statements to call the services. The calls are resolved through the `libjvm.x` DLL side file, which you must include in the link step of any COBOL program that uses object-oriented language.

For example, the following code creates a Java String object from the EBCDIC string 'MyConverter'. (This code fragment is from the J2EE client program, which is shown in full in [“Example: J2EE client written in COBOL”](#) on page 613.)

```

Move z"MyConverter" to stringBuffer
Call "NewStringPlatform"
    using by value JNIEnvPtr
                    address of stringBuffer
                    address of jstring1
                    0
returning rc

```

If the EBCDIC services are the only JNI services that you call from a COBOL program, you do not need to copy the `JNI.cpy` copybook. You also do not need to establish addressability with the JNI environment pointer.

**Services for UTF-8:** The Java Native Interface also provides services for conversion between `jstring` object references and UTF-8 strings. These services are not recommended for use in COBOL programs due to the difficulty in handling UTF-8 character strings on the z/OS platform.

#### related tasks

[“Accessing JNI services” on page 601](#)

[“Coding interoperable data types in COBOL and Java” on page 606](#)

[“Declaring arrays and strings for Java” on page 606](#)

[“Using national data \(Unicode\)](#)

[in COBOL” on page 124](#)

[Chapter 16, “Compiling, linking, and running OO applications,” on page 273](#)

## Example: J2EE client written in COBOL

The following example shows a COBOL client program that can access enterprise beans that run on a J2EE-compliant EJB server.

The COBOL client is equivalent to the J2EE client program in the Getting Started section of the *Java 2 Enterprise Edition Developer's Guide*. For your convenience in comparing implementations, the second example shows the equivalent Java client from the guide. (The enterprise bean is the Java implementation of the simple currency-converter enterprise bean, and is in the same guide.)

You can find an alternate version of the Java enterprise bean and client code in *The Java EE 5 Tutorial*, referenced below.

### COBOL client (ConverterClient.cbl)

```
Process pgmname(longmixed),dll,thread
*****
* Demo J2EE client written in COBOL.
*
* Based on the sample J2EE client written in Java, which is
* given in the "Getting Started" chapter of "The Java(TM) 2
* Enterprise Edition Developer's Guide."
*
* The client:
*   - Locates the home interface of a session enterprise bean
*     (a simple currency converter bean)
*   - Creates an enterprise bean instance
*   - Invokes a business method (currency conversion)
*****
Identification division.
Program-id. "ConverterClient" is recursive.
Environment Division.
Configuration section.
Repository.
    Class InitialCtx is "javax.naming.InitialContext"
    Class PortableRemoteObject
        is "javax.rmi.PortableRemoteObject"
    Class JavaObject is "java.lang.Object"
    Class JavaClass is "java.lang.Class"
    Class JavaException is "java.lang.Exception"
    Class jstring is "jstring"
    Class Converter is "Converter"
    Class ConverterHome is "ConverterHome".
Data division.
Working-storage section.
01 initialCtx object reference InitialCtx.
01 obj object reference JavaObject.
01 classObj object reference JavaClass.
01 ex object reference JavaException.
01 currencyConverter object reference Converter.
01 home object reference ConverterHome.
01 homeObj redefines home object reference JavaObject.
01 jstring1 object reference jstring.
01 stringBuf pic X(500) usage display.
```

```

01 len          pic s9(9) comp-5.
01 rc           pic s9(9) comp-5.
01 amount       comp-2.
Linkage section.
  Copy JNI.
Procedure division.
  Set address of JNIenv to JNIEnvPtr
  Set address of JNINativeInterface to JNIenv

*****
* Create JNDI naming context. *
*****
  Invoke InitialContext New returning initialCtx
  Perform JavaExceptionCheck

*****
* Create a jstring object for the string "MyConverter" for use *
* as argument to the lookup method. *
*****
  Move z"MyConverter" to stringBuf
  Call "NewStringPlatform"
    using by value JNIEnvPtr
    address of stringBuf
    address of jstring1
    0
  returning rc
  If rc not = zero then
    Display "Error occurred creating jstring object"
    Stop run
  End-if

*****
* Use the lookup method to obtain a reference to the home *
* object bound to the name "MyConverter". (This is the JNDI *
* name specified when deploying the J2EE application.) *
*****
  Invoke initialCtx "lookup" using by value jstring1
  returning obj
  Perform JavaExceptionCheck

*****
* Narrow the home object to be of type ConverterHome. *
* First obtain class object for the ConverterHome class, by *
* passing the null-terminated ASCII string "ConverterHome" to *
* the FindClass API. Then use this class object as the *
* argument to the static method "narrow". *
*****
  Move z"ConverterHome" to stringBuf
  Call "__etoa"
    using by value address of stringBuf
    returning len
  If len = -1 then
    Display "Error occurred on ASCII conversion"
    Stop run
  End-if
  Call FindClass
    using by value JNIEnvPtr
    address of stringBuf
    returning classObj
  If classObj = null
    Display "Error occurred locating ConverterHome class"
    Stop run
  End-if
  Invoke PortableRemoteObject "narrow"
    using by value obj
    classObj
    returning homeObject
  Perform JavaExceptionCheck

*****
* Create the ConverterEJB instance and obtain local object *
* reference for its remote interface *
*****
  Invoke home "create" returning currencyConverter
  Perform JavaExceptionCheck

*****
* Invoke business methods *
*****
  Invoke currencyConverter "dollarToYen"
    using by value +100.00E+0
    returning amount

```

```

Perform JavaExceptionCheck

Display amount

Invoke currencyConverter "yenToEuro"
    using by value +100.00E+0
    returning amount
Perform JavaExceptionCheck

Display amount

*****
* Remove the object and return.
*
*****
Invoke currencyConverter "remove"
Perform JavaExceptionCheck

Goback
.

*****
* Check for thrown Java exceptions
*
*****
JavaExceptionCheck.
    Call ExceptionOccurred using by value JNIEnvPtr
    returning ex
    If ex not = null then
        Call ExceptionClear using by value JNIEnvPtr
        Display "Caught an unexpected exception"
        Invoke ex "printStackTrace"
        Stop run
    End-if
.
End program "ConverterClient".

```

## Java client (ConverterClient.java)

```

/*
 *
 * Copyright 2000 Sun Microsystems, Inc. All Rights Reserved.
 *
 * This software is the proprietary information of Sun Microsystems, Inc.
 * Use is subject to license terms.
 *
 */

import javax.naming.Context;
import javax.naming.InitialContext;
import javax.rmi.PortableRemoteObject;

import Converter;
import ConverterHome;

public class ConverterClient {

    public static void main(String[] args) {
        try {
            Context initial = new InitialContext();
            Object objref = initial.lookup("MyConverter");

            ConverterHome home =
                (ConverterHome)PortableRemoteObject.narrow(objref,
                                                            ConverterHome.class);

            Converter currencyConverter = home.create();

            double amount = currencyConverter.dollarToYen(100.00);
            System.out.println(String.valueOf(amount));
            amount = currencyConverter.yenToEuro(100.00);
            System.out.println(String.valueOf(amount));

            currencyConverter.remove();

        } catch (Exception ex) {
            System.err.println("Caught an unexpected exception!");
            ex.printStackTrace();
        }
    }
}

```

```
}  
}
```

**related tasks**

Chapter 16, “Compiling, linking, and running OO applications,” on page 273

[\*WebSphere for z/OS: Applications\*](#)

[\*Java 2 Enterprise Edition Developer's Guide \(Getting Started\)\*](#)

[\*The Java EE 5 Tutorial \(Getting Started with Enterprise Beans\)\*](#)

---

## Part 7. Specialized processing



---

## Chapter 35. Interrupts and checkpoint/restart

When programs run for an extended period of time, interruptions might halt processing before the end of a job. The checkpoint/restart functions of z/OS let an interrupted program be restarted at the beginning of a job step or at a checkpoint that you have set.

Because the checkpoint/restart functions cause a lot of extra processing, use them only when you anticipate interruptions caused by machine malfunctions, input or output errors, or intentional operator intervention.

The checkpoint routine starts from the COBOL program object that contains your program. While your program is running, the checkpoint routine creates records at points that you have designated using the COBOL RERUN clause. A checkpoint record contains a snapshot of the information in the registers and main storage when the program reached the checkpoint.

The restart routine restarts an interrupted program. You can perform a restart at any time after the program was interrupted: either immediately (automatic restart), or later (deferred restart).

### related tasks

[“Setting checkpoints” on page 619](#)

[“Restarting programs” on page 622](#)

[“Resubmitting jobs for restart” on page 624](#)

*z/OS DFSMS: Checkpoint/Restart*

### related references

[“DD statements for defining checkpoint data sets” on page 620](#)

[“Messages generated during checkpoint” on page 622](#)

[“Formats for requesting deferred restart” on page 623](#)

---

## Setting checkpoints

To set checkpoints, use job control statements and use the RERUN clause in the ENVIRONMENT DIVISION. Associate each RERUN clause with a particular COBOL file.

The RERUN clause indicates that a checkpoint record is to be written to a checkpoint data set whenever a specified number of records in the COBOL file have been processed or when END OF VOLUME is reached. You cannot use the RERUN clause with files that are defined with the EXTERNAL attribute.

You can write checkpoint records from several COBOL files to one checkpoint data set, but you must use a separate data set exclusively for checkpoint records. You cannot embed checkpoint records in one of your program data sets.

**Restrictions:** A checkpoint data set must have sequential organization. You cannot write checkpoints in VSAM data sets or in data sets that are allocated to extended-format QSAM data sets. Also, a checkpoint cannot be taken if any program in the run unit has an extended-format QSAM data set that is open.

Checkpoint records are written in the checkpoint data set defined by a DD statement. In the DD statement, you also choose the checkpoint method:

### Single (store single checkpoints)

Only one checkpoint record exists at any given time. After the first checkpoint record is written, any succeeding checkpoint record overlays the previous one.

This method is acceptable for most programs. You save space in the checkpoint data set, and you can restart your program at the latest checkpoint.

### Multiple (store multiple contiguous checkpoints)

Checkpoints are recorded and numbered sequentially. Each checkpoint is saved.

Use this method if you want to restart a program at a checkpoint other than the latest one taken.

You must use the multiple checkpoint method for complete compliance with the 85 COBOL Standard.

Checkpoints during sort operations have the following requirements:

- If checkpoints are to be taken during a sort operation, add a DD statement for SORTCKPT in the job control procedure for execution.
- You can take checkpoint records on ASCII-collated sorts, but the *system-name* that indicates the checkpoint data set must not specify an ASCII file.

#### related tasks

[“Using checkpoint/restart with DFSORT” on page 221](#)

[“Designing checkpoints” on page 620](#)

[“Testing for a successful checkpoint” on page 620](#)

#### related references

[“DD statements for defining checkpoint data sets” on page 620](#)

## Designing checkpoints

Design your checkpoints at critical points in your program so that data can be easily reconstructed. Do not change the contents of files between the time of a checkpoint and the time of the restart.

In a program that uses disk files, design the program so that you can identify previously processed records. For example, consider a disk file that contains loan records that are periodically updated for interest due. If a checkpoint is taken, records are updated, and then the program is interrupted, you would want to test that the records that are updated after the last checkpoint are not updated again when the program is restarted. To do this, set up a date field in each record, and update the field each time the record is processed. Then, after the restart, test the field to determine whether the record was already processed.

For efficient repositioning of a print file, take checkpoints on the file only after printing the last line of a page.

## Testing for a successful checkpoint

After each input or output statement that issues a checkpoint, the RETURN-CODE special register is updated with the return code from the checkpoint routine. Therefore, you can test whether the checkpoint was successful and decide whether conditions are right to allow a restart.

If the return code is greater than 4, an error has occurred in the checkpoint. Check the return code to prevent a restart that could cause incorrect output.

#### related references

*z/OS DFSMS: Checkpoint/Restart* (Return codes)

## DD statements for defining checkpoint data sets

To define checkpoint data sets, use DD statements.

#### For tape:

```
//ddname DD DSN=dataset-name,
//          [VOLUME=SER=volser,]UNIT=device-type,
//          DISP=(NEW|MOD,PASS)
```

#### For direct-access devices:

```
//ddname DD DSN=dataset-name,
//          [VOLUME=(PRIVATE,RETAIN,SER=volser),]
//          UNIT=device-type,SPACE=(subparms),
//          DISP=(NEW|MOD,PASS,KEEP)
```

**ddname**

Provides a link to the DD statement. The same as the ddname portion of the *assignment-name* used in the COBOL RERUN clause.

**data-set-name**

Identifies the checkpoint data set to the restart procedure. The name given to the data set used to record checkpoint records.

**volser**

Identifies the volume by serial number.

**device-type**

Identifies the device.

**subparms**

Specifies the amount of track space needed for the data set.

**MOD**

Specifies the multiple contiguous checkpoint method.

**NEW**

Specifies the single checkpoint method.

**PASS**

Prevents deletion of the data set at successful completion of the job step, unless the job step is the last in the job. If it is the last step, the data set is deleted.

**KEEP**

Keeps the data set if the job step abnormally ends.

[“Examples: defining checkpoint data sets” on page 621](#)

## Examples: defining checkpoint data sets

The following examples show the JCL and COBOL coding you can use to define checkpoint data sets.

### Writing single checkpoint records, using tape:

```
//CHECKPT DD DSN=CHECK1,VOLUME=SER=ND0003,
//          UNIT=TAPE,DISP=(NEW,KEEP),LABEL=(,NL)

ENVIRONMENT DIVISION.

RESTART ON CHECKPT EVERY
5000 RECORDS OF ACCT-FILE.
```

### Writing single checkpoint records, using disk:

```
//CHEK DD DSN=CHECK2,
//        VOLUME=(PRIVATE,RETAIN,SER=DB0030),
//        UNIT=3380,DISP=(NEW,KEEP),SPACE=(CYL,5)

ENVIRONMENT DIVISION.

RESTART ON CHEK EVERY
20000 RECORDS OF PAYCODE.
RESTART ON CHEK EVERY
30000 RECORDS OF IN-FILE.
```

### Writing multiple contiguous checkpoint records, using tape:

```
//CHECKPT DD DSN=CHECK3,VOLUME=SER=111111,
//          UNIT=TAPE,DISP=(MOD,PASS),LABEL=(,NL)

ENVIRONMENT DIVISION.

RESTART ON CHECKPT EVERY
10000 RECORDS OF PAY-FILE.
```

## Messages generated during checkpoint

The system checkpoint routine advises the operator of the status of the checkpoints taken by displaying informative messages on the console.

Each time a checkpoint is successfully completed, a message is displayed that associates the jobname (*ddname*, *unit*, *volser*) with the checkpoint taken (*checkid*).

The control program assigns *checkid* as an eight-character string. The first character is the letter C, followed by a decimal number that indicates the checkpoint. For example, the following message indicates the fourth checkpoint taken in the job step:

```
checkid C0000004
```

## Restarting programs

The system restart routine retrieves the information recorded in a checkpoint record, restores the contents of main storage and all registers, and restarts the program.

You can begin the restart routine in one of two ways:

- Automatically at the time an interruption stopped the program
- At a later time as a deferred restart

The RD parameter of the job control language determines the type of restart. You can use the RD parameter on either the JOB or the EXEC statement. If coded on the JOB statement, the parameter overrides any RD parameters on the EXEC statement.

To suppress both restart and writing checkpoints, code RD=NC.

**Restriction:** If you try to restart at a checkpoint taken by a COBOL program during a SORT or MERGE operation, an error message is issued and the restart is canceled. Only checkpoints taken by DFSORT are valid.

Data sets that have the SYSOUT parameter coded in their DD statements are handled in various ways depending on the type of restart.

If the checkpoint data set is multivolume, include in the VOLUME parameter the sequence number of the volume on which the checkpoint entry was written. If the checkpoint data set is on a 7-track tape with nonstandard labels or no labels, the SYSCHK DD statement must contain DCB=(TRTCH=C, . . .).

### related tasks

[“Using checkpoint/restart with DFSORT” on page 221](#)

[“Requesting automatic restart” on page 622](#)

[“Requesting deferred restart” on page 623](#)

## Requesting automatic restart

Automatic restart occurs only at the latest checkpoint taken. If no checkpoint was taken before interruption, automatic restart occurs at the beginning of the job step.

Whenever automatic restart is to occur, the system repositions all devices except unit-record devices.

If you want automatic restart, code RD=R or RD=RNC:

- RD=R indicates that restart is to occur at the latest checkpoint. Code the RERUN clause for at least one data set in the program in order to record checkpoints. If no checkpoint is taken before interruption, restart occurs at the beginning of the job step.
- RD=RNC indicates that no checkpoint is to be written, and that any restart is to occur at the beginning of the job step. In this case, RERUN clauses are unnecessary; if any are present, they are ignored.

If you omit the RD parameter, the CHKPT macro instruction remains active, and checkpoints can be taken during processing. If an interrupt occurs after the first checkpoint, automatic restart will occur.

To restart automatically, a program must satisfy the following conditions:

- In the program you must request restart by using the RD parameter or by taking a checkpoint.
- An abend that terminated the job must return a code that allows restart.
- The operator must authorize the restart.

[“Example: requesting a step restart” on page 624](#)

## Requesting deferred restart

Deferred restart can occur at any checkpoint, not necessarily the latest one taken. You can restart your program at a checkpoint other than at the beginning of the job step.

When a deferred restart has been successfully completed, the system displays a message on the console stating that the job has been restarted. Control is then given to your program.

If you want deferred restart, code the RD parameter as RD=NR. This form of the parameter suppresses automatic restart but allows a checkpoint record to be written provided that a RERUN clause was coded.

Request a deferred restart by using the RESTART parameter on the JOB card and a SYSCHK DD statement to identify the checkpoint data set. If a SYSCHK DD statement is present in a job and the JOB statement does not contain the RESTART parameter, the SYSCHK DD statement is ignored. If a RESTART parameter without the CHECKID subparameter is included in a job, a SYSCHK DD statement must not appear before the first EXEC statement for the job.

[“Example: restarting a job at a specific checkpoint step” on page 624](#)

### related references

[“Formats for requesting deferred restart” on page 623](#)

## Formats for requesting deferred restart

The formats for the RESTART parameter of the JOB statement and the SYSCHK DD statements are as shown below.

```
//jobname JOB MSGLEVEL=1,RESTART=(request[,checkid])
//SYSCHK DD DSN=dataset-name,
// DISP=OLD[,UNIT=device-type,
// VOLUME=SER=volser]
```

### MSGLEVEL=1 (or MSGLEVEL=(1,y))

MSGLEVEL is required.

### RESTART=(request,[checkid])

Identifies the particular checkpoint at which restart is to occur.

#### **request**

Takes one of the following forms:

**\***

Indicates restart at the beginning of the job.

#### **stepname**

Indicates restart at the beginning of a job step.

#### **stepname.procstep**

Indicates restart at a procedure step within the job step.

#### **checkid**

Identifies the checkpoint where restart is to occur.

### SYSCHK

The ddname used to identify a checkpoint data set to the control program. The SYSCHK DD statement must immediately precede the first EXEC statement of the resubmitted job, and must follow any JOBLIB statement.

**data-set-name**

Identifies the checkpoint data set. It must be the same name that was used when the checkpoint was taken.

**device-type and volser**

Identify the device type and the serial number of the volume that contains the checkpoint data set.

[“Example: requesting a deferred restart” on page 624](#)

**Example: requesting a deferred restart**

This example shows JCL to restart the GO step of an IGYWCLG procedure at checkpoint identifier (CHECKID) C0000003.

```
//jobname JOB MSGLEVEL=1,RESTART=(stepname.GO,C0000003)
//SYSPCHK DD DSN=CHKPT,
//          DISP=OLD[,UNIT=3380,VOLUME=SER=111111]
//          . . .
```

**Resubmitting jobs for restart**

When you resubmit a job for restart, be careful with any DD statements that might affect the execution of the restarted job step. The restart routine uses information from DD statements in the resubmitted job to reset files for use after restart.

If you want a data set to be deleted at the end of a job step, give it a conditional disposition of PASS or KEEP (rather than DELETE). This disposition allows the data set to be available if an interruption forces a restart. If you want to restart a job at the beginning of a step, you must first discard any data set created (defined as NEW in a DD statement) in the previous run, or change the DD statement to mark the data set as OLD.

The system automatically repositions input data sets that are on tape or disk.

[“Example: resubmitting a job for a step restart” on page 625](#)

[“Example: resubmitting a job for a checkpoint restart” on page 625](#)

**Example: restarting a job at a specific checkpoint step**

This example shows a sequence of job control statements for restarting a job at a specific step.

```
//PAYROLL JOB MSGLEVEL=1,REGION=80K,
//          RESTART=(STEP1,CHECKPT4)
//JOBLIB DD DSN=PRIV.LIB3,DISP=OLD
//SYSPCHK DD DSN=CHKPTLIB,
//          [UNIT=TAPE,VOL=SER=456789,]
//          DISP=(OLD,KEEP)
//STEP1 EXEC PGM=PROG4,TIME=5
```

**Example: requesting a step restart**

This example shows the use of the RD parameter, which requests step restart for any abnormally terminated job step.

```
//J1234 JOB 386,SMITH,MSGLEVEL=1,RD=R
//S1 EXEC PGM=MYPROG
//INDATA DD DSN=INVENT[,UNIT=TAPE],DISP=OLD,
//          [VOLUME=SER=91468,]
//          LABEL=RETPD=14
//REPORT DD SYSOUT=A
//WORK DD DSN=T91468,DISP=(,KEEP),
//          UNIT=SYSDA,SPACE=(3000,(5000,500)),
```

```
//
//DDCKPNT DD VOLUME=(PRIVATE,RETAIN,,6)
//          UNIT=TAPE,DISP=(MOD,PASS,CATLG),
//          DSNNAME=C91468,LABEL=(,NL)
```

The DDCKPNT DD statement defines a checkpoint data set. For this step, after a RERUN clause is performed, only automatic checkpoint restart can occur unless a CHKPT cancel is issued.

## Example: resubmitting a job for a step restart

This example shows the changes that you might make to the JCL before you resubmit a job for step restart.

```
//J3412 JOB 386,SMITH,MSGLEVEL=1,RD=R,RESTART=*
//S1 EXEC PGM=MYPROG
//INDATA DD DSNNAME=INVENT[,UNIT=TAPE],DISP=OLD,
//        [VOLUME=SER=91468,]LABEL=RETPD=14
//REPORT DD SYSOUT=A
//WORK DD DSNNAME=S91468,
//        DISP=(,KEEP),UNIT=SYSDA,
//        SPACE=(3000,(5000,500)),
//        VOLUME=(PRIVATE,RETAIN,,6)
//DDCHKPNT DD UNIT=TAPE,DISP=(MOD,PASS,CATLG),
//          DSNNAME=R91468,LABEL=(,NL)
```

The following changes were made in the example above:

- The job name has been changed (from J1234 to J3412) to distinguish the original job from the restarted job.
- The RESTART parameter has been added to the JOB statement, and indicates that restart is to begin with the first job step.
- The WORK DD statement was originally assigned a conditional disposition of KEEP for this data set:
  - If the step terminated normally in the previous run of the job, the data set was deleted, and no changes need to be made to this statement.
  - If the step abnormally terminated, the data set was kept. In that case, define a new data set (S91468 instead of T91468, as shown), or change the status of the data set to OLD before resubmitting the job.
- A new data set (R91468 instead of C91468) has also been defined as the checkpoint data set.

[“Example: requesting a step restart” on page 624](#)

## Example: resubmitting a job for a checkpoint restart

This example shows the changes that you might make to JCL before you resubmit a job for checkpoint restart.

```
//J3412 JOB 386,SMITH,MSGLEVEL=1,RD=R,
//        RESTART=(*,C00000002)
//SYSCHK DD DSNNAME=C91468,DISP=OLD
//S1 EXEC PGM=MYPROG
//INDATA DD DSNNAME=INVENT,UNIT=TAPE,DISP=OLD,
//        VOLUME=SER=91468,LABEL=RETPD=14
//REPORT DD SYSOUT=A
//WORK DD DSNNAME=T91468,DISP=(,KEEP),
//        UNIT=SYSDA,SPACE=(3000,(5000,500)),
//        VOLUME=(PRIVATE,RETAIN,,6)
//DDCKPNT DD UNIT=TAPE,DISP=(MOD,KEEP,CATLG),
//          DSNNAME=C91468,LABEL=(,NL)
```

The following changes were made in the example above:

- The job name has been changed (from J1234 to J3412) to distinguish the original job from the restarted job.

- The RESTART parameter has been added to the JOB statement, and indicates that restart is to begin with the first step at the checkpoint entry named C0000002.
- The DD statement DDCKPNT was originally assigned a conditional disposition of CATLG for the checkpoint data set:
  - If the step terminated normally in the previous run of the job, the data set was kept. In that case, the SYSCHK DD statement must contain all of the information necessary for retrieving the checkpoint data set.
  - If the job abnormally terminated, the data set was cataloged. In that case, the only parameters required on the SYSCHK DD statement are DSNAME and DISP as shown.

If a checkpoint is taken in a job that is running when V=R is specified, the job cannot be restarted until adequate nonpageable dynamic storage becomes available.

## Chapter 36. Using zlib compression from a COBOL program

Refer to the following example including instructions and tricks about using zlib compression from a COBOL program.

```
//PROCLIB JCLLIB ORDER=IGYV6R10.SIGYPROC
//EXAMPLE1 EXEC IGYWCLG
//COBOL.STEPLIB DD DISP=SHR,DSNAME=IGYV6R10.SIGYCOMP
//SYSADATA DD SYSOUT=*
//COBOL.SYSIN DD *
      CBL PGMNAME(LONGMIXED)
      *****
      *
      * This is a sample testcase to show how you can call zlib.
      * It initializes compression (deflate) and then deflates some
      * data, then initializes decompression (inflate) and inflates
      * the same data.
      *
      * Some of the key differences from 'typical' COBOL are:
      * - Compiler option PGMNAME(LONGMIXED) is required.
      *   This means that the Program-Id name has to be a literal
      * - This program uses COMP-5 data items so that the program
      *   can work with any setting of the TRUNC compiler option
      * - Rather than passing the zstream structure by REFERENCE like
      *   most COBOL programs, we pass the ADDRESS OF using the
      *   BY VALUE phrase to avoid high-order bit getting set
      * - This sample has DISPLAY statements to tell you if it was
      *   successful or not, and they should be removed for production*
      * - The binder (linkage editor) needs to have LIBRARY
      *   statements in order to access the functions in the
      *   /usr/lpp/hzc/lib/libz.a archive file. See the sample
      *   LKED.SYSIN statements below
      *
      *****
      Id Division.
      Program-id. 'ZLIB'.
      *
      Data Division.

      Working-Storage Section.
      **> Memory for tests. 'data' to be compressed
      01 zinput   pic X(65536) value x'00'.
      01 zoutput  pic X(65536) value x'00'.
      01 z.
      *
      02 next_in  is a Pointer to zstring
      02 next_in  Pointer.
      02 avail_in  Pic S9(9)    Comp-5.
      02 total_in  Pic S9(9)    Comp-5.
      *
      02 next_out is a Pointer to zstring
      02 next_out  Pointer.
      02 avail_out  Pic S9(9)    Comp-5.
      02 total_out  Pic S9(9)    Comp-5.
      *
      02 msg      is a Pointer to zstring
      02 msg      Pointer.
      02 state    Pointer.
      02 zalloc   Function-pointer.
      02 zfree    Function-pointer.
      02 opaque   Function-pointer.
      02 data_type Pic S9(9)    Comp-5.
      02 Adler    Pic S9(9)    Comp-5.
      02 reserved Pic S9(9)    Comp-5.
      01 y.
      *
      02 next_in  is a Pointer to zstring
      02 next_in  Pointer.
      02 avail_in  Pic S9(9)    Comp-5.
      02 total_in  Pic S9(9)    Comp-5.
      *
      02 next_out is a Pointer to zstring
      02 next_out  Pointer.
      02 avail_out  Pic S9(9)    Comp-5.
      02 total_out  Pic S9(9)    Comp-5.
      *
      02 msg      is a Pointer to zstring
      02 msg      Pointer.
      02 state    Pointer.
```

```

02  zalloc      Function-pointer.
02  zfree       Function-pointer.
02  opaque      Function-pointer.
02  data_type   Pic S9(9)   Comp-5.
02  Adler       Pic S9(9)   Comp-5.
02  reserved    Pic S9(9)   Comp-5.

77  rc-disp Pic S9(9) Display Sign leading separate.

Linkage Section.
77  zstring Pic x(1000).
77  rc      Pic S9(9) Comp-5.

Procedure Division returning rc.
**>*****
**>*****
**> Setup the z_stream structure with defaults
**>*****
    Set zalloc of z to Null
    Set zfree  of z to Null
    Set opaque of z to Null

*   *>*****
*   *>
*   *> Call deflateInit to initialize the deflate stream
*   *> service using a GZIP wrapper
*   *>
*   *>*****
Call 'DEIN2' Using By Value Address of z,
                                By Value  -1, 8, 31, 8, 0,
                                By Content '1.2.7',
                                By Value  Length Of z

    returning rc

    If rc NOT = 0 Then
        Move rc to rc-disp
        Display 'Error: deflateInit failed with Return Code '
                                rc-disp
        If msg of z NOT = Null Then
            Set Address of zstring to msg of z
            Display 'Message = ' zstring
        Else
            Display 'Message pointer is NULL '
        End-if
        Move -1 To Return-code rc

        Goback
    Else
        Display 'deflateInit Successful ! '
    End-if

*****
* Initialize available input, output, total in for deflate
*****
    Compute avail_in of z = 65536
    Compute avail_out of z = 65536
    Compute total_in of z = 0
*****
* Set input and output pointers
*****
    Set next_out of z to Address of zoutput
    Set next_in of z to Address of zinput

*   *>*****
*   *>
*   *> Call deflate to compress the data. We only call it
*   *> once with a flush mode of Z_FINISH (4) which indicates
*   *> to end the stream
*   *>
*   *>*****
Call 'deflate' Using By Value Address of z
                                BY Value 4 Returning rc

    If rc NOT = 1 Then
        Move rc to rc-disp
        Display ' Error: deflate returned ' rc-disp

        If msg of z NOT = Null Then
            Set Address of zstring to msg of z
            Display zstring
        End-if

```

```

        Display "avail_in of z= "   avail_in of z
        Display "total_in of z= "   total_in of z
        Display "avail_out of z= "  avail_out of z
        Display "total_out of z= "  total_out of z

        Call 'DEEND' Using By Value address of z returning rc

        Move -1 To Return-code rc
        Goback
    Else
        Display 'deflate Successful ! '
    End-if

    Display 'After deflate '
    Display 'avail_in of z= '   avail_in of z
    Display 'total_in of z= '   total_in of z
    Display 'avail_out of z= '  avail_out of z
    Display 'total_out of z= '  total_out of z

* /*****
* /*
* /* Now that we are done , call deflateEnd to cleanup the
* /* deflate internal state.
* /*
* /*
* /*****
    Call 'DEEND' Using By Value Address of z returning rc
    If rc Not = 0 Then
        Move rc to rc-disp
        Display 'Error: deflateEnd returned ' rc-disp

        If msg of z NOT = Null Then
            Move -1 To Return-code rc
            Goback
        End-if
    Else
        Display 'deflateEnd Successful ! '
    End-if

* /*****
* /*
* /* Inflate the data we just deflated. Call inflateInit to
* /* initialize the inflate stream
* /*
* /*
* /*****
    Set zalloc of y to Null
    Set zfree of y to Null

    Set opaque of y to Null

    Call 'ININ2' Using By Value Address of y,
                                By Value 31,
                                By Content '1.2.7',
                                By VALUE Length Of y

        returning rc

    If rc NOT = 0 Then
        Move rc to rc-disp
        Display 'Error: inflateInit failed with Return Code '
                                rc-disp

        If msg of y NOT = Null Then
            Set Address of zstring to msg of y
            Display zstring
        End-if
        Move -1 To Return-code rc
        Goback
    Else
        Display 'inflateInit Successful ! '
    End-if

* /*****
* /*
* /* Set the amount of input based on what deflate returned
* /* and what we expect the output size to be.
* /*
* /*
* /*****
    Compute avail_in of y = total_out of z
    Compute avail_out of y = 65536
    Compute total_in of y = 0

    Set next_out of y to Address of zinput

```

```

        Set next_in of y to Address of zoutput

* /*****
* /*
* /* Call inflate to decompress the data. Note that we expect */
* /* this to end with a Z_STREAM_END (1) since we provided the */
* /* full stream above. */
* /*
* /*****
    Call 'inflate' Using By Value Address of y
                      By Value 0 Returning rc

    If rc Not = 1 Then
        Move rc to rc-disp
        Display 'Error: inflate returned ' rc-disp

        If msg of z NOT = Null Then
            Set Address of zstring to msg of z
            Display zstring
        End-if

        Display "avail_in of y= " avail_in of z
        Display "total_in of y= " total_in of z
        Display "avail_out of y= " avail_out of z
        Display "total_out of y= " total_out of z

        Call 'INEND' Using By Value Address of y Returning rc
        Move -1 To Return-code rc
        Goback
    Else
        Display 'inflate Successful ! '
    End-if

    Display 'After inflate '
    Display 'avail_in of y= ' avail_in of y
    Display 'total_in of y= ' total_in of y
    Display 'avail_out of y= ' avail_out of y
    Display 'total_out of y= ' total_out of y

* /*****
* /*
* /* Now that we are done call inflateEnd to cleanup the */
* /* internal inflate state of the stream. */
* /*
* /*****
    Call 'INEND' Using By Value Address of y Returning rc
    If rc Not = 0 Then

        If rc Not = 0 Then
            Move rc to rc-disp
            Display 'Error: inflateEnd returned ' rc-disp

            If msg of z NOT = Null Then
                Move -1 To Return-code rc
                Goback
            End-if
        Else
            Display 'inflateEnd Successful ! '
        End-if

        Move zero to return-code rc
        Goback.

/*
//LKED.SYSIN DD *
LIBRARY '/usr/lpp/hzc/lib/libzz.a'
/*
//LKED.SYSLIB DD DSN=CEEZ240.SCEELKED,DISP=SHR
//LKED.SYSLMOD DD DSN=MYLOAD.COBOL.LOAD(ZLIB),DISP=SHR
//GO.STEPLIB DD DSN=CEEV240.SCEERUN,DISP=SHR
//GO.SYSUDUMP DD DUMMY
//GO.SYSSORT DD DUMMY
//GO.SYSOUT DD SYSOUT=*
//

```

---

## Part 8. Improving performance and productivity



---

## Chapter 37. Tuning your program

When a program is comprehensible, you can assess its performance. A tangled control flow makes a program difficult to understand and maintain, and inhibits the optimization of its code.

To improve the performance of your program, examine at least these aspects:

- Underlying algorithms: For best performance, using sound algorithms is essential. For example:
  - A sophisticated algorithm for sorting a million items might be hundreds of thousands of times faster than a simple algorithm.
  - If the program frequently accesses data, reduce the number of steps to access the data.
- Data structures: Using data structures that are appropriate for the algorithms is essential.

You can write programs that result in better generated code sequences and use system services more efficiently. These additional aspects can affect performance:

- Coding techniques: Use a programming style that enables the optimizer to choose efficient data types and handle tables efficiently.
- Optimization: You can optimize code by using the OPTIMIZE compiler option.
- Compiler options and `USE FOR DEBUGGING ON ALL PROCEDURES`: Some compiler options and language affect program efficiency.
- Runtime environment: Consider your choice of runtime options.
- Running under CICS, IMS, or VSAM: Heeding various tips can help make these programs run more efficiently.

### related concepts

[“Optimization” on page 638](#)

### related tasks

[“Using an optimal programming style” on page 633](#)

[“Choosing efficient data types” on page 634](#)

[“Handling tables efficiently” on page 636](#)

[“Optimizing your code” on page 638](#)

[“Choosing compiler features to enhance performance” on page 639](#)

[“Running efficiently with CICS, IMS, or VSAM” on page 644](#)

*Language Environment Programming Guide* (Specifying runtime options)

### related references

[“Performance-related compiler options” on page 640](#)

*Language Environment Programming Guide* (Storage performance considerations)

**I** *Enterprise COBOL Version 6 Release 1 Performance Tuning Guide*

---

## Using an optimal programming style

The coding style you use can affect how the optimizer handles your code. You can improve optimization by using structured programming techniques, factoring expressions, using symbolic constants, and grouping constant and duplicate computations.

### related tasks

[“Using structured programming” on page 634](#)

[“Factoring expressions” on page 634](#)

[“Using symbolic constants” on page 634](#)

## Using structured programming

Using structured programming statements, such as EVALUATE and inline PERFORM, makes your program more comprehensible and generates a more linear control flow. As a result, the optimizer can operate over larger regions of the program, which gives you more efficient code.

Use top-down programming constructs. Out-of-line PERFORM statements are a natural means of doing top-down programming. Out-of-line PERFORM statements can often be as efficient as inline PERFORM statements, because the optimizer can simplify or remove the linkage code.

Avoid using the following constructs:

- ALTER statements
- Explicit GO TO statements
- PERFORM procedures that involve irregular control flow (such as preventing control from passing to the end of the procedure and returning to the PERFORM statement)

## Factoring expressions

By factoring expressions in your programs, you can potentially eliminate a lot of unnecessary computation.

For example, the first block of code below is more efficient than the second block of code:

```
MOVE ZERO TO TOTAL
PERFORM VARYING I FROM 1 BY 1 UNTIL I = 10
    COMPUTE TOTAL = TOTAL + ITEM(I)
END-PERFORM
COMPUTE TOTAL = TOTAL * DISCOUNT
```

```
MOVE ZERO TO TOTAL
PERFORM VARYING I FROM 1 BY 1 UNTIL I = 10
    COMPUTE TOTAL = TOTAL + ITEM(I) * DISCOUNT
END-PERFORM
```

The optimizer does not factor expressions.

## Using symbolic constants

To have the optimizer recognize a data item as a constant throughout the program, initialize it with a VALUE clause and do not change it anywhere in the program.

If you pass a data item to a subprogram BY REFERENCE, the optimizer treats it as an external data item and assumes that it is changed at every subprogram call.

## Choosing efficient data types

---

Using the SYNCHRONIZED clause can produce more efficient code.

Consistent data types can reduce the need for conversions during operations on data items. You can also improve program performance by carefully determining when to use fixed-point and floating-point data types.

### related concepts

[“Formats for numeric data” on page 45](#)

### related tasks

[“Choosing efficient computational data items” on page 635](#)

[“Using consistent data types” on page 635](#)

[“Making arithmetic expressions efficient” on page 635](#)

[“Making exponentiations efficient” on page 636](#)

## Choosing efficient computational data items

When you use a data item mainly for arithmetic or as a subscript, code `USAGE BINARY` on the data description entry for the item. The operations for manipulating binary data are faster than those for manipulating decimal data.

However, if a fixed-point arithmetic statement has intermediate results with a large precision (number of significant digits), the compiler uses decimal arithmetic anyway, after converting the operands to packed-decimal form. For fixed-point arithmetic statements, the compiler normally uses binary arithmetic for simple computations with binary operands if the precision is eight or fewer digits. Above 18 digits, the compiler always uses decimal arithmetic. With a precision of nine to 18 digits, the compiler uses either form.

To produce the most efficient code for a `BINARY` data item, ensure that it has:

- A sign (an `S` in its `PICTURE` clause)
- Eight or fewer digits

For a data item that is larger than eight digits or is used with `DISPLAY` or `NATIONAL` data items, use `PACKED-DECIMAL`. The code generated for `PACKED-DECIMAL` data items can be as fast as that for `BINARY` data items in some cases, especially if the statement is complicated or specifies rounding.

To produce the most efficient code for a `PACKED-DECIMAL` data item, ensure that it has:

- A sign (an `S` in its `PICTURE` clause)
- An odd number of digits (9s in the `PICTURE` clause), so that it occupies an exact number of bytes without a half byte left over
- 15 or fewer digits in the `PICTURE` specification on `ARCH(7)` machines. If a `PACKED-DECIMAL` data item has more than 31 digits, library routines are used. For a `PACKED-DECIMAL` data item with 16-31 digits on `ARCH(8)` or higher level machines, the compiler uses instructions that are more efficient than library calls, but not as fast as if the data item has 15 or fewer digits.

## Using consistent data types

In operations on operands of different types, one of the operands must be converted to the same type as the other. Each conversion requires several instructions. For example, one of the operands might need to be scaled to give it the appropriate number of decimal places.

You can largely avoid conversions by using consistent data types and by giving both operands the same usage and also appropriate `PICTURE` specifications. That is, you should ensure that two numbers to be compared, added, or subtracted not only have the same usage but also the same number of decimal places (9s after the `V` in the `PICTURE` clause).

## Making arithmetic expressions efficient

Computation of arithmetic expressions that are evaluated in floating point is most efficient when the operands need little or no conversion. Use operands that are `COMP-1` or `COMP-2` to produce the most efficient code.

Define integer items as `BINARY` or `PACKED-DECIMAL` with nine or fewer digits to afford quick conversion to floating-point data. Also, conversion from a `COMP-1` or `COMP-2` item to a fixed-point integer with nine or fewer digits, without `SIZE ERROR` in effect, is efficient when the value of the `COMP-1` or `COMP-2` item is less than 1,000,000,000.

## Making exponentiations efficient

Use floating point for exponentiations for large exponents to achieve faster evaluation and more accurate results.

For example, the first statement below is computed more quickly and accurately than the second statement:

```
COMPUTE fixed-point1 = fixed-point2 ** 100000.E+00  
COMPUTE fixed-point1 = fixed-point2 ** 100000
```

A floating-point exponent causes floating-point arithmetic to be used to compute the exponentiation.

## Using VOLATILE clauses efficiently

Optimization of data items that are defined with the VOLATILE clause is significantly restricted. Therefore, use the VOLATILE clause only when appropriate.

In particular, it is important to understand that when the VOLATILE clause is used on a group item, the compiler treats all data items subordinate to the group item as volatile, and all higher-level group items that contain the volatile group item are treated as volatile, too. If a particular member of a group needs to be treated as volatile, specify the VOLATILE clause on the data description entry for that item only, where possible.

At present, the primary reason to use the VOLATILE clause is for data items that are set or referenced inside an LE condition handler but are defined outside the LE condition handler program. The VOLATILE clause guarantees that such items are handled correctly by the optimizer. For more information on when to use VOLATILE, see *VOLATILE clause* in the *Enterprise COBOL for z/OS Language Reference*.

## Handling tables efficiently

You can use several techniques to improve the efficiency of table-handling operations, and to influence the optimizer. The return for your efforts can be significant, particularly when table-handling operations are a major part of an application.

The following two guidelines affect your choice of how to refer to table elements:

- Use indexing rather than subscripting.

Although the compiler can eliminate duplicate indexes and subscripts, the original reference to a table element is more efficient with indexes (even if the subscripts were BINARY). The value of an index has the element size factored into it, whereas the value of a subscript must be multiplied by the element size when the subscript is used. The index already contains the displacement from the start of the table, and this value does not have to be calculated at run time. However, subscripting might be easier to understand and maintain.

- Use relative indexing.

Relative index references (that is, references in which an unsigned numeric literal is added to or subtracted from the index-name) are executed at least as fast as direct index references, and sometimes faster. There is no merit in keeping alternative indexes with the offset factored in.

Whether you use indexes or subscripts, the following coding guidelines can help you get better performance:

- Specify the element length so that it matches that of related tables.

When you index or subscript tables, it is most efficient if all the tables have the same element length. That way, the stride for the last dimension of the tables is the same, and the optimizer can reuse the rightmost index or subscript computed for one table. If both the element lengths and the number of occurrences in each dimension are equal, then the strides for dimensions other than the last are also equal, resulting in greater commonality between their subscript computations. The optimizer can then reuse indexes or subscripts other than the rightmost.

- Avoid errors in references by coding index and subscript checks into your program.

If you need to validate indexes and subscripts, it might be faster to code your own checks than to use the SSRANGE compiler option.

You can also improve the efficiency of tables by using these guidelines:

- Use binary data items for all subscripts.

When you use subscripts to address a table, use a BINARY signed data item with eight or fewer digits. In some cases, using four or fewer digits for the data item might also improve processing time.

- Use binary data items for variable-length table items.

For tables with variable-length items, you can improve the code for OCCURS DEPENDING ON (ODO). To avoid unnecessary conversions each time the variable-length items are referenced, specify BINARY for OCCURS . . . DEPENDING ON objects.

- Use fixed-length data items whenever possible.

Copying variable-length data items into a fixed-length data item before a period of high-frequency use can reduce some of the overhead associated with using variable-length data items.

- Organize tables according to the type of search method used.

If the table is searched sequentially, put the data values most likely to satisfy the search criteria at the beginning of the table. If the table is searched using a binary search algorithm, put the data values in the table sorted alphabetically on the search key field.

#### **related concepts**

[“Optimization of table references” on page 637](#)

#### **related tasks**

[“Referring to an item in a table” on page 68](#)

[“Choosing efficient data types” on page 634](#)

#### **related references**

[“SSRANGE” on page 338](#)

## **Optimization of table references**

The COBOL compiler optimizes table references in several ways.

For the table element reference ELEMENT (S1 S2 S3), where S1, S2, and S3 are subscripts, the compiler evaluates the following expression:

```
comp_s1 * d1 + comp_s2 * d2 + comp_s3 * d3 + base_address
```

Here comp\_s1 is the value of S1 after conversion to binary, comp\_s2 is the value of S2 after conversion to binary, and so on. The strides for each dimension are d1, d2, and d3. The *stride* of a given dimension is the distance in bytes between table elements whose occurrence numbers in that dimension differ by 1 and whose other occurrence numbers are equal. For example, the stride d2 of the second dimension in the above example is the distance in bytes between ELEMENT (S1 1 S3) and ELEMENT (S1 2 S3).

Index computations are similar to subscript computations, except that no multiplication needs to be done. Index values have the stride factored into them. They involve loading the indexes into registers, and these data transfers can be optimized, much as the individual subscript computation terms are optimized.

### ***Optimization of variable-length items***

A group item that contains a subordinate OCCURS DEPENDING ON data item has a variable length. The program must perform special code every time a variable-length data item is referenced.

Because this code is out-of-line, it might interrupt optimization. Furthermore, the code to manipulate variable-length data items is much less efficient than that for fixed-size data items and can significantly

increase processing time. For instance, the code to compare or move a variable-length data item might involve calling a library routine and is much slower than the same code for fixed-length data items.

### ***Comparison of direct and relative indexing***

Relative index references are as fast as or faster than direct index references.

The direct indexing in ELEMENT (I5, J3, K2) requires this preprocessing:

```
SET I5 TO I
SET I5 UP BY 5
SET J3 TO J
SET J3 DOWN BY 3
SET K2 TO K
SET K2 UP BY 2
```

This processing makes the direct indexing less efficient than the relative indexing in ELEMENT (I + 5, J - 3, K + 2).

#### **related concepts**

[“Optimization” on page 638](#)

#### **related tasks**

[“Handling tables efficiently” on page 636](#)

## **Optimizing your code**

---

When your program is ready for final testing, specify the OPTIMIZE (1 | 2) compiler option so that the tested code and the production code are identical.

If you frequently run a program without recompiling it during development, you might also want to use OPTIMIZE (1 | 2). However, if you recompile frequently, the overhead for OPTIMIZE (1 | 2) might outweigh its benefits unless you are using the assembler language expansion (LIST compiler option) to fine-tune the program.

For unit-testing a program, you will probably find it easier to debug code that has not been optimized.

To see how the optimizer works on a program, compile it with different levels of optimization and compare the generated code. (Use the LIST compiler option to request the assembler listing of the generated code.)

#### **related concepts**

[“Optimization” on page 638](#)

#### **related references**

[“LIST” on page 315](#)

[“OPTIMIZE” on page 325](#)

## **Optimization**

To improve the efficiency of the generated code, you can use the OPTIMIZE (1) or OPTIMIZE (2) compiler option.

OPTIMIZE (1) causes the COBOL optimizer to do the following optimizations:

- Eliminate unnecessary transfers of control and inefficient branches, including those generated by the compiler that are not evident from looking at the source program.
- Simplify the compiled code for a PERFORM statement. The compiler replicates the PERFORM a number of times to avoid linkage code.
- Eliminate duplicate computations (such as subscript computations and repeated statements) that have no effect on the results of the program.
- Eliminate constant computations by performing them when the program is compiled.

- Eliminate constant conditional expressions.
- Aggregate moves of contiguous items (such as those that often occur with the use of MOVE CORRESPONDING) into a single move. Both the source and target must be contiguous for the moves to be aggregated.
- Delete from the program, and identify with a warning message, code that can never be performed (unreachable code elimination).
- Discard unreferenced data items from the DATA DIVISION, and suppress generation of code to initialize these data items to their VALUE clauses. (The optimizer takes this action only when you use the STGOPT option.)

OPTIMIZE (2) causes the COBOL optimizer to do further optimizations:

- Simplify operations more aggressively and schedule instructions.
- Do interblock optimizations such as global value propagation and loop invariant code motion.

## Contained program procedure integration

In contained program procedure integration, the contained program code replaces a CALL to a contained program. The resulting program runs faster without the overhead of CALL linkage and with more linear control flow.

**Program size:** If several CALL statements call contained programs and these programs replace each such statement, the containing program can become large. The optimizer then chooses the next best optimization for the CALL statement.

### related concepts

[“PERFORM procedure integration” on page 639](#)

### related references

[“OPTIMIZE” on page 325](#)

## PERFORM procedure integration

PERFORM procedure integration is the process whereby a PERFORM statement is replaced by its performed procedures. The advantage is that the resulting program runs faster without the overhead of PERFORM linkage and with more orderly control flow.

**Program size:** If the performed procedures are invoked by several PERFORM statements and replace each such statement, the program could become large. The optimizer limits this increase, after which it no longer integrates these procedures.

### related references

[“INLINE” on page 312](#)

INLINE directive (Enterprise COBOL for z/OS Language Reference)

## Choosing compiler features to enhance performance

Your choice of performance-related compiler options and your use of the USE FOR DEBUGGING ON ALL PROCEDURES statement can affect how well your program is optimized.

You might have a customized system that requires certain options for optimum performance. Do these steps:

1. To see what your system defaults are, get a short listing for any program and review the listed option settings.
2. Determine which options are fixed as nonoverridable at your installation by checking with your system programmer.
3. For the options not fixed at installation, select performance-related options for compiling your programs.

**Important:** Confer with your system programmer about how to tune COBOL programs. Doing so will ensure that the options you choose are appropriate for programs at your site.

Another compiler feature to consider is the `USE FOR DEBUGGING ON ALL PROCEDURES` statement. It can greatly affect the compiler optimizer. The `ON ALL PROCEDURES` option generates extra code at each transfer to a procedure name. Although very useful for debugging, it can make the program significantly larger and inhibit optimization substantially.

Although COBOL allows segmentation language, you will not improve storage allocation by using it, because COBOL does not perform overlay.

#### related concepts

[“Optimization” on page 638](#)

#### related tasks

[“Optimizing your code” on page 638](#)

[“Getting listings” on page 370](#)

#### related references

[“Performance-related compiler options” on page 640](#)

## Performance-related compiler options

In the table below you can see a description of the purpose of each option, its performance advantages and disadvantages, and usage notes where applicable.

Table 90. <i>Performance-related compiler options</i>				
Compiler option	Purpose	Performance advantages	Performance disadvantages	Usage notes
AFP (NOVOLATILE) (see <a href="#">“AFP” on page 289</a> )	To control the compiler usage of the Additional Floating Point (AFP) registers that are provided by z/Architecture processors	AFP (NOVOLATILE) lets the compiler generate more efficient code sequences for programs with floating point operations.	None	Poorly behaved assembler code might not adhere to the standard calling convention and might fail to correctly preserve values in Floating Point registers. With AFP (NOVOLATILE), COBOL programs can safely call such routines.
ARCH (see <a href="#">“ARCH” on page 290</a> )	To specify the machine architecture for which the executable program instructions are to be generated	If you specify a higher ARCH level, the machine generates code that uses newer and faster instructions instead of the sequences of common instructions.	None	Your application might abend if it runs on a processor with an architecture level lower than that specified for the ARCH option.
ARITH(EXTEND) (see <a href="#">“ARITH” on page 291</a> )	To increase the maximum number of digits allowed for decimal numbers	None	ARITH(EXTEND) causes some degradation in performance for all decimal data types because of larger intermediate results.	The amount of degradation that you experience depends directly on the amount of decimal data that you use.
AWO (see <a href="#">“AWO” on page 292</a> )	To get optimum use of buffer and device space for QSAM files	Can result in performance savings, because this option results in fewer calls to data management services to handle input and output	None	If you use AWO, the <code>APPLY WRITE - ONLY</code> clause is in effect for all QSAM files in the program that have V-mode records.
BLOCK0 (see <a href="#">“BLOCK0” on page 293</a> )	To take advantage of system-determined block size for QSAM output files	Can result in enhanced processing speed and minimized storage requirements for QSAM output files	None	If you use BLOCK0, a <code>BLOCK CONTAINS 0</code> clause is activated for all QSAM files in the program that specify neither <code>BLOCK CONTAINS</code> nor <code>RECORDING MODE U</code> in the file description entry.

Table 90. *Performance-related compiler options (continued)*

Compiler option	Purpose	Performance advantages	Performance disadvantages	Usage notes
DATA (31) (see <a href="#">“DATA” on page 300</a> )	To have DFSMS allocate QSAM buffers above the 16 MB line (by using the RENT and DATA (31) compiler options)	Because extended-format QSAM data sets can require many buffers, allocating the buffers in unrestricted storage avoids virtual storage constraint problems.	None	On a z/OS system with DFSMS, if your application processes striped extended-format QSAM data sets, use the RENT and DATA (31) compiler options to have the input-output buffers for your QSAM files allocated from storage above the 16 MB line.
DYNAM (see <a href="#">“DYNAM” on page 305</a> )	To have subprograms (called through the CALL statement) dynamically loaded at run time	Subprograms are easier to maintain, because the application does not have to be link-edited again if a subprogram is changed.	There is a slight performance penalty, because the call must go through a Language Environment routine.	To free virtual storage that is no longer needed, issue the CANCEL statement.
FASTSRT (see <a href="#">“FASTSRT” on page 308</a> )	To specify that the IBM DFSORT product (or equivalent) will handle all of the input and output	Eliminates the overhead of returning to Enterprise COBOL after each record is processed	None	FASTSRT is recommended if direct work files are used for the sort work files. Not all sorts are eligible for this option.
HGPR (see <a href="#">“HGPR” on page 310</a> )	To control the compiler usage of the 64-bit registers provided by z/Architecture processors.	If you specify HGPR(NOPRESERVE), the compiler omits preserving the high-halves of the 64-bit GPRs that a program is using, which improves performance.	None	If your program modifies and does not save the high-halves of the registers, but calling programs depend on the unchanged values, the application might give incorrect results.  <b>Exception:</b> It does not apply if the caller of this program is Enterprise COBOL, Enterprise PL/I or z/OS XL C/C++ programs.
INLINE (see <a href="#">“INLINE” on page 312</a> )	To control the compiler usage of inlining procedures (paragraphs or sections) referenced by PERFORM statements in the source program.	Specifying INLINE allows the compiler to decide whether to inline procedures referenced by PERFORM statements. This typically improves performance when the application contains commonly occurring and often-executed procedures.	Specifying INLINE usually increases the size of the module. For commonly occurring but rarely executed procedures, you can use the >>INLINE OFF directive to prevent the compiler from inlining that procedure and increasing the module size.	You can use the INLINE compiler option to indicate that a procedure should be considered eligible for inlining, but the decision whether to inline a procedure in a specific PERFORM statement or not is made by the compiler.
MAXPCF (see <a href="#">“MAXPCF” on page 317</a> )	To reduce optimization in programs that require excessive compilation time or excessive storage requirements because of large sizes or complexity.	None	If you specify MAXPCF( <i>n</i> ) and <i>n</i> is not zero, when the program complexity factor exceeds <i>n</i> , any specification of OPTIMIZE(1) or OPTIMIZE(2) is reset to OPTIMIZE(0), and a warning message is generated.	None

Table 90. *Performance-related compiler options (continued)*

Compiler option	Purpose	Performance advantages	Performance disadvantages	Usage notes
NUMPROC (PFD) (see <a href="#">“NUMPROC”</a> on page 322)	To have invalid sign processing bypassed for numeric operations	Generates significantly more efficient code for numeric comparisons	For most references to COMP-3 and DISPLAY numeric data items, NUMPROC (PFD) inhibits extra code from being generated to “fix up” signs. This extra code might also inhibit some other types of optimizations. The extra code is generated with NUMPROC (NOPFD).	If you use NUMPROC (PFD), the compiler assumes and requires that all decimal items contain the preferred sign values and bypasses the sign “fix-up” process. However, because not all external data files contain the proper signs for COMP-3 or DISPLAY numeric data, and programs might use REDEFINES, group moves, or parameter passing in ways that do not ensure preferred signs, the NUMPROC (PFD) might not be appropriate for many programs.
OPTIMIZE (0   1   2) (see <a href="#">“OPTIMIZE”</a> on page 325)	To optimize generated code for better performance	Generally results in more efficient runtime code	Longer compile time: OPTIMIZE (1   2) requires more processing time for compiles than OPTIMIZE (0).	OPTIMIZE (0) is generally used during program development when frequent compiles are needed; it also allows for symbolic debugging. For production runs, OPTIMIZE (1   2) is recommended.
STGOPT (see <a href="#">“STGOPT”</a> on page 339)	To optimize storage allocation in DATA DIVISION	Generally results in less storage usage	None	STGOPT deletes unused data items, which might be undesirable in the case of time stamps or data items that are used only as markers for dump reading.
RENT (see <a href="#">“RENT”</a> on page 330)	To generate a reentrant program	Enables the program to be placed in shared storage (LPA/ELPA) for faster execution	Generates additional code to ensure that the program is reentrant	None
RMODE (ANY) (see <a href="#">“RMODE”</a> on page 331)	To let the program be loaded anywhere	None	None	None
SSRANGE (see <a href="#">“SSRANGE”</a> on page 338)	To verify that all table references and reference modification expressions are in proper bounds	SSRANGE generates additional code for verifying table references. Using NOSSRANGE causes that code not to be generated.	With SSRANGE specified, checks for valid ranges do affect compiler performance.	In general, if you need to verify the table references only a few times instead of at every reference, coding your own checks might be faster than using SSRANGE. For performance-sensitive applications, NOSSRANGE is recommended.
TEST (see <a href="#">“TEST”</a> on page 340)	To get full debugging capability when using Debug Tool and to get a symbolic dump of the data items in CEEDUMP. You can also get a symbolic dump of the data items in CEEDUMP with NOTEST (DWARF).	None	Some reduction in optimization occurs when the TEST option is used. More reduction in optimization occurs when the EJPD suboption of TEST is used.	For production runs, using NOTEST or TEST (NOEJPD) is recommended.  If during a production run, you want a symbolic dump of the data items in a formatted dump if the program abends, compile using TEST or with NOTEST (DWARF).
THREAD (see <a href="#">“THREAD”</a> on page 343)	To enable programs for execution in a Language Environment enclave that has multiple POSIX threads or PL/I tasks	None	There is a slight performance penalty because of the overhead of serialization logic.	A slight performance penalty occurs in either a threaded or nonthreaded environment.

Table 90. <i>Performance-related compiler options</i> (continued)				
Compiler option	Purpose	Performance advantages	Performance disadvantages	Usage notes
TRUNC (OPT) (see <a href="#">“TRUNC” on page 344</a> )	To avoid having code generated to truncate the receiving fields of arithmetic operations	Does not generate extra code and generally improves performance	Both TRUNC (BIN) and TRUNC (STD) generate extra code whenever a BINARY data item is changed. TRUNC (BIN) is usually the slowest of these options.	TRUNC (STD) conforms to the 85 COBOL Standard, but TRUNC (BIN) and TRUNC (OPT) do not. With TRUNC (OPT), the compiler assumes that the data conforms to the PICTURE and USAGE specifications. TRUNC (OPT) is recommended where possible.

### related concepts

[“Optimization” on page 638](#)

[“Storage and its addressability” on page 37](#)

### related tasks

[“Generating a list of compiler messages” on page 262](#)

[“Evaluating performance” on page 643](#)

[“Optimizing buffer and device space” on page 10](#)

[“Choosing compiler features to enhance performance” on page 639](#)

[“Improving sort performance with FASTSORT” on page 216](#)

[“Using striped extended-format QSAM data sets” on page 169](#)

[“Handling tables efficiently” on page 636](#)

### related references

[“Sign representation of zoned and packed-decimal data” on page 51](#)

[“Allocation of buffers for QSAM files” on page 170](#)

[Chapter 17, “Compiler options,” on page 283](#)

[“Conflicting compiler options” on page 287](#)

## Evaluating performance

Fill in the following worksheet to help you evaluate the performance of your program. If you answer yes to each question, you are probably improving the performance.

In thinking about the performance tradeoff, be sure you understand the function of each option as well as the performance advantages and disadvantages. You might prefer function over increased performance in many instances.

Table 91. <i>Performance-tuning worksheet</i>		
Compiler option	Consideration	Yes?
ARCH	Do you use the highest architecture level possible for all environments in which your programs will run? For example, if the lowest level architecture you have including your disaster recovery machines is z10, are you using ARCH(8)?	
AWO	Do you use the AWO option when possible?	
BLOCK0	Do you use BLOCK0 for QSAM files?	
DATA	When you use QSAM striped data sets, do you use the RENT and DATA(31) options? Is the program object AMODE 31? Are you running with ALL31(ON)?	
DYNAM	Can you use NODYNAM? Consider the performance tradeoffs.	
FASTSORT	When you use direct work files for the sort work files, did you use the FASTSORT option?	

Table 91. **Performance-tuning worksheet** (continued)

Compiler option	Consideration	Yes?
NUMPROC	Do you use NUMPROC (PFD) when possible?	
OPTIMIZE	Do you use a non-zero OPTIMIZE level for production runs?	
SSRANGE	Do you use NOSSRANGE for production runs?	
TEST	Do you use NOTEST or TEST (NOEJPD) for production runs?	
TRUNC	Do you use TRUNC (OPT) when possible?	
ZONEDATA	Do you use ZONEDATA (PFD) when possible?	

**related concepts**

[“Storage and its addressability” on page 37](#)

**related tasks**

[“Choosing compiler features to enhance performance” on page 639](#)

**related references**

[“Performance-related compiler options” on page 640](#)

## Running efficiently with CICS, IMS, or VSAM

You can improve performance for online programs running under CICS or IMS, or programs that use VSAM, by following these tips.

**CICS:** If your application runs under CICS, convert EXEC CICS LINK commands to COBOL CALL statements to improve transaction response time.

**IMS:** If your application runs under IMS, preloading the application program and the library routines can help reduce the overhead of loading and searching. It can also reduce the input-output activity.

For better system performance, use the RENT compiler option and preload the applications and library routines when possible. You can also use the Language Environment library routine retention (LRR) function to improve performance in IMS/TM regions.

**VSAM:** When you use VSAM files, increase the number of data buffers for sequential access or index buffers for random access. Also, select a control interval size (CISZ) that is appropriate for the application. A smaller CISZ results in faster retrieval for random processing at the expense of inserts. A larger CISZ is more efficient for sequential processing.

For better performance, access the records sequentially and avoid using multiple alternate indexes when possible. If you use alternate indexes, access method services builds them more efficiently than the AIXBLD runtime option.

**related tasks**

[“Coding COBOL programs to run under CICS” on page 407](#)

[Chapter 22, “Developing COBOL programs for IMS,” on page 427](#)

[“Improving VSAM performance” on page 195](#)

*Language Environment Customization*

**related references**

*Language Environment Programming Guide* (Specifying runtime options)

## Choosing static or dynamic calls

---

If you can arrange your modules, and the programs that frequently call each other are in one module, static calls are faster than dynamic calls.

For more information, see [“Performance considerations of static and dynamic calls” on page 456](#).

### **related concepts**

[“Performance considerations of static and dynamic calls” on page 456](#)



---

## Chapter 38. Simplifying coding

You can use coding techniques to improve your productivity. By using the COPY statement, the format 2 SORT statement, COBOL intrinsic functions, and Language Environment callable services, you can avoid repetitive coding and having to code many arithmetic calculations or other complex tasks.

If your program contains frequently used code sequences (such as blocks of common data items, input-output routines, error routines, or even entire COBOL programs), write the code sequences once and put them in a COBOL copy library. You can use the COPY statement to retrieve these code sequences and have them included in your program at compile time. Using copybooks in this manner eliminates repetitive coding.

To sort a table, you can use the format 2 SORT statement to simplify coding. It provides a much simpler way compared to the format 1 SORT statement.

COBOL provides various capabilities for manipulating strings and numbers. These capabilities can help you simplify your coding.

The Language Environment date and time callable services store dates as fullword binary integers and store time stamps as long (64-bit) floating-point values. These formats let you do arithmetic calculations on date and time values simply and efficiently. You do not need to write special subroutines that use services outside the language library to perform such calculations.

### related tasks

[“Using numeric intrinsic functions” on page 54](#)

[“Using math-oriented callable services” on page 56](#)

[“Using date callable services” on page 57](#)

[“Eliminating repetitive coding” on page 647](#)

[“Converting data items \(intrinsic functions\)” on page 111](#)

[“Evaluating data items \(intrinsic functions\)” on page 114](#)

[“Using Language Environment callable services” on page 649](#)

### related references

[“Using the format 2 SORT statement to sort a table” on page 652](#)

---

## Eliminating repetitive coding

To include stored source statements in a program, use the COPY statement in any program division and at any code sequence level. You can nest COPY statements to any depth.

To specify more than one copy library, use either multiple system definitions or a combination of multiple definitions and the IN/OF phrase (IN/OF *library-name*):

### MVS batch

Use JCL to concatenate data sets in your SYSLIB DD statement. Alternatively, define multiple DD statements and use the IN/OF phrase of the COPY statement.

### TSO

Use the ALLOCATE command to concatenate data sets for SYSLIB. Alternatively, issue multiple ALLOCATE statements and use the IN/OF phrase of the COPY statement.

### z/OS UNIX

Use the SYSLIB environment variable to define multiple paths to your copybooks. Alternatively, use multiple environment variables and use the IN/OF phrase of the COPY statement.

For example:

```
COPY MEMBER1 OF COPYLIB
```

If you omit this qualifying phrase, the default is SYSLIB.

**COPY and debugging line:** In order for the text copied to be treated as debug lines, for example, as if there were a D inserted in column 7, put the D on the first line of the COPY statement. A COPY statement cannot itself be a debugging line; if it contains a D, and WITH DEBUGGING mode is not specified, the COPY statement is nevertheless processed.

[“Example: using the COPY statement” on page 648](#)

#### related references

[Chapter 18, “Compiler-directing statements,” on page 357](#)

## Example: using the COPY statement

These examples show how you can use the COPY statement to include library text in a program.

Suppose the library entry CFILEA consists of the following FD entries:

```
BLOCK CONTAINS 20 RECORDS
RECORD CONTAINS 120 CHARACTERS
LABEL RECORDS ARE STANDARD
DATA RECORD IS FILE-OUT.
01 FILE-OUT      PIC X(120).
```

You can retrieve the text-name CFILEA by using the COPY statement in a source program as follows:

```
FD FILEA
    COPY CFILEA.
```

The library entry is copied into your program, and the resulting program listing looks like this:

```
FD FILEA
    COPY CFILEA.
C   BLOCK CONTAINS 20 RECORDS
C   RECORD CONTAINS 120 CHARACTERS
C   LABEL RECORDS ARE STANDARD
C   DATA RECORD IS FILE-OUT.
C   01 FILE-OUT      PIC X(120).
```

In the compiler source listing, the COPY statement prints on a separate line. C precedes copied lines.

Assume that a copybook with the text-name DOWORK is stored by using the following statements:

```
COMPUTE QTY-ON-HAND = TOTAL-USED-NUMBER-ON-HAND
MOVE QTY-ON-HAND to PRINT-AREA
```

To retrieve the copybook identified as DOWORK, code:

```
paragraph-name.
    COPY DOWORK.
```

The statements that are in the DOWORK procedure will follow *paragraph-name*.

If you use the EXIT compiler option to provide a LIBEXIT module, your results might differ from those shown here.

**Note:** To save compile time, you might group related items in a copybook, but not necessarily have a single large copybook with unrelated items in it.

#### related tasks

[“Eliminating repetitive coding” on page 647](#)

#### related references

[Chapter 18, “Compiler-directing statements,” on page 357](#)

## Using Language Environment callable services

---

Language Environment callable services make many types of programming tasks easier. You call them by using the CALL statement.

Language Environment services help you with the following tasks:

- Handling conditions

The Language Environment condition-handling facilities enable COBOL applications to react to unexpected errors. You can use language constructs or runtime options to select the level at which to handle each condition. For example, you can handle a particular error in your COBOL program, let Language Environment take care of it, or have the operating system handle it.

In support of Language Environment condition handling, COBOL provides procedure-pointer data items.

- Managing dynamic storage

These services enable you to get, free, and reallocate storage. You can also create your own storage pools.

- Calculating dates and times

If you use the date and time services, you can get the current local time and date in several formats, and perform date and time conversions. Two callable services, CEEQCEN and CEESCEN, provide a predictable way to handle two-digit years, such as 91 for 1991 or 09 for 2009.

- Making math calculations

Calculations that are easy to perform with mathematical callable services include logarithmic, exponential, trigonometric, square root, and integer functions.

COBOL also supports a set of intrinsic functions that include some of the same mathematical and date functions as those provided by the callable services. The Language Environment callable services and intrinsic functions provide equivalent results, with a few exceptions. You should be familiar with these differences before deciding which to use.

- Handling messages

Message-handling services include services for getting, dispatching, and formatting messages. Messages for non-CICS applications can be directed to files or printers. CICS messages are directed to a CICS transient data queue. Language Environment splits messages to accommodate the record length of the destination, and presents messages in the correct national language such as Japanese or English.

- Supporting national languages

These services make it easy for your applications to support the language that application users want. You can set the language and country, and obtain default date, time, number, and currency formats. For example, you might want dates to appear as 23 June 09 or as 6,23,09.

- General services such as starting Debug Tool and obtaining a Language Environment formatted dump

Debug Tool provides advanced debugging functions for COBOL applications, including both batch and interactive debugging of CICS programs. Debug Tool enables you to debug a COBOL application from the host or, in conjunction with the Debug Perspective of IBM Developer for z/OS, from a Windows-based workstation.

Depending on the options that you select, the Language Environment formatted dump might contain the names and values of data items, and information about conditions, program tracebacks, control blocks, storage, and files. All Language Environment dumps have a common, well-labeled, easy-to-read format.

[“Example: Language Environment callable services” on page 651](#)

### **related concepts**

[“Sample list of Language Environment callable services” on page 650](#)

**related tasks**

[“Using numeric intrinsic functions” on page 54](#)

[“Using math-oriented callable services” on page 56](#)

[“Using date callable services” on page 57](#)

[“Calling Language Environment services” on page 651](#)

[“Using procedure and function pointers” on page 461](#)

**Sample list of Language Environment callable services**

The following table shows some examples of the callable services that are available with Language Environment. Many more services are available than those listed.

<i>Table 92. Language Environment callable services</i>		
<b>Function type</b>	<b>Service</b>	<b>Purpose</b>
Condition handling	CEEHDLR	To register a user condition handler
	CEESGL	To raise or signal a condition
	CEEMRCR	To indicate where the program will resume running after the condition handler has finished
Dynamic storage	CEEGTST	To get storage
	CEECZST	To change the size of a previously allocated storage block
	CEEFRST	To free storage
Date and time	CEECBLDY	To convert a string that represents a date into COBOL integer date format, which represents a date as the number of days since 31 December 1600
	CEEQCEN, CEESCEN	To query and set the Language Environment century window, which is valuable when a program uses two digits to express a year
	CEEGMTO	To calculate the difference between the local system time and Greenwich Mean Time
	CEELOCT	To get the current local time in your choice of three formats
Math	CEESIABS	To calculate the absolute value of an integer
	CEESSNWN	To calculate the nearest whole number for a single-precision floating-point number
	CEESSCOS	To calculate the cosine of an angle
Message handling	CEEMOUT	To dispatch a message
	CEEMGET	To retrieve a message
National language support	CEE3LNG	To change or query the current national language
	CEE3CTY	To change or query the current national country
	CEE3MCS	To obtain the default currency symbol for a given country
General	CEE3DMP	To obtain a Language Environment formatted dump
	CEETEST	To start a debugging tool, such as Debug Tool

**related references**

*Language Environment Programming Reference*

## Calling Language Environment services

To invoke a Language Environment service, use a CALL statement with the correct parameters for that service. Define the variables for the CALL statement in the DATA DIVISION with the definitions that are required by that service.

```
77 argument      comp-1.
77 feedback-code pic x(12) display.
77 result        comp-1.

CALL "CEESSSQT" using argument, feedback-code, result
```

In the example above, Language Environment service CEESSSQT calculates the value of the square root of the variable `argument` and returns this value in the variable `result`.

You can choose whether to specify the feedback code parameter. If you specify it, the value returned in `feedback-code` indicates whether the service completed successfully. If you specify OMITTED instead of the feedback code, and the service is not successful, a Language Environment condition is automatically signaled to the Language Environment condition manager. You can handle such a condition by recovery logic implemented in a user-written condition handler, or let the default Language Environment processing for unhandled conditions occur. In either case, you avoid having to write logic to check the feedback code explicitly after each call.

If you call a Language Environment callable service and specify OMITTED for the feedback code, the RETURN-CODE special register is set to 0 if the service is successful. It is not altered if the service is unsuccessful. If you do not specify OMITTED for the feedback code, the RETURN-CODE special register is always set to 0 regardless of whether the service completed successfully.

[“Example: Language Environment callable services” on page 651](#)

### related concepts

*Language Environment Programming Guide* (General callable services)

### related references

*Language Environment Programming Reference* (General callable services)

CALL statement (*Enterprise COBOL for z/OS Language Reference*)

## Example: Language Environment callable services

This example shows a COBOL program that uses the Language Environment services CEEDAYS and CEEDATE to format and display a date from the results of a COBOL ACCEPT statement.

Using CEEDAYS and CEEDATE reduces the coding that would be required without Language Environment.

```
ID DIVISION.
PROGRAM-ID. HOHOHO.
*****
* FUNCTION:  DISPLAY TODAY'S DATE IN THE FOLLOWING FORMAT: *
*           WWWWWWWWW, MMMMMMM DD, YYYY                  *
*           For example: TUESDAY, SEPTEMBER 15, 2009      *
*           *****
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01  CHRDATE.
    05 CHRDATE-LENGTH    PIC S9(4) COMP VALUE 10.
    05 CHRDATE-STRING    PIC X(10).
01  PICSTR.
    05 PICSTR-LENGTH     PIC S9(4) COMP.
    05 PICSTR-STRING     PIC X(80).
*
77  LILIAN PIC            S9(9) COMP.
77  FORMATTED-DATE       PIC X(80).
*
PROCEDURE DIVISION.
*****
```

```

*   USE LANGUAGE ENVIRONMENT CALLABLE SERVICES TO PRINT OUT *
*   TODAY'S DATE FROM COBOL ACCEPT STATEMENT. *
*****
ACCEPT CHRDATE-STRING FROM DATE.

*
MOVE "YYMMDD" TO PICSTR-STRING.
MOVE 6 TO PICSTR-LENGTH.
CALL "CEEDAYS" USING CHRDATE , PICSTR , LILIAN , OMITTED.

*
MOVE " WWWWWWWWZ, MMMMMMMZ DD, YYYY " TO PICSTR-STRING.
MOVE 50 TO PICSTR-LENGTH.
CALL "CEEDATE" USING LILIAN , PICSTR , FORMATTED-DATE ,
    OMITTED.

*
DISPLAY "*****".
DISPLAY FORMATTED-DATE.
DISPLAY "*****".

*
STOP RUN.

```

## Using the format 2 SORT statement to sort a table

It is recommended to use the format 2 SORT statement to sort a table. It provides the following benefits when compared to the format 1 SORT statement.

<i>Table 93. Comparison of format 1 and format 2 SORT statements</i>		
<b>Characteristics</b>	<b>Format 1 SORT statements</b>	<b>Format 2 SORT statements</b>
Can be used to sort a file or a table	Yes	No, it is for tables only
Requires DFSORT or equivalent sorting program	Yes	No
Supported in CICS	Limited	Yes
Supported in UNIX System Services	No	Yes
Supported in programs that are compiled with the THREAD option	No	Yes
Table can be sorted by using a single SORT statement, which simplifies coding	No, it requires the SELECT clauses, SD entries with record descriptions, and input and output procedures	Yes
Keys for sorting can be specified as part of the table definition, which can also be used in the SEARCH ALL statement	No, keys must be specified in the SORT statement. If the table is to be searched by using SEARCH ALL as well, the keys must also be redundantly specified as part of the table definition.	Yes, and it also supports specifying keys in the SORT statement if needed
Can filter or preprocess table elements during the sorting process	Yes, using input and output procedures	No, all of the table elements are passed to SORT as-is
Uses special registers that include SORT-CONTROL, SORT-CORE-SIZE, SORT-FILE-SIZE, SORT-MESSAGE, SORT-MODE-SIZE, and SORT-RETURN	Yes	No
Can be executed within the range of an input or output procedure	No	Yes

**Note:** Do not use the format 2 SORT with large tables in an environment where storage is constrained, because the format 2 SORT uses heap storage to do the sort.

**related references**

SORT statement (*Enterprise COBOL for z/OS Language Reference*)



---

## Appendix A. Intermediate results and arithmetic precision

The compiler handles arithmetic statements as a succession of operations performed according to operator precedence, and sets up intermediate fields to contain the results of those operations. The compiler uses algorithms to determine the number of integer and decimal places to reserve.

Intermediate results are possible in the following cases:

- In an ADD or SUBTRACT statement that contains more than one operand immediately after the verb
- In a COMPUTE statement that specifies a series of arithmetic operations or multiple result fields
- In an arithmetic expression contained in a conditional statement or in a reference-modification specification
- In an ADD, SUBTRACT, MULTIPLY, or DIVIDE statement that uses the GIVING option and multiple result fields
- In a statement that uses an intrinsic function as an operand
- In a statement that contains the ROUNDED phrase

[“Example: calculation of intermediate results” on page 656](#)

The precision of intermediate results depends on whether you compile using the default option ARITH(COMPAT) (referred to as *compatibility mode*) or using ARITH(EXTEND) (referred to as *extended mode*).

In compatibility mode, evaluation of arithmetic operations is unchanged from that in releases of IBM COBOL before COBOL for OS/390 & VM Version 2 Release 2:

- A maximum of 30 digits is used for fixed-point intermediate results.
- Floating-point intrinsic functions return long-precision (64-bit) floating-point results.
- Expressions that contain floating-point operands, fractional exponents, or floating-point intrinsic functions are evaluated as if all operands that are not in floating point are converted to long-precision floating point and floating-point operations are used to evaluate the expression.
- Floating-point literals and external floating-point data items are converted to long-precision floating point for processing.

In extended mode, evaluation of arithmetic operations has the following characteristics:

- A maximum of 31 digits is used for fixed-point intermediate results.
- Floating-point intrinsic functions return extended-precision (128-bit) floating-point results.
- Expressions that contain floating-point operands, fractional exponents, or floating-point intrinsic functions are evaluated as if all operands that are not in floating point are converted to extended-precision floating point and floating-point operations are used to evaluate the expression.
- Floating-point literals and external floating-point data items are converted to extended-precision floating point for processing.

### related concepts

[“Formats for numeric data” on page 45](#)

[“Fixed-point contrasted with floating-point arithmetic” on page 59](#)

### related references

[“Fixed-point data and intermediate results” on page 657](#)

[“Floating-point data and intermediate results” on page 662](#)

[“Arithmetic expressions in nonarithmetic statements” on page 663](#)

[“ARITH” on page 291](#)

## Terminology used for intermediate results

---

To understand this information about intermediate results, you need to understand the following terminology.

***i***

The number of integer places carried for an intermediate result. (If you use the **ROUNDED** phrase, one more integer place might be carried for accuracy if necessary.)

***d***

The number of decimal places carried for an intermediate result. (If you use the **ROUNDED** phrase, one more decimal place might be carried for accuracy if necessary.)

***dmax***

In a particular statement, the largest of the following items:

- The number of decimal places needed for the final result field or fields
- The maximum number of decimal places defined for any operand, except divisors or exponents
- The *outer-dmax* for any function operand

***inner-dmax***

In reference to a function, the largest of the following items:

- The number of decimal places defined for any of its elementary arguments
- The *dmax* for any of its arithmetic expression arguments
- The *outer-dmax* for any of its embedded functions

***outer-dmax***

The number of decimal places that a function result contributes to operations outside of its own evaluation (for example, if the function is an operand in an arithmetic expression, or an argument to another function).

***op1***

The first operand in a generated arithmetic statement (in division, the divisor).

***op2***

The second operand in a generated arithmetic statement (in division, the dividend).

***i1 , i2***

The number of integer places in *op1* and *op2*, respectively.

***d1 , d2***

The number of decimal places in *op1* and *op2*, respectively.

***ir***

The intermediate result when a generated arithmetic statement or operation is performed. (Intermediate results are generated either in registers or storage locations.)

***ir1 , ir2***

Successive intermediate results. (Successive intermediate results might have the same storage location.)

**related references**

**ROUNDED** phrase (*Enterprise COBOL for z/OS Language Reference*)

## Example: calculation of intermediate results

---

The following example shows how the compiler performs an arithmetic statement as a succession of operations, storing intermediate results as needed.

```
COMPUTE Y = A + B * C - D / E + F ** G
```

The result is calculated in the following order:

1. Exponentiate F by G yielding *ir1*.
2. Multiply B by C yielding *ir2*.
3. Divide E into D yielding *ir3*.
4. Add A to *ir2* yielding *ir4*.
5. Subtract *ir3* from *ir4* yielding *ir5*.
6. Add *ir5* to *ir1* yielding Y.

#### related tasks

[“Using arithmetic expressions” on page 54](#)

#### related references

[“Terminology used for intermediate results” on page 656](#)

## Fixed-point data and intermediate results

The compiler determines the number of integer and decimal places in an intermediate result.

### Addition, subtraction, multiplication, and division

The following table shows the precision theoretically possible as the result of addition, subtraction, multiplication, or division.

Operation	Integer places	Decimal places
+ or -	$(i1 \text{ or } i2) + 1$ , whichever is greater	$d1$ or $d2$ , whichever is greater
*	$i1 + i2$	$d1 + d2$
/	$i2 + d1$	$(d2 - d1)$ or $dmax$ , whichever is greater

You must define the operands of any arithmetic statements with enough decimal places to obtain the accuracy you want in the final result.

The following table shows the number of places the compiler carries for fixed-point intermediate results of arithmetic operations that involve addition, subtraction, multiplication, or division in *compatibility mode* (that is, when the default compiler option ARITH (COMPAT) is in effect):

Value of $i + d$	Value of $d$	Value of $i + dmax$	Number of places carried for $ir$
<30 or =30	Any value	Any value	$i$ integer and $d$ decimal places
>30	< $dmax$ or = $dmax$	Any value	$30 - d$ integer and $d$ decimal places
		<30 or =30	$i$ integer and $30 - i$ decimal places
		>30	$30 - dmax$ integer and $dmax$ decimal places

The following table shows the number of places the compiler carries for fixed-point intermediate results of arithmetic operations that involve addition, subtraction, multiplication, or division in *extended mode* (that is, when the compiler option ARITH (EXTEND) is in effect):

Value of $i + d$	Value of $d$	Value of $i + dmax$	Number of places carried for $ir$
<31 or =31	Any value	Any value	$i$ integer and $d$ decimal places

Value of $i + d$	Value of $d$	Value of $i + d_{max}$	Number of places carried for $ir$
>31	< $d_{max}$ or $=d_{max}$	Any value	31- $d$ integer and $d$ decimal places
	> $d_{max}$	<31 or $=31$	$i$ integer and 31- $i$ decimal places
		>31	31- $d_{max}$ integer and $d_{max}$ decimal places

## Exponentiation

Exponentiation is represented by the expression  $op1 ** op2$ . Based on the characteristics of  $op2$ , the compiler handles exponentiation of fixed-point numbers in one of three ways:

- When  $op2$  is expressed with decimals, floating-point instructions are used.
- When  $op2$  is an integral literal or constant, the value  $d$  is computed as

$$d = d1 * |op2|$$

and the value  $i$  is computed based on the characteristics of  $op1$ :

- When  $op1$  is a data-name or variable,

$$i = i1 * |op2|$$

- When  $op1$  is a literal or constant,  $i$  is set equal to the number of integers in the value of  $op1 ** |op2|$ .

In compatibility mode (compilation using ARITH(COMPAT)), the compiler having calculated  $i$  and  $d$  takes the action indicated in the table below to handle the intermediate results  $ir$  of the exponentiation.

Value of $i + d$	Other conditions	Action taken
<30	Any	$i$ integer and $d$ decimal places are carried for $ir$ .
$=30$	$op1$ has an odd number of digits.	$i$ integer and $d$ decimal places are carried for $ir$ .
	$op1$ has an even number of digits.	Same action as when $op2$ is an integral data-name or variable (shown below). Exception: for a 30-digit integer raised to the power of literal 1, $i$ integer and $d$ decimal places are carried for $ir$ .
>30	Any	Same action as when $op2$ is an integral data-name or variable (shown below)

In extended mode (compilation using ARITH(EXTEND)), the compiler having calculated  $i$  and  $d$  takes the action indicated in the table below to handle the intermediate results  $ir$  of the exponentiation.

Value of $i + d$	Other conditions	Action taken
<31	Any	$i$ integer and $d$ decimal places are carried for $ir$ .
$=31$ or $>31$	Any	Same action as when $op2$ is an integral data-name or variable (shown below). Exception: for a 31-digit integer raised to the power of literal 1, $i$ integer and $d$ decimal places are carried for $ir$ .

If  $op2$  is negative, the value of 1 is then divided by the result produced by the preliminary computation. The values of  $i$  and  $d$  that are used are calculated following the division rules for fixed-point data already shown above.

- When *op2* is an integral data-name or variable, *dmax* decimal places and 30-*dmax* (compatibility mode) or 31-*dmax* (extended mode) integer places are used. *op1* is multiplied by itself ( $|op2| - 1$ ) times for nonzero *op2*.

If *op2* is equal to 0, the result is 1. Division-by-0 and exponentiation SIZE ERROR conditions apply.

Fixed-point exponents with more than nine significant digits are always truncated to nine digits. If the exponent is a literal or constant, an E-level compiler diagnostic message is issued; otherwise, an informational message is issued at run time.

[“Example: exponentiation in fixed-point arithmetic” on page 659](#)

#### related references

[“Terminology used for intermediate results” on page 656](#)

[“Truncated intermediate results” on page 659](#)

[“Binary data and intermediate results” on page 660](#)

[“Floating-point data and intermediate results” on page 662](#)

[“Intrinsic functions evaluated in fixed-point arithmetic” on page 660](#)

[“ARITH” on page 291](#)

SIZE ERROR phrases (*Enterprise COBOL for z/OS Language Reference*)

## Example: exponentiation in fixed-point arithmetic

The following example shows how the compiler performs an exponentiation to a nonzero integer power as a succession of multiplications, storing intermediate results as needed.

```
COMPUTE Y = A ** B
```

If B is equal to 4, the result is computed as shown below. The values of *i* and *d* that are used are calculated according to the multiplication rules for fixed-point data and intermediate results (referred to below).

1. Multiply A by A yielding an internal intermediate result *iir1*.
2. Multiply *iir1* by A yielding an internal intermediate result *iir2*.
3. Multiply *iir2* by A yielding an internal intermediate result *iir3*.
4. Move *iir3* to *ir4*.

*ir4* has *dmax* decimal places. Because B is positive, *ir4* is moved to Y. If B were equal to -4, however, an additional fifth step would be performed:

5. Divide *ir4* into 1 yielding *ir5*.

*ir5* has *dmax* decimal places, and would then be moved to Y.

**Note:** The internal intermediate results (*iir1*, *iir2*, and *iir3*) obtained by the internal library routine performing the exponential calculation in steps 1, 2, and 3 above do not use the same decimal precision as *ir4* and *ir5* above. Instead, those intermediate results are much more precise, ensuring the most accurate result possible in *ir4* or *ir5*.

#### related references

[“Terminology used for intermediate results” on page 656](#)

[“Fixed-point data and intermediate results” on page 657](#)

## Truncated intermediate results

Whenever the number of digits in an intermediate result exceeds 30 in compatibility mode or 31 in extended mode, the compiler truncates to 30 (compatibility mode) or 31 (extended mode) digits and issues a warning. If truncation occurs at run time, a message is issued and the program continues running.

If you want to avoid the truncation of intermediate results that can occur in fixed-point calculations, use floating-point operands (COMP - 1 or COMP - 2) instead.

**related concepts**

[“Formats for numeric data” on page 45](#)

**related references**

[“Fixed-point data and intermediate results” on page 657](#)

[“ARITH” on page 291](#)

## Binary data and intermediate results

If an operation that involves binary operands requires intermediate results longer than 18 digits, the compiler converts the operands to internal decimal before performing the operation. If the result field is binary, the compiler converts the result from internal decimal to binary.

Binary operands are most efficient when intermediate results will not exceed nine digits.

**related references**

[“Fixed-point data and intermediate results” on page 657](#)

[“ARITH” on page 291](#)

## Intrinsic functions evaluated in fixed-point arithmetic

The compiler determines the *inner-dmax* and *outer-dmax* values for an intrinsic function from the characteristics of the function.

## Integer functions

Integer intrinsic functions return an integer; thus their *outer-dmax* is always zero. For those integer functions whose arguments must all be integers, the *inner-dmax* is thus also always zero.

The following table summarizes the *inner-dmax* and the precision of the function result.

Function	Inner-dmax	Digit precision of function result
DATE - OF - INTEGER	0	8
DATE - TO - YYYYMMDD	0	8
DAY - OF - INTEGER	0	7
DAY - TO - YYYYDDD	0	7
FACTORIAL	0	30 in compatibility mode, 31 in extended mode
INTEGER - OF - DATE	0	7
INTEGER - OF - DAY	0	7
LENGTH	n/a	9
MOD	0	min( <i>i1 i2</i> )
ORD	n/a	3
ORD - MAX		9
ORD - MIN		9
YEAR - TO - YYYY	0	4

Function	Inner-dmax	Digit precision of function result
INTEGER		For a fixed-point argument: one more digit than in the argument. For a floating-point argument: 30 in compatibility mode, 31 in extended mode.
INTEGER-PART		For a fixed-point argument: same number of digits as in the argument. For a floating-point argument: 30 in compatibility mode, 31 in extended mode.

## Mixed functions

A *mixed* intrinsic function is a function whose result type depends on the type of its arguments. A mixed function is fixed point if all of its arguments are numeric and none of its arguments is floating point. (If any argument of a mixed function is floating point, the function is evaluated with floating-point instructions and returns a floating-point result.) When a mixed function is evaluated with fixed-point arithmetic, the result is integer if all of the arguments are integer; otherwise, the result is fixed point.

For the mixed functions MAX, MIN, RANGE, REM, and SUM, the *outer-dmax* is always equal to the *inner-dmax* (and both are thus zero if all the arguments are integer). To determine the precision of the result returned for these functions, apply the rules for fixed-point arithmetic and intermediate results (as referred to below) to each step in the algorithm.

### MAX

1. Assign the first argument to the function result.
2. For each remaining argument, do the following steps:
  - a. Compare the algebraic value of the function result with the argument.
  - b. Assign the greater of the two to the function result.

### MIN

1. Assign the first argument to the function result.
2. For each remaining argument, do the following steps:
  - a. Compare the algebraic value of the function result with the argument.
  - b. Assign the lesser of the two to the function result.

### RANGE

1. Use the steps for MAX to select the maximum argument.
2. Use the steps for MIN to select the minimum argument.
3. Subtract the minimum argument from the maximum.
4. Assign the difference to the function result.

### REM

1. Divide argument one by argument two.
2. Remove all noninteger digits from the result of step 1.
3. Multiply the result of step 2 by argument two.
4. Subtract the result of step 3 from argument one.
5. Assign the difference to the function result.

### SUM

1. Assign the value 0 to the function result.
2. For each argument, do the following steps:
  - a. Add the argument to the function result.
  - b. Assign the sum to the function result.

### related references

[“Terminology used for intermediate results” on page 656](#)

[“Fixed-point data and intermediate results” on page 657](#)

[“Floating-point data and intermediate results” on page 662](#)

[“ARITH” on page 291](#)

## Floating-point data and intermediate results

---

If any operation in an arithmetic expression is computed in floating-point arithmetic, the entire expression is computed as if all operands were converted to floating point and the operations were performed using floating-point instructions.

Floating-point instructions are used to compute an arithmetic expression if any of the following conditions is true of the expression:

- A receiver or operand is COMP-1, COMP-2, external floating point, or a floating-point literal.
- An exponent contains decimal places.
- An exponent is an expression that contains an exponentiation or division operator, and *dmax* is greater than zero.
- An intrinsic function is a floating-point function.

In compatibility mode, if an expression is computed in floating-point arithmetic, the precision used to evaluate the arithmetic operations is determined as follows:

- Single precision is used if all receivers and operands are COMP-1 data items and the expression contains no multiplication or exponentiation operations.
- In all other cases, long precision is used.

Whenever long-precision floating point is used for one operation in an arithmetic expression, all operations in the expression are computed as if long floating-point instructions were used.

In extended mode, if an expression is computed in floating-point arithmetic, the precision used to evaluate the arithmetic operations is determined as follows:

- Single precision is used if all receivers and operands are COMP-1 data items and the expression contains no multiplication or exponentiation operations.
- Long precision is used if all receivers and operands are COMP-1 or COMP-2 data items, at least one receiver or operand is a COMP-2 data item, and the expression contains no multiplication or exponentiation operations.
- In all other cases, extended precision is used.

Whenever extended-precision floating point is used for one operation in an arithmetic expression, all operations in the expression are computed as if extended-precision floating-point instructions were used.

**Alert:** If a floating-point operation has an intermediate result field in which exponent overflow occurs, the job is abnormally terminated.

## Exponentiations evaluated in floating-point arithmetic

In compatibility mode, floating-point exponentiations are always evaluated using long floating-point arithmetic. In extended mode, floating-point exponentiations are always evaluated using extended-precision floating-point arithmetic.

The value of a negative number raised to a fractional power is undefined in COBOL. For example,  $(-2)^{**3}$  is equal to -8, but  $(-2)^{** (3.000001)}$  is undefined. When an exponentiation is evaluated in floating point and there is a possibility that the result is undefined, the exponent is evaluated at run time to determine if it has an integral value. If not, a diagnostic message is issued.

## Intrinsic functions evaluated in floating-point arithmetic

In compatibility mode, floating-point intrinsic functions always return a long (64-bit) floating-point value. In extended mode, floating-point intrinsic functions always return an extended-precision (128-bit) floating-point value.

Mixed functions that have at least one floating-point argument are evaluated using floating-point arithmetic.

### related references

[“Terminology used for intermediate results” on page 656](#)

[“ARITH” on page 291](#)

## Arithmetic expressions in nonarithmetic statements

Arithmetic expressions can appear in contexts other than arithmetic statements. For example, you can use an arithmetic expression with the IF or EVALUATE statement.

In such statements, the rules for intermediate results with fixed-point data and for intermediate results with floating-point data apply, with the following changes:

- Abbreviated IF statements are handled as though the statements were not abbreviated.
- In an explicit relation condition where at least one of the comparands is an arithmetic expression, *dmax* is the maximum number of decimal places for any operand of either comparand, excluding divisors and exponents. The rules for floating-point arithmetic apply if any of the following conditions is true:
  - Any operand in either comparand is COMP -1, COMP -2, external floating point, or a floating-point literal.
  - An exponent contains decimal places.
  - An exponent is an expression that contains an exponentiation or division operator, and *dmax* is greater than zero.

For example:

```
IF operand-1 = expression-1 THEN . . .
```

If *operand-1* is a data-name defined to be COMP -2, the rules for floating-point arithmetic apply to *expression-1* even if it contains only fixed-point operands, because it is being compared to a floating-point operand.

- When the comparison between an arithmetic expression and another data item or arithmetic expression does not use a relational operator (that is, there is no explicit relation condition), the arithmetic expression is evaluated without regard to the attributes of its comparand. For example:

```
EVALUATE expression-1  
  WHEN expression-2 THRU expression-3  
  WHEN expression-4  
END-EVALUATE
```

In the statement above, each arithmetic expression is evaluated in fixed-point or floating-point arithmetic based on its own characteristics.

### related concepts

[“Fixed-point contrasted with floating-point arithmetic” on page 59](#)

### related references

[“Terminology used for intermediate results” on page 656](#)

[“Fixed-point data and intermediate results” on page 657](#)

[“Floating-point data and intermediate results” on page 662](#)

IF statement (*Enterprise COBOL for z/OS Language Reference*)

EVALUATE statement (*Enterprise COBOL for z/OS Language Reference*)  
Conditional expressions (*Enterprise COBOL for z/OS Language Reference*)

---

## Appendix B. Converting double-byte character set (DBCS) data

The Language Environment service routines IGZCA2D and IGZCD2A were intended for converting alphanumeric data items that contain DBCS data to and from pure DBCS data items in order to reliably perform operations such as STRING, UNSTRING, and reference modification.

These service routines continue to be provided for compatibility; however, using national data items and the national conversion operations is now recommended instead for this purpose.

The service routines do not support a code-page argument and are not sensitive to the code page specified by the CODEPAGE compiler option. The DBCS compiler option does not affect their operation.

### related tasks

[“Converting to or from national \(Unicode\) representation” on page 131](#)

[“Processing alphanumeric data items that contain DBCS data” on page 144](#)

### related references

[“DBCS notation” on page 665](#)

[“Alphanumeric to DBCS data conversion \(IGZCA2D\)” on page 665](#)

[“DBCS to alphanumeric data conversion \(IGZCD2A\)” on page 667](#)

[“CODEPAGE” on page 295](#)

---

## DBCS notation

The symbols shown below are used in the DBCS data conversion examples to describe DBCS items.

Symbols	Meaning
< and >	Shift-out (SO) and shift-in (SI), respectively
D0, D1, D2, . . . , Dn	Any DBCS character except for double-byte EBCDIC characters that correspond to single-byte EBCDIC characters
.A, .B, .C, . . .	Any double-byte EBCDIC character that corresponds to a single-byte EBCDIC character. The period (.) represents the value X'42'.
A single letter, such as A, B, or s	Any single-byte EBCDIC character

---

## Alphanumeric to DBCS data conversion (IGZCA2D)

The Language Environment IGZCA2D service routine converts alphanumeric data that contains double-byte characters to pure DBCS data.

### IGZCA2D syntax

To use the IGZCA2D service routine, pass the following four parameters to the routine by using the CALL statement:

#### ***parameter-1***

The sending field for the conversion, handled as an alphanumeric data item.

#### ***parameter-2***

The receiving field for the conversion, handled as a DBCS data item.

You cannot use reference modification with *parameter-2*.

### ***parameter-3***

The number of bytes in *parameter-1* to be converted.

It can be the LENGTH OF special register of *parameter-1*, or a 4-byte USAGE IS BINARY data item containing the number of bytes of *parameter-1* to be converted. Shift codes count as 1 byte each.

### ***parameter-4***

The number of bytes in *parameter-2* that will receive the converted data.

It can be the LENGTH OF special register of *parameter-2*, or a 4-byte USAGE IS BINARY data item containing the number of bytes of *parameter-2* to receive the converted data.

### **Usage notes**

- You can pass *parameter-1*, *parameter-3*, and *parameter-4* to the routine BY REFERENCE or BY CONTENT, but you must pass *parameter-2* BY REFERENCE.
- The compiler does not perform syntax checking on these parameters. Ensure that the parameters are correctly set and passed in the CALL statement to the conversion routine. Otherwise, results are unpredictable.
- When creating *parameter-2* from *parameter-1*, IGZCA2D makes these changes:
  - Removes the shift codes, leaving the DBCS data unchanged
  - Converts the single-byte (nonspace) EBCDIC character X'nn' to a character represented by X'42nn'
  - Converts the single-byte space (X'40') to DBCS space (X'4040'), instead of X'4240'
- IGZCA2D does not change the contents of *parameter-1*, *parameter-3*, or *parameter-4*.
- The valid range for the contents of *parameter-3* and for the contents of *parameter-4* is 1 to 134,217,727.

[“Example: IGZCA2D” on page 667](#)

### **related references**

[“IGZCA2D return codes” on page 666](#)

## **IGZCA2D return codes**

IGZCA2D sets the RETURN-CODE special register to reflect the status of the conversion.

Table 94. <b>IGZCA2D return codes</b>	
Return code	Explanation
0	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> .
2	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . <i>parameter-2</i> was padded on the right with DBCS spaces.
4	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . The DBCS data placed in <i>parameter-2</i> was truncated on the right.
6	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . A single-byte character in the range X'00' to X'3F' or X'FF' was encountered. The valid single-byte character was converted into an out-of-range DBCS character.
8	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . A single-byte character in the range X'00' to X'3F' or X'FF' was encountered. The valid single-byte character was converted into an out-of-range DBCS character.  <i>parameter-2</i> was padded on the right with DBCS spaces.

Table 94. <b>IGZCA2D</b> return codes (continued)	
Return code	Explanation
10	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . A single-byte character in the range X'00' to X'3F' or X'FF' was encountered. The valid single-byte character was converted into an out-of-range DBCS character.  The DBCS data in <i>parameter-2</i> was truncated on the right.
12	An odd number of bytes was found between paired shift codes in <i>parameter-1</i> . No conversion occurred.
13	Unpaired or nested shift codes were found in <i>parameter-1</i> . No conversion occurred.
14	<i>parameter-1</i> and <i>parameter-2</i> were overlapping. No conversion occurred.
15	The value provided for <i>parameter-3</i> or <i>parameter-4</i> was out of range. No conversion occurred.
16	An odd number of bytes was coded in <i>parameter-4</i> . No conversion occurred.

## Example: IGZCA2D

This example CALL statement converts the alphanumeric data in *alpha-item* to DBCS data. The results of the conversion are placed in *dbcs-item*.

```
CALL "IGZCA2D" USING BY REFERENCE alpha-item dbc-item
BY CONTENT LENGTH OF alpha-item LENGTH OF dbc-item
```

Suppose the contents of *alpha-item* and *dbcs-item* and the lengths before the conversion are:

```
alpha-item = AB<D1D2D3>CD
dbcs-item  = D4D5D6D7D8D9D0
```

```
LENGTH OF alpha-item = 12
LENGTH OF dbc-item   = 14
```

Then after the conversion, *alpha-item* and *dbcs-item* will contain:

```
alpha-item = AB<D1D2D3>CD
dbcs-item  = .A.BD1D2D3.C.D
```

The content of the RETURN-CODE register is 0.

### related references

[“DBCS notation” on page 665](#)

## DBCS to alphanumeric data conversion (IGZCD2A)

The Language Environment IGZCD2A routine converts pure DBCS data to alphanumeric data that can contain double-byte characters.

## IGZCD2A syntax

To use the IGZCD2A service routine, pass the following four parameters to the routine using the CALL statement:

### ***parameter-1***

The sending field for the conversion, handled as a DBCS data item.

**parameter-2**

The receiving field for the conversion, handled as an alphanumeric data item.

**parameter-3**

The number of bytes in *parameter-1* to be converted.

It can be the LENGTH OF special register of *parameter-1*, or a 4-byte USAGE IS BINARY data item containing the number of bytes of *parameter-1* to be converted.

**parameter-4**

The number of bytes in *parameter-2* that will receive the converted data.

It can be the LENGTH OF special register of *parameter-2*, or a 4-byte USAGE IS BINARY data item containing the number of bytes of *parameter-2* to receive the converted data. Shift codes count as 1 byte each.

**Usage notes**

- You can pass *parameter-1*, *parameter-3*, and *parameter-4* to the routine BY REFERENCE or BY CONTENT, but you must pass *parameter-2* BY REFERENCE.
- The compiler does not perform syntax checking on these parameters. Ensure that the parameters are correctly set and passed to the conversion routine. Otherwise, results are unpredictable.
- When creating *parameter-2* from *parameter-1*, IGZCD2A makes these changes:
  - Inserts shift codes around DBCS characters that do not correspond to single-byte EBCDIC characters
  - Converts DBCS characters to single-byte characters when the DBCS characters correspond to single-byte EBCDIC characters
  - Converts the DBCS space (X'4040') to a single-byte space (X'40')
- IGZCD2A does not change the contents of *parameter-1*, *parameter-3*, or *parameter-4*.
- If the converted data contains double-byte characters, shift codes are counted in the length of *parameter-2*.
- The valid range for the contents of *parameter-3* and for the contents of *parameter-4* is 1 to 134,217,727.

[“Example: IGZCD2A” on page 669](#)

**related references**

[“IGZCD2A return codes” on page 668](#)

**IGZCD2A return codes**

IGZCD2A sets the RETURN-CODE special register to reflect the status of the conversion.

Table 95. <b>IGZCD2A return codes</b>	
Return code	Explanation
0	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> .
2	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . <i>parameter-2</i> was padded on the right with single-byte spaces.
4	<i>parameter-1</i> was converted and the results were placed in <i>parameter-2</i> . <i>parameter-2</i> was truncated on the right. <sup>1</sup>
14	<i>parameter-1</i> and <i>parameter-2</i> were overlapping. No conversion occurred.
15	The value of <i>parameter-3</i> or <i>parameter-4</i> was out of range. No conversion occurred.
16	An odd number of bytes was coded in <i>parameter-3</i> . No conversion occurred.

Table 95. <b>IGZCD2A</b> return codes (continued)	
Return code	Explanation
	1. If a truncation occurs within the DBCS characters, the truncation is on an even-byte boundary and a shift-in (SI) is inserted. If necessary, the alphanumeric data is padded with a single-byte space after the shift-in.

## Example: IGZCD2A

This example CALL statement converts the DBCS data in `dbcs-item` to alphanumeric data with double-byte characters. The results of the conversion are placed in `alpha-item`.

```
CALL "IGZCD2A" USING BY REFERENCE dbc-item alpha-item
BY CONTENT LENGTH OF dbc-item LENGTH OF alpha-item
```

Suppose the contents of `dbcs-item` and `alpha-item` and the lengths before the conversion are:

```
dbcs-item = .A.BD1D2D3.C.D
alpha-item = ssssssssssss
```

```
LENGTH OF dbc-item = 14
LENGTH OF alpha-item = 12
```

Then after the conversion, `dbcs-item` and `alpha-item` will contain:

```
dbcs-item = .A.BD1D2D3.C.D
alpha-item = AB<D1D2D3>CD
```

The content of the RETURN-CODE register is 0.

### related references

[“DBCS notation” on page 665](#)



## Appendix C. XML reference material

The following information describes the XML exception codes that might be returned during XML parsing or XML generation.

### related references

[“XML PARSE exceptions with XMLPARSE\(XMLSS\) in effect” on page 671](#)

[“XML PARSE exceptions with XMLPARSE\(COMPAT\) in effect” on page 673](#)

[“XML GENERATE exceptions” on page 679](#)

[XML specification](#)

## XML PARSE exceptions with XMLPARSE(XMLSS) in effect

When the z/OS XML System Services parser passes control to your processing procedure for an exception event, the XML -CODE special register contains the exception code, which is formed from a return code and a reason code.

The return code and reason code are each a halfword binary value. The exception code is the concatenation of those two values: the return code in the high-order halfword, and the reason code in the low-order halfword.

The return codes and reason codes are documented as hexadecimal values in the *z/OS XML System Services User's Guide and Reference*, referenced below, and in [Table 96 on page 671](#) below.

After most exception events, the parser does not continue processing; the value in XML -CODE at the end of the XML PARSE statement is the original exception code set by the parser.

When the processing procedure returns to the parser after the exception event, control transfers to the statement specified in the ON EXCEPTION phrase, or to the end of the XML PARSE statement if you did not code an ON EXCEPTION phrase.

### Validation exceptions:

If you code an XML PARSE statement that contains the VALIDATING phrase, and the z/OS XML System Services parser determines that the document is not valid, the parser generates return code 24 (hexadecimal 18, XRC\_NOT\_VALID).

### Exceptions that are unique to Enterprise COBOL:

Some exceptions are unique to Enterprise COBOL and thus are not documented in the *z/OS XML System Services User's Guide and Reference*, for example, errors that occur during XML schema retrieval. The return code for exceptions with reason codes in the hexadecimal range 800 to 899 is 4 (hexadecimal 0004, XRC\_WARNING). For other exceptions, the return code is 16 (hexadecimal 0010, XRC\_FATAL). The exception code (the value in special register XML -CODE), is formed from this return code concatenated with one of the reason codes shown in the following table.

Table 96. Reason codes for XML PARSE exceptions that are unique to Enterprise COBOL	
Reason code (hexadecimal)	Description
700	VALIDATING WITH FILE is not supported under CICS.
701	The optimized XML schema that was read in was too short, or the file was empty.
702	The file identifier for the schema was not a ddname or environment-variable name.
703	The DSN value contained a space character in a position where a space is not allowed.
704	The DSN value specified a temporary data set.

Table 96. *Reason codes for XML PARSE exceptions that are unique to Enterprise COBOL (continued)*

Reason code (hexadecimal)	Description
705	The PATH value contained an unescaped space character.
706	The PATH value contained a path name that was not an absolute path.
707	Memory allocation for the XML schema buffer failed.
708	The environment variable was null or contained only spaces.
709	The environment variable contained an invalid keyword.
710	The DSN value contained an invalid character after the member name.
711	The DSN value did not specify a member name.
712	The DSN value did not specify a data set name, or parentheses were not specified correctly.
713	The PATH value did not specify a path name, or parentheses were not specified correctly.
714	The DSN value contained an extra parenthesis.
715	The PATH value contained an extra parenthesis.
716	The DSN value was missing the closing parenthesis.
717	The PATH value was missing the closing parenthesis.
718	The DSN value contained an escape character.
720	A character reference for an unrepresentable character was not resolved.
721	An unrepresentable character reference in the document type declaration is not supported.
800	The attribute name used an undeclared prefix.
801	The START-OF-ELEMENT name used an undeclared prefix. (The END-OF-ELEMENT name must match, so using the same undeclared prefix does not cause another exception.)
900	Internal error. Report the error to your service representative.

For any of the reason codes except 900, correct the error and then retry your program.

#### **related concepts**

[“XML-CODE” on page 512](#)

[“XML events” on page 511](#)

#### **related tasks**

[“Handling XML PARSE exceptions” on page 527](#)

#### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

XML PARSE statement (*Enterprise COBOL for z/OS Language Reference*)  
*z/OS XML System Services User's Guide and Reference*

## XML PARSE exceptions with XMLPARSE(COMPAT) in effect

When an exception event occurs, the XML parser that is provided with the Enterprise COBOL library sets special register XML - CODE to a value that identifies the exception. Depending on the value in XML - CODE, the parser might or might not be able to continue processing after the exception, as detailed in the information referenced below.

### related references

[“XML PARSE exceptions that allow continuation” on page 673](#)

[“XML PARSE exceptions that do not allow continuation” on page 676](#)

## XML PARSE exceptions that allow continuation

If the XMLPARSE (COMPAT) compiler option is in effect, whether the XML parser can continue processing after an exception event depends upon the value of the exception code.

The parser can continue processing if the exception code, which is in special register XML - CODE, is within one of the following ranges:

- 1 - 99
- 100,001 - 165,535

The following table describes each exception, and identifies the actions that the parser takes if you request that it continue after the exception. Some of the descriptions use the following terms:

- *Actual document encoding*
- *Document encoding declaration*

For definitions of the terms, see the related concept about XML input document encoding.

Table 97. XML PARSE exceptions that allow continuation		
Exception code (decimal)	Description	Parser action on continuation
1	The parser found an invalid character while scanning white space outside element content.  For further information about white space, see the related concept about XML input document encoding.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
2	The parser found an invalid start of a processing instruction, element, comment, or document type declaration outside element content.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
3	The parser found a duplicate attribute name.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
4	The parser found the markup character '<' in an attribute value.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.

Table 97. ***XML PARSE exceptions that allow continuation*** (continued)

<b>Exception code (decimal)</b>	<b>Description</b>	<b>Parser action on continuation</b>
5	The start and end tag names of an element did not match.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
6	The parser found an invalid character in element content.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
7	The parser found an invalid start of an element, comment, processing instruction, or CDATA section in element content.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
8	The parser found in element content the CDATA closing character sequence ']]>' without the matching opening character sequence '<![CDATA['.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
9	The parser found an invalid character in a comment.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
10	The parser found in a comment the character sequence '- -' (two hyphens) not followed by '>'.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
11	The parser found an invalid character in a processing instruction data segment.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
12	The XML declaration was not at the beginning of the document.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
13	The parser found an invalid digit in a hexadecimal character reference (of the form <code>&amp;#xddd;</code> ).	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.

Table 97. ***XML PARSE exceptions that allow continuation*** (continued)

<b>Exception code (decimal)</b>	<b>Description</b>	<b>Parser action on continuation</b>
14	The parser found an invalid digit in a decimal character reference (of the form &#dddd;).	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
15	The encoding declaration value in the XML declaration did not begin with lowercase or uppercase A through Z.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
16	A character reference did not refer to a legal XML character.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
17	The parser found an invalid character in an entity reference name.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
18	The parser found an invalid character in an attribute value.	The parser continues detecting errors until it reaches the end of the document or encounters an error that does not allow continuation. The parser does not signal any further normal events, except for the END-OF-DOCUMENT event.
70	The actual document encoding was EBCDIC, and the CODEPAGE compiler option specified a supported EBCDIC code page, but the document encoding declaration did not specify a supported EBCDIC code page.	The parser uses the encoding specified by the CODEPAGE compiler option.
71	The actual document encoding was EBCDIC, and the document encoding declaration specified a supported EBCDIC encoding, but the CODEPAGE compiler option did not specify a supported EBCDIC code page.	The parser uses the encoding specified by the document encoding declaration.
72	The actual document encoding was EBCDIC, the CODEPAGE compiler option did not specify a supported EBCDIC code page, and the document did not contain an encoding declaration.	The parser uses EBCDIC code page 1140 (USA, Canada, . . . Euro Country Extended Code Page).

<i>Table 97. XML PARSE exceptions that allow continuation (continued)</i>		
<b>Exception code (decimal)</b>	<b>Description</b>	<b>Parser action on continuation</b>
73	The actual document encoding was EBCDIC, but neither the CODEPAGE compiler option nor the document encoding declaration specified a supported EBCDIC code page.	The parser uses EBCDIC code page 1140 (USA, Canada, . . . Euro Country Extended Code Page).
82	The actual document encoding was ASCII, but the document did not contain an encoding declaration.	The parser uses ASCII code page 819 (ISO-8859-1 Latin 1/Open Systems).
83	The actual document encoding was ASCII, but the document encoding declaration did not specify code page 813, 819, or 920.	The parser uses ASCII code page 819 (ISO-8859-1 Latin 1/Open Systems).
92	The document data item was alphanumeric, but the actual document encoding was Unicode UTF-16.	The parser uses code page 1200 (Unicode UTF-16).
100,001 - 165,535	The CODEPAGE compiler option and the document encoding declaration specified different supported EBCDIC code pages. XML - CODE contains the code page CCSID for the encoding declaration plus 100,000.	If you set XML - CODE to zero before returning from the EXCEPTION event, the parser uses the encoding specified by the CODEPAGE compiler option. If you set XML - CODE to the CCSID for the document encoding declaration (by subtracting 100,000), the parser uses this encoding.

#### **related concepts**

[“XML-CODE” on page 512](#)

[“XML input document encoding” on page 523](#)

#### **related tasks**

[“Handling XML PARSE exceptions” on page 527](#)

#### **related references**

[“XMLPARSE” on page 350 \(compiler option\)](#)

## **XML PARSE exceptions that do not allow continuation**

If the XMLPARSE (COMPAT) compiler option is in effect, the XML parser cannot continue processing if any of the exceptions described below occurs.

No further events are returned from the parser for any of these exceptions even if the processing procedure sets XML - CODE to zero before passing control back to the parser. The parser transfers control to the statement in the ON EXCEPTION phrase, if specified, otherwise to the end of the XML PARSE statement.

<i>Table 98. XML PARSE exceptions that do not allow continuation (for XMLPARSE (COMPAT))</i>	
<b>Exception code (decimal)</b>	<b>Description</b>
100	The parser reached the end of the document while scanning the start of the XML declaration.

*Table 98. XML PARSE exceptions that do not allow continuation (for XMLPARSE (COMPAT)) (continued)*

<b>Exception code (decimal)</b>	<b>Description</b>
101	The parser reached the end of the document while looking for the end of the XML declaration.
102	The parser reached the end of the document while looking for the root element.
103	The parser reached the end of the document while looking for the version information in the XML declaration.
104	The parser reached the end of the document while looking for the version information value in the XML declaration.
106	The parser reached the end of the document while looking for the encoding declaration value in the XML declaration.
108	The parser reached the end of the document while looking for the standalone declaration value in the XML declaration.
109	The parser reached the end of the document while scanning an attribute name.
110	The parser reached the end of the document while scanning an attribute value.
111	The parser reached the end of the document while scanning a character reference or entity reference in an attribute value.
112	The parser reached the end of the document while scanning an empty element tag.
113	The parser reached the end of the document while scanning the root element name.
114	The parser reached the end of the document while scanning an element name.
115	The parser reached the end of the document while scanning character data in element content.
116	The parser reached the end of the document while scanning a processing instruction in element content.
117	The parser reached the end of the document while scanning a comment or CDATA section in element content.
118	The parser reached the end of the document while scanning a comment in element content.
119	The parser reached the end of the document while scanning a CDATA section in element content.
120	The parser reached the end of the document while scanning a character reference or entity reference in element content.
121	The parser reached the end of the document while scanning after the close of the root element.
122	The parser found a possible invalid start of a document type declaration.
123	The parser found a second document type declaration.
124	The first character of the root element name was not a letter, '_', or ':'.
125	The first character of the first attribute name of an element was not a letter, '_', or ':'.
126	The parser found an invalid character either in or following an element name.
127	The parser found a character other than '=' following an attribute name.

*Table 98. XML PARSE exceptions that do not allow continuation (for XMLPARSE (COMPAT)) (continued)*

<b>Exception code (decimal)</b>	<b>Description</b>
128	The parser found an invalid attribute value delimiter.
130	The first character of an attribute name was not a letter, '_', or ':'.
131	The parser found an invalid character either in or following an attribute name.
132	An empty element tag was not terminated by a '>' following the '/'.
133	The first character of an element end tag name was not a letter, '_', or ':'.
134	An element end tag name was not terminated by a '>'.
135	The first character of an element name was not a letter, '_', or ':'.
136	The parser found an invalid start of a comment or CDATA section in element content.
137	The parser found an invalid start of a comment.
138	The first character of a processing instruction target name was not a letter, '_', or ':'.
139	The parser found an invalid character in or following a processing instruction target name.
140	A processing instruction was not terminated by the closing character sequence '?>'.
141	The parser found an invalid character following '&' in a character reference or entity reference.
142	The version information was not present in the XML declaration.
143	'version' in the XML declaration was not followed by '='.
144	The version declaration value in the XML declaration is either missing or improperly delimited.
145	The version information value in the XML declaration specified a bad character, or the start and end delimiters did not match.
146	The parser found an invalid character following the version information value closing delimiter in the XML declaration.
147	The parser found an invalid attribute instead of the optional encoding declaration in the XML declaration.
148	'encoding' in the XML declaration was not followed by '='.
149	The encoding declaration value in the XML declaration is either missing or improperly delimited.
150	The encoding declaration value in the XML declaration specified a bad character, or the start and end delimiters did not match.
151	The parser found an invalid character following the encoding declaration value closing delimiter in the XML declaration.
152	The parser found an invalid attribute instead of the optional standalone declaration in the XML declaration.
153	standalone in the XML declaration was not followed by '='.
154	The standalone declaration value in the XML declaration is either missing or improperly delimited.
155	The standalone declaration value was neither 'yes' nor 'no' only.

Table 98. ***XML PARSE exceptions that do not allow continuation (for XMLPARSE (COMPAT))*** (continued)

Exception code (decimal)	Description
156	The standalone declaration value in the XML declaration specified a bad character, or the start and end delimiters did not match.
157	The parser found an invalid character following the standalone declaration value closing delimiter in the XML declaration.
158	The XML declaration was not terminated by the proper character sequence '>', or contained an invalid attribute.
159	The parser found the start of a document type declaration after the end of the root element.
160	The parser found the start of an element after the end of the root element.
315	The <i>actual document encoding</i> was UTF-16 little-endian, which the parser does not support on this platform.
316	The actual document encoding was UCS4, which the parser does not support.
317	The parser cannot determine the document encoding. The document might be damaged.
318	The actual document encoding was UTF-8, which the parser does not support.
320	The document data item was national, but the actual document encoding was EBCDIC.
321	The document data item was national, but the actual document encoding was ASCII.
500 - 599	Internal error. Report the error to your service representative.

#### related concepts

[“XML-CODE” on page 512](#)

#### related tasks

[“Handling XML PARSE exceptions” on page 527](#)

## XML GENERATE exceptions

One of several exception codes might be returned in the XML - CODE special register during XML generation. If one of these exceptions occurs, control is passed to the statement in the ON EXCEPTION phrase, or to the end of the XML GENERATE statement if you did not code an ON EXCEPTION phrase.

Table 99. ***XML GENERATE exceptions***

Exception code (decimal)	Description
400	The receiver was too small to contain the generated XML document. The COUNT IN data item, if specified, contains the count of character positions that were actually generated.
401	A DBCS data-name contained a character that, when converted to Unicode, was not valid in an XML element or attribute name.
402	The first character of a DBCS data-name, when converted to Unicode, was not valid as the first character of an XML element or attribute name.
403	The value of an OCCURS DEPENDING ON variable exceeded 16,777,215.

Table 99. ***XML GENERATE exceptions*** (continued)

Exception code (decimal)	Description
410	The CCSID page specified by the CODEPAGE compiler option is not supported for conversion to Unicode.
411	The CCSID specified by the CODEPAGE compiler option is not a supported single-byte EBCDIC CCSID.
414	The CCSID specified for the XML document was invalid or was not supported.
415	The receiver was national, but the encoding specified for the document was not UTF-16.
416	The XML namespace identifier contained invalid XML characters.
417	<p>Element character content or an attribute value contained characters that are illegal in XML content. XML generation has continued, with the element tag name or the attribute name prefixed with 'hex.' and the original data value represented in the document in hexadecimal.</p> <p>Any TYPE IS CONTENT specification is ignored, and the item is treated as an element.</p>
418	Substitution characters were generated by encoding conversion.
419	The XML namespace prefix was invalid.
420	The receiver was alphanumeric and the input included national or DBCS data or names, but the encoding specified for the document was not 1208.
600-699	Internal error. Report the error to your service representative.

**related tasks**

[“Handling XML GENERATE exceptions” on page 550](#)

## Appendix D. JSON GENERATE exceptions

One of several exception codes might be returned in the JSON-CODE special register during JSON generation. If one of these exceptions occurs, control is passed to the statement in the ON EXCEPTION phrase, or to the end of the JSON GENERATE statement if you did not code an ON EXCEPTION phrase.

*Table 100. JSON GENERATE exceptions*

Exception code (decimal)	Description
1	The receiver was too small to contain the generated JSON text. The COUNT IN data item, if specified, contains the count of character positions that were actually generated.
507	Internal error. The LE runtime level might not be up-to-date. Install the latest LE runtime PTFs. If the error persists, report the error to your service representative.
500 - 599 (except 507)	Internal error. Report the error to your service representative.



# Appendix E. EXIT compiler option

You can use the EXIT compiler option to provide user-supplied modules in place of various compiler functions. For details about processing of each exit module, error handling for exit modules, or using the EXIT option with CICS, SQL and SQLIMS statements, see the following topics.

**related tasks**

- [“Using the user-exit work area” on page 683](#)
- [“Calling from exit modules” on page 684](#)
- [Using the EXIT compiler option with CICS, SQL and SQLIMS statements](#)

**related references**

- [“EXIT” on page 305](#)
- [“Processing of INEXIT” on page 684](#)
- [“Processing of LIBEXIT” on page 685](#)
- [“Processing of PRTEXTIT” on page 688](#)
- [“Processing of ADEXIT” on page 690](#)
- [“Processing of MSGEXIT” on page 691](#)
- [“Error handling for exit modules” on page 700](#)

## Using the user-exit work area

When you use one of the user exits, the compiler provides a work area in which you can save the address of GETMAIN storage obtained by the exit module. Having such a work area lets the module be reentrant.

The user-exit work area consists of 6 fullwords that reside on a fullword boundary. These fullwords are initialized to binary zeros before the first exit routine is invoked. The address of the work area is passed to the exit module in a parameter list. After initialization, the compiler makes no further reference to the work area.

The words in the user-exit work area are used by the individual exit modules as shown in the following table.

Table 101. <i>Layout of the user-exit work area</i>	
Word number	Used by module:
1	INEXIT
2	LIBEXIT
3	PRTEXTIT
4	ADEXIT
5	(Reserved)
6	MSGEXIT

**related references**

- [“Processing of INEXIT” on page 684](#)
- [“Processing of LIBEXIT” on page 685](#)
- [“Processing of PRTEXTIT” on page 688](#)
- [“Processing of ADEXIT” on page 690](#)
- [“Processing of MSGEXIT” on page 691](#)

# Calling from exit modules

To call COBOL programs or library routines within your exit modules, use standard COBOL linkage. You need to be aware of the register conventions in order to trace the call chain correctly.

When a call is made to a program or to a routine in an exit module, the registers are set up as follows:

- R1**  
Points to the parameter list passed to the called program or library routine
- R13**  
Points to the register save area provided by the calling program or routine
- R14**  
Holds the return address of the calling program or routine
- R15**  
Holds the address of the called program or routine

Exit modules must have RMODE attribute 24 and AMODE attribute ANY.

## related concepts

[“Storage and its addressability” on page 37](#)

# Processing of INEXIT

The INEXIT exit module is used to read the primary source code instead of obtaining it directly from SYSIN.

Table 102. <i>INEXIT processing</i>	
Action by compiler	Action by exit module
Loads the exit module ( <i>mod1</i> ) during initialization	
Calls the exit module with an OPEN operation code (op code)	Prepares its source for processing. Passes the status of the OPEN request back to the compiler.
Calls the exit module with a GET op code when a source statement is needed	Returns either the address and length of the next statement or the end-of-data indication (if no more source statements exist)
Calls the exit module with a CLOSE op code when the end-of-data is presented	Releases any resources that are related to its output

## INEXIT parameters

The compiler uses 10 parameters, passed by reference, to communicate with the exit module. The return code, data length, and data parameters are set by the exit module for return to the compiler; the other items are passed from the compiler to the exit module.

Table 103. <i>INEXIT parameters</i>		
Parameter number	Parameter item	Description of item
1	User-exit type	Halfword that identifies which user exit is to perform the operation.  1=INEXIT

Table 103. **INEXIT parameters** (continued)

Parameter number	Parameter item	Description of item
2	Operation code	Halfword that indicates the type of operation: <ul style="list-style-type: none"> <li>• 0=OPEN</li> <li>• 1=CLOSE</li> <li>• 2=GET</li> </ul>
3	Return code	Fullword, set by the exit module, that indicates the success of the requested operation: <ul style="list-style-type: none"> <li>• 0=Operation was successful</li> <li>• 4=End-of-data</li> <li>• 12=Operation failed</li> </ul>
4	User-exit work area	Six-fullword work area provided by the compiler for use by the user-exit module. First word: for use by INEXIT
5	Data length	Fullword, set by the exit module, that specifies the length of the record being returned by the GET operation (must be 80)
6	Data or <i>str1</i>	Fullword, set by the exit module, that contains the address of the record in a user-owned buffer, for the GET operation. <i>str1</i> applies only to OPEN. The first halfword (on a halfword boundary) contains the length of the string, followed by the string.
7	Not used	(Used only by LIBEXIT and MSGEXIT)
8	Not used	(Used only by LIBEXIT)
9	Not used	(Used only by LIBEXIT)
10	Not used	(Used only by LIBEXIT)

#### related tasks

[“Using the user-exit work area” on page 683](#)

[“Calling from exit modules” on page 684](#)

[Using the EXIT compiler option with CICS, SQL and SQLIMS statements](#)

## Processing of LIBEXIT

The LIBEXIT exit module is used in place of the SYSLIB, or *library-name*, data set. Calls are made to the module by the compiler to obtain copybooks whenever COPY or BASIS statements are encountered.

Table 104. **LIBEXIT processing**

Action by compiler	Action by exit module
Loads the exit module ( <i>mod2</i> ) during initialization	
Calls the exit module with an OPEN operation code (op code)	Prepares the specified <i>library-name</i> for processing. Passes the status of the OPEN request to the compiler.

<i>Table 104. LIBEXIT processing (continued)</i>	
Action by compiler	Action by exit module
Calls the exit module with a FIND op code if the <i>library-name</i> was successfully opened	Establishes positioning at the requested <i>text-name</i> (or <i>basis-name</i> ) in the specified <i>library-name</i> ; this place becomes the active copybook. Passes an appropriate return code to the compiler when positioning is complete.
Calls the exit module with a GET op code	Passes the compiler either the length and address of the record to be copied from the active copybook or the end-of-data indicator
Calls the exit module with a CLOSE op code when the end-of-data is presented	Releases any resources that are related to its input

## Processing of LIBEXIT with nested COPY statements

Any record from the active copybook can contain a COPY statement.

You cannot make recursive calls to *text-name*. That is, a copybook can be named only once in a set of nested COPY statements until the end-of-data for that copybook is reached.

The following table shows how the processing of LIBEXIT changes when there are one or more valid COPY statements that are not nested.

<i>Table 105. LIBEXIT processing with nonnested COPY statements</i>	
Action by compiler	Action by exit module
Loads the exit module ( <i>mod2</i> ) during initialization	
Calls the exit module with an OPEN operation code (op code)	Prepares the specified <i>library-name</i> for processing. Passes the status of the OPEN request to the compiler.
Calls the exit module with a FIND op code if the <i>library-name</i> was successfully opened	Establishes positioning at the requested <i>text-name</i> (or <i>basis-name</i> ) in the specified <i>library-name</i> ; this place becomes the active copybook. Passes an appropriate return code to the compiler when positioning is complete.
Calls the exit module with a FIND op code if the <i>library-name</i> was successfully opened	Reestablishes positioning at the previous active copybook. Passes an appropriate return code to the compiler when positioning is complete.
Calls the exit module with a GET op code. Verifies that the same record was passed.	Passes the compiler the same record as was passed previously from this copybook. After verification, passes either the length and address of the record to be copied from the active copybook or the end-of-data indicator.
Calls the exit module with a CLOSE op code when the end-of-data is presented	Releases any resources that are related to its input

The following table shows how the processing of LIBEXIT changes when the compiler encounters a valid nested COPY statement.

<i>Table 106. LIBEXIT processing with nested COPY statements</i>	
Action by compiler	Action by exit module
If the requested <i>library-name</i> from the nested COPY statement was not previously opened, calls the exit module with an OPEN op code	Pushes its control information about the active copybook onto a stack. Completes the requested action (OPEN). The newly requested <i>text-name</i> (or <i>basis-name</i> ) becomes the active copybook.
Calls the exit module with a FIND op code for the requested new <i>text-name</i>	Pushes its control information about the active copybook onto a stack. Completes the requested action (FIND). The newly requested <i>text-name</i> (or <i>basis-name</i> ) becomes the active copybook.
Calls the exit module with a GET op code	Passes the compiler either the length and address of the record to be copied from the active copybook or the end-of-data indicator. At end-of-data, pops its control information from the stack.

## LIBEXIT parameters

The compiler uses 10 parameters, passed by reference, to communicate with the exit module. The return code, data length, and data parameters are set by the exit module for return to the compiler; the other items are passed from the compiler to the exit module.

<i>Table 107. LIBEXIT parameters</i>		
Parameter number	Parameter item	Description of item
1	User-exit type	Halfword that identifies which user exit is to perform the operation. 2=LIBEXIT
2	Operation code	Halfword that indicates the type of operation: <ul style="list-style-type: none"> <li>• 0=OPEN</li> <li>• 1=CLOSE</li> <li>• 2=GET</li> <li>• 4=FIND</li> </ul>
3	Return code	Fullword, set by the exit module, that indicates the success of the requested operation: <ul style="list-style-type: none"> <li>• 0=Operation was successful</li> <li>• 4=End-of-data</li> <li>• 12=Operation failed</li> </ul>
4	User-exit work area	Six-fullword work area provided by the compiler for use by the user-exit module. Second word: for use by LIBEXIT
5	Data length	Fullword, set by the exit module, that specifies the length of the record being returned by the GET operation (must be 80)

Table 107. **LIBEXIT** parameters (continued)

Parameter number	Parameter item	Description of item
6	Data or <i>str2</i>	Fullword, set by the exit module, that contains the address of the record in a user-owned buffer, for the GET operation.  <i>str2</i> applies only to OPEN. The first halfword (on a halfword boundary) contains the length of the string, followed by the string.
7	System <i>library-name</i>	Eight-character area that contains the <i>library-name</i> from the COPY statement. Processing and conversion rules for a program-name are applied. Padded with blanks if required. Applies to OPEN, CLOSE, and FIND.
8	System <i>text-name</i>	Eight-character area that contains the <i>text-name</i> from the COPY statement ( <i>basis-name</i> from BASIS statement). Processing and conversion rules for a program-name are applied. Padded with blanks if required. Applies only to FIND.
9	Library-name	Thirty-character area that contains the full <i>library-name</i> from the COPY statement. Padded with blanks if required, and used as is (not folded to uppercase). Applies to OPEN, CLOSE, and FIND.
10	Text-name	Thirty-character area that contains the full <i>text-name</i> from the COPY statement. Padded with blanks if required, and used as is (not folded to uppercase). Applies only to FIND.

#### related tasks

[“Using the user-exit work area” on page 683](#)

[“Calling from exit modules” on page 684](#)

[Using the EXIT compiler option with CICS, SQL and SQLIMS statements](#)

## Processing of PRTEXTIT

The PRTEXTIT exit module is used in place of the SYSPRINT data set.

Table 108. **PRTEXTIT** processing

Action by compiler	Action by exit module
Loads the exit module ( <i>mod3</i> ) during initialization	
Calls the exit module with an OPEN operation code (op code)	Prepares its output destination for processing. Passes the status of the OPEN request to the compiler.
Calls the exit modules with a PUT op code when a line is to be printed, supplying the address and length of the record that is to be printed	Passes the status of the PUT request to the compiler by a return code. The first byte of the record to be printed contains an ANSI printer control character.
Calls the exit module with a CLOSE op code when the end-of-data is presented	Releases any resources that are related to its output destination

## PRTEXT parameters

The compiler uses 10 parameters, passed by reference, to communicate with the exit module. The return code, data length, and data buffer parameters are set by the exit module for return to the compiler; the other items are passed from the compiler to the exit module.

Table 109. <i>PRTEXT parameters</i>		
Parameter number	Parameter item	Description of item
1	User-exit type	Halfword that identifies which user exit is to perform the operation. 3=PRTEXT
2	Operation code	Halfword that indicates the type of operation: <ul style="list-style-type: none"><li>• 0=OPEN</li><li>• 1=CLOSE</li><li>• 3=PUT</li></ul>
3	Return code	Fullword, set by the exit module, that indicates the success of the requested operation: <ul style="list-style-type: none"><li>• 0=Operation was successful</li><li>• 12=Operation failed</li></ul>
4	User-exit work area	Six-fullword work area provided by the compiler for use by the user-exit module. Third word: for use by PRTEXT
5	Data length	Fullword that specifies the length of the record being supplied by the PUT operation (the compiler sets this value to 133)
6	Data buffer or <i>str3</i>	Data buffer where the compiler has placed the record to be printed by the PUT operation. <i>str3</i> applies only to OPEN. The first halfword (on a halfword boundary) contains the length of the string, followed by the string.
7	Not used	(Used only by LIBEXIT and MSGEXIT)
8	Not used	(Used only by LIBEXIT)
9	Not used	(Used only by LIBEXIT)
10	Not used	(Used only by LIBEXIT)

### related tasks

[“Using the user-exit work area” on page 683](#)

[“Calling from exit modules” on page 684](#)

[Using the EXIT compiler option with CICS, SQL and SQLIMS statements](#)

## Processing of ADEXIT

The ADEXIT module is called for each SYSADATA record immediately after the record has been written out to the file.

To use an ADEXIT module, you must compile using the ADATA option to produce SYSADATA output, and code the SYSADATA DD statement.

<i>Table 110. ADEXIT processing</i>	
Action by compiler	Action by exit module
Loads the exit module ( <i>mod4</i> ) during initialization	
Calls the exit module with an OPEN operation code (op code)	Prepares its output destination for processing. Passes the status of the OPEN request to the compiler.
Calls the exit module with a PUT op code when the compiler has written a SYSADATA record, supplying the address and length of the SYSADATA record	Passes the status of the PUT request to the compiler by a return code
Calls the exit module with a CLOSE op code when the end-of-data is presented	Releases any resources

## ADEXIT parameters

The compiler uses 10 parameters, passed by reference, to communicate with the exit module. The return code, data length, and data buffer parameters are set by the exit module for return to the compiler; the other items are passed from the compiler to the exit module.

<i>Table 111. ADEXIT parameters</i>		
Parameter number	Parameter item	Description of item
1	User-exit type	Halfword that identifies which user exit is to perform the operation. 4=ADEXIT
2	Operation code	Halfword that indicates the type of operation: <ul style="list-style-type: none"><li>• 0=OPEN</li><li>• 1=CLOSE</li><li>• 3=PUT</li></ul>
3	Return code	Fullword, set by the exit module, that indicates the success of the requested operation: <ul style="list-style-type: none"><li>• 0=Operation was successful</li><li>• 12=Operation failed</li></ul>
4	User-exit work area	Six-fullword work area provided by the compiler for use by the user-exit module. Fourth word: for use by ADEXIT
5	Data length	Fullword that specifies the length of the record being supplied by the PUT operation

Table 111. **ADEXIT parameters** (continued)

Parameter number	Parameter item	Description of item
6	Data buffer or <i>str4</i>	Fullword that contains the address of the data buffer where the compiler has placed the record to be printed by the PUT operation.  <i>str4</i> applies only to OPEN. The first halfword (on a halfword boundary) contains the length of the string, followed by the string.
7	Not used	(Used only by LIBEXIT and MSGEXIT)
8	Not used	(Used only by LIBEXIT)
9	Not used	(Used only by LIBEXIT)
10	Not used	(Used only by LIBEXIT)

#### related tasks

[“Using the user-exit work area” on page 683](#)

[“Calling from exit modules” on page 684](#)

[Using the EXIT compiler option with CICS, SQL and SQLIMS statements](#)

#### related references

[“ADATA” on page 288](#)

## Processing of MSGEXIT

The MSGEXIT module is used to customize compiler diagnostic messages and FIPS messages. The module can customize a message either by changing its severity or suppressing it.

If the MSGEXIT module assigns a severity to a FIPS message, the message is converted into a diagnostic message. (The message is shown in the summary of diagnostic messages in the listing.)

A MSGEXIT summary at the end of the compiler listing shows how many messages were changed in severity and how many messages were suppressed.

Table 112. **MSGEXIT processing**

Action by compiler	Action by exit module
Loads the exit module ( <i>mod5</i> ) during initialization	
Calls the exit module with an OPEN operation code (op code)	Optionally processes <i>str5</i> and passes the status of the OPEN request to the compiler
Calls the exit module with a MSGSEV operation code (op code) when the compiler is about to issue a diagnostic message or FIPS message	One of the following actions: <ul style="list-style-type: none"> <li>Indicates no customization of the message (by setting return code to 0)</li> <li>Specifies a new severity for (or suppression of) the message, and sets return code to 4</li> <li>Indicates that the operation failed (by setting return code to 12)</li> </ul>
Calls the exit module with a CLOSE op code	Optionally frees storage and passes the status of the CLOSE request to the compiler

Table 112. <b>MSGEXIT processing</b> (continued)	
Action by compiler	Action by exit module
Deletes the exit module ( <i>mod5</i> ) during compiler termination	

## MSGEXIT parameters

The compiler uses 10 parameters, passed by reference, to communicate with the exit module. The return code and user-requested severity parameters are set by the exit module for return to the compiler; the other items are passed from the compiler to the exit module.

Table 113. <b>MSGEXIT parameters</b>		
Parameter number	Parameter item	Description of item
1	User-exit type	Halfword that identifies which user exit is to perform the operation. 6=MSGEXIT
2	Operation code	Halfword that indicates the type of operation: <ul style="list-style-type: none"> <li>• 0=OPEN</li> <li>• 1=CLOSE</li> <li>• 5=MSGSEV: customize message severity</li> </ul>
3	Return code	Fullword, set by the exit module, that indicates the success of the requested operation. For op code MSGSEV: <ul style="list-style-type: none"> <li>• 0=Message not customized</li> <li>• 4=Message found and customized</li> <li>• 12=Operation failed</li> </ul>
4	User-exit work area	Six-fullword work area provided by the compiler for use by the user-exit module. Sixth word: for use by MSGEXIT
5	Not used	(Used by the other exits)
6	Message exit data	Three-halfword area (on a halfword boundary). <ul style="list-style-type: none"> <li>• First halfword: the message number of the message to be customized</li> <li>• Second halfword: for a diagnostic message, the default severity; for a FIPS message, the FIPS category as a numeric code</li> <li>• Third halfword: the user-requested severity for the message (-1 to indicate suppression)</li> </ul>
7	<i>str5</i>	First halfword (on a halfword boundary): the length of the string, followed by the string
8	Not used	(Used only by LIBEXIT)
9	Not used	(Used only by LIBEXIT)

Table 113. <b>MSGEXIT</b> parameters (continued)		
Parameter number	Parameter item	Description of item
10	Not used	(Used only by LIBEXIT)

[“Example: MSGEXIT user exit” on page 695](#)

#### related tasks

[“Using the user-exit work area” on page 683](#)

[“Calling from exit modules” on page 684](#)

[“Customizing compiler-message severities” on page 693](#)

[Using the EXIT compiler option with CICS, SQL and SQLIMS statements](#)

## Customizing compiler-message severities

To change the severities of compiler messages or suppress compiler messages (including FIPS messages), do the steps described below.

1. Code and compile a COBOL program named ERRMSG. The program needs only a PROGRAM-ID paragraph, as described in the related task.
2. Review the ERRMSG listing, which contains a complete list of compiler messages with their message numbers, severities, and message text.
3. Decide which messages you want to customize.

To understand the customizations that are possible, see the related reference about customizable compiler-message severities.

4. Code a MSGEXIT module to implement the customizations. Refer to the sample MSGEXIT that is included with the COBOL compiler in the SIGYSAMP dataset called IGYMSGXT. For details, see [“Example: MSGEXIT user exit” on page 695](#).
  - a. Verify that the operation-code parameter indicates message-severity customization.
  - b. Check the two input values in the message-exit-data parameter: the message number; and the default severity for a diagnostic message or the FIPS category for a FIPS message.  
  
The FIPS category is expressed as numeric code. For details, see the related reference about customizable compiler-message severities.
  - c. For a message that you want to customize, set the user-requested severity in the message-exit-data parameter to indicate either:
    - A new message severity, by coding severity 0, 4, 8, or 12
    - Message suppression, by coding severity -1
  - d. Set the return code to one of the following values:
    - 0, to indicate that the message was not customized
    - 4, to indicate that the message was found and customized
    - 12, to indicate that the operation failed and that compilation should be terminated
5. Compile and link your MSGEXIT module.
6. Add the data set that contains your MSGEXIT module to the compiler concatenation by using a STEPLIB or JOBLIB DD statement.
7. Recompile program ERRMSG, but use compiler option EXIT (MSGEXIT (msgmod) ), where msgmod is the name of your MSGEXIT module.
8. Review the listing and check for:
  - Updated message severities

- Suppressed messages (indicated by XX in place of the severity)
- Unsupported severity changes or unsupported message suppression (indicated by a severity-U diagnostic message, and compiler termination with return code 16)

#### related tasks

[“Generating a list of compiler messages” on page 262](#)

#### related references

[“Severity codes for compiler diagnostic messages” on page 263](#)

[“Customizable compiler-message severities” on page 694](#)

[“Effect of message customization on compilation return code” on page 695](#)

[“Error handling for exit modules” on page 700](#)

## Customizable compiler-message severities

To customize compiler-message severities, you need to understand the possible severities of compiler diagnostic messages, the levels or categories of FIPS messages, and the permitted customizations of message severities.

The possible severity codes for compiler diagnostic messages are described in the related reference about severity codes.

The eight categories of FIPS (FLAGSTD) messages are shown in the following table. The category of any given FIPS message is passed as a numeric code to the MSGEXIT module. Those numeric codes are shown in the second column.

<i>Table 114. FIPS (FLAGSTD) message categories</i>		
<b>FIPS level or category</b>	<b>Numeric code</b>	<b>Description</b>
D	81	Debug module level 1
E	82	Extension (IBM)
H	83	High level
I	84	Intermediate level
N	85	Segmentation module level 1
O	86	Obsolete elements
Q	87	High-level and obsolete elements
S	88	Segmentation module level 2

FIPS messages have an implied severity of zero (severity I).

#### Permitted message-severity customizations:

You can change the severity of a compiler message in the following ways:

- Severity-I and severity-W compiler diagnostic messages, and FIPS messages, can be changed to have any severity from I through S.

Assigning a severity to a FIPS message converts the FIPS message to a diagnostic message of the assigned severity.

As examples, you can:

- Lower an optimizer warning to severity I.
- Disallow REDEFINING a smaller item with a larger item by raising the severity of message 1154.
- Disallow complex OCCURS DEPENDING ON by changing FIPS message 8235 from a category-E FIPS message to a severity-S compiler diagnostic message.

- Severity-E messages can be raised to severity S, but not lowered to severity I or W, because an error condition has occurred in the program.
- Severity-S and severity-U messages cannot be changed to have a different severity.

You can request suppression of compiler messages as follows:

- I, W, and FIPS messages can be suppressed.
- E and S messages cannot be suppressed.

#### related references

[“Severity codes for compiler diagnostic messages” on page 263](#)

[“FLAGSTD” on page 309](#)

[“Effect of message customization on compilation return code” on page 695](#)

## Effect of message customization on compilation return code

If you use a MSGEXIT module, the final return code from the compilation of a program could be affected as described below.

If you change the severity of a message, the return code from the compilation might also be changed. For example, if a compilation produces one diagnostic message, and it is a severity-E message, the compilation return code would normally be 8. But if the MSGEXIT module changes the severity of that message to severity S, then the return code from compilation would be 12.

If you suppress a message, the return code from the compilation is no longer affected by the severity of that message. For example, if a compilation produces one diagnostic message, and it is a severity-W message, the compilation return code would normally be 4. But if the MSGEXIT module suppresses that message, then the return code from compilation would be 0.

#### related tasks

[“Customizing compiler-message severities” on page 693](#)

#### related references

[“Severity codes for compiler diagnostic messages” on page 263](#)

## Example: MSGEXIT user exit

The following example shows a MSGEXIT user-exit module that changes message severities and suppresses messages. This example is included with Enterprise COBOL V6 in the SIGYSAMP dataset, in member IGYMSGXT.

For helpful tips about using a message-exit module, see the comments within the code.

```
*****
* IGYMSGXT - Sample COBOL program for MSGEXIT *
*****
*
* IBM Enterprise COBOL for z/OS *
*          Version 6 Release 1 Modification 0 *
*
* LICENSED MATERIALS - PROPERTY OF IBM. *
*
* 5655-EC6 COPYRIGHT IBM CORP. 2016 *
* ALL RIGHTS RESERVED *
*
* US GOVERNMENT USERS RESTRICTED RIGHTS - USE, *
* DUPLICATION OR DISCLOSURE RESTRICTED BY GSA *
* ADP SCHEDULE CONTRACT WITH IBM CORP. *
*
*****
* Function: This is a SAMPLE user exit for the MSGEXIT *
*           suboption of the EXIT compiler option. This exit *
*           can be used to customize the severity of or *
*           suppress compiler diagnostic messages and FIPS *
*           messages. This example program includes several *
*           sample customizations to show how customizations *
```

```

*          are done. If you do not want the sample          *
*          customizations then either delete the unwanted   *
*          lines of code or comment them out with a comment *
*          indicator in column 7 (*).                        *
*-----*
*
*  USAGE NOTE: To use this user exit program, make the      *
*              link-edited load module available to your    *
*              compiles that will use the MSGEXIT suboption *
*              of the EXIT compiler option. Also, the name   *
*              should be changed, since IBM recommends that *
*              you avoid having programs with names that     *
*              start with IGY.                               *
*              Sample steps to take:                        *
*              1) Make your customizations                  *
*              2) Change program name (E.G. MYEXIT)         *
*              3) Compile and link into a dataset           *
*              4) Include that dataset in your compile      *
*                 JCL concatenation for the compile step.   *
*                 If you link into USER.COBOLLIB:          *
*
*              //COBOL.STEPLIB DD DSNAME=SYS1.SIGYCOMP,DISP=SHR *
*              //              DD DSNAME=USER.COBOLLIB,DISP=SHR *
*
*              5) Finally, compile your programs with the   *
*                 EXIT compiler option, EG:                 *
*                 EXIT(MSGEXIT(MYEXIT))                    *
*
*  COMPILE NOTE: Compile this program with NOEXIT.         *
*
*****
Id Division.
Program-Id. IGYMSGXT.
Data Division.

Working-Storage Section.

*****
*
*  Local variables.
*
*****

77 EXIT-TYPEN          PIC 9(4).
77 EXIT-DEFAULT-SEV-FIPS PIC X.

*****
*
*  Definition of the User-Exit Parameter List, which is
*  passed from the COBOL compiler to the user-exit module.
*
*****

Linkage Section.
01 EXIT-TYPE          PIC 9(4)    COMP.
01 EXIT-OPERATION     PIC 9(4)    COMP.
01 EXIT-RETURNCODE    PIC 9(9)    COMP.
01 EXIT-WORK-AREA.
   02 EXIT-WORK-AREA-PTR OCCURS 6  POINTER.
01 EXIT-DUMMY         POINTER.
01 EXIT-MESSAGE-PARMS.
   02 EXIT-MESSAGE-NUM PIC 9(4)    COMP.
   02 EXIT-DEFAULT-SEV PIC 9(4)    COMP.
   02 EXIT-USER-SEV    PIC S9(4)   COMP.
01 EXIT-STRING.
   02 EXIT-STR-LEN PIC 9(4)    COMP.
   02 EXIT-STR-TXT PIC X(64).

*****
*****
*
*  Begin PROCEDURE DIVISION
*
*  Check parameters and perform the operation requested.
*
*****
*****

Procedure Division Using EXIT-TYPE          EXIT-OPERATION
                        EXIT-RETURNCODE     EXIT-WORK-AREA
                        EXIT-DUMMY           EXIT-MESSAGE-PARMS

```

```

EXIT-STRING      EXIT-DUMMY
EXIT-DUMMY       EXIT-DUMMY.

Compute EXIT-RETURNCODE = 0

Evaluate TRUE

*****
* Handle a bad invocation of this exit by the compiler.      *
* This could happen if this routine was used for one of the  *
* other EXITS, such as INEXIT, PRTEXIT or LIBEXIT.           *
*****
When EXIT-TYPE Not = 6
    Move EXIT-TYPE to EXIT-TYPEN
    Display '**** Invalid exit routine identifier'
    Display '**** EXIT TYPE = ' EXIT-TYPE
    Compute EXIT-RETURNCODE = 16

*****
* Handle the OPEN call to this exit by the compiler          *
* Display the exit string (str5 in syntax diagram) from      *
* the EXIT(MSGEXIT('str5',mod5)) option specification.      *
*****
When EXIT-OPERATION = 0
* Display 'Opening MSGEXIT'
* If EXIT-STR-LEN Not Zero Then
*     Display ' str5 len = ' EXIT-STR-LEN
*     Display ' str5 = ' EXIT-STR-TXT(1:EXIT-STR-LEN)
* End-If
Continue

*****
* Handle the CLOSE call to this exit by the compiler          *
*****
When EXIT-OPERATION = 1
* Display 'Closing MSGEXIT'
Goback

*****
* Handle the customize message severity call to this exit    *
* Display information about every customized severity.        *
*****
When EXIT-OPERATION = 5
* Display 'MSGEXIT called with MSGSEV'
If EXIT-MESSAGE-NUM < 8000 Then
    Perform Error-Messages-Severity
Else
    Perform FIPS-Messages-Severity
End-If

* If EXIT-RETURNCODE = 4 Then
*     Display '>>> Customizing message ' EXIT=MESSAGE-NUM
*     ' with new severity ' EXIT=USER-SEV ' <<<<'
* If EXIT-MESSAGE-NUM > 8000 Then
*     Display 'FIPS sev = ' EXIT-DEFAULT-SEV-FIPS '<<<<'
* End-If
* End-If

*****
* Handle a bad invocation of this exit by the compiler.      *
* The compiler should not invoke this exit with EXIT-TYPE = 6 *
* and an opcode other than 0, 1, or 5. This should not happen *
* and IBM service should be contacted if it does.           *
*****
When Other
    Display '**** Invalid MSGEXIT routine operation '
    Display '**** EXIT OPCODE = ' EXIT-OPERATION
    Compute EXIT-RETURNCODE = 16

End-Evaluate

Goback.

*****
* ERROR MESSAGE PROCESSOR                                     *
*****
Error-Messages-Severity.

* Assume message severity will be customized...
Compute EXIT-RETURNCODE = 4

Evaluate EXIT-MESSAGE-NUM

```

```

*****
*   Change severity of message 1154(W) to 12 ('S')
*   This is the case of redefining a large item
*   with a smaller item, IBM Req # MR0904063236
*****
      When(1154)
        Compute EXIT-USER-SEV = 12

*****
*   Modify the severity of RULES messages to enforce coding
*   standards or highlight coding that you want to avoid.
*   Here are the message numbers and what they flag:
*   1348 RULES(NOEVENTPACK)      Even digit packed-decimal items
*   1353 RULES(NOSLACKBYTES)     Slack bytes within records
*   1379 RULES(NOSLACKBYTES)     Slack bytes between records
*   2159 RULES(NOENDPERIOD)      Cond stmt terminated by period
*   2224 RULES(NOLAXPERF)        Ineff. type for PERFORM VARYING
*   2246 RULES(NOLAXPERF)        Ineff. type for subscript
*   2247 RULES(NOLAXPERF)        Compiler option NOAWO in effect
*   2248 RULES(NOLAXPERF)        Option ARITH(EXTEND) in effect
*   2249 RULES(NOLAXPERF)        Option NOBLOCK0 in effect
*   2250 RULES(NOLAXPERF)        Option NOFASTSRT in effect
*   2251 RULES(NOLAXPERF)        Option NUMPROC(NOPFD) in effect
*   2252 RULES(NOLAXPERF)        Option OPTIMIZE(0) in effect
*   2253 RULES(NOLAXPERF)        Option SSRANGE in effect
*   2254 RULES(NOLAXPERF)        Option THREAD in effect
*   2255 RULES(NOLAXPERF)        Option TRUNC(STD) in effect
*   2256 RULES(NOLAXPERF)        Option TRUNC(BIN) in effect
*   3084 RULES(NOLAXPERF)        Ineff. type for arith sender
*   3123 RULES(NOLAXPERF)        Lots of padding in alph MOVE
*
*****
      When(1348)          >> Disallow even-digit Comp-3
        Compute EXIT-USER-SEV = 12
      When(1353) When(1379) >> Disallow slack bytes
        Compute EXIT-USER-SEV = 12
      When(2159)          >> Disallow period-termination
        Compute EXIT-USER-SEV = 12  >> of conditional stmts
*   Highlight poorly performing COBOL features
      When(2224)          >> Ineff. type for PERFORM VARYING
      When(2246)          >> Ineff. type for subscript
      When(2247)          >> Compiler option NOAWO in effect
      When(2248)          >> Option ARITH(EXTEND) in effect
      When(2249)          >> Option NOBLOCK0 in effect
      When(2250)          >> Option NOFASTSRT in effect
      When(2251)          >> Option NUMPROC(NOPFD) in effect
      When(2252)          >> Option OPTIMIZE(0) in effect
      When(2253)          >> Option SSRANGE in effect
      When(2254)          >> Option THREAD in effect
      When(2255)          >> Option TRUNC(STD) in effect
      When(2256)          >> Option TRUNC(BIN) in effect
      When(3084)          >> Ineff. type for arith sender
      When(3123)          >> Lots of padding in alph MOVE
        Compute EXIT-USER-SEV = 8

*****
*   Change severity of messages 3178(I) to highlight File
*   Definitions that could lead to wrong-length read conditions.
*   Message 3178 is issued when the length of the shortest
*   record description is less than the FROM integer in the
*   RECORD IS VARYING clause, and when the length of the
*   longest record description is greater than the TO integer
*   in the RECORD IS VARYING clause.
*****
      When(3178)
        Compute EXIT-USER-SEV = 8

*****
*   Change severity of messages 3188(W) and 3189(W)
*   to 12 ('S'). This is to force a fix for all
*   SEARCH ALL cases that might behave differently
*   between COBOL compilers previous to Enterprise
*   COBOL release V3R4 and later compilers suchas
*   Enterprise COBOL Version 4 Release 2.
*   Another way to handle this migration is to analyze all of
*   the warnings you get and then change them to I-level when
*   the analysis is complete.
*****
      When(3188) When(3189)
        Compute EXIT-USER-SEV = 12

```

```

*****
* Change severity of message 4019 to suppress this message.
* Message 4019 says 'Compiler option "OPTFILE" was specified, "
* but file SYSOPTF could not be opened. No options from a
* "SYSOPTF" file were used.
* This customization would allow users to specify OPTFILE
* as a default option and it would only have an affect
* if there is a SYSOPTF file present
*****
    When(4019)
        Compute EXIT-USER-SEV = -1

*****
* Change severity of 'optimization' messages to suppress them
* so that compilation Return Code can be zero (RC=0)
* 7300: The code from lines &2 in program '&1' can never
*       be executed and was therefore discarded.
* 7301: A zero base was raised to a zero power in a numeric
*       literal exponentiation. The result was set to 1.
* 7302: A zero base was raised to a negative power in a numeric
*       literal exponentiation. The result was set to 0.
* 7304: An exception "&1" occurred while processing numeric
*       literals. The result of the operation was set to zero.
* 7307: This statement may cause a program exception at execution
*       time.
* 7309: There may be a loop from the "PERFORM" statement at "
*       "PERFORM (line &1)" to itself.
* 7312: Procedure starting at 'proc-name' (line 'num') was
*       copied one or more times to be inlined for PERFORM
*       statements. xxx total bytes were generated from
*       copying that procedure.
*****
    When(7300) When(7301) When(7302) When(7304)
    When(7307) When(7309) When(7312)
        Compute EXIT-USER-SEV = -1    *> Suppress the messages

*****
* Change severity of message 7311(W) to 12 ('S'). This is the *
* case of INITCHECK messages about uninitialized data items. *
*****
    When(7311)
        Compute EXIT-USER-SEV = 12

*****
* Message severity Not customized
*****
    When Other
        Compute EXIT-RETURNCODE = 0

    End-Evaluate
    .
*****
* FIPS MESSAGE PROCESSOR *
*****
    Fips-Messages-Severity.

* Assume message severity will be customized...
    Compute EXIT-RETURNCODE = 4

* Convert numeric FIPS(FLAGSTD) 'category' to character
* See the Programming Guide for description of FIPS category

    EVALUATE EXIT-DEFAULT-SEV
        When 81
            MOVE 'D' To EXIT-DEFAULT-SEV-FIPS
        When 82
            MOVE 'E' To EXIT-DEFAULT-SEV-FIPS
        When 83
            MOVE 'H' To EXIT-DEFAULT-SEV-FIPS
        When 84
            MOVE 'I' To EXIT-DEFAULT-SEV-FIPS
        When 85
            MOVE 'N' To EXIT-DEFAULT-SEV-FIPS
        When 86
            MOVE 'O' To EXIT-DEFAULT-SEV-FIPS
        When 87
            MOVE 'Q' To EXIT-DEFAULT-SEV-FIPS
        When 88
            MOVE 'S' To EXIT-DEFAULT-SEV-FIPS
        When Other
            Continue
    End-Evaluate

```

```

*****
* Example of using FIPS category to force coding
* restrictions. This is not a recommendation!
*   Change severity of all OBSOLETE item FIPS
*   messages to 'S'
*****
*   If EXIT-DEFAULT-SEV-FIPS = '0' Then
*       Display '>>>> Default customizing FIPS category '
*       EXIT-DEFAULT-SEV-FIPS ' msg ' EXIT-MESSAGE-NUM '<<<<'
*       Compute EXIT-USER-SEV = 12
*   End-If

      Evaluate EXIT-MESSAGE-NUM
*****
*       Change severity of message 8062(0) to 8 ('E')
*       8062 = GO TO without proc name
*****
      When(8062)
          Compute EXIT-USER-SEV = 8

*****
*       Change severity of message 8193(E) to 0('I')
*       8193 = GOBACK
*****
      When(8193)
          Compute EXIT-USER-SEV = 0

*****
*       Change severity of message 8235(E) to 8 (Error)
*       to disallow Complex Occurs Depending On
*       8235 = Complex Occurs Depending On
*****
      When(8235)
          Compute EXIT-USER-SEV = 08

*****
*       Change severity of message 8270(0) to -1 (Suppress)
*       8270 = SERVICE LABEL
*****
      When(8270)
          Compute EXIT-USER-SEV = -1

*****
*       Message severity Not customized
*****
      When Other
          For the default set '0' to 'S' case...
          If EXIT-USER-SEV = 12 Then
              Compute EXIT-RETURNCODE = 4
          Else
              Compute EXIT-RETURNCODE = 0
          End-If

      End-Evaluate

      END PROGRAM IGYMSGXT.

```

## Error handling for exit modules

The conditions described below can occur during processing of the user exits.

### Exit load failure:

Message IGYSI5207-U is written to the operator if a LOAD request for any of the user exits fails:

An error occurred while attempting to load user exit *exit-name*.

### Exit open failure:

Message IGYSI5208-U is written to the operator if an OPEN request for any of the user exits fails:

An error occurred while attempting to open user exit *exit-name*.

### PRTEXT PUT failure:

- Message IGYSI5203-U is written to the listing:

```
A PUT request to the PRTEXT user exit failed with return code nn.
```

- Message IGYSI5217-U is written to the operator:

```
An error occurred in PRTEXT user exit exit-name. Compiler terminated.
```

### **SYSIN GET failures:**

The following messages might be written to the listing:

- IGYSI5204-U:

```
The record address was not set by the exit-name user exit.
```

- IGYSI5205-U:

```
A GET request from the INEXIT user exit failed with return code nn.
```

- IGYSI5206-U:

```
The record length was not set by the exit-name user exit.
```

### **ADEXIT PUT failure:**

- Message IGYSI5225-U is written to the operator:

```
An error occurred in ADEXIT user exit exit-name. Compiler terminated.
```

- Message IGYSI5226-U is written to the listing:

```
A PUT request to the ADEXIT user exit failed with return code nn.
```

### **MSGEXIT failures:**

**Customization failure:** Message IGYPP5293-U is written to the listing if an unsupported severity change or unsupported message suppression is attempted:

```
MSGEXIT user exit exit-name specified a message severity customization that is not supported. The message number, default severity, and user-specified severity were: mm, ds, us. Change MSGEXIT user exit exit-name to correct this error.
```

**General failure:** Message IGYPP5064-U is written to the listing if the MSGEXIT module sets the return code to a nonzero value other than 4:

```
A call to the MSGEXIT user exit routine exit-name failed with return code nn.
```

In the MSGEXIT messages, the two characters *PP* indicate the phase of the compiler that issued the message that resulted in a call to the MSGEXIT module.

#### **related tasks**

[“Customizing compiler-message severities” on page 693](#)

## **Using the EXIT compiler option with CICS, SQL and SQLIMS statements**

When you compile using suboptions of the EXIT compiler option, and your program contains EXEC CICS, EXEC SQL, or EXEC SQLIMS statements, the actions that you can take in the exit modules depend on

whether you use the separate CICS translator and DB2 precompiler, or the integrated CICS translator and DB2 coprocessor.

If the program contains EXEC SQLIMS statements, the actions that you can take in the exit modules are the actions that are listed for the integrated translator.

The following table shows which actions you can take in the exit modules depending on whether you use the integrated or separate translators.

<b>Table 115. Actions possible in exit modules for CICS, SQL and SQLIMS statements</b>			
<b>Compile with suboption</b>	<b>Translated with integrated or separate CICS and DB2 translators?</b>	<b>Possible actions</b>	<b>Comments</b>
INEXIT	Integrated	Can process EXEC CICS, EXEC SQL, and EXEC SQLIMS statements in the INEXIT module	The INEXIT module does not get control of the COBOL statements that are generated for the EXEC statements.
	Separate	Can process the COBOL statements that are generated for the EXEC statements in the INEXIT module	You can change the generated statements in the INEXIT module, but doing so is not supported by IBM.
LIBEXIT	Integrated	Can process in the LIBEXIT module the statements that are brought in by the EXEC SQL INCLUDE and EXEC SQLIMS INCLUDE statements. Can process EXEC CICS source statements in the LIBEXIT module.	EXEC SQL INCLUDE and EXEC SQLIMS INCLUDE statements are processed like COBOL COPY statements.
	Separate	Can process the COBOL statements that are generated for the EXEC CICS statements in the LIBEXIT module	You can process the input statements that are brought in by the EXEC SQL INCLUDE and SQLIMS INCLUDE statements only by using the INEXIT suboption.
PRTEXTIT	Integrated	Can process the EXEC CICS , EXEC SQL, and EXEC SQLIMS source statements from the SOURCE listing in the PRTEXTIT module	The PRTEXTIT module does not have access to the COBOL statements that are generated.
	Separate	Can process the COBOL SOURCE listing statements that are generated for the EXEC statements in the PRTEXTIT module	
ADEXIT	Integrated	Can process the EXEC CICS, EXEC SQL, and EXEC SQLIMS source statements in the ADEXIT module	The ADEXIT module does not have access to the COBOL statements that are generated.
	Separate	Can process the COBOL SYSADATA statements that are generated for the EXEC statements in the ADEXIT module	

<i>Table 115. Actions possible in exit modules for CICS, SQL and SQLIMS statements (continued)</i>			
<b>Compile with suboption</b>	<b>Translated with integrated or separate CICS and DB2 translators?</b>	<b>Possible actions</b>	<b>Comments</b>
MSGEXIT	Integrated	Can process CICS and DB2 messages in the MSGEXIT module	
	Separate	Cannot process CICS and DB2 messages in the MSGEXIT module	Messages from CICS are shown in the separate CICS translator listing; messages from DB2 are shown in the DB2 precompiler listing.

#### **related concepts**

[“Integrated CICS translator” on page 412](#)

[“DB2 coprocessor” on page 417](#)

#### **related tasks**

[“Compiling with the CICS option” on page 411](#)

[“Compiling with the SQL option” on page 421](#)

#### **related references**

[“Processing of INEXIT” on page 684](#)

[“Processing of LIBEXIT” on page 685](#)

[“Processing of PRTEXT” on page 688](#)

[“Processing of ADEXIT” on page 690](#)

[“Processing of MSGEXIT” on page 691](#)



## Appendix F. JNI.cpy copybook

This listing shows the JNI.cpy copybook, which you can use to access the Java Native Interface (JNI) services from your COBOL programs.

JNI.cpy contains sample COBOL data definitions that correspond to the Java JNI types, and contains JNINativeInterface, the JNI environment structure that contains function pointers for accessing the JNI callable services.

JNI.cpy is in the z/OS UNIX file system in the include subdirectory of the COBOL install directory (typically /usr/lpp/cobol/include). JNI.cpy is analogous to the header file jni.h that C programmers use to access the JNI.

```
*****
* COBOL declarations for Java native method interoperation      *
*                                                                 *
* To use the Java Native Interface callable services from a     *
* COBOL program:                                                *
* 1) Use a COPY statement to include this file into the         *
*    the Linkage Section of the program, e.g.                  *
*    Linkage Section.                                          *
*    Copy JNI                                                  *
* 2) Code the following statements at the beginning of the     *
*    Procedure Division:                                       *
*    Set address of JNIEnv to JNIEnvPtr                        *
*    Set address of JNINativeInterface to JNIEnv               *
*****
*
* Sample JNI type definitions in COBOL
*
*01 jboolean1 pic X.
* 88 jboolean1-true value X'01' through X'FF'.
* 88 jboolean1-false value X'00'.
*
*01 jbyte1 pic X.
*
*01 jchar1 pic N usage national.
*
*01 jshort1 pic s9(4) comp-5.
*01 jint1 pic s9(9) comp-5.
*01 jlong1 pic s9(18) comp-5.
*
*01 jfloat1 comp-1.
*01 jdouble1 comp-2.
*
*01 jobject1 object reference.
*01 jclass1 object reference.
*01 jstring1 object reference jstring.
*01 jarray1 object reference jarray.
*
*01 jbooleanArray1 object reference jbooleanArray.
*01 jbyteArray1 object reference jbyteArray.
*01 jcharArray1 object reference jcharArray.
*01 jshortArray1 object reference jshortArray.
*01 jintArray1 object reference jintArray.
*01 jlongArray1 object reference jlongArray.
*01 floatArray1 object reference floatArray.
*01 jdoubleArray1 object reference jdoubleArray.
*01 jobjectArray1 object reference jobjectArray.

* Possible return values for JNI functions.
* 01 JNI-RC pic S9(9) comp-5.
* success
* 88 JNI-OK value 0.
* unknown error
* 88 JNI-ERR value -1.
* thread detached from the VM
* 88 JNI-EDETACHED value -2.
* JNI version error
* 88 JNI-EVERSION value -3.
* not enough memory
* 88 JNI-ENOMEM value -4.
```

```

* VM already created
  88 JNI-EEXIST    value -5.
* invalid arguments
  88 JNI-EINVAL    value -6.

* Used in ReleaseScalarArrayElements
  01 releaseMode pic s9(9) comp-5.
    88 JNI-COMMIT value 1.
    88 JNI-ABORT  value 2.

  01 JNIenv pointer.

* JNI Native Method Interface - environment structure.
  01 JNINativeInterface.
    02 pointer.
    02 pointer.
    02 pointer.
    02 pointer.
    02 GetVersion                function-pointer.
    02 DefineClass               function-pointer.
    02 FindClass                 function-pointer.
    02 FromReflectedMethod      function-pointer.
    02 FromReflectedField       function-pointer.
    02 ToReflectedMethod        function-pointer.
    02 GetSuperclass             function-pointer.
    02 IsAssignableFrom          function-pointer.
    02 ToReflectedField         function-pointer.
    02 Throw                     function-pointer.
    02 ThrowNew                  function-pointer.
    02 ExceptionOccurred         function-pointer.
    02 ExceptionDescribe         function-pointer.
    02 ExceptionClear            function-pointer.
    02 FatalError                function-pointer.
    02 PushLocalFrame            function-pointer.
    02 PopLocalFrame             function-pointer.
    02 NewGlobalRef              function-pointer.
    02 DeleteGlobalRef           function-pointer.
    02 DeleteLocalRef            function-pointer.
    02 IsSameObject              function-pointer.
    02 NewLocalRef               function-pointer.
    02 EnsureLocalCapacity       function-pointer.
    02 AllocObject               function-pointer.
    02 NewObject                 function-pointer.
    02 NewObjectV                function-pointer.
    02 NewObjectA                function-pointer.
    02 GetObjectClass             function-pointer.
    02 IsInstanceOf              function-pointer.
    02 GetMethodID               function-pointer.
    02 CallObjectMethod          function-pointer.
    02 CallObjectMethodV         function-pointer.
    02 CallObjectMethodA         function-pointer.
    02 CallBooleanMethod         function-pointer.
    02 CallBooleanMethodV        function-pointer.
    02 CallBooleanMethodA        function-pointer.
    02 CallByteMethod            function-pointer.
    02 CallByteMethodV           function-pointer.
    02 CallByteMethodA           function-pointer.
    02 CallCharMethod            function-pointer.
    02 CallCharMethodV           function-pointer.
    02 CallCharMethodA           function-pointer.
    02 CallShortMethod           function-pointer.
    02 CallShortMethodV          function-pointer.
    02 CallShortMethodA          function-pointer.
    02 CallIntMethod             function-pointer.
    02 CallIntMethodV            function-pointer.
    02 CallIntMethodA            function-pointer.
    02 CallLongMethod            function-pointer.
    02 CallLongMethodV           function-pointer.
    02 CallLongMethodA           function-pointer.
    02 CallFloatMethod           function-pointer.
    02 CallFloatMethodV          function-pointer.
    02 CallFloatMethodA          function-pointer.
    02 CallDoubleMethod          function-pointer.
    02 CallDoubleMethodV         function-pointer.
    02 CallDoubleMethodA         function-pointer.
    02 CallVoidMethod            function-pointer.
    02 CallVoidMethodV           function-pointer.
    02 CallVoidMethodA           function-pointer.
    02 CallNonvirtualObjectMethod function-pointer.
    02 CallNonvirtualObjectMethodV function-pointer.
    02 CallNonvirtualObjectMethodA function-pointer.
    02 CallNonvirtualBooleanMethod function-pointer.

```

02	CallNonvirtualBooleanMethodV	function-pointer.
02	CallNonvirtualBooleanMethodA	function-pointer.
02	CallNonvirtualByteMethod	function-pointer.
02	CallNonvirtualByteMethodV	function-pointer.
02	CallNonvirtualByteMethodA	function-pointer.
02	CallNonvirtualCharMethod	function-pointer.
02	CallNonvirtualCharMethodV	function-pointer.
02	CallNonvirtualCharMethodA	function-pointer.
02	CallNonvirtualShortMethod	function-pointer.
02	CallNonvirtualShortMethodV	function-pointer.
02	CallNonvirtualShortMethodA	function-pointer.
02	CallNonvirtualIntMethod	function-pointer.
02	CallNonvirtualIntMethodV	function-pointer.
02	CallNonvirtualIntMethodA	function-pointer.
02	CallNonvirtualLongMethod	function-pointer.
02	CallNonvirtualLongMethodV	function-pointer.
02	CallNonvirtualLongMethodA	function-pointer.
02	CallNonvirtualFloatMethod	function-pointer.
02	CallNonvirtualFloatMethodV	function-pointer.
02	CallNonvirtualFloatMethodA	function-pointer.
02	CallNonvirtualDoubleMethod	function-pointer.
02	CallNonvirtualDoubleMethodV	function-pointer.
02	CallNonvirtualDoubleMethodA	function-pointer.
02	CallNonvirtualVoidMethod	function-pointer.
02	CallNonvirtualVoidMethodV	function-pointer.
02	CallNonvirtualVoidMethodA	function-pointer.
02	GetFieldID	function-pointer.
02	GetObjectField	function-pointer.
02	GetBooleanField	function-pointer.
02	GetByteField	function-pointer.
02	GetCharField	function-pointer.
02	GetShortField	function-pointer.
02	GetIntField	function-pointer.
02	GetLongField	function-pointer.
02	GetFloatField	function-pointer.
02	GetDoubleField	function-pointer.
02	SetObjectField	function-pointer.
02	SetBooleanField	function-pointer.
02	SetByteField	function-pointer.
02	SetCharField	function-pointer.
02	SetShortField	function-pointer.
02	SetIntField	function-pointer.
02	SetLongField	function-pointer.
02	SetFloatField	function-pointer.
02	SetDoubleField	function-pointer.
02	GetStaticMethodID	function-pointer.
02	CallStaticObjectMethod	function-pointer.
02	CallStaticObjectMethodV	function-pointer.
02	CallStaticObjectMethodA	function-pointer.
02	CallStaticBooleanMethod	function-pointer.
02	CallStaticBooleanMethodV	function-pointer.
02	CallStaticBooleanMethodA	function-pointer.
02	CallStaticByteMethod	function-pointer.
02	CallStaticByteMethodV	function-pointer.
02	CallStaticByteMethodA	function-pointer.
02	CallStaticCharMethod	function-pointer.
02	CallStaticCharMethodV	function-pointer.
02	CallStaticCharMethodA	function-pointer.
02	CallStaticShortMethod	function-pointer.
02	CallStaticShortMethodV	function-pointer.
02	CallStaticShortMethodA	function-pointer.
02	CallStaticIntMethod	function-pointer.
02	CallStaticIntMethodV	function-pointer.
02	CallStaticIntMethodA	function-pointer.
02	CallStaticLongMethod	function-pointer.
02	CallStaticLongMethodV	function-pointer.
02	CallStaticLongMethodA	function-pointer.
02	CallStaticFloatMethod	function-pointer.
02	CallStaticFloatMethodV	function-pointer.
02	CallStaticFloatMethodA	function-pointer.
02	CallStaticDoubleMethod	function-pointer.
02	CallStaticDoubleMethodV	function-pointer.
02	CallStaticDoubleMethodA	function-pointer.
02	CallStaticVoidMethod	function-pointer.
02	CallStaticVoidMethodV	function-pointer.
02	CallStaticVoidMethodA	function-pointer.
02	GetStaticFieldID	function-pointer.
02	GetStaticObjectField	function-pointer.
02	GetStaticBooleanField	function-pointer.
02	GetStaticByteField	function-pointer.
02	GetStaticCharField	function-pointer.
02	GetStaticShortField	function-pointer.

02 GetStaticIntField	function-pointer.
02 GetStaticLongField	function-pointer.
02 GetStaticFloatField	function-pointer.
02 GetStaticDoubleField	function-pointer.
02 SetStaticObjectField	function-pointer.
02 SetStaticBooleanField	function-pointer.
02 SetStaticByteField	function-pointer.
02 SetStaticCharField	function-pointer.
02 SetStaticShortField	function-pointer.
02 SetStaticIntField	function-pointer.
02 SetStaticLongField	function-pointer.
02 SetStaticFloatField	function-pointer.
02 SetStaticDoubleField	function-pointer.
02 NewString	function-pointer.
02 GetStringLength	function-pointer.
02 GetStringChars	function-pointer.
02 ReleaseStringChars	function-pointer.
02 NewStringUTF	function-pointer.
02 GetStringUTFLength	function-pointer.
02 GetStringUTFChars	function-pointer.
02 ReleaseStringUTFChars	function-pointer.
02 GetArrayLength	function-pointer.
02 NewObjectArray	function-pointer.
02 GetObjectArrayElement	function-pointer.
02 SetObjectArrayElement	function-pointer.
02 NewBooleanArray	function-pointer.
02 NewByteArray	function-pointer.
02 NewCharArray	function-pointer.
02 NewShortArray	function-pointer.
02 NewIntArray	function-pointer.
02 NewLongArray	function-pointer.
02 NewFloatArray	function-pointer.
02 NewDoubleArray	function-pointer.
02 GetBooleanArrayElements	function-pointer.
02 GetByteArrayElements	function-pointer.
02 GetCharArrayElements	function-pointer.
02 GetShortArrayElements	function-pointer.
02 GetIntArrayElements	function-pointer.
02 GetLongArrayElements	function-pointer.
02 GetFloatArrayElements	function-pointer.
02 GetDoubleArrayElements	function-pointer.
02 ReleaseBooleanArrayElements	function-pointer.
02 ReleaseByteArrayElements	function-pointer.
02 ReleaseCharArrayElements	function-pointer.
02 ReleaseShortArrayElements	function-pointer.
02 ReleaseIntArrayElements	function-pointer.
02 ReleaseLongArrayElements	function-pointer.
02 ReleaseFloatArrayElements	function-pointer.
02 ReleaseDoubleArrayElements	function-pointer.
02 GetBooleanArrayRegion	function-pointer.
02 GetByteArrayRegion	function-pointer.
02 GetCharArrayRegion	function-pointer.
02 GetShortArrayRegion	function-pointer.
02 GetIntArrayRegion	function-pointer.
02 GetLongArrayRegion	function-pointer.
02 GetFloatArrayRegion	function-pointer.
02 GetDoubleArrayRegion	function-pointer.
02 SetBooleanArrayRegion	function-pointer.
02 SetByteArrayRegion	function-pointer.
02 SetCharArrayRegion	function-pointer.
02 SetShortArrayRegion	function-pointer.
02 SetIntArrayRegion	function-pointer.
02 SetLongArrayRegion	function-pointer.
02 SetFloatArrayRegion	function-pointer.
02 SetDoubleArrayRegion	function-pointer.
02 RegisterNatives	function-pointer.
02 UnregisterNatives	function-pointer.
02 MonitorEnter	function-pointer.
02 MonitorExit	function-pointer.
02 GetJavaVM	function-pointer.
02 GetStringRegion	function-pointer.
02 GetStringUTFRegion	function-pointer.
02 GetPrimitiveArrayCritical	function-pointer.
02 ReleasePrimitiveArrayCritical	function-pointer.
02 GetStringCritical	function-pointer.
02 ReleaseStringCritical	function-pointer.
02 NewWeakGlobalRef	function-pointer.
02 DeleteWeakGlobalRef	function-pointer.
02 ExceptionCheck	function-pointer.

**related tasks**

[“Compiling OO applications under z/OS UNIX” on page 273](#)

[“Accessing JNI services” on page 601](#)



## Appendix G. COBOL SYSADATA file contents

When you use the ADATA compiler option, the compiler produces a file, the SYSADATA file, that contains additional program data. You can use this file instead of the compiler listing to extract information about the program. For example, you can extract information about the program for symbolic debugging tools or cross-reference tools.

[“Example: SYSADATA” on page 713](#)

### related references

[“ADATA” on page 288](#)

[“Compiler options that affect the SYSADATA file” on page 711](#)

[“SYSADATA record types” on page 712](#)

[“SYSADATA record descriptions” on page 714](#)

## Compiler options that affect the SYSADATA file

Several compiler options could affect the contents of the SYSADATA file.

### COMPILE

NOCOMPILE (W|E|S) might stop compilation prematurely, resulting in the loss of specific messages.

### EXIT

INEXIT prohibits identification of the compilation source file.

### LANGUAGE

LANGUAGE controls the message text (Uppercase English, Mixed-Case English, or Japanese). Selection of Japanese could result in DBCS characters written to Error Identification records.

### NUM

NUM causes the compiler to use the contents of columns 1-6 in the source records for line numbering, rather than using generated sequence numbers. Any invalid (nonnumeric) or out-of-sequence numbers are replaced with a number one higher than that of the previous record.

### TEST

TEST causes additional object text records to be created that also affect the contents of the SYSADATA file.

The SYSADATA fields shown in the following table contain line numbers whose contents differ depending on the NUM | NONUM setting.

Type	Field	Record
0020	AE_LINE	External Symbol record
0030	ATOK_LINE	Token record
0032	AF_STMT	Source Error record
0038	AS_STMT	Source record
0039	AS_REP_EXP_SLIN	COPY REPLACING record
0039	AS_REP_EXP_ELIN	COPY REPLACING record
0042	ASY_STMT	Symbol record
0044	AX_DEFN	Symbol Cross Reference record
0044	AX_STMT	Symbol Cross Reference record
0046	AN_STMT	Nested Program record

The Type 0038 Source record contains two fields that relate to line numbers and record numbers:

- AS\_STMT contains the compiler line number in both the NUM and NONUM cases.
- AS\_CUR\_REC# contains the physical source record number.

These two fields can always be used to correlate the compiler line numbers, used in all the above fields, with physical source record numbers.

The remaining compiler options have no direct effect on the SYSADATA file, but might trigger generation of additional error messages associated with the specific option, such as FLAGSTD or SSRANGE.

[“Example: SYSADATA” on page 713](#)

#### related references

[“SYSADATA record types” on page 712](#)

[“COMPILE” on page 297](#)

[“EXIT” on page 305](#)

[“LANGUAGE” on page 313](#)

[“NUMBER” on page 320](#)

[“TEST” on page 340](#)

## SYSADATA record types

The SYSADATA file contains records classified into different record types. Each type of record provides information about the COBOL program being compiled.

Each record consists of two parts:

- A 12-byte header section, which has the same structure for all record types, and contains the record code that identifies the type of record
- A variable-length data section, which varies by record type

<i>Table 116. SYSADATA record types</i>	
Record type	What it does
<a href="#">“Job identification record: X'0000” on page 717</a>	Provides information about the environment used to process the source data
<a href="#">“ADATA identification record: X'0001” on page 718</a>	Provides common information about the records in the SYSADATA file
<a href="#">“Compilation unit start   end record: X'0002” on page 718</a>	Marks the beginning and ending of compilation units in a source file
<a href="#">“Options record: X'0010” on page 719</a>	Describes the compiler options used for the compilation
<a href="#">“External symbol record: X'0020” on page 729</a>	Describes all external names in the program, definitions, and references
<a href="#">“Parse tree record: X'0024” on page 730</a>	Defines a node in the parse tree of the program
<a href="#">“Token record: X'0030” on page 755</a>	Defines a source token
<a href="#">“Source error record: X'0032” on page 782</a>	Describes errors in source program statements
<a href="#">“Source record: X'0038” on page 782</a>	Describes a single source line
<a href="#">“COPY REPLACING record: X'0039” on page 783</a>	Describes an instance of text replacement as a result of a match of COPY . . . REPLACING <i>operand-1</i> with text in the copybook
<a href="#">“Symbol record: X'0042” on page 784</a>	Describes a single symbol defined in the program. There is one symbol record for each symbol defined in the program.

Table 116. <b>SYSADATA record types</b> (continued)	
Record type	What it does
<a href="#">“Symbol cross-reference record: X'0044'” on page 796</a>	Describes references to a single symbol
<a href="#">“Nested program record: X'0046'” on page 798</a>	Describes the name and nesting level of a program
<a href="#">“Library record: X'0060'” on page 798</a>	Describes the library files and members used from each library
<a href="#">“Statistics record: X'0090'” on page 799</a>	Describes the statistics about the compilation
<a href="#">“EVENTS record: X'0120'” on page 799</a>	EVENTS records provide compatibility with COBOL/370. The record format is identical with that in COBOL/370, with the addition of the standard ADATA header at the beginning of the record and a field indicating the length of the EVENTS record data.

## Example: SYSADATA

The following sample shows part of the listing of a COBOL program. If this COBOL program were compiled with the ADATA option, the records produced in the associated data file would be in the sequence shown in the table below.

000001	IDENTIFICATION DIVISION.	AD000020
000002	PROGRAM-ID. AD04202.	AD000030
000003	ENVIRONMENT DIVISION.	AD000040
000004	DATA DIVISION.	AD000050
000005	WORKING-STORAGE SECTION.	AD000060
000006	77 COMP3-FLD2 pic S9(3)v9.	AD000070
000007	PROCEDURE DIVISION.	AD000080
000008	STOP RUN.	

Type	Description
<b>X'0120'</b>	EVENTS Timestamp record
<b>X'0120'</b>	EVENTS Processor record
<b>X'0120'</b>	EVENTS File-ID record
<b>X'0120'</b>	EVENTS Program record
<b>X'0001'</b>	ADATA Identification record
<b>X'0000'</b>	Job Identification record
<b>X'0010'</b>	Options record
<b>X'0038'</b>	Source record for statement 1
<b>X'0038'</b>	Source record for statement 2
<b>X'0038'</b>	Source record for statement 3
<b>X'0038'</b>	Source record for statement 4
<b>X'0038'</b>	Source record for statement 5
<b>X'0038'</b>	Source record for statement 6
<b>X'0038'</b>	Source record for statement 7
<b>X'0038'</b>	Source record for statement 8

Type	Description
X'0020'	External Symbol record for AD04202
X'0044'	Symbol Cross Reference record for STOP
X'0044'	Symbol Cross Reference record for COMP3-FLD2
X'0044'	Symbol Cross Reference record for AD04202
X'0042'	Symbol record for AD04202
X'0042'	Symbol record for COMP3-FLD2
X'0090'	Statistics record
X'0120'	EVENTS FileEnd record

#### related references

[“SYSADATA record descriptions” on page 714](#)

## SYSADATA record descriptions

The formats of the records written to the associated data file are shown in the related references below.

In the fields described in each of the record types, these symbols occur:

#### C

Indicates character (EBCDIC or ASCII) data

#### H

Indicates 2-byte binary integer data

#### F

Indicates 4-byte binary integer data

#### A

Indicates 4-byte binary integer address and offset data

#### X

Indicates hexadecimal (bit) data or 1-byte binary integer data

No boundary alignments are implied by any data type, and the implied lengths above might be changed by the presence of a length indicator (Ln). All integer data is in big-endian or little-endian format depending on the indicator bit in the header flag byte. *Big-endian* format means that bit 0 is always the most significant bit and bit *n* is the least significant bit. *Little-endian* refers to "byte-reversed" integers as seen on Intel processors.

All undefined fields and unused values are reserved.

#### related references

[“Common header section” on page 715](#)

[“Job identification record: X'0000” on page 717](#)

[“ADATA identification record: X'0001” on page 718](#)

[“Compilation unit start | end record: X'0002” on page 718](#)

[“Options record: X'0010” on page 719](#)

[“External symbol record: X'0020” on page 729](#)

[“Parse tree record: X'0024” on page 730](#)

[“Token record: X'0030” on page 755](#)

[“Source error record: X'0032” on page 782](#)

[“Source record: X'0038” on page 782](#)

[“COPY REPLACING record: X'0039” on page 783](#)

[“Symbol record: X'0042” on page 784](#)

[“Symbol cross-reference record: X'0044” on page 796](#)

[“Nested program record: X'0046” on page 798](#)

“Library record: X'0060” on page 798  
“Statistics record: X'0090” on page 799  
“EVENTS record: X'0120” on page 799

## Common header section

---

The table below shows the format of the header section that is common for all record types. For MVS and VSE, each record is preceded by a 4-byte RDW (record-descriptor word) that is normally used only by access methods and stripped off by download utilities.

Table 117. <i>SYSADATA</i> common header section		
Field	Size	Description
Language code	XL1	<b>16</b> High Level Assembler
		<b>17</b> COBOL on all platforms
		<b>40</b> PL/I on supported platforms

Table 117. **SYSADATA common header section** (continued)

Field	Size	Description
Record type	HL2	<p>The record type, which can be any of the following ones:</p> <p><b>X'0000'</b> Job Identification record<sup>1</sup></p> <p><b>X'0001'</b> ADATA Identification record</p> <p><b>X'0002'</b> Compilation unit start/end record</p> <p><b>X'0010'</b> Options record<sup>1</sup></p> <p><b>X'0020'</b> External Symbol record</p> <p><b>X'0024'</b> Parse Tree record</p> <p><b>X'0030'</b> Token record</p> <p><b>X'0032'</b> Source Error record</p> <p><b>X'0038'</b> Source record</p> <p><b>X'0039'</b> COPY REPLACING record</p> <p><b>X'0042'</b> Symbol record</p> <p><b>X'0044'</b> Symbol Cross-Reference record</p> <p><b>X'0046'</b> Nested Program record</p> <p><b>X'0060'</b> Library record</p> <p><b>X'0090'</b> Statistics record<sup>1</sup></p> <p><b>X'0120'</b> EVENTS record</p>
Associated data architecture level	XL1	<p><b>3</b> Definition level for the header structure</p>
Flag	XL1	<p><b>.... ..1.</b> ADATA record integers are in little-endian (Intel) format</p> <p><b>.... ....1</b> This record is continued in the next record</p> <p><b>1111 11..</b> Reserved for future use</p>
Associated data record edition level	XL1	Used to indicate a new format for a specific record type, usually 0
Reserved	CL4	Reserved for future use

Table 117. **SYSADATA common header section** (continued)

Field	Size	Description
Associated data field length	HL2	The length in bytes of the data following the header
1. When a batch compilation (sequence of programs) is run with the ADATA option, there will be multiple Job Identification, Options, and Statistics records for each compilation.		

The mapping of the 12-byte header does not include the area used for the variable-length record-descriptor word required by the access method on MVS and VSE.

## Job identification record: X'0000'

The following table shows the contents of the job identification record.

Table 118. **SYSADATA job identification record**

Field	Size	Description
Date	CL8	The date of the compilation in the format YYYYMMDD
Time	CL4	The time of the compilation in the format HHMM
Product number	CL8	The product number of the compiler that produced the associated data file
Product version	CL8	The version number of the product that produced the associated data file, in the form V.R.M
BLD Level	CL8	The build level information (of the form PYMMDD) of the product that produced the associated data file
System ID	CL24	The system identification of the system on which the compilation was run
Job name	CL8	The MVS job name of the compilation job
Step name	CL8	The MVS step name of the compilation step
Proc step	CL8	The MVS procedure step name of the compilation procedure
Number of input files <sup>1</sup>	HL2	The number of input files recorded in this record. The following group of seven fields will occur <i>n</i> times depending on the value in this field.
...Input file number	HL2	The assigned sequence number of the file
...Input file name length	HL2	The length of the following input file name
...Volume serial number length	HL2	The length of the volume serial number
...Member name length	HL2	The length of the member name
...Input file name	CL( <i>n</i> )	The name of the input file for the compilation
...Volume serial number	CL( <i>n</i> )	The volume serial number of the (first) volume on which the input file resides
...Member name	CL( <i>n</i> )	Where applicable, the name of the member in the input file

Table 118. **SYSADATA job identification record** (continued)

Field	Size	Description
1. Where the number of input files would exceed the record size for the associated data file, the record is continued on the next record. The current number of input files (for that record) is stored in the record, and the record is written to the associated data file. The next record contains the rest of the input files. The count of the number of input files is a count for the current record.		

## ADATA identification record: X'0001'

The following table shows the contents of the ADATA identification record.

Table 119. **ADATA identification record**

Field	Size	Description
Time (binary)	XL8	Universal Time (UT) as a binary number of microseconds since midnight Greenwich Mean Time, with the low-order bit representing 1 microsecond. This time can be used as a time-zone-independent time stamp.  On Windows and AIX systems, only bytes 5-8 of the field are used as a fullword binary field that contains the time.
CCSID <sup>1</sup>	XL2	Coded Character Set Identifier
Character-set flags	XL1	<b>X'80'</b> EBCDIC (IBM-037) <b>X'40'</b> ASCII (IBM-1252)
Code-page name length	XL2	Length of the code-page name that follows
Code-page name	CL(n)	Name of the code page
1. The appropriate CCS flag will always be set. If the CCSID is set to nonzero, the code-page name length will be zero. If the CCSID is set to zero, the code-page name length will be nonzero and the code-page name will be present.		

## Compilation unit start | end record: X'0002'

The following table shows the contents of the compilation unit start|end record.

Table 120. **SYSADATA compilation unit start | end record**

Field	Size	Description
Type	HL2	Compilation unit type, which is one of the following options: <b>X'0000'</b> Start compilation unit <b>X'0001'</b> End compilation unit
Reserved	CL2	Reserved for future use
Reserved	FL4	Reserved for future use

## Options record: X'0010'

The following table shows the contents of the options record.

Table 121. <i>SYSADATA options record</i>		
Field	Size	Description
Option byte 0	XL1	<b>1111 1111</b> Reserved for future use
Option byte 1	XL1	<b>1... ..</b> Bit 1 = DECK, Bit 0 = NODECK  <b>.1... ..</b> Bit 1 = ADATA, Bit 0 = NOADATA  <b>..1. ....</b> Bit 1 = COLLSEQ (EBCDIC), Bit 0 = COLLSEQ (LOCALE   BINARY) (Windows and AIX only)  <b>...1 ....</b> Bit 1 = SEPOBJ, Bit 0 = NOSEPOBJ (Windows and AIX only)  <b>.... 1...</b> Bit 1 = NAME, Bit 0 = NONAME  <b>.... .1..</b> Bit 1 = OBJECT, Bit 0 = NOOBJECT  <b>.... ..1.</b> Bit 1 = SQL, Bit 0 = NOSQL  <b>.... ...1</b> Bit 1 = CICS, Bit 0 = NOCICS
Option byte 2	XL1	<b>1... ..</b> Bit 1 = OFFSET, Bit 0 = NOOFFSET  <b>.1... ..</b> Bit 1 = MAP, Bit 0 = NOMAP  <b>..1. ....</b> Bit 1 = LIST, Bit 0 = NOLIST  <b>...1 ....</b> Bit 1 = DBCSXREF, Bit 0 = NOBCSXREF  <b>.... 1...</b> Bit 1 = XREF (SHORT), Bit 0 = not XREF (SHORT). This flag should be used in combination with the flag at bit 7. XREF (FULL) is indicated by this flag being off and the flag at bit 7 being on.  <b>.... .1..</b> Bit 1 = SOURCE, Bit 0 = NOSOURCE  <b>.... ..1.</b> Bit 1 = VBREF, Bit 0 = NOVBREF  <b>.... ...1</b> Bit 1 = XREF, Bit 0 = not XREF. See also flag at bit 4 above.

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Option byte 3	XL1	<p><b>1... ..</b>            Bit 1 = FLAG imbedded diagnostics level specified (a value y is specified as in FLAG(x,y))</p> <p><b>.1... ..</b>            Bit 1 = FLAGSTD, Bit 0 = NOFLAGSTD</p> <p><b>..1. ....</b>            Bit 1 = NUM, Bit 0 = NONUM</p> <p><b>...1 ....</b>            Bit 1 = SEQUENCE, Bit 0 = NOSEQUENCE</p> <p><b>.... 1...</b>            Bit 1 = SOSI, Bit 0 = NOSOSI (Windows and AIX only)</p> <p><b>.... .1..</b>            Bit 1 = NSYMBOL (NATIONAL), Bit 0 = NSYMBOL (DBCS)</p> <p><b>.... ..1.</b>            Bit 1 = PROFILE, Bit 0 = NOPROFILE (AIX only)</p> <p><b>.... ...1</b>            Bit 1 = WORD, Bit 0 = NOWORD</p>
Option byte 4	XL1	<p><b>1... ..</b>            Bit 1 = ADV, Bit 0 = NOADV</p> <p><b>.1... ..</b>            Bit 1 = APOST, Bit 0 = QUOTE</p> <p><b>..1. ....</b>            Bit 1 = DYNAM, Bit 0 = NODYNAM</p> <p><b>...1 ....</b>            Bit 1 = AWO, Bit 0 = NOAWO</p> <p><b>.... 1...</b>            Bit 1 = RMODE specified, Bit 0 = RMODE (AUTO)</p> <p><b>.... .1..</b>            Bit 1 = RENT, Bit 0 = NORENT</p> <p><b>.... ..1.</b>            Bit 1 = RES: this flag will always be set on for COBOL.</p> <p><b>.... ...1</b>            Bit 1 = RMODE (24), Bit 0 = RMODE (ANY)</p>

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Option byte 5	XL1	<p><b>1... ..</b>  Bit 1 = SQLCCSID, Bit 0 = NOSQLCCSID</p> <p><b>.1... ..</b>  Bit 1 = OPT(1 2), Bit 0 = OPT(0)</p> <p><b>..1. ....</b>  Bit 1 = SQLIMS, Bit 0 = NOSQLIMS</p> <p><b>...1 ....</b>  Bit 1 = DBCS, Bit 0 = NODBCS</p> <p><b>.... 1...</b>  Bit 1 = AFP(VOLATILE), Bit 0 = AFP(NOVOLATILE)</p> <p><b>.... .1..</b>  Bit 1 = SSRANGE, Bit 0 = NOSSRANGE</p> <p><b>.... ..1.</b>  Bit 1 = TEST, Bit 0 = NOTEST</p> <p><b>.... ...1</b>  Bit 1 = PROBE, Bit 0 = NOPROBE (Windows only)</p>
Option byte 6	XL1	<p><b>1... ..</b>  Bit 1 = SRCFORMAT(EXTEND), Bit 0 = SRCFORMAT(COMPAT)</p> <p><b>..1. ....</b>  Bit 1 = NUMPROC(PFD), Bit 0 = NUMPROC(NOPFD)</p> <p><b>...1 ....</b>  Bit 1 = NUMCLS(ALT), Bit 0 = NUMCLS(PRIM)</p> <p><b>.... .1..</b>  Bit 1 = BINARY(S390), Bit 0 = BINARY(NATIVE) (Windows and AIX only)</p> <p><b>.... ..1.</b>  Bit 1 = TRUNC(STD), Bit 0 = TRUNC(OPT)</p> <p><b>.... ...1</b>  Bit 1 = ZWB, Bit 0 = NOZWB</p> <p><b>.1.. 1...</b>  Reserved for future use</p>
Option byte 7	XL1	<p><b>1... ..</b>  Bit 1 = ALLOWCBL, Bit 0 = NOALLOWCBL</p> <p><b>.1... ..</b>  Bit 1 = TERM, Bit 0 = NOTERM</p> <p><b>..1. ....</b>  Bit 1 = DUMP, Bit 0 = NODUMP</p> <p><b>.... ..1.</b>  Bit 1 = CURRENCY, Bit 0 = NOCURRENCY</p> <p><b>...1 11.1</b>  Reserved for future use</p>

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Option byte 8	XL1	<b>1... ..</b> Bit 1 = RULES, Bit 0 = NORULES <b>.1... ..</b> Bit 1 = OPTFILE, Bit 0 = not OPTFILE <b>..1. ....</b> Bit 1 = ADDR (64), Bit 0 = ADDR (32) (AIX only) <b>.... 1...</b> Bit 1 = BLOCK0, Bit 0 = NOBLOCK0 <b>.... ..1.</b> Bit 1 = DISPSIGN (SEP), Bit 0 = DISPSIGN (COMPAT) <b>.... ....1</b> Bit 1 = STGOPT, Bit 0 = NOSTGOPT <b>1..1 .1..</b> Reserved for future use
Option byte 9	XL1	<b>1... ..</b> Bit 1 = DATA (24), Bit 0 = DATA (31) <b>.1... ..</b> Bit 1 = FASTSRT, Bit 0 = NOFASTSRT <b>.... .1..</b> Bit 1 = THREAD, Bit 0 = NOTHREAD <b>..11 1.11</b> Reserved for future use
Option byte A	XL1	<b>1... ..</b> Bit 1 = HGPR (PRESERVE), Bit 0 = HGPR (NOPRESERVE) <b>.1... ..</b> Bit 1 = XMLPARSE (XMLSS), Bit 0 = XMLPARSE (COMPAT) <b>..1. ....</b> Bit 1 = MAP (DEC), Bit 0 = MAP (HEX) <b>...1....</b> Reserved <b>....1...</b> Bit 1 = SUPPRESS, Bit 0 = NOSUPPRESS <b>.....1..</b> Bit 1 = VSAMOPENFS (SUCC), BIT 0 = VSAMOPENFS (COMPAT) <b>.....11</b> Reserved for future use
Option byte B	XL1	<b>1111 1111</b> Reserved for future use

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Option byte C	XL1	<p><b>1... ..</b> Bit 1 = NCOLLSEQ (LOCALE) (Windows and AIX only)</p> <p><b>.1... ..</b> Reserved for future use</p> <p><b>..1. ....</b> Bit 1 = INTDATE (LILIAN), Bit 0 = INTDATE (ANSI)</p> <p><b>...1 ....</b> Bit 1 = NCOLLSEQ (BINARY) (Windows and AIX only)</p> <p><b>.... 1...</b> Bit 1 = CHAR (EBCDIC), Bit 0 = CHAR (NATIVE) (Windows and AIX only)</p> <p><b>.... .1..</b> Bit 1 = FLOAT (HEX), Bit 0 = FLOAT (NATIVE) (Windows and AIX only)</p> <p><b>.... ..1.</b> Bit 1 = COLLSEQ (BINARY) (Windows and AIX only)</p> <p><b>.... ...1</b> Bit 1 = COLLSEQ (LOCALE) (Windows and AIX only)</p>
Option byte D	XL1	<p><b>1... ..</b> Bit 1 = DLL, Bit 0 = NODLL</p> <p><b>.1... ..</b> Bit 1 = EXPORTALL, Bit 0 = NOEXPORTALL</p> <p><b>..1. ....</b> Bit 1 = CODEPAGE</p> <p><b>...1 ....</b> Bit 1 = SOURCEFORMAT (EXTEND), Bit 0 = SOURCEFORMAT (COMPAT) (Windows and AIX only)</p> <p><b>.... ..1.</b> Bit 1 = WSCLEAR, Bit 0 = NOWSCLEAR (Windows and AIX only)</p> <p><b>.... ...1</b> Bit 1 = BEOPT, Bit 0 = NOBEOPT (Windows and AIX only)</p> <p><b>.... 11..</b> Reserved for future use</p>
Option byte E	XL1	<p><b>1.....</b> Bit 1 = VLR (COMPAT), Bit 0 = VLR (STANDARD)</p> <p><b>.1... ..</b> Bit 1 = DIAGTRUNC, Bit 0 = NODIAGTRUNC</p> <p><b>.... .1..</b> Bit 1 = LSTFILE (UTF-8), Bit 0 = LSTFILE (LOCALE) (Windows and AIX only)</p> <p><b>.... ..1.</b> Bit 1 = MDECK, Bit 0 = NOMDECK</p> <p><b>.... ...1</b> Bit 1 = MDECK (NOCOMPILE)</p> <p><b>..11 1...</b> Reserved for future use</p>

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Option byte F	XL1	<p><b>1... ..</b> Bit 1 = DIVIDE (S390), Bit 0 = DIVIDE (NATIVE) (AIX Only)</p> <p><b>.1... ..</b> Bit 1 = COPYRIGHT, Bit 0 = NOCOPYRIGHT</p> <p><b>..1. ....</b> Bit 1 = QUALIFY (EXTEND), Bit 0 = QUALIFY (COMPAT)</p> <p><b>...1 ....</b> Bit 1 = SERVICE, Bit 0 = NOSERVICE</p> <p><b>.... 1...</b> Bit 1 = ZONEDATA (MIG)</p> <p><b>.... .1..</b> Bit 1 = ZONEDATA (NOPFD)</p> <p><b>.... ..1.</b> Bit 1 = NUMCHECK (ZON   PAC   BIN   ABD   MSG), Bit 0 = NONUMCHECK</p> <p><b>.... ...1</b> Bit 1 = PARMCHECK (ABD   MSG), Bit 0 = NOPARMCHECK</p>
Option byte G	XL1	<p><b>1... ..</b> Bit 1 = NUMCHECK (ZON), Bit 0 = NUMCHECK (NOZON)</p> <p><b>.1... ..</b> Bit 1 = NUMCHECK (PAC), Bit 0 = NUMCHECK (NOPAC)</p> <p><b>..1. ....</b> Bit 1 = NUMCHECK (BIN), Bit 0 = NUMCHECK (NOBIN)</p> <p><b>...1 ....</b> Bit 1 = NUMCHECK (MSG), Bit 0 = NUMCHECK (ABD)</p> <p><b>.... 1...</b> Bit 1 = NUMCHECK (ZON (NOALPHNUM)), Bit 0 = NUMCHECK (ZON (ALPHNUM))</p> <p><b>.... .111</b> Reserved for future use</p>
Option byte H	XL1	<p><b>1... ..</b> Bit 1 = PARMCHECK (ABD), Bit 0 = PARMCHECK (MSG) (if PARMCHECK in effect)</p> <p><b>.1... ..</b> Reserved for future use</p>

Table 121. <b>SYSADATA options record</b> (continued)		
Field	Size	Description
Flag level	XL1	<b>X'00'</b> Flag(I) <b>X'04'</b> Flag(W) <b>X'08'</b> Flag(E) <b>X'0C'</b> Flag(S) <b>X'10'</b> Flag(U) <b>X'FF'</b> No flag
Imbedded diagnostic level	XL1	<b>X'00'</b> Flag(I) <b>X'04'</b> Flag(W) <b>X'08'</b> Flag(E) <b>X'0C'</b> Flag(S) <b>X'10'</b> Flag(U) <b>X'FF'</b> No flag
FLAGSTD (FIPS) specification	XL1	<b>1... ..</b> Minimum <b>.1.. ..</b> Intermediate <b>..1. ....</b> High <b>...1 ....</b> IBM extensions <b>.... 1...</b> Level-1 segmentation <b>.... .1..</b> Level-2 segmentation <b>.... ..1.</b> Debugging <b>.... ...1</b> Obsolete
Reserved for flagging	XL1	<b>1111 1111</b> Reserved for future use

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Compiler mode	XL1	<b>X'00'</b> Unconditional Nocompile, Nocompile(I) <b>X'04'</b> Nocompile(W) <b>X'08'</b> Nocompile(E) <b>X'0C'</b> Nocompile(S) <b>X'FF'</b> Compile
Space value	CL1	
Data for 3-valued options	XL1	<b>1... ....</b> NAME (ALIAS) specified <b>.1.. ....</b> Reserved for future use <b>..1. ....</b> TRUNC (BIN) specified <b>...1 ....</b> PARMCHECK (ABD) (if PARMCHECK in effect) <b>.... 1...</b> INITCHECK (STRICT) specified <b>.... .111</b> Reserved for future use
TEST suboptions	XL1	<b>..1. ....</b> TEST (EJPD) <b>...1 ....</b> TEST (SOURCE) <b>11.. 1111</b> Reserved for TEST suboptions
OUTDD name length	HL2	Length of OUTDD name
RWT ID Length	HL2	Length of Reserved Word Table identifier
BLD LEVEL	CL8	Product build level information (of the form PYYMMDD)
PGMNAME suboptions	XL1	<b>1... ....</b> Bit 1 = PGMNAME (COMPAT) <b>.1.. ....</b> Bit 1 = PGMNAME (LONGUPPER) <b>..1. ....</b> Bit 1 = PGMNAME (LONGMIXED) <b>...1 1111</b> Reserved for future use

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
Entry interface suboptions	XL1	<b>1... ..</b> Bit 1 = EntryInterface(System) (Windows only) <b>.1... ..</b> Bit 1 = EntryInterface(OptLink) (Windows only) <b>..11 1111</b> Reserved for future use
CALLINTERFACE suboptions	XL1	<b>1... ..</b> Bit 1 = CALLINTERFACE(DLL) <b>.1... ..</b> Bit 1 = CALLINTERFACE(DYNAMIC) <b>..11 1111</b> Reserved for future use
ARITH suboption	XL1	<b>1... ..</b> Bit 1 = ARITH (COMPAT) <b>.1... ..</b> Bit 1 = ARITH (EXTEND) <b>..11 1111</b> Reserved for future use
DBCS Req	FL4	DBCS XREF storage requirement
DBCS ORDPGM length	HL2	Length of name of DBCS Ordering Program
DBCS ENCTBL length	HL2	Length of name of DBCS Encode Table
DBCS ORD TYPE	CL2	DBCS Ordering type
Reserved	CL5	Reserved for future use
Optimize level	XL1	Optimization level $0 \leq n \leq 2$
Converted SO	CL1	Converted SO hexadecimal value
Converted SI	CL1	Converted SI hexadecimal value
Language ID	CL2	This field holds the two-character abbreviation (one of <i>EN</i> , <i>UE</i> , <i>JA</i> , or <i>JP</i> ) from the LANGUAGE option.
Reserved	CL8	Reserved for future use
INEXIT name length	HL2	Length of SYSIN user-exit name
PRTEXT name length	HL2	Length of SYSPRINT user-exit name
LIBEXIT name length	HL2	Length of Libraryuser-exit name
ADEXIT name length	HL2	Length of ADATA user-exit name
CURROPT	CL5	CURRENCY option value
ARCH	XL1	ARCH level number
Reserved	CL2	Reserved for future use
CODEPAGE	HL2	CODEPAGE CCSID option value
Reserved	CL50	Reserved for future use

Table 121. **SYSADATA options record** (continued)

Field	Size	Description
LINECNT	HL2	LINECOUNT value
Reserved	CL2	Reserved for future use
BUFSIZE	FL4	BUFSIZE option value
Reserved	FL4	Reserved for future use
Phase residence bits byte 1	XL1	<b>1... ..</b> Bit 1 = IGYCLIBR in user region <b>.1... ..</b> Bit 1 = IGYCSCAN in user region <b>..1. ....</b> Bit 1 = IGYCDSCN in user region <b>...1 ....</b> Bit 1 = IGYCGROU in user region <b>.... 1...</b> Bit 1 = IGYCPSCN in user region <b>.... .1..</b> Bit 1 = IGYCPANA in user region <b>.... ..1.</b> Bit 1 = IGYCFGEN in user region <b>.... ...1</b> Bit 1 = IGYCPGEN in user region
Phase residence bits byte 2	XL1	<b>.1... ..</b> Bit 1 = IGYCLSTR in user region <b>..1. ....</b> Bit 1 = IGYCXREF in user region <b>...1 ....</b> Bit 1 = IGYCDMAP in user region <b>.... ..1.</b> Bit 1 = IGYCDIAG in user region <b>.... ...1</b> Bit 1 = IGYCDGEN in user region <b>1... 11..</b> Reserved for future use
Phase residence bits bytes 3 and 4	XL2	Reserved
Reserved	CL8	Reserved for future use
OUTDD name	CL(n)	OUTDD name
RWT	CL(n)	Reserved word table identifier
DBCS ORDPGM	CL(n)	DBCS Ordering program name
DBCS ENCTBL	CL(n)	DBCS Encode table name
INEXIT name	CL(n)	SYSIN user-exit name
PRTEXIT name	CL(n)	SYSPRINT user-exit name

<i>Table 121. SYSADATA options record (continued)</i>		
Field	Size	Description
LIBEXIT name	CL(n)	Library user-exit name
ADEXIT name	CL(n)	ADATA user-exit name

## External symbol record: X'0020'

The following table shows the contents of the external symbol record.

<i>Table 122. SYSADATA external symbol record</i>		
Field	Size	Description
Section type	XL1	<b>X'00'</b> PROGRAM - ID name (main entry point name) <b>X'01'</b> ENTRY name (secondary entry point name) <b>X'02'</b> External reference (referenced external entry point) <b>X'04'</b> Not applicable for COBOL <b>X'05'</b> Not applicable for COBOL <b>X'06'</b> Not applicable for COBOL <b>X'0A'</b> Not applicable for COBOL <b>X'12'</b> Internal reference (referenced internal subprogram) <b>X'C0'</b> External class-name (OO COBOL class definition) <b>X'C1'</b> METHOD - ID name (OO COBOL method definition) <b>X'C6'</b> Method reference (OO COBOL method reference) <b>X'FF'</b> Not applicable for COBOL Types X'12', X'C0', X'C1' and X'C6' are for COBOL only.
Flags	XL1	Not applicable for COBOL
Reserved	HL2	Reserved for future use
Symbol-ID	FL4	Symbol-ID of program that contains the reference (only for types x'02' and x'12')
Line number	FL4	Line number of statement that contains the reference (only for types x'02' and x'12')
Section length	FL4	Not applicable for COBOL
LD ID	FL4	Not applicable for COBOL
Reserved	CL8	Reserved for future use

<i>Table 122. SYSADATA external symbol record (continued)</i>		
Field	Size	Description
External name length	HL2	Number of characters in the external name
Alias name length	HL2	Not applicable for COBOL
External name	CL(n)	The external name
Alias section name	CL(n)	Not applicable for COBOL

## Parse tree record: X'0024'

The following table shows the contents of the parse tree record.

<i>Table 123. SYSADATA parse tree record</i>		
Field	Size	Description
Node number	FL4	The node number generated by the compiler, starting at 1
Node type	HL2	The type of the node:  <b>001</b> Program <b>002</b> Class <b>003</b> Method
		<b>101</b> IDENTIFICATION DIVISION <b>102</b> ENVIRONMENT DIVISION <b>103</b> DATA DIVISION <b>104</b> PROCEDURE DIVISION <b>105</b> End Program/Method/Class
		<b>201</b> Declaratives body <b>202</b> Nondeclaratives body
		<b>301</b> Section <b>302</b> Procedure section
		<b>401</b> Paragraph <b>402</b> Procedure paragraph

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		<b>501</b> Sentence <b>502</b> File definition <b>503</b> Sort file definition <b>504</b> Program-name <b>505</b> Program attribute <b>508</b> ENVIRONMENT DIVISION clause <b>509</b> CLASS attribute <b>510</b> METHOD attribute <b>511</b> USE statement
		<b>601</b> Statement <b>602</b> Data description clause <b>603</b> Data entry <b>604</b> File description clause <b>605</b> Data entry name <b>606</b> Data entry level <b>607</b> EXEC entry

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>701</b> EVALUATE subject phrase <b>702</b> EVALUATE WHEN phrase <b>703</b> EVALUATE WHEN OTHER phrase <b>704</b> SEARCH WHEN phrase <b>705</b> INSPECT CONVERTING phrase <b>706</b> INSPECT REPLACING phrase <b>707</b> INSPECT TALLYING phrase <b>708</b> PERFORM UNTIL phrase <b>709</b> PERFORM VARYING phrase <b>710</b> PERFORM AFTER phrase <b>711</b> Statement block <b>712</b> Scope terminator <b>713</b> INITIALIZE REPLACING phrase <b>714</b> EXEC CICS Command <b>715</b> INITIALIZE WITH FILLER <b>716</b> INITIALIZE TO VALUE <b>717</b> INITIALIZE TO DEFAULT <b>718</b> ALLOCATE INITIALIZED <b>719</b> ALLOCATE LOC <b>720</b> DATA DIVISION phrase

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>801</b> Phrase
		<b>802</b> ON phrase
		<b>803</b> NOT phrase
		<b>804</b> THEN phrase
		<b>805</b> ELSE phrase
		<b>806</b> Condition
		<b>807</b> Expression
		<b>808</b> Relative indexing
		<b>809</b> EXEC CICS Option
		<b>810</b> Reserved word
		<b>811</b> INITIALIZE REPLACING category

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		<b>901</b> Section or paragraph name <b>902</b> Identifier <b>903</b> Alphabet-name <b>904</b> Class-name <b>905</b> Condition-name <b>906</b> File-name <b>907</b> Index-name <b>908</b> Mnemonic-name <b>910</b> Symbolic-character <b>911</b> Literal <b>912</b> Function identifier <b>913</b> Data-name <b>914</b> Special register <b>915</b> Procedure reference <b>916</b> Arithmetic operator <b>917</b> All procedures <b>918</b> INITIALIZE literal (no tokens) <b>919</b> ALL literal or figcon <b>920</b> Keyword class test name <b>921</b> Reserved word at identifier level <b>922</b> Unary operator <b>923</b> Relational operator

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		<b>1001</b> Subscript <b>1002</b> Reference modification
Node subtype	HL2	The subtype of the node. For Section type: <b>0001</b> CONFIGURATION Section <b>0002</b> INPUT-OUTPUT Section <b>0003</b> FILE SECTION <b>0004</b> WORKING-STORAGE SECTION <b>0005</b> LINKAGE SECTION <b>0006</b> LOCAL-STORAGE SECTION <b>0007</b> REPOSITORY Section

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<p>For Paragraph type:</p> <p><b>0001</b> PROGRAM-ID paragraph</p> <p><b>0002</b> AUTHOR paragraph</p> <p><b>0003</b> INSTALLATION paragraph</p> <p><b>0004</b> DATE-WRITTEN paragraph</p> <p><b>0005</b> SECURITY paragraph</p> <p><b>0006</b> SOURCE-COMPUTER paragraph</p> <p><b>0007</b> OBJECT-COMPUTER paragraph</p> <p><b>0008</b> SPECIAL-NAMES paragraph</p> <p><b>0009</b> FILE-CONTROL paragraph</p> <p><b>0010</b> I-O-CONTROL paragraph</p> <p><b>0011</b> DATE-COMPILED paragraph</p> <p><b>0012</b> CLASS-ID paragraph</p> <p><b>0013</b> METHOD-ID paragraph</p> <p><b>0014</b> REPOSITORY paragraph</p>

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		<p>For ENVIRONMENT DIVISION clause type:</p> <p><b>0001</b> WITH DEBUGGING MODE</p> <p><b>0002</b> MEMORY-SIZE</p> <p><b>0003</b> SEGMENT-LIMIT</p> <p><b>0004</b> CURRENCY-SIGN</p> <p><b>0005</b> DECIMAL POINT</p> <p><b>0006</b> PROGRAM COLLATING SEQUENCE</p> <p><b>0007</b> ALPHABET</p> <p><b>0008</b> SYMBOLIC-CHARACTER</p> <p><b>0009</b> CLASS</p> <p><b>0010</b> ENVIRONMENT NAME</p> <p><b>0011</b> SELECT</p> <p><b>0012</b> XML-SCHEMA</p>

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<p>For data description clause type:</p> <p><b>0001</b> BLANK WHEN ZERO</p> <p><b>0002</b> DATA-NAME OR FILLER</p> <p><b>0003</b> JUSTIFIED</p> <p><b>0004</b> OCCURS</p> <p><b>0005</b> PICTURE</p> <p><b>0006</b> REDEFINES</p> <p><b>0007</b> RENAMES</p> <p><b>0008</b> SIGN</p> <p><b>0009</b> SYNCHRONIZED</p> <p><b>0010</b> USAGE</p> <p><b>0011</b> VALUE</p> <p><b>0012</b> VOLATILE</p> <p><b>0023</b> GLOBAL</p> <p><b>0024</b> EXTERNAL</p>

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		For file description clause type:
		<b>0001</b> FILE STATUS
		<b>0002</b> ORGANIZATION
		<b>0003</b> ACCESS MODE
		<b>0004</b> RECORD KEY
		<b>0005</b> ASSIGN
		<b>0006</b> RELATIVE KEY
		<b>0007</b> PASSWORD
		<b>0008</b> PROCESSING MODE
		<b>0009</b> RECORD DELIMITER
		<b>0010</b> PADDING CHARACTER
		<b>0011</b> BLOCK CONTAINS
		<b>0012</b> RECORD CONTAINS
		<b>0013</b> LABEL RECORDS
		<b>0014</b> VALUE OF
		<b>0015</b> DATA RECORDS
		<b>0016</b> LINAGE
		<b>0017</b> ALTERNATE KEY
		<b>0018</b> LINES AT TOP

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0019</b> LINES AT BOTTOM <b>0020</b> CODE-SET <b>0021</b> RECORDING MODE <b>0022</b> RESERVE <b>0023</b> GLOBAL <b>0024</b> EXTERNAL <b>0025</b> LOCK

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		For Statement type:
		<b>0002</b> NEXT SENTENCE
		<b>0003</b> ACCEPT
		<b>0004</b> ADD
		<b>0005</b> ALTER
		<b>0006</b> CALL
		<b>0007</b> CANCEL
		<b>0008</b> CLOSE
		<b>0009</b> COMPUTE
		<b>0010</b> CONTINUE
		<b>0011</b> DELETE
		<b>0012</b> DISPLAY
		<b>0013</b> DIVIDE (INTO)
		<b>0113</b> DIVIDE (BY)
		<b>0014</b> ENTER
		<b>0015</b> ENTRY
		<b>0016</b> EVALUATE
		<b>0017</b> EXIT
		<b>0018</b> GO
		<b>0019</b> GOBACK
		<b>0020</b> IF
		<b>0021</b> INITIALIZE
		<b>0022</b> INSPECT

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0023</b> INVOKE <b>0024</b> MERGE <b>0025</b> MOVE <b>0026</b> MULTIPLY <b>0027</b> OPEN <b>0028</b> PERFORM <b>0029</b> READ <b>0030</b> READY <b>0031</b> RELEASE <b>0032</b> RESET <b>0033</b> RETURN <b>0034</b> REWRITE <b>0035</b> SEARCH <b>0036</b> SERVICE

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0037</b> SET <b>0038</b> SORT <b>0039</b> START <b>0040</b> STOP <b>0041</b> STRING <b>0042</b> SUBTRACT <b>0043</b> UNSTRING <b>0044</b> EXEC SQL <b>0144</b> EXEC CICS <b>0045</b> WRITE <b>0046</b> XML <b>0047</b> ALLOCATE <b>0048</b> FREE <b>0049</b> JSON

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<p>For Phrase type:</p> <p><b>0001</b> INTO</p> <p><b>0002</b> DELIMITED</p> <p><b>0003</b> INITIALIZE. .REPLACING</p> <p><b>0004</b> INSPECT. .ALL</p> <p><b>0005</b> INSPECT. .LEADING</p> <p><b>0006</b> SET. .TO</p> <p><b>0007</b> SET. .UP</p> <p><b>0008</b> SET. .DOWN</p> <p><b>0009</b> PERFORM. .TIMES</p> <p><b>0010</b> DIVIDE. .REMAINDER</p> <p><b>0011</b> INSPECT. .FIRST</p> <p><b>0012</b> SEARCH. .VARYING</p> <p><b>0013</b> MORE-LABELS</p> <p><b>0014</b> SEARCH ALL</p> <p><b>0015</b> SEARCH. .AT END</p> <p><b>0016</b> SEARCH. .TEST INDEX</p> <p><b>0017</b> GLOBAL</p> <p><b>0018</b> LABEL</p>

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0019</b> DEBUGGING <b>0020</b> SEQUENCE <b>0021</b> Reserved for future use <b>0022</b> Reserved for future use <b>0023</b> Reserved for future use <b>0024</b> TALLYING <b>0025</b> Reserved for future use <b>0026</b> ON SIZE ERROR <b>0027</b> ON OVERFLOW <b>0028</b> ON ERROR <b>0029</b> AT END <b>0030</b> INVALID KEY <b>0031</b> END-OF-PAGE <b>0032</b> USING

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0033</b> BEFORE <b>0034</b> AFTER <b>0035</b> EXCEPTION <b>0036</b> CORRESPONDING <b>0037</b> Reserved for future use <b>0038</b> RETURNING <b>0039</b> GIVING <b>0040</b> THROUGH <b>0041</b> KEY <b>0042</b> DELIMITER <b>0043</b> POINTER <b>0044</b> COUNT <b>0045</b> METHOD <b>0046</b> PROGRAM <b>0047</b> INPUT <b>0048</b> OUTPUT <b>0049</b> I-O <b>0050</b> EXTEND <b>0051</b> RELOAD <b>0052</b> ASCENDING

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		<b>0053</b> DESCENDING <b>0054</b> DUPLICATES <b>0055</b> NATIVE (USAGE) <b>0056</b> INDEXED <b>0057</b> FROM <b>0058</b> FOOTING <b>0059</b> LINES AT BOTTOM <b>0060</b> LINES AT TOP <b>0061</b> XML ENCODING <b>0062</b> XML GENERATE XML-DECLARATION <b>0063</b> XML GENERATE ATTRIBUTES <b>0064</b> XML GENERATE NAMESPACE <b>0065</b> XML PARSE PROCESSING <b>0066</b> XML PARSE VALIDATING <b>0067</b> XML GENERATE NAME <b>0068</b> XML GENERATE TYPE <b>0069</b> XML GENERATE SUPPRESS

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		For Function identifier type:
		<b>0001</b> COS
		<b>0002</b> LOG
		<b>0003</b> MAX
		<b>0004</b> MIN
		<b>0005</b> MOD
		<b>0006</b> ORD
		<b>0007</b> REM
		<b>0008</b> SIN
		<b>0009</b> SUM
		<b>0010</b> TAN
		<b>0011</b> ACOS
		<b>0012</b> ASIN
		<b>0013</b> ATAN
		<b>0014</b> CHAR
		<b>0015</b> MEAN
		<b>0016</b> SQRT
		<b>0017</b> LOG10
		<b>0018</b> RANGE
		<b>0019</b> LENGTH
		<b>0020</b> MEDIAN

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0021</b> NUMVAL <b>0022</b> RANDOM <b>0023</b> ANNUITY <b>0024</b> INTEGER <b>0025</b> ORD-MAX <b>0026</b> ORD-MIN <b>0027</b> REVERSE <b>0028</b> MIDRANGE <b>0029</b> NUMVAL-C <b>0030</b> VARIANCE <b>0031</b> FACTORIAL <b>0032</b> LOWER-CASE

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<b>0033</b> UPPER-CASE <b>0034</b> CURRENT-DATE <b>0035</b> INTEGER-PART <b>0036</b> PRESENT-VALUE <b>0037</b> WHEN-COMPILED <b>0038</b> DAY-OF-INTEGERS <b>0039</b> INTEGER-OF-DAY <b>0040</b> DATE-OF-INTEGERS <b>0041</b> INTEGER-OF-DATE <b>0042</b> STANDARD-DEVIATION <b>0043</b> YEAR-TO-YYYY <b>0044</b> DAY-TO-YYYYDDD <b>0045</b> DATE-TO-YYYYMMDD <b>0049</b> DISPLAY-OF <b>0050</b> NATIONAL-OF <b>0051</b> UPOS <b>0052</b> UVALID <b>0053</b> UWIDTH <b>0054</b> ULENGTH <b>0055</b> USUBSTR <b>0056</b> USUPPLEMENTARY

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		For Special Register type: <b>0001</b> ADDRESS OF <b>0002</b> LENGTH OF
		For Keyword Class Test Name type: <b>0001</b> ALPHABETIC <b>0002</b> ALPHABETIC-LOWER <b>0003</b> ALPHABETIC-UPPER <b>0004</b> DBCS <b>0005</b> KANJI <b>0006</b> NUMERIC <b>0007</b> NEGATIVE <b>0008</b> POSITIVE <b>0009</b> ZERO
		For Reserved Word type: <b>0001</b> TRUE <b>0002</b> FALSE <b>0003</b> ANY <b>0004</b> THRU
		For Identifier, Data-name, Index-name, Condition-name or Mnemonic-name type: <b>0001</b> REFERENCED <b>0002</b> CHANGED <b>0003</b> REFERENCED & CHANGED

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<p>For Initialize literal type:</p> <p><b>0001</b> ALPHABETIC</p> <p><b>0002</b> ALPHANUMERIC</p> <p><b>0003</b> NUMERIC</p> <p><b>0004</b> ALPHANUMERIC-EDITED</p> <p><b>0005</b> NUMERIC-EDITED</p> <p><b>0006</b> DBCS/EGCS</p> <p><b>0007</b> NATIONAL</p> <p><b>0008</b> NATIONAL-EDITED</p>
		<p>For Procedure-name type:</p> <p><b>0001</b> SECTION</p> <p><b>0002</b> PARAGRAPH</p>

Table 123. **SYSADATA** parse tree record (continued)

Field	Size	Description
		For Reserved word at identifier level type:
		<b>0001</b> ROUNDED
		<b>0002</b> TRUE
		<b>0003</b> ON
		<b>0004</b> OFF
		<b>0005</b> SIZE
		<b>0006</b> DATE
		<b>0007</b> DAY
		<b>0008</b> DAY-OF-WEEK
		<b>0009</b> TIME
		<b>0010</b> WHEN-COMPILED
		<b>0011</b> PAGE
		<b>0012</b> DATE YYYYMMDD
		<b>0013</b> DAY YYYYDDD
		<b>0014</b> Attribute
		<b>0015</b> Element
		<b>0016</b> Content
		<b>0017</b> Numeric
		<b>0018</b> Nonnumeric
		<b>0019</b> Every
		<b>0020</b> When

Table 123. *SYSADATA parse tree record (continued)*

Field	Size	Description
		<p>For Arithmetic Operator type:</p> <p><b>0001</b> PLUS</p> <p><b>0002</b> MINUS</p> <p><b>0003</b> TIMES</p> <p><b>0004</b> DIVIDE</p> <p><b>0005</b> DIVIDE REMAINDER</p> <p><b>0006</b> EXPONENTIATE</p> <p><b>0007</b> NEGATE</p>
		<p>For Relational Operator type:</p> <p><b>0008</b> LESS</p> <p><b>0009</b> LESS OR EQUAL</p> <p><b>0010</b> EQUAL</p> <p><b>0011</b> NOT EQUAL</p> <p><b>0012</b> GREATER</p> <p><b>0013</b> GREATER OR EQUAL</p> <p><b>0014</b> AND</p> <p><b>0015</b> OR</p> <p><b>0016</b> CLASS CONDITION</p> <p><b>0017</b> NOT CLASS CONDITION</p>
Parent node number	FL4	The node number of the parent of the node
Left sibling node number	FL4	The node number of the left sibling of the node, if any. If none, the value is zero.

Table 123. <i>SYSADATA parse tree record (continued)</i>		
Field	Size	Description
Symbol ID	FL4	<p>The Symbol ID of the node, if it is a user-name of one of the following types:</p> <ul style="list-style-type: none"> <li>• Data entry</li> <li>• Identifier</li> <li>• File-name</li> <li>• Index-name</li> <li>• Procedure-name</li> <li>• Condition-name</li> <li>• Mnemonic-name</li> </ul> <p>This value corresponds to the Symbol ID in a Symbol (Type 42) record, except for procedure-names where it corresponds to the Paragraph ID.</p> <p>For all other node types this value is zero.</p>
Section Symbol ID	FL4	<p>The Symbol ID of the section containing the node, if it is a qualified paragraph-name reference. This value corresponds to the Section ID in a Symbol (Type 42) record.</p> <p>For all other node types this value is zero.</p>
First token number	FL4	The number of the first token associated with the node
Last token number	FL4	The number of the last token associated with the node
Reserved	FL4	Reserved for future use
Flags	CL1	<p>Information about the node:</p> <p><b>X'80'</b> Reserved</p> <p><b>X'40'</b> Generated node, no tokens</p>
Reserved	CL3	Reserved for future use

## Token record: X'0030'

The compiler does not generate token records for any lines that are treated as comment lines, which include, but are not limited to, items in the following list.

- Comment lines, which are source lines that have an asterisk (\*) or a slash (/) in column 7
- The following compiler-directing statements:
  - \*CBL (\*CONTROL)
  - BASIS
  - COPY
  - DELETE
  - EJECT
  - INSERT
  - REPLACE
  - SKIP1

- SKIP2
- SKIP3
- TITLE
- Debugging lines, which are source lines that have a D in column 7, if WITH DEBUGGING MODE is not specified

Table 124. <i>SYSADATA</i> token record		
Field	Size	Description
Token number	FL4	The token number within the source file generated by the compiler, starting at 1. Any copybooks have already been included in the source.
Token code	HL2	<p>The type of token (user-name, literal, reserved word, and so forth). For reserved words, the compiler reserved-word table values are used.</p> <p>For PICTURE strings, the special code 0000 is used.</p> <p>For each piece (other than the last) of a continued token, the special code 3333 is used.</p> <p>Otherwise, the following codes are used:</p> <p><b>0001</b> ACCEPT</p> <p><b>0002</b> ADD</p> <p><b>0003</b> ALTER</p> <p><b>0004</b> CALL</p> <p><b>0005</b> CANCEL</p> <p><b>0007</b> CLOSE</p> <p><b>0009</b> COMPUTE</p> <p><b>0011</b> DELETE</p> <p><b>0013</b> DISPLAY</p> <p><b>0014</b> DIVIDE</p> <p><b>0017</b> READY</p> <p><b>0018</b> END-PERFORM</p> <p><b>0019</b> ENTER</p>

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0020</b> ENTRY <b>0021</b> EXIT <b>0022</b> EXEC EXECUTE <b>0023</b> GO <b>0024</b> IF <b>0025</b> INITIALIZE <b>0026</b> INVOKE <b>0027</b> INSPECT <b>0028</b> MERGE <b>0029</b> MOVE

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0030</b> MULTIPLY <b>0031</b> OPEN <b>0032</b> PERFORM <b>0033</b> READ <b>0035</b> RELEASE <b>0036</b> RETURN <b>0037</b> REWRITE <b>0038</b> SEARCH <b>0040</b> SET <b>0041</b> SORT <b>0042</b> START <b>0043</b> STOP <b>0044</b> STRING <b>0045</b> SUBTRACT <b>0048</b> UNSTRING <b>0049</b> USE <b>0050</b> WRITE <b>0051</b> CONTINUE <b>0052</b> END-ADD <b>0053</b> END-CALL

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0054</b> END-COMPUTE <b>0055</b> END-DELETE <b>0056</b> END-DIVIDE <b>0057</b> END-EVALUATE <b>0058</b> END-IF <b>0059</b> END-MULTIPLY <b>0060</b> END-READ <b>0061</b> END-RETURN <b>0062</b> END-REWRITE <b>0063</b> END-SEARCH <b>0064</b> END-START <b>0065</b> END-STRING <b>0066</b> END-SUBTRACT <b>0067</b> END-UNSTRING <b>0068</b> END-WRITE <b>0069</b> GOBACK

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0070</b> EVALUATE
		<b>0071</b> RESET
		<b>0072</b> SERVICE
		<b>0073</b> END-INVOKE
		<b>0074</b> END-EXEC
		<b>0075</b> XML
		<b>0076</b> END-XML
		<b>0077</b> ALLOCATE
		<b>0078</b> FREE
		<b>0079</b> JSON
		<b>0080</b> END-JSON
		<b>0099</b> FOREIGN-VERB
		<b>0101</b> DATA-NAME
		<b>0105</b> DASHED-NUM
		<b>0106</b> DECIMAL
		<b>0107</b> DIV-SIGN
		<b>0108</b> EQ
		<b>0109</b> EXPONENTIATION
		<b>0110</b> GT

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0111</b> INTEGER
		<b>0112</b> LT
		<b>0113</b> LPAREN
		<b>0114</b> MINUS-SIGN
		<b>0115</b> MULT-SIGN
		<b>0116</b> NONUMLIT
		<b>0117</b> PERIOD
		<b>0118</b> PLUS-SIGN
		<b>0121</b> RPAREN
		<b>0122</b> SIGNED-INTEGER
		<b>0123</b> QUID
		<b>0124</b> COLON
		<b>0125</b> IEOF
		<b>0126</b> EGCS-LIT
		<b>0127</b> COMMA-SPACE
		<b>0128</b> SEMICOLON-SPACE
		<b>0129</b> PROCEDURE-NAME
		<b>0130</b> FLT-POINT-LIT
		<b>0131</b> Language Environment

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0132</b> GE <b>0133</b> IDREF <b>0134</b> EXPREF <b>0136</b> CICS <b>0137</b> NEW <b>0138</b> NATIONAL-LIT <b>0200</b> ADDRESS <b>0201</b> ADVANCING <b>0202</b> AFTER <b>0203</b> ALL <b>0204</b> ALPHABETIC <b>0205</b> ALPHANUMERIC <b>0206</b> ANY <b>0207</b> AND <b>0208</b> ALPHANUMERIC-EDITED <b>0209</b> BEFORE <b>0210</b> BEGINNING <b>0211</b> FUNCTION

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0212</b> CONTENT <b>0213</b> CORR CORRESPONDING <b>0214</b> DAY <b>0215</b> DATE <b>0216</b> DEBUG-CONTENTS <b>0217</b> DEBUG-ITEM <b>0218</b> DEBUG-LINE <b>0219</b> DEBUG-NAME <b>0220</b> DEBUG-SUB-1 <b>0221</b> DEBUG-SUB-2 <b>0222</b> DEBUG-SUB-3 <b>0223</b> DELIMITED <b>0224</b> DELIMITER <b>0225</b> DOWN

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0226</b> NUMERIC-EDITED <b>0227</b> XML-EVENT <b>0228</b> END-OF-PAGE EOP <b>0229</b> EQUAL <b>0230</b> ERROR <b>0231</b> XML-NTEXT <b>0232</b> EXCEPTION <b>0233</b> EXTEND <b>0234</b> FIRST <b>0235</b> FROM <b>0236</b> GIVING <b>0237</b> GREATER <b>0238</b> I-O <b>0239</b> IN <b>0240</b> INITIAL <b>0241</b> INTO <b>0242</b> INVALID <b>0243</b> SQL

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0244</b> LESS <b>0245</b> LINAGE-COUNTER <b>0246</b> XML-TEXT <b>0247</b> LOCK <b>0248</b> GENERATE <b>0249</b> NEGATIVE <b>0250</b> NEXT <b>0251</b> NO <b>0252</b> NOT <b>0253</b> NUMERIC <b>0254</b> KANJI <b>0255</b> OR <b>0256</b> OTHER <b>0257</b> OVERFLOW <b>0258</b> PAGE <b>0259</b> CONVERTING

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0260</b> POINTER <b>0261</b> POSITIVE <b>0262</b> DBCS <b>0263</b> PROCEDURES <b>0264</b> PROCEED <b>0265</b> REFERENCES <b>0266</b> DAY-OF-WEEK <b>0267</b> REMAINDER <b>0268</b> REMOVAL <b>0269</b> REPLACING <b>0270</b> REVERSED <b>0271</b> REWIND <b>0272</b> ROUNDED <b>0273</b> RUN <b>0274</b> SENTENCE <b>0275</b> STANDARD <b>0276</b> RETURN-CODE SORT-CORE-SIZE SORT-FILE-SIZE SORT-MESSAGE SORT-MODE-SIZE SORT-RETURN TALLY XML-CODE

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0277</b> TALLYING <b>0278</b> SUM <b>0279</b> TEST <b>0280</b> THAN <b>0281</b> UNTIL <b>0282</b> UP <b>0283</b> UPON <b>0284</b> VARYING <b>0285</b> RELOAD <b>0286</b> TRUE

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0287</b> THEN
		<b>0288</b> RETURNING
		<b>0289</b> ELSE
		<b>0290</b> SELF
		<b>0291</b> SUPER
		<b>0292</b> WHEN-COMPILED
		<b>0293</b> ENDING
		<b>0294</b> FALSE
		<b>0295</b> REFERENCE
		<b>0296</b> NATIONAL-EDITED
		<b>0297</b> COM-REG
		<b>0298</b> ALPHABETIC-LOWER
		<b>0299</b> ALPHABETIC-UPPER
		<b>0301</b> REDEFINES
		<b>0302</b> OCCURS
		<b>0303</b> SYNC SYNCHRONIZED
		<b>0304</b> MORE-LABELS
		<b>0305</b> JUST JUSTIFIED

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0306</b> SHIFT-IN <b>0307</b> BLANK <b>0308</b> VALUE <b>0309</b> COMP COMPUTATIONAL <b>0310</b> COMP-1 COMPUTATIONAL-1 <b>0311</b> COMP-3 COMPUTATIONAL-3 <b>0312</b> COMP-2 COMPUTATIONAL-2 <b>0313</b> COMP-4 COMPUTATIONAL-4 <b>0314</b> DISPLAY-1 <b>0315</b> SHIFT-OUT

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0316</b> INDEX <b>0317</b> USAGE <b>0318</b> SIGN <b>0319</b> LEADING <b>0320</b> SEPARATE <b>0321</b> INDEXED <b>0322</b> LEFT <b>0323</b> RIGHT <b>0324</b> PIC PICTURE <b>0325</b> VALUES <b>0326</b> GLOBAL <b>0327</b> EXTERNAL <b>0328</b> BINARY <b>0329</b> PACKED-DECIMAL <b>0330</b> EGCS <b>0331</b> PROCEDURE-POINTER <b>0332</b> COMP-5 COMPUTATIONAL-5 <b>0333</b> FUNCTION-POINTER

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>0334</b> TYPE <b>0335</b> JNIENVPTR <b>0336</b> NATIONAL <b>0337</b> GROUP-USAGE <b>0342</b> VOLATILE <b>0401</b> HIGH-VALUE HIGH-VALUES <b>0402</b> LOW-VALUE LOW-VALUES <b>0403</b> QUOTE QUOTES <b>0404</b> SPACE SPACES <b>0405</b> ZERO

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0406</b> ZEROES ZEROS <b>0407</b> NULL NULLS <b>0501</b> BLOCK <b>0502</b> BOTTOM <b>0505</b> CHARACTER <b>0506</b> CODE <b>0507</b> CODE-SET <b>0514</b> FILLER <b>0516</b> FOOTING <b>0520</b> LABEL <b>0521</b> LENGTH <b>0524</b> LINAGE <b>0526</b> OMITTED <b>0531</b> RENAMES <b>0543</b> TOP <b>0545</b> TRAILING <b>0549</b> RECORDING <b>0601</b> INHERITS <b>0603</b> RECURSIVE

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0701</b> ACCESS <b>0702</b> ALSO <b>0703</b> ALTERNATE <b>0704</b> AREA AREAS <b>0705</b> ASSIGN <b>0707</b> COLLATING <b>0708</b> COMMA <b>0709</b> CURRENCY <b>0710</b> CLASS <b>0711</b> DECIMAL-POINT <b>0712</b> DUPLICATES <b>0713</b> DYNAMIC <b>0714</b> EVERY

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0716</b> MEMORY <b>0717</b> MODE <b>0718</b> MODULES <b>0719</b> MULTIPLE <b>0720</b> NATIVE <b>0721</b> OFF <b>0722</b> OPTIONAL <b>0723</b> ORGANIZATION <b>0724</b> POSITION <b>0725</b> PROGRAM <b>0726</b> RANDOM <b>0727</b> RELATIVE <b>0728</b> RERUN <b>0729</b> RESERVE <b>0730</b> SAME <b>0731</b> SEGMENT-LIMIT <b>0732</b> SELECT <b>0733</b> SEQUENCE <b>0734</b> SEQUENTIAL

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0736</b> SORT-MERGE <b>0737</b> STANDARD-1 <b>0738</b> TAPE <b>0739</b> WORDS <b>0740</b> PROCESSING <b>0741</b> APPLY <b>0742</b> WRITE-ONLY <b>0743</b> COMMON <b>0744</b> ALPHABET <b>0745</b> PADDING <b>0746</b> SYMBOLIC <b>0747</b> STANDARD-2 <b>0748</b> OVERRIDE <b>0750</b> PASSWORD <b>0751</b> XML-SCHEMA

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0801</b> ARE IS <b>0802</b> ASCENDING <b>0803</b> AT <b>0804</b> BY <b>0805</b> CHARACTERS <b>0806</b> CONTAINS <b>0808</b> COUNT <b>0809</b> DEBUGGING <b>0810</b> DEPENDING <b>0811</b> DESCENDING <b>0812</b> DIVISION <b>0814</b> FOR <b>0815</b> ORDER <b>0816</b> INPUT <b>0817</b> REPLACE <b>0818</b> KEY <b>0819</b> LINE LINES

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0820</b> XML-INFORMATION <b>0821</b> OF <b>0822</b> ON <b>0823</b> OUTPUT <b>0825</b> RECORD <b>0826</b> RECORDS <b>0827</b> REEL <b>0828</b> SECTION <b>0829</b> SIZE <b>0830</b> STATUS <b>0831</b> THROUGH THRU <b>0832</b> TIME <b>0833</b> TIMES <b>0834</b> TO <b>0836</b> UNIT

Table 124. **SYSADATA** token record (continued)

Field	Size	Description
		<b>0837</b> USING <b>0838</b> WHEN <b>0839</b> WITH <b>0840</b> SQLIMS <b>0841</b> DEFAULT <b>0901</b> PROCEDURE <b>0902</b> DECLARATIVES <b>0903</b> END <b>1001</b> DATA <b>1002</b> FILE <b>1003</b> FD <b>1004</b> SD <b>1005</b> WORKING-STORAGE <b>1006</b> LOCAL-STORAGE <b>1007</b> LINKAGE <b>1101</b> ENVIRONMENT <b>1102</b> CONFIGURATION <b>1103</b> SOURCE-COMPUTER <b>1104</b> OBJECT-COMPUTER

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>1105</b> SPECIAL-NAMES <b>1106</b> REPOSITORY <b>1107</b> INPUT-OUTPUT <b>1108</b> FILE-CONTROL <b>1109</b> I-O-CONTROL <b>1201</b> ID IDENTIFICATION <b>1202</b> PROGRAM-ID <b>1203</b> AUTHOR <b>1204</b> INSTALLATION <b>1205</b> DATE-WRITTEN <b>1206</b> DATE-COMPILED <b>1207</b> SECURITY <b>1208</b> CLASS-ID <b>1209</b> METHOD-ID <b>1210</b> METHOD <b>1211</b> FACTORY

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>1212</b> OBJECT
		<b>2020</b> TRACE
		<b>2046</b> SUPPRESS
		<b>3000</b> DATADEF
		<b>3001</b> F-NAME
		<b>3002</b> UPSI-SWITCH
		<b>3003</b> CONDNAME
		<b>3004</b> CONDVAR
		<b>3005</b> BLOB
		<b>3006</b> CLOB
		<b>3007</b> DBCLOB
		<b>3008</b> BLOB-LOCATOR
		<b>3009</b> CLOB-LOCATOR
		<b>3010</b> DBCLOB-LOCATOR
		<b>3011</b> BLOB-FILE
		<b>3012</b> CLOB-FILE
		<b>3013</b> DBCLOB-FILE
		<b>3014</b> DFHRESP

Table 124. **SYSADATA token record** (continued)

Field	Size	Description
		<b>5001</b> PARSE <b>5002</b> AUTOMATIC <b>5003</b> PREVIOUS <b>5004</b> ENCODING <b>5005</b> NAMESPACE <b>5006</b> NAMESPACE-PREFIX <b>5007</b> XML-DECLARATION <b>5008</b> ATTRIBUTES <b>5009</b> VALIDATING <b>5010</b> UNBOUNDED <b>5011</b> ATTRIBUTE <b>5012</b> ELEMENT <b>5013</b> NONNUMERIC <b>5014</b> NAME <b>5015</b> CYCLE <b>5016</b> PARAGRAPH <b>5020</b> AS <b>5021</b> INITIALIZED <b>9999</b> COBOL
Token length	HL2	The length of the token
Token column	FL4	The starting column number of the token in the source listing
Token line	FL4	The line number of the token in the source listing

<i>Table 124. SYSADATA token record (continued)</i>		
Field	Size	Description
Flags	CL1	Information about the token: <b>X'80'</b> Token is continued <b>X'40'</b> Last piece of continued token  Note that for PICTURE strings, even if the source token is continued, there will be only one Token record generated. It will have a token code of 0000, the token column and line of the first piece, the length of the complete string, no continuation flags set, and the token text of the complete string.
Reserved	CL7	Reserved for future use
Token text	CL(n)	The actual token string

## Source error record: X'0032'

The following table shows the contents of the source error record.

<i>Table 125. SYSADATA source error record</i>		
Field	Size	Description
Statement number	FL4	The statement number of the statement in error
Error identifier	CL16	The error message identifier (left-justified and padded with blanks)
Error severity	HL2	The severity of the error
Error message length	HL2	The length of the error message text
Line position	XL1	The line position indicator provided in FIPS messages
Reserved	CL7	Reserved for future use
Error message	CL(n)	The error message text

## Source record: X'0038'

The following table shows the contents of the source record.

<i>Table 126. SYSADATA source record</i>		
Field	Size	Description
Line number	FL4	The listing line number of the source record
Input record number	FL4	The input source record number in the current input file
Primary file number	HL2	The input file's assigned sequence number if this record is from the primary input file. (Refer to the Input file <i>n</i> field in the Job identification record).
Library file number	HL2	The library input file's assigned sequence number if this record is from a COPY BASIS input file. (Refer to the Member File ID <i>n</i> field in the Library record.)

Table 126. <b>SYSADATA source record</b> (continued)		
Field	Size	Description
Reserved	CL8	Reserved for future use
Parent record number	FL4	The parent source record number. This will be the record number of the COPY BASIS statement.
Parent primary file number	HL2	The parent file's assigned sequence number if the parent of this record is from the primary input file. (Refer to the Input file <i>n</i> field in the Job Identification Record.)
Parent library assigned file number	HL2	The parent library file's assigned sequence number if this record's parent is from a COPY BASIS input file. (Refer to the COPY/BASIS Member File ID <i>n</i> field in the Library record.)
Reserved	CL8	Reserved for future use
Length of source record	HL2	The length of the actual source record following
Reserved	CL10	Reserved for future use
Source record	CL( <i>n</i> )	

## COPY REPLACING record: X'0039'

One COPY REPLACING type record will be emitted each time a REPLACING action takes place. That is, whenever *operand-1* of the REPLACING phrase is matched with text in the copybook, a COPY REPLACING TEXT record will be written.

The following table shows the contents of the COPY REPLACING record.

Table 127. <b>SYSADATA COPY REPLACING record</b>		
Field	Size	Description
Starting line number of replaced string	FL4	The listing line number of the start of the text that resulted from REPLACING
Starting column number of replaced string	FL4	The listing column number of the start of the text that resulted from REPLACING
Ending line number of replaced string	FL4	The listing line number of the end of the text that resulted from REPLACING
Ending column number of replaced string	FL4	The listing column number of the end of the text that resulted from REPLACING
Starting line number of original string	FL4	The source file line number of the start of the text that was changed by REPLACING
Starting column number of original string	FL4	The source file column number of the start of the text that was changed by REPLACING
Ending line number of original string	FL4	The source file line number of the end of the text that was changed by REPLACING
Ending column number of original string	FL4	The source file column number of the end of the text that was changed by REPLACING

## Symbol record: X'0042'

The following table shows the contents of the symbol record.

Table 128. <i>SYSADATA</i> symbol record		
Field	Size	Description
Symbol ID	FL4	Unique ID of symbol
Line number	FL4	The listing line number of the source record in which the symbol is defined or declared
Level	XL1	True level-number of symbol (or relative level-number of a data item within a structure). For COBOL, this can be in the range 01-49, 66 (for RENAMEs items), 77, or 88 (for condition items).
Qualification indicator	XL1	<b>X'00'</b> Unique name; no qualification needed. <b>X'01'</b> This data item needs qualification. The name is not unique within the program. This field applies only when this data item is <i>not</i> the level-01 name.
Symbol type	XL1	<b>X'68'</b> Class-name (Class-ID) <b>X'58'</b> Method-name <b>X'40'</b> Data-name <b>X'20'</b> Procedure-name <b>X'10'</b> Mnemonic-name <b>X'08'</b> Program-name <b>X'81'</b> Reserved The following ORed are into the above types, when applicable: <b>X'04'</b> External <b>X'02'</b> Global

Table 128. **SYSADATA** symbol record (continued)

Field	Size	Description
Symbol attribute	XL1	<p><b>X'01'</b> Numeric</p> <p><b>X'02'</b> Elementary character of one of these classes:</p> <ul style="list-style-type: none"> <li>• Alphabetic</li> <li>• Alphanumeric</li> <li>• DBCS</li> <li>• National</li> </ul> <p><b>X'03'</b> Group</p> <p><b>X'04'</b> Pointer</p> <p><b>X'05'</b> Index data item</p> <p><b>X'06'</b> Index-name</p> <p><b>X'07'</b> Condition</p> <p><b>X'0F'</b> File</p> <p><b>X'10'</b> Sort file</p> <p><b>X'17'</b> Class-name (repository)</p> <p><b>X'18'</b> Object reference</p> <p><b>X'19'</b> Currency-sign symbol</p> <p><b>X'1A'</b> XML schema name</p>

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
Clauses	XL1	<p>Clauses specified in symbol definition.</p> <p>For symbols that have a symbol attribute of Numeric (X'01'), Elementary character (X'02'), Group (X'03'), Pointer (X'04'), Index data item (X'05'), or Object reference (X'18'):</p> <p><b>1... ..</b> Value</p> <p><b>.1... ..</b> Indexed</p> <p><b>..1. ....</b> Redefines</p> <p><b>...1 ....</b> Renames</p> <p><b>.... 1...</b> Occurs</p> <p><b>.... .1..</b> Has Occurs keys</p> <p><b>.... ..1.</b> Occurs Depending On</p> <p><b>.... ...1</b> Occurs in parent</p> <p>For file types:</p> <p><b>1... ..</b> Select</p> <p><b>.1... ..</b> Assign</p> <p><b>..1. ....</b> Rerun</p> <p><b>...1 ....</b> Same area</p> <p><b>.... 1...</b> Same record area</p> <p><b>.... .1..</b> Recording mode</p> <p><b>.... ..1.</b> Reserved</p> <p><b>.... ...1</b> Record</p>

Table 128. **SYSADATA** symbol record (continued)

Field	Size	Description
		For mnemonic-name symbols:
		<b>01</b> CSP
		<b>02</b> C01
		<b>03</b> C02
		<b>04</b> C03
		<b>05</b> C04
		<b>06</b> C05
		<b>07</b> C06
		<b>08</b> C07
		<b>09</b> C08
		<b>10</b> C09
		<b>11</b> C10
		<b>12</b> C11
		<b>13</b> C12
		<b>14</b> S01
		<b>15</b> S02
		<b>16</b> S03
		<b>17</b> S04
		<b>18</b> S05
		<b>19</b> CONSOLE

Table 128. **SYSADATA** symbol record (continued)

Field	Size	Description
		<b>20</b> SYSIN SYSIPT <b>22</b> SYSOUT SYSLST SYSLIST <b>24</b> SYSPUNCH SYSPCH <b>26</b> UPSI-0 <b>27</b> UPSI-1 <b>28</b> UPSI-2 <b>29</b> UPSI-3 <b>30</b> UPSI-4 <b>31</b> UPSI-5 <b>32</b> UPSI-6 <b>33</b> UPSI-7 <b>34</b> AFP-5A
Data flags 1	XL1	For file types, and for symbols that have a symbol attribute of Numeric (X'01 '), Elementary character (X'02 '), Group (X'03 '), Pointer (X'04 '), Index data item (X'05 '), or Object reference (X'18 '): <b>1... ....</b> Redefined <b>.1... ....</b> Renamed <b>..1. ....</b> Synchronized <b>...1 ....</b> Implicitly redefined <b>.... 1...</b> Volatile <b>.... .1..</b> Implicit redefines <b>.... ..1.</b> FILLER <b>.... ...1</b> Level 77

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
Data flags 2	XL1	<p>For symbols that have a symbol attribute of Numeric (X'01'):</p> <p><b>1... ..</b> Binary</p> <p><b>.1... ..</b> External floating point (of USAGE DISPLAY or USAGE NATIONAL)</p> <p><b>..1. ....</b> Internal floating point</p> <p><b>...1 ....</b> Packed</p> <p><b>.... 1...</b> External decimal (of USAGE DISPLAY or USAGE NATIONAL)</p> <p><b>.... .1..</b> Scaled negative</p> <p><b>.... ..1.</b> Numeric edited (of USAGE DISPLAY or USAGE NATIONAL)</p> <p><b>.... ...1</b> Reserved for future use</p> <p>For symbols that have a symbol attribute of Elementary character (X'02') or Group (X'03'):</p> <p><b>1... ..</b> Alphabetic</p> <p><b>.1... ..</b> Alphanumeric</p> <p><b>..1. ....</b> Alphanumeric edited</p> <p><b>...1 ....</b> Group contains its own ODO object</p> <p><b>.... 1...</b> DBCS item</p> <p><b>.... .1..</b> Group variable length</p> <p><b>.... ..1.</b> EGCS item</p> <p><b>.... ...1</b> EGCS edited</p>

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
		<p>For file types:</p> <p><b>1... ..</b> Object of ODO in record</p> <p><b>.1... ..</b> Subject of ODO in record</p> <p><b>..1. ....</b> Sequential access</p> <p><b>...1 ....</b> Random access</p> <p><b>.... 1...</b> Dynamic access</p> <p><b>.... .1..</b> Locate mode</p> <p><b>.... ..1.</b> Record area</p> <p><b>.... ...1</b> Reserved for future use</p>
Data flags 3	XL1	<p><b>1... ..</b> All records are the same length</p> <p><b>.1... ..</b> Fixed length</p> <p><b>..1. ....</b> Variable length</p> <p><b>...1 ....</b> Undefined</p> <p><b>.... 1...</b> Spanned</p> <p><b>.... .1..</b> Blocked</p> <p><b>.... ..1.</b> Apply write only</p> <p><b>.... ...1</b> Same sort merge area</p>

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
File organization and attributes	XL1	<b>1... ..</b> Physical sequential (on host, QSAM) <b>.1... ..</b> ASCII <b>..1. ....</b> Standard label <b>...1 ....</b> User label <b>.... 1...</b> Sequential organization <b>.... .1..</b> Indexed organization <b>.... ..1.</b> Relative organization <b>.... ...1</b> Line sequential
USAGE clause	FL1	<b>X'00'</b> USAGE IS DISPLAY <b>X'01'</b> USAGE IS COMP-1 <b>X'02'</b> USAGE IS COMP-2 <b>X'03'</b> USAGE IS PACKED-DECIMAL or USAGE IS COMP-3 <b>X'04'</b> USAGE IS BINARY, USAGE IS COMP, USAGE IS COMP-4, or USAGE IS COMP-5 <b>X'05'</b> USAGE IS DISPLAY-1 <b>X'06'</b> USAGE IS POINTER <b>X'07'</b> USAGE IS INDEX <b>X'08'</b> USAGE IS PROCEDURE-POINTER <b>X'09'</b> USAGE IS OBJECT-REFERENCE <b>X'0A'</b> FUNCTION-POINTER <b>X'0B'</b> NATIONAL

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
Sign clause	FL1	<b>X'00'</b> No SIGN clause <b>X'01'</b> SIGN IS LEADING <b>X'02'</b> SIGN IS LEADING SEPARATE CHARACTER <b>X'03'</b> SIGN IS TRAILING <b>X'04'</b> SIGN IS TRAILING SEPARATE CHARACTER
Indicators	FL1	<b>X'01'</b> Has JUSTIFIED clause. Right-justified attribute is in effect. <b>X'02'</b> Has BLANK WHEN ZERO clause.
Size	FL4	The size of this data item. The actual number of bytes this item occupies in storage. If a DBCS item, the number is in bytes, not characters. For variable-length items, this field will reflect the maximum size of storage reserved for this item by the compiler. Also known as the "Length attribute."
Precision	FL1	The precision of a fixed or float data item
Scale	FL1	The scale factor of a fixed data item. This is the number of digits to the right of the decimal point.

Table 128. **SYSADATA** symbol record (continued)

Field	Size	Description
Storage type	FL1	<b>00</b> Not applicable <b>01</b> Files <b>02</b> Working-Storage <b>03</b> Linkage Section <b>05</b> Special registers <b>07</b> Indexed by variable <b>10</b> UPSI switch <b>13</b> Variably located items <b>14</b> External data <b>15</b> Alphanumeric FUNC <b>16</b> Alphanumeric EVAL <b>17</b> Object data <b>19</b> Local-Storage <b>20</b> Factory data <b>21</b> XML - TEXT and XML - NTEXT
Date format	FL1	Reserved for future use

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
Data flags 4	XL1	<p>For symbols that have a symbol attribute of Numeric (X'01'):</p> <p><b>1... ..</b>  Numeric national</p> <p>For symbols that have a symbol attribute of Elementary character (X'02'):</p> <p><b>1... ..</b>  National</p> <p><b>.1... ..</b>  National edited</p> <p>For symbols that have a symbol attribute of Group (X'03'):</p> <p><b>1... ..</b>  Group-Usage National</p> <p><b>.1... ..</b>  Unbounded length group</p>
Data flags 5	XL1	<p>OCCURS flags:</p> <p><b>1... ..</b>  UNBOUNDED</p>
Base locator Cell	FL2	Base locator cell number
Symbol Identifier	FL4	Number identifying the symbol
Structure displacement	AL4	Offset of symbol within structure. This offset is set to 0 for variably located items.
Parent displacement	AL4	Byte offset from immediate parent of the item being defined.
Parent ID	FL4	The symbol ID of the immediate parent of the item being defined.
Redefined ID	FL4	The symbol ID of the data item that this item redefines, if applicable.
Start-renamed ID	FL4	If this item is a level-66 item, the symbol ID of the starting COBOL data item that this item renames. If not a level-66 item, this field is set to 0.
End-renamed ID	FL4	If this item is a level-66 item, the symbol ID of the ending COBOL data item that this item renames. If not a level-66 item, this field is set to 0.
Program-name symbol ID	FL4	ID of the program-name of the program or the class-name of the class where this symbol is defined.
OCCURS minimum Paragraph ID	FL4	<p>Minimum value for OCCURS</p> <p>Proc-name ID for a paragraph-name</p>
OCCURS maximum Section ID	FL4	<p>Maximum value for OCCURS</p> <p>Proc-name ID for a section-name</p>
Dimensions	FL4	Number of dimensions

Table 128. **SYSADATA symbol record** (continued)

Field	Size	Description
Case bit vector	XL4	The case of the characters in the symbol name is represented with one bit per character. Each bit has the following meaning:  <b>0</b> Uppercase  <b>1</b> Lowercase  Bit 0 represents the case of the first character, bit 1 represents the case of the second character, and so forth.
Reserved	CL8	Reserved for future use
Value pairs count	HL2	Count of value pairs
Symbol name length	HL2	Number of characters in the symbol name
Picture data length for data-name or Assignment-name length for file-name	HL2	Number of characters in the picture data; zero if symbol has no associated PICTURE clause. (Length of the PICTURE field.) Length represents the field as it is found in the source input. This length does not represent the expanded field for PICTURE items that contain a replication factor. The maximum COBOL length for a PICTURE string is 50 bytes. Zero in this field indicates no PICTURE specified.  Number of characters in the external file-name if this is a file-name. This is the DD name part of the assignment-name. Zero if file-name and ASSIGN USING specified.
Initial Value length for data-name  External class-name length for CLASS-ID	HL2	Number of characters in the symbol value; zero if symbol has no initial value  Number of characters in the external class-name for CLASS-ID
ODO symbol name ID for data-name  ID of ASSIGN data-name if file-name	FL4	If data-name, ID of the ODO symbol name; zero if ODO not specified  If file-name, Symbol-ID for ASSIGN USING data-name; zero if ASSIGN TO specified
Keys count	HL2	The number of keys defined
Index count	HL2	Count of Index symbol IDs; zero if none specified
Symbol name	CL(n)	
Picture data string for data-name or Assignment-name for file-name	CL(n)	The PICTURE character string <i>exactly</i> as the user types it in. The character string includes all symbols, parentheses, and replication factor.  The external file-name if this is a file-name. This is the DD name part of the assignment-name.
Index ID list	(n)FL4	ID of each index symbol name
Keys	(n)XL8	This field contains data describing keys specified for an array. The following three fields are repeated as many times as specified in the 'Keys count' field.

Table 128. <b>SYSADATA symbol record</b> (continued)		
Field	Size	Description
...Key Sequence	FL1	Ascending or descending indicator. <b>X'00'</b> DESCENDING <b>X'01'</b> ASCENDING
...Filler	CL3	Reserved
...Key ID	FL4	The symbol ID of the data item that is the key field in the array
Initial Value data for data-name  External class-name for CLASS-ID	CL(n)	This field contains the data specified in the INITIAL VALUE clause for this symbol. The following four subfields are repeated according to the count in the 'Value pairs count' field. The total length of the data in this field is contained in the 'Initial value length' field.  The external class-name for CLASS-ID.
...1st value length	HL2	Length of first value
...1st value data	CL(n)	1st value.  This field contains the literal (or figurative constant) as it is specified in the VALUE clause in the source file. It includes any beginning and ending delimiters, embedded quotation marks, and SHIFT IN and SHIFT OUT characters. If the literal spans multiple lines, the lines are concatenated into one long string. If a figurative constant is specified, this field contains the actual reserved word, not the value associated with that word.
...2nd value length	HL2	Length of second value, zero if not a THRU value pair
...2nd value data	CL(n)	2nd value.  This field contains the literal (or figurative constant) as it is specified in the VALUE clause in the source file. It includes any beginning and ending delimiters, embedded quotation marks, and SHIFT IN and SHIFT OUT characters. If the literal spans multiple lines, the lines are concatenated into one long string. If a figurative constant is specified, this field contains the actual reserved word, not the value associated with that word.

## Symbol cross-reference record: X'0044'

The following table shows the contents of the symbol cross-reference record.

Table 129. <b>SYSADATA symbol cross-reference record</b>		
Field	Size	Description
Symbol length	HL2	The length of the symbol
Statement definition	FL4	The statement number where the symbol is defined or declared  <b>For STATEMENT XREF only:</b> Statement count - total number of references to this statement.

Table 129. **SYSADATA symbol cross-reference record** (continued)

Field	Size	Description
Number of references <sup>1</sup>	HL2	The number of references in this record to the symbol following
Cross-reference type	XL1	<b>X'01'</b> Program <b>X'02'</b> Procedure <b>X'03'</b> statement <b>X'04'</b> Symbol or data-name <b>X'05'</b> Method <b>X'06'</b> Class
Reserved	CL7	Reserved for future use
Symbol name	CL(n)	The symbol. Variable length.
...Reference flag	CL1	For symbol or data-name references: <b>C' '</b> Blank means reference only <b>C'M'</b> Modification reference flag For Procedure type symbol references: <b>C'A'</b> ALTER (procedure-name) <b>C'D'</b> GO TO (procedure-name) DEPENDING ON <b>C'E'</b> End of range of (PERFORM) through (procedure-name) <b>C'G'</b> GO TO (procedure-name) <b>C'P'</b> PERFORM (procedure-name) <b>C'T'</b> (ALTER) TO PROCEED TO (procedure-name) <b>C'U'</b> Use for debugging (procedure-name)
...Statement number	XL4	The statement number on which the symbol or statement is referenced

Table 129. **SYSADATA symbol cross-reference record** (continued)

Field	Size	Description
<p>1. The reference flag field and the statement number field occur as many times as the number of references field dictates. For example, if there is a value of 10 in the number of references field, there will be 10 occurrences of the reference flag and statement number pair for data-name, procedure, or program symbols, or 10 occurrences of the statement number for statements.</p> <p>Where the number of references would exceed the record size for the SYSADATA file, the record is continued on the next record. The continuation flag is set in the common header section of the record.</p>		

## Nested program record: X'0046'

The following table shows the contents of the nested program record.

Table 130. **SYSADATA nested program record**

Field	Size	Description
Statement definition	FL4	The statement number where the symbol is defined or declared
Nesting level	XL1	Program nesting level
Program attributes	XL1	<b>1... ....</b> Initial <b>.1... ....</b> Common <b>..1. ....</b> PROCEDURE DIVISION using <b>...1 1111</b> Reserved for future use
Reserved	XL1	Reserved for future use
Program-name length	XL1	Length of the following field
Program-name	CL(n)	The program-name

## Library record: X'0060'

The following table shows the contents of the SYSADATA library record.

Table 131. **SYSADATA library record**

Field	Size	Description
Number of members <sup>1</sup>	HL2	Count of the number of COPY/INCLUDE code members described in this record
Library name length	HL2	The length of the library name
Library volume length	HL2	The length of the library volume ID
Concatenation number	XL2	Concatenation number of the library
Library ddname length	HL2	The length of the library ddname
Reserved	CL4	Reserved for future use

<i>Table 131. SYSADATA library record (continued)</i>		
Field	Size	Description
Library name	CL(n)	The name of the library from which the COPY/INCLUDE member was retrieved
Library volume	CL(n)	The volume identification of the volume where the library resides
Library ddname	CL(n)	The ddname (or equivalent) used for this library
...COPY/BASIS member file ID <sup>2</sup>	HL2	The library file ID of the name following
...COPY/BASIS name length	HL2	The length of the name following
...COPY/BASIS name	CL(n)	The name of the COPY/BASIS member that has been used
<p>1. If 10 COPY members are retrieved from a library, the "Number of members" field will contain 10 and there will be 10 occurrences of the "COPY/BASIS member file ID" field, the "COPY/BASIS name length" field, and the "COPY/BASIS name" field.</p> <p>2. If COPY/BASIS members are retrieved from different libraries, a library record is written to the SYSADATA file for each unique library.</p>		

## Statistics record: X'0090'

The following table shows the contents of the statistics record.

<i>Table 132. SYSADATA statistics record</i>		
Field	Size	Description
Source records	FL4	The number of source records processed
DATA DIVISION statements	FL4	The number of DATA DIVISION statements processed
PROCEDURE DIVISION statements	FL4	The number of PROCEDURE DIVISION statements processed
Compilation number	HL2	Batch compilation number
Error severity	XL1	The highest error message severity
Flags	XL1	<b>1... ....</b> End of Job indicator <b>.1... ....</b> Class definition indicator <b>..11 1111</b> Reserved for future use
EOJ severity	XL1	The maximum return code for the compile job
Program-name length	XL1	The length of the program-name
Program-name	CL(n)	Program-name

## EVENTS record: X'0120'

Events records are included in the ADATA file to provide compatibility with previous levels of the compiler.

Events records are of the following types:

- Time stamp
- Processor
- File end
- Program
- File ID
- Error

*Table 133. SYSADATA EVENTS TIMESTAMP record layout*

Field	Size	Description
Header	CL12	Standard ADATA record header
Record length	HL2	Length of following EVENTS record data (excluding this halfword)
EVENTS record type TIMESTAMP record	CL12	C'TIMESTAMP'
Blank separator	CL1	
Revision level	XL1	
Blank separator	CL1	
Date	XL8	YYYYMMDD
Hour	XL2	HH
Minutes	XL2	MI
Seconds	XL2	SS

*Table 134. SYSADATA EVENTS PROCESSOR record layout*

Field	Size	Description
Header	CL12	Standard ADATA record header
Record length	HL2	Length of following EVENTS record data (excluding this halfword)
EVENTS record type PROCESSOR record	CL9	C'PROCESSOR'
Blank separator	CL1	
Revision level	XL1	
Blank separator	CL1	
Output file ID	XL1	
Blank separator	CL1	
Line-class indicator	XL1	

*Table 135. SYSADATA EVENTS FILE END record layout*

Field	Size	Description
Header	CL12	Standard ADATA record header
Record length	HL2	Length of following EVENTS record data (excluding this halfword)

*Table 135. SYSADATA EVENTS FILE END record layout (continued)*

Field	Size	Description
EVENTS record type FILE END record	CL7	C'FILEEND'
Blank separator	CL1	
Revision level	XL1	
Blank separator	CL1	
Input file ID	XL1	
Blank separator	CL1	
Expansion indicator	XL1	

*Table 136. SYSADATA EVENTS PROGRAM record layout*

Field	Size	Description
Header	CL12	Standard ADATA record header
Record length	HL2	Length of following EVENTS record data (excluding this halfword)
EVENTS record type PROGRAM record	CL7	C'PROGRAM'
Blank separator	CL1	
Revision level	XL1	
Blank separator	CL1	
Output file ID	XL1	
Blank separator	CL1	
Program input record number	XL1	

*Table 137. SYSADATA EVENTS FILE ID record layout*

Field	Size	Description
Header	CL12	Standard ADATA record header
Record length	HL2	Length of following EVENTS record data (excluding this halfword)
EVENTS record type FILE ID record	CL7	C'FILEID'
Blank separator	CL1	
Revision level	XL1	
Blank separator	CL1	
Input source file ID	XL1	File ID of source file
Blank separator	CL1	
Reference indicator	XL1	
Blank separator	CL1	

*Table 137. SYSADATA EVENTS FILE ID record layout (continued)*

Field	Size	Description
Source file name length	H2	
Blank separator	CL1	
Source file name	CL(n)	

*Table 138. SYSADATA EVENTS ERROR record layout*

Field	Size	Description
Header	CL12	Standard ADATA record header
Record length	HL2	Length of following EVENTS record data (excluding this halfword)
EVENTS record type ERROR record	CL5	C'ERROR'
Blank separator	CL1	
Revision level	XL1	
Blank separator	CL1	
Input source file ID	XL1	File ID of source file
Blank separator	CL1	
Annot class	XL1	Annot-class message placement
Blank separator	CL1	
Error input record number	XL10	
Blank separator	CL1	
Error start line number	XL10	
Blank separator	CL1	
Error token start number	XL1	Column number of error token start
Blank separator	CL1	
Error end line number	XL10	
Blank separator	CL1	
Error token end number	XL1	Column number of error token end
Blank separator	CL1	
Error message ID number	XL9	
Blank separator	CL1	
Error message severity code	XL1	
Blank separator	CL1	
Error message severity level number	XL2	

<i>Table 138. SYSADATA EVENTS ERROR record layout (continued)</i>		
<b>Field</b>	<b>Size</b>	<b>Description</b>
Blank separator	CL1	
Error message length	HL3	
Blank separator	CL1	
Error message text	CL(n)	



---

## Appendix H. Using sample programs

The sample programs, which are included on your product tape, demonstrate many language elements and concepts of COBOL.

This information contains the following items:

- Overview of the programs, including program charts for two of the samples
- Format and sample of the input data
- Sample of reports produced
- Information about how to run the programs
- List of the language elements and concepts that are illustrated

Pseudocode and other comments about the programs are included in the program prolog, which you can obtain in a program listing.

There are three sample programs:

- IGYTCARA is an example of using QSAM files and VSAM indexed files, and shows how to use many COBOL intrinsic functions.
- IGYTCARB is an example of using IBM Interactive System Product Facility (ISPF).
- IGYTSALE is an example of using several of the features of the Language Environment callable services.

### **related concepts**

[“IGYTCARA: batch application” on page 805](#)

[“IGYTCARB: interactive program” on page 809](#)

[“IGYTSALE: nested program application” on page 811](#)

---


## IGYTCARA: batch application

A company that has several local offices wants to establish employee carpools. Application IGYTCARA validates the transaction-file entries (QSAM sequential file processing) and updates a main file (VSAM indexed file processing).

This batch application does two tasks:

- Produces reports of employees who can share rides from the same home location to the same work location
- Updates the carpool data:
  - Adds data for new employees
  - Changes information for participating employees
  - Deletes employee records
  - Lists update requests that are not valid

The following diagram shows the parts of the application and how they are organized:



### related tasks

[“Preparing to run IGYTCARA” on page 808](#)

### related references

[“Input data for IGYTCARA” on page 806](#)

[“Report produced by IGYTCARA” on page 807](#)

[“Language elements and concepts that are illustrated” on page 819](#)

## Input data for IGYTCARA

As input to the program, the company collected information from interested employees, coded the information, and produced an input file. Here is an example of the format of the input file (spaces between fields are left out, as they would be in your input file) with an explanation of each item.

A10111	ROBERTS	AB1021	CRYSTAL	COURTSAN	FRANCISCO	CA9990141555501904155551387H1W1D
↑↑↑↑↑		↑		↑		↑↑↑↑↑
12	3	4	5	6	7	8
						9
						10
						11

1. Transaction code
2. Shift
3. Home code
4. Work code
5. Commuter name

6. Home address
7. Home phone
8. Work phone
9. Home location code
10. Work location code
11. Driving status code

This sample below shows a section of the input file:

```
A10111ROBERTS AB1021 CRYSTAL COURTSAN FRANCISCOCA9990141555501904155551387H1W1D
A20212KAHN DE789 EMILY LANE SAN FRANCISCOCA9992141555518904155552589H2W2D
P48899 99ASDFG0005557890123ASDFGHJ T
R10111ROBERTS AB1221 CRYSTAL COURTSAN FRANCISCOCA9990141555501904155551387H1W1D
A20212KAHN DE789 EMILY LANE SAN FRANCISCOCA9992141555518904155552589H2W2D
D20212KAHN DE
D20212KAHN DE
A20212KAHN DE789 EMILY LANE SAN FRANCISCOCA9992141555518904155552589H2W2D
A10111BONNICK FD1025 FIFTH AVENUE SAN FRANCISCOCA9990541555595904155557895H8W3
A10111PETERSON SW435 THIRD AVENUE SAN FRANCISCOCA9990541555546904155553717H3W4
. . .
```

## Report produced by IGYTCARA

The following sample shows the first page of the output report produced by IGYTCARA. Your actual output might vary slightly in appearance, depending on your system.

```
1REPORT #: IGYTCAR1 COMMUTER FILE UPDATE LIST PAGE #: 1
-PROGRAM #: IGYTCAR1 RUN TIME: 01:40 RUN DATE: 11/24/2003
-----
TRANS|RE-|SHIFT| COMMUTER | HOME | HOME PHONE | HOME LOCATION JUNCTION |STA-|
CODE |TYPE|WORK CODE| NAME | ADDRESS | WORK PHONE | WORK LOCATION JUNCTION |TUS | TRANS. ERROR
-----
A NEW 1 01 11 ROBERTS AB 1021 CRYSTAL COURT (415) 555-0190 RODNEY/CRYSTAL D
SAN FRANCISCO CA 99901 (415) 555-1387 BAYFAIR PLAZA
A NEW 2 02 12 KAHN DE 789 EMILY LANE (415) 555-1890 COYOTE D
SAN FRANCISCO CA 99921 (415) 555-2589 14TH STREET/166TH AVENUE
P 4 88 99 (000) 555-7890 HOME CODE ' ' NOT FOUND. T
99 ASDFG (123) ASD-FGHJ WORK CODE ' ' NOT FOUND.
TRANSACT. CODE
SHIFT CODE
HOME LOC. CODE
WORK LOC. CODE
LAST NAME
INITIALS
ADDRESS
CITY
STATE CODE
ZIPCODE
HOME PHONE
WORK PHONE
HOME JUNCTION
WORK JUNCTION
DRIVING STATUS
-----
R OLD 1 01 11 ROBERTS AB 1021 CRYSTAL COURT (415) 555-0190 RODNEY/CRYSTAL D
SAN FRANCISCO CA 99901 (415) 555-1387 BAYFAIR PLAZA
NEW 1 01 11 ROBERTS AB 1221 CRYSTAL COURT (415) 555-0190 RODNEY/CRYSTAL D
SAN FRANCISCO CA 99901 (415) 555-1387 BAYFAIR PLAZA
A 2 02 12 KAHN DE 789 EMILY LANE (415) 555-1890 COYOTE D
SAN FRANCISCO CA 99921 (415) 555-2589 14TH STREET/166TH AVENUE DUPLICATE REC.
D OLD 2 02 12 KAHN DE 789 EMILY LANE (415) 555-1890 COYOTE D
SAN FRANCISCO CA 99921 (415) 555-2589 14TH STREET/166TH AVENUE
D 2 02 12 KAHN DE REC. NOT FOUND
A NEW 2 02 12 KAHN DE 789 EMILY LANE (415) 555-1890 COYOTE D
SAN FRANCISCO CA 99921 (415) 555-2589 14TH STREET/166TH AVENUE
A NEW 1 01 11 BONNICK FD 1025 FIFTH AVENUE (415) 555-9590 RODNEY
SAN FRANCISCO CA 99905 (415) 555-7895 17TH FREEWAY SAN LEANDRO
A NEW 1 01 11 PETERSON SW 435 THIRD AVENUE (415) 555-4690 RODNEY/THIRD AVENUE
```

## Preparing to run IGYTCARA

All files required by the IGYTCARA program (IGYTCARA, IGYTCODE, and IGYTRANX) are supplied on the product installation tape. These files are located in the IGY.V6R1M0.SIGYSAMP data set.

Data-set and procedure names might be changed at installation time. Check with your system programmer to verify these names.

Do not change these options on the CBL statement in the source file for IGYTCARA:

- NOADV
- NODYNAM
- NONAME
- NONUMBER
- QUOTE
- SEQUENCE

With these options in effect, the program will not cause any diagnostic messages to be issued. You can use the sequence number string in the source file to search for the language elements used.

### related concepts

[“IGYTCARA: batch application” on page 805](#)

### related tasks

[“Running IGYTCARA” on page 808](#)

### related references

[“Input data for IGYTCARA” on page 806](#)

[“Report produced by IGYTCARA” on page 807](#)

[“Language elements and concepts that are illustrated” on page 819](#)

## Running IGYTCARA

The following procedure compiles, link-edits, and runs the IGYTCARA program. If you want only to compile or only to compile and link-edit the program, you must change the IGYWCLG cataloged procedure.

To run IGYTCARA under z/OS, use JCL to define a VSAM cluster and compile the program. Insert the information specific to your system and installation (accounting information, volume serial number, unit name, cluster prefix) in the fields that are shown in lowercase letters. These examples use the name IGYTCAR.MASTFILE; you can use another name if you want to.

1. Use this JCL to create the required VSAM cluster:

```
//CREATE JOB (acct-info),'IGYTCAR CREATE VSAM',MSGLEVEL=(1,1),
// TIME=(0,29)
//CREATE EXEC PGM=IDCAMS
//VOL1 DD VOL=SER=your-volume-serial,UNIT=your-unit,DISP=SHR
//SYSPRINT DD SYSOUT=A
//SYSIN DD *
DELETE your-prefix.IGYTCAR.MASTFILE -
FILE(VOL1) -
PURGE
DEFINE CLUSTER -
(NAME(your-prefix.IGYTCAR.MASTFILE) -
VOLUME(your-volume-serial) -
FILE(VOL1) -
INDEXED -
RECSZ(80 80) -
KEYS(16 0) -
CYLINDERS(2))
/*
```

To remove any existing cluster, a DELETE is issued before the VSAM cluster is created.

2. Use the following JCL to compile, link-edit, and run the IGYTCARA program:

```
//IGYTCARA JOB (acct-info), 'IGYTCAR', MSGLEVEL=(1,1), TIME=(0,29)
//TEST EXEC IGYWCLG
//COBOL.SYSLIB DD DSN=IGY.V6R1M0.SIGYSAMP, DISP=SHR
//COBOL.SYSIN DD DSN=IGY.V6R1M0.SIGYSAMP(IGYTCARA), DISP=SHR
//GO.SYSOUT DD SYSOUT=A
//GO.COMMUTR DD DSN=your-prefix.IGYTCAR.MASTFILE, DISP=SHR
//GO.LOCCODE DD DSN=IGY.V6R1M0.SIGYSAMP(IGYTCODE), DISP=SHR
//GO.UPDTRANS DD DSN=IGY.V6R1M0.SIGYSAMP(IGYTRANX), DISP=SHR
//GO.UPDPRINT DD SYSOUT=A, DCB=BLKSIZE=133
//
```

#### related tasks

[Chapter 10, “Processing VSAM files,” on page 173](#)

#### related references

[“Compile, link-edit, and run procedure \(IGYWCLG\)” on page 241](#)

## IGYTCARB: interactive program

IGYTCARB contains an interactive program for entering carpool data by using IBM Interactive System Productivity Facility (ISPF) to invoke Dialog Manager and Enterprise COBOL. IGYTCARB creates a file that can be used as input for a carpool listing or matching program such as IGYTCARA.

The input data for IGYTCARB is the same as that for IGYTCARA. IGYTCARB lets you append to the information in your input file by using an ISPF panel. An example of the panel used by IGYTCARB is shown below:

```
----- CARPOOL DATA ENTRY -----
New Data Entry                                Previous Entry
Type =====> -                               A, R, or D      A
Shift =====> -                               1, 2, or 3     1
Home Code ==> --                               2 Chars       01
Work Code ==> --                               2 Chars       11
Name =====> -----                         9 Chars       POPOWICH
Initials ==> --                               2 Chars       AD
Address ==> -----                           18 Chars      134 SIXTH AVENUE
City =====> -----                         13 Chars      SAN FRANCISCO
State =====> --                             2 Chars       CA
Zip Code ==> -----                           5 Chars       99903
Home Phone => -----                         10 Chars      4155553390
Work Phone => -----                         10 Chars      4155557855
Home Jnc code > --                             2 Chars       H3
Work Jnc Code > --                             2 Chars       W7
Commuter Stat > -                             D, R or blank
```

#### related tasks

[“Preparing to run IGYTCARB” on page 809](#)

## Preparing to run IGYTCARB

Run the IGYTCARB program under Interactive System Productivity Facility (ISPF). All files required by IGYTCARB (IGYTCARB, IGYTRANB, and IGYTPNL) are supplied on the product installation tape in the IGY.V6R1M0.SIGYSAMP data set.

Data-set names and procedure-names might be changed at installation time. Check with your system programmer to verify the names.

Do not change the following options in the CBL statement in the source file for IGYTCARB:

- NONUMBER
- QUOTE
- SEQUENCE

With these options in effect, the program will not cause any diagnostic messages to be issued. You can use the sequence number string in the source file to search for language elements.

## related concepts

[“IGYTCARB: interactive program” on page 809](#)

## related tasks

[“Running IGYTCARB” on page 810](#)

## related references

[“Language elements and concepts that are illustrated” on page 819](#)

# Running IGYTCARB

The following procedure compiles, link-edits, and runs the IGYTCARB program. If you want only to compile or only to compile and link-edit the program, you must change the procedure.

To run IGYTCARB under z/OS, do the following steps:

1. Using the ISPF editor, change the ISPF/PDF Primary Option Panel (ISR@PRIM) or some other panel to include the IGYTCARB invocation. Panel ISR@PRIM is in your site's PDF panel data set (normally ISRPLIB).

The following example shows an ISR@PRIM panel modified, in two identified locations, to include the IGYTCARB invocation. If you add or change an option in the upper portion of the panel definition, you must also add or change the corresponding line on the lower portion of the panel.

```
%----- ISPF/PDF PRIMARY OPTION PANEL -----+
%OPTION ==>_ZCMD
%
% 0 +ISPF PARMS - Specify terminal and user parameters +USERID - &ZUSER
% 1 +BROWSE - Display source data or output listings +TIME - &ZTIME
% 2 +EDIT - Create or change source data +TERMINAL - &ZTERM
% 3 +UTILITIES - Perform utility functions +PF KEYS - &ZKEYS
% 4 +FOREGROUND - Invoke language processors in foreground
% 5 +BATCH - Submit to batch for language processing
% 6 +COMMAND - Enter TSO or Workstation commands
% 7 +DIALOG TEST - Perform dialog testing
% 8 +LM UTILITIES- Perform library management utility functions
% C +IGYTCARB - Run IGYTCARB UPDATE TRANSACTION PROGRAM (1)
% T +TUTORIAL - Display information about ISPF/PDF
% X +EXIT - Terminate using console, log, and list defaults
%
%
+Enter%END+command to terminate ISPF.
%
)INIT
 .HELP = ISR00003
 &ZPRIM = YES /* ALWAYS A PRIMARY OPTION MENU */
 &ZHTOP = ISR00003 /* TUTORIAL TABLE OF CONTENTS */
 &ZHINDEX = ISR91000 /* TUTORIAL INDEX - 1ST PAGE */
 VPUT (ZHTOP,ZHINDEX) PROFILE
)PROC
 &Z1 = TRUNC(&ZCMD,1)
 IF (&Z1 &notsym.= '.')
 &ZSEL = TRANS( TRUNC (&ZCMD, '.'))
 0, 'PANEL(ISPOPTA)'
 1, 'PGM(ISRBRO) PARM(ISRBRO01)'
 2, 'PGM(ISREDIT) PARM(P,ISREDM01)'
 3, 'PANEL(ISRUTIL)'
 4, 'PANEL(ISRFPA)'
 5, 'PGM(ISRJB1) PARM(ISRJPA) NOCHECK'
 6, 'PGM(ISRPCC)'
 7, 'PGM(ISRYXDR) NOCHECK'
 8, 'PANEL(ISRLPRIM)'
 C, 'PGM(IGYTCARB)' (2)
 T, 'PGM(ISPTUTOR) PARM(ISR00000)'
 , , ,
 X, 'EXIT'
 *, '?' )
 &ZTRAIL = .TRAIL
 IF (&Z1 = '.') .msg = ISPD141
)END
```

As indicated by **(1)** in this example, you add IGYTCARB to the upper portion of the panel by entering:

```
% C +IGYTCARB - Run IGYTCARB UPDATE TRANSACTION PROGRAM
```

You add the corresponding line on the lower portion of the panel, indicated by **(2)**, by entering:

```
C, 'PGM(IGYTCARB)'
```

2. Place ISR@PRIM (or your other modified panel) and IGYTPNL in a library and make this library the first library in the ISPLIB concatenation.
3. Comment sequence line IB2200 and uncomment sequence line IB2210 in IGYTCARB. (The OPEN EXTEND statement is supported under z/OS.)
4. Compile and link-edit IGYTCARB and place the resulting program object in your LOADLIB.
5. Allocate ISPLLIB by using the following command:

```
ALLOCATE FILE(ISPLLIB) DATASET(DSN1, SYS1.COBLIB, DSN2) SHR REUSE
```

Here *DSN1* is the library name of the LOADLIB from step 4. *DSN2* is your installed ISPLIB.

6. Allocate the input and output data sets by using the following command:

```
ALLOCATE FILE(UPDTRANS) DA('IGY.V6R1M0.SIGYSAMP(IGYTRANB)') SHR REUSE
```

7. Allocate ISPLLIB by using the following command:

```
ALLOCATE FILE(ISPLLIB) DATASET(DSN3, DSN4) SHR REUSE
```

Here *DSN3* is the library containing the modified panels. *DSN4* is the ISPF panel library.

8. Invoke IGYTCARB by using your modified panel.

#### related references

*ISPF Dialog Developer's Guide and Reference*


## IGYTSALE: nested program application

Application IGYTSALE tracks product sales and sales commissions for a sporting-goods distributor.


This nested program application does the following tasks:

1. Keeps a record of the product line, customers, and number of salespeople. This data is stored in a file called IGYTABLE.
2. Maintains a file that records valid transactions and transaction errors. All transactions that are not valid are flagged, and the results are printed in a report. Transactions to be processed are in a file called IGYTRANA.
3. Processes transactions and report sales by location.
4. Records an individual's sales performance and commission, and prints the results in a report.
5. Reports the sale and shipment dates in local time and UTC (Universal Time Coordinate), and calculates the response time.

The following diagram shows the parts of the application as a hierarchy:



The following diagram shows how the parts are nested:



### related tasks

[“Preparing to run IGYTSALE” on page 818](#)

### related references

[“Input data for IGYTSALE” on page 812](#)


[“Reports produced by IGYTSALE” on page 814](#)

[“Language elements and concepts that are illustrated” on page 819](#)

## Input data for IGYTSALE

As input to our program, the distributor collected information about its customers, salespeople, and products, coded the information, and produced an input file.

This input file, called IGYTABLE, is loaded into three separate tables for use during transaction processing. The format of the file is as follows, with an explanation of the items below:



1. Record type
2. Customer code
3. Customer name
4. Product code
5. Product description
6. Product unit price
7. Salesperson number
8. Salesperson name
9. Date of hire
10. Commission rate


The value of field 1 (C, P, or S) determines the format of the input record. The following sample shows a section of IGYTABLE:

```

S1111Edyth Phillips 062484042327
S1122Chuck Morgan 052780084425
S1133Art Tung 022882061728
S1144Billy Jim Bob 010272121150
S1155Chris Preston 122083053377
S1166Al Willie Roz 111276100000
P01Footballs 0000620
P02Football Equipment 0032080
P03Football Uniform 0004910
P04Basketballs 0002220
P05Basketball Rim/Board0008830
P06Basketball Uniform 0004220
C01L. A. Sports
C02Gear Up
C03Play Outdoors
C04Sports 4 You
C05Sports R US
C06Stay Active
C07Sport Shop
C08Stay Sporty
C09Hot Sports
C10The Sportsman
C11Playing Ball
C12Sports Play
. . .

```

In addition, the distributor collected information about sales transactions. Each transaction represents an individual salesperson's sales to a particular customer. The customer can purchase from one to five items during each transaction. The transaction information is coded and put into an input file, called IGYTRANA. The format of this file is as follows, with an explanation of the items below:



1. Sales order number
2. Invoiced items (number of different items ordered)
3. Date of sale (year month day hour minutes seconds)
4. Sales area
5. Salesperson number
6. Customer code
7. Date of shipment (year month day hour minutes seconds)
8. Product code
9. Quantity sold

Fields 8 and 9 occur one to eight times depending on the number of different items ordered (field 2). The following sample shows a section of IGYTRANA:

```
A00001119900227010101CNTRL VALLEY11442019900228259999
A00004119900310100530CNTRL VALLEY11441019900403150099
A00005119900418222409CNTRL VALLEY11441219900419059900
A00006119900523151010CNTRL VALLEY11442019900623250004
  419990324591515SAN DIEGO 11615 60200132200110522045100
B11114419901111003301SAN DIEGO 11661519901114260200132200110522041100
A00007119901115003205CNTRL VALLEY11332019901117120023
C00125419900118101527SF BAY AREA 11331519900120160200112200250522145111
B11116419901201132013SF BAY AREA 11331519901203060200102200110522045102
B11117319901201070833SAN Diego 11656619901203330200132200120522041100
B11118419901221191544SAN DIEGO 11661419901223160200142200130522040300
B11119419901210211544SAN DIEGO 11221219901214060200152200160522050500
B11120419901212000816SAN DIEGO 11220419901213150200052200160522040100
B11121419901201131544SAN DIEGO 11330219901203120200112200140522250100
B11122419901112073312SAN DIEGO 11221019901113100200162200260522250100
B11123919901110123314SAN DIEGO 11660919901114260200270500110522250100140010
B11124219901313510000SAN DIEGO 116611 1 0200042200120a22141100
B11125419901215012510SAN DIEGO 11661519901216110200162200130522141111
B11126119901111000034SAN DIEGO 11331619901113260022
B11127119901110154100SAN DIEGO 11221219901113122000
B11128419901110175001SAN DIEGO 11661519901113260200132200160521041104
. . .
```

## Reports produced by IGYTSALE

The figures referenced below are samples of IGYTSALE output.

The program records the following data in reports:

- Transaction errors
- Sales by product and area
- Individual sales performance and commissions
- Response time between the sale date and the date the sold products are shipped

Your output might vary slightly in appearance, depending on your system.

[“Example: IGYTSALE transaction errors” on page 815](#)

[“Example: IGYTSALE sales analysis by product by area” on page 815](#)

[“Example: IGYTSALE sales and commissions” on page 817](#)

[“Example: IGYTSALE response time from sale to ship” on page 818](#)

## Example: IGYTSALE transaction errors

The following sample of IGYTSALE output shows transaction errors in the last column.

Day of Report: Tuesday		C O B O L		S P O R T S		11/24/2003	03:12	Page: 1
Sales Order	Inv. Items	Sales Time Stamp	Sales Area	Sales Pers	Cust. Code	Product And Quantity Sold	Ship Date Stamp	
-----	-----	-----	-----	-----	-----	-----	-----	
	4	19990324591515	SAN DIEGO	116	15	60200132200110522045100		Error Descriptions -Sales order number is missing -Date of sale time stamp is
invalid								
table								-Salesperson number not numeric -Product code not in product-
invalid								-Date of ship time stamp is
B11117	3	19901201070833	SAN Diego	1165	66	330200132200120522041100	19901203	Error Descriptions -Sales area not in area-table -Salesperson not in sales-per-
table								-Customer code not in customer-
table								-Product code not in product-
table								
B11123	9	19901110123314	SAN DIEGO	1166	09	260200270500110522250100140010	19901114	-Quantity sold not numeric Error Descriptions -Invoiced items is invalid -Product and quantity not
checked								-Date of ship time stamp is
invalid								
B11124	2	19901313510000	SAN DIEGO	1166	11	1 0200042200120a22141100		Error Descriptions -Date of sale time stamp is
invalid								-Product code is invalid -Date of ship time stamp is
invalid								
133		81119110000	LOS ANGELES	1166	10	040112110210160321251104		Error Descriptions -Sales order number is invalid -Invoiced items is invalid -Date of sale time stamp is
invalid								-Product and quantity not
checked								-Date of ship time stamp is
invalid								
C11133	4	1990111944		1166	10	040112110210160321251104		Error Descriptions -Date of sale time stamp is
invalid								-Sales area is missing -Date of ship time stamp is
invalid								
C11138	4	19901117091530	LOS ANGELES	1155		113200102010260321250004	19901119	Error Descriptions -Customer code is invalid
D00009	9	19901201222222	CNTRL COAST	115	19	141 1131221	19901202	Error Descriptions -Invoiced items is invalid

## Example: IGYTSALE sales analysis by product by area

The following sample of IGYTSALE output shows sales by product and area.

Day of Report: Tuesday		C O B O L		S P O R T S		11/24/2003	03:12	Page: 1
				Sales Analysis By Product By Area				
				Areas of Sale				
			CNTRL COAST		CNTRL VALLEY		LOS ANGELES	
							NORTH COAST	
							SAN DIEGO	
							SF BAY AREA	
Totals		Codes						Product
=====								
==		Product Number 04						
		Basketballs						
		Units Sold				433		2604   5102
8139		Unit Price				22.20		22.20   22.20
		Amount of Sale				\$9,612.60		\$57,808.80   \$113,264.40
		\$180,685.80						
-----								
--		Product Number 05						
		Basketball Rim/Board						
		Units Sold			9900	2120	11	2700
14731		Unit Price			88.30	88.30	88.30	88.30
		Amount of Sale			\$874,170.00	\$187,196.00	\$971.30	\$238,410.00
		\$1,300,747.30						

-----							
--							
Product Number 06							
Basketball Uniform							
Units Sold							
1390				990	200	200	
Unit Price							
				42.20	42.20	42.20	
Amount of Sale							
\$58,658.00				\$41,778.00	\$8,440.00	\$8,440.00	
-----							
--							
Product Number 10							
Baseball Cage							
Units Sold							
7031	45		3450	16	200	3320	
Unit Price							
	890.00		890.00	890.00	890.00	890.00	
Amount of Sale							
\$6,257,590.00	\$40,050.00		\$3,070,500.00	\$14,240.00	\$178,000.00	\$2,954,800.00	
-----							
--							
Product Number 11							
Baseball Uniform							
Units Sold							
19249	10003		3578		2922	2746	
Unit Price							
	45.70		45.70		45.70	45.70	
Amount of Sale							
\$879,679.30	\$457,137.10		\$163,514.60		\$133,535.40	\$125,492.20	
-----							
--							
Product Number 12							
Softballs							
Units Sold							
4946	10	137	2564	13	2200	22	
Unit Price							
	1.40	1.40	1.40	1.40	1.40	1.40	
Amount of Sale							
\$6,924.40	\$14.00	\$191.80	\$3,589.60	\$18.20	\$3,080.00	\$30.80	
-----							
--							
Product Number 13							
Softball Bats							
Units Sold							
14068	3227		3300	1998	5444	99	
Unit Price							
	12.60		12.60	12.60	12.60	12.60	
Amount of Sale							
\$177,256.80	\$40,660.20		\$41,580.00	\$25,174.80	\$68,594.40	\$1,247.40	
-----							
--							
Product Number 14							
Softball Gloves							
Units Sold							
13395	1155		136	3119	3833	5152	
Unit Price							
	12.00		12.00	12.00	12.00	12.00	
Amount of Sale							
\$160,740.00	\$13,860.00		\$1,632.00	\$37,428.00	\$45,996.00	\$61,824.00	
-----							
--							
Product Number 15							
Softball Cage							
Units Sold							
5496	997	99	2000		2400		
Unit Price							
	890.00	890.00	890.00		890.00		
Amount of Sale							
\$4,891,440.00	\$887,330.00	\$88,110.00	\$1,780,000.00		\$2,136,000.00		
-----							
--							
Product Number 16							
Softball Uniform							
Units Sold							
6890	44		465	16	6165	200	
Unit Price							
	45.70		45.70	45.70	45.70	45.70	
Amount of Sale							
\$314,873.00	\$2,010.80		\$21,250.50	\$731.20	\$281,740.50	\$9,140.00	
-----							
--							
Product Number 25							
RacketBalls							

Units Sold	1001	10003	1108	8989	200	522
Unit Price	0.60	0.60	0.60	0.60	0.60	0.60
Amount of Sale	\$600.60	\$6,001.80	\$664.80	\$5,393.40	\$120.00	\$313.20
-----						
Product Number 26						
Racketball Rackets						
Units Sold	21		862	194	944	31
Unit Price	12.70		12.70	12.70	12.70	12.70
Amount of Sale	\$266.70		\$10,947.40	\$2,463.80	\$11,988.80	\$393.70
-----						
=====						
Total Units Sold	16503	20139	20016	15346	29812	17394 *
Total Sales	\$1,441,929.40	\$968,473.60	\$5,290,487.50	\$128,198.70	\$3,163,713.90	\$3,274,945.70 *
=====						

## Example: IGYTSALE sales and commissions

The following sample of IGYTSALE output shows sales performance and commissions by salesperson.

Day of Report: Tuesday	C O B O L	S P O R T S	11/24/2003	03:12	Page: 1	
Salesperson: Billy Jim Bob			Sales and Commission Report			
Customers:	Number of Orders	Products Ordered	Total for Order	Discount (if any)	Discount Amount	Commission Earned
-----						
Sports Stop	3	10117	\$6,161.40	2.25%	\$138.63	\$746.45
The Sportsman	1	99	\$88,110.00	5.06%	\$4,458.36	\$10,674.52
Sports Play	1	9900	\$874,170.00	7.59%	\$66,349.50	\$105,905.69
-----						
Totals:	5	20116	\$968,441.40		\$70,946.49	\$117,326.66
Salesperson: Willie Al Roz						
Customers:	Number of Orders	Products Ordered	Total for Order	Discount (if any)	Discount Amount	Commission Earned
-----						
Winners Club	4	13998	\$1,572,775.90	7.59%	\$119,373.69	\$157,277.59
Winning Sports	1	3222	\$48,777.20	3.38%	\$1,648.66	\$4,877.72
The Sportsman	1	1747	\$27,415.50	3.38%	\$926.64	\$2,741.55
Play Outdoors	1	2510	\$18,579.60	3.38%	\$627.99	\$1,857.96
-----						
Totals:	7	21477	\$1,667,548.20		\$122,576.98	\$166,754.82
Salesperson: Art Tung						
Customers:	Number of Orders	Products Ordered	Total for Order	Discount (if any)	Discount Amount	Commission Earned
-----						
Sports Stop	1	23	\$32.20	2.25%	\$7.2	\$1.98
Winners Club	2	16057	\$2,274,885.00	7.59%	\$172,663.77	\$140,424.10
Gear Up	1	3022	\$107,144.00	7.59%	\$8,132.22	\$6,613.78
Sports Club	1	22	\$279.40	2.25%	\$6.28	\$17.24
Sports Fans Shop	1	1044	\$20,447.30	3.38%	\$691.11	\$1,262.17
L. A. Sports	1	1163	\$979,198.10	7.59%	\$74,321.13	\$60,443.94
-----						
Totals:	7	21331	\$3,381,986.00		\$255,815.23	\$208,763.21
Salesperson: Chuck Morgan						
Customers:	Number of Orders	Products Ordered	Total for Order	Discount (if any)	Discount Amount	Commission Earned
-----						
Sports Play	3	7422	\$3,817,245.40	7.59%	\$289,728.92	\$322,270.94
Sports 4 You	1	3022	\$398,335.40	7.59%	\$30,233.65	\$33,629.46
The Sportsman	1	3022	\$285,229.40	7.59%	\$21,648.91	\$24,080.49
Sports 4 Winners	1	1100	\$68,509.40	5.06%	\$3,466.57	\$5,783.90
Sports Club	1	12027	\$1,324,256.10	7.59%	\$100,511.03	\$111,800.32
-----						
Totals:	7	26593	\$5,893,575.70		\$445,589.08	\$497,565.11
Salesperson: Chris Preston						
Customers:	Number of Orders	Products Ordered	Total for Order	Discount (if any)	Discount Amount	Commission Earned
-----						
Playing Ball	1	5535	\$1,939,219.10	7.59%	\$147,186.72	\$103,509.69
Play Sports	1	5675	\$225,130.80	7.59%	\$17,087.42	\$12,016.80
Winners Club	1	631	\$14,069.70	2.25%	\$316.56	\$750.99
The Jock Shop	1	2332	\$28,716.60	3.38%	\$970.62	\$1,532.80
-----						
Totals:	4	14173	\$2,207,136.20		\$165,561.32	\$117,810.28
Salesperson: Edyth Phillips						
Customers:	Number of Orders	Products Ordered	Total for Order	Discount (if any)	Discount Amount	Commission Earned

Sports Play	2	3575	\$92,409.90	5.06%	\$4,675.94	\$3,911.43
Winning Sports	1	11945	\$56,651.40	5.06%	\$2,866.56	\$2,397.88
Totals:	3	15520	\$149,061.30		\$7,542.50	\$6,309.31
Grand Totals:	33	119210	\$14,267,748.80		\$1,068,031.60	\$1,114,529.39

## Example: IGYTSALE response time from sale to ship

The following sample of IGYTSALE output shows response time between the sale date in the United States and the date the sold products are shipped to Europe.

Day of Report: Monday COBOL SPORTS 11/24/2003 03:12 Page: 1						
Response Time from USA Sale to European Ship						
Prod Code	Units Sold	Sale Date/Time(PST) YYYYMMDD HHMMSS	Ship Date YYYYMMDD	Ship Day	Response Time Days	
25	9999	19900226 010101	19900228	WED	.95	
15	99	19900310 100530	19900403	TUE	23.57	
05	9900	19900418 222409	19900419	THU	.06	
25	4	19900523 151010	19900623	SAT	30.36	
04	1100	19901110 003301	19901114	WED	2.97	
12	23	19901114 003205	19901117	SAT	1.97	
14	5111	19900118 101527	19900120	SAT	1.57	
04	5102	19901201 132013	19901203	MON	1.44	
04	300	19901221 191544	19901223	SUN	1.19	
05	500	19901210 211544	19901214	FRI	3.11	
04	100	19901211 000816	19901213	THU	.99	
25	100	19901201 131544	19901203	MON	1.44	
25	100	19901112 073312	19901113	TUE	.68	
14	1111	19901214 012510	19901216	SUN	.94	
26	22	19901110 000034	19901113	TUE	1.99	
12	2000	19901110 154100	19901113	TUE	2.34	
04	1104	19901110 175001	19901113	TUE	2.25	
12	114	19901229 115522	19901230	SUN	.50	
15	2000	19901110 190113	19901114	WED	3.20	
10	1440	19901112 001500	19901115	THU	1.98	
25	1104	19901118 120101	19901119	MON	.49	
25	4	19901118 110030	19901119	MON	.54	
12	144	19901114 010510	19901119	MON	3.95	
14	112	19901119 010101	19901122	THU	1.95	
26	321	19901117 173945	19901119	MON	1.26	
13	1221	19901101 135133	19901102	FRI	.42	
10	22	19901029 210000	19901030	TUE	.12	
14	35	19901130 160500	19901201	SAT	.32	
11	9005	19901211 050505	19901212	WED	.78	
06	990	19900511 214409	19900515	TUE	3.09	
13	1998	19900712 150100	19900716	MON	3.37	
26	31	19901010 185559	19901011	THU	.21	
14	30	19901210 195500	19901212	WED	1.17	

## Preparing to run IGYTSALE

All files required by the IGYTSALE program (IGYTSALE, IGYTCRC, IGYTPRC, IGYTSRC, IGYTABLE, and IGYTRANA) are on the product installation tape in the IGY.V6R1M0.SIGYSAMP data set.

You can change data-set names and procedure-names at installation time. Check with your system programmer to verify these names.

Do not change these options in the CBL statement in the source file for IGYTSALE:

- NONUMBER
- SEQUENCE
- NONUMBER
- QUOTE

With these options in effect, the program might not cause any diagnostic messages to be issued. You can use the sequence number string in the source file to search for the language elements used.

When you run IGYTSALE, the following messages are printed to the SYSOUT data set:

```
Program IGYTSALE Begins
There were 00041 records processed in this program
Program IGYTSALE Normal End
```

#### related concepts

[“IGYTSALE: nested program application” on page 811](#)

#### related tasks

[“Running IGYTSALE” on page 819](#)

#### related references

[“Input data for IGYTSALE” on page 812](#)

[“Reports produced by IGYTSALE” on page 814](#)

[“Language elements and concepts that are illustrated” on page 819](#)

## Running IGYTSALE

Use the following JCL to compile, link-edit, and run the IGYTSALE program. If you want only to compile or only to compile and link-edit the program, change the IGYWCLG cataloged procedure.

Insert the accounting information for your system or installation in the fields that are shown in lowercase letters.

```
//IGYTSALE JOB (acct-info), 'IGYTSALE', MSGLEVEL=(1,1), TIME=(0,29)
//TEST EXEC IGYWCLG
//COBOL.SYSLIB DD DSN=IGY.V6R1M0.SIGYSAMP, DISP=SHR
//COBOL.SYSIN DD DSN=IGY.V6R1M0.SIGYSAMP(IGYTSALE), DISP=SHR
//GO.SYSOUT DD SYSOUT=A
//GO.IGYTABLE DD DSN=IGY.V6R1M0.SIGYSAMP(IGYTABLE), DISP=SHR
//GO.IGYTRANS DD DSN=IGY.V6R1M0.SIGYSAMP(IGYTRANA), DISP=SHR
//GO.IGYPRINT DD SYSOUT=A, DCB=BLKSIZE=133
//GO.IGYPRT2 DD SYSOUT=A, DCB=BLKSIZE=133
//
```

## Language elements and concepts that are illustrated

The sample programs illustrate several COBOL language elements and concepts.

To find the applicable language element for a sample program, locate the abbreviation for that program in the sequence string:

Sample program	Abbreviation
IGYTcara	IA
IGYTcarb	IB
IGYTSale	IS

The following table lists the language elements and programming concepts that the sample programs illustrate. The language element or concept is described, and the sequence string is shown. The sequence string is the special character string that appears in the sequence field of the source file. You can use this string as a search argument for locating the elements in the listing.

Language element or concept	Sequence string
ACCEPT . . . FROM DAY-OF-WEEK	IS0900
ACCEPT . . . FROM DATE	IS0901
ACCEPT . . . FROM TIME	IS0902

Language element or concept	Sequence string
ADD . . . TO	IS4550
AFTER ADVANCING	IS2700
AFTER PAGE	IS2600
ALL	IS4200
ASSIGN	IS1101
AUTHOR	IA0040
CALL	IS0800
Callable services (Language Environment): 1. CEEDATM: format date or time output 2. CEEDCOD: feedback code check 3. CEEGMT0: UTC offset from local time 4. CEELOCT: local date and time 5. CEESECS: convert time stamp to seconds	1. IS0875, IS2575 2. IS0905 3. IS0904 4. IS0850 5. IS2350, IS2550
CLOSE files	IS1900
Comma, semicolon, and space interchangeable	IS3500, IS3600
COMMON statement for nested programs	IS4600
Complex OCCURS DEPENDING ON	IS0700, IS3700
COMPUTE	IS4501
COMPUTE ROUNDED	IS4500
CONFIGURATION SECTION	IA0970
CONFIGURATION SECTION (optional)	IS0200
CONTINUE statement	IA5310, IA5380
COPY statement	IS0500
DATA DIVISION (optional)	IS5100
Data validation	IA5130-6190
Do-until (PERFORM . . . TEST AFTER)	IA4900-5010, IA7690-7770
Do-while (PERFORM . . . TEST BEFORE)	IS1660
END-ADD	IS2900
END-COMPUTE	IS4510
END-EVALUATE	IA6590, IS2450
END-IF	IS1680
END-MULTIPLY	IS3100
END-PERFORM	IS1700
END PROGRAM	IA9990
END-READ	IS1800
END-SEARCH	IS3400

Language element or concept	Sequence string
ENVIRONMENT DIVISION (optional)	IS0200
Error handling, termination of program	IA4620, IA5080, IA7800-7980
EVALUATE statement	IA6270-6590
EVALUATE . . . ALSO	IS2400
EXIT PROGRAM not only statement in paragraph	IS2000
Exponentiation	IS4500
EXTERNAL clause	IS1200
FILE-CONTROL entry for sequential file	IA1190-1300
FILE-CONTROL entry for VSAM indexed file	IA1070-1180
FILE SECTION (optional)	IS0200
FILE STATUS code check	IA4600-4630, IA4760-4790
FILLER (optional)	IS0400
Flags, level-88, definition	IA1730-1800, IA2440-2480, IA2710
Flags, level-88, testing	IA4430, IA5200-5250
FLOATING POINT	IS4400
GLOBAL statement	IS0300
INITIAL statement for nested programs	IS2300
INITIALIZE	IS2500
Initializing a table in the DATA DIVISION	IA2920-4260
Inline PERFORM statement	IA4410-4520
I-O-CONTROL paragraphs (optional)	IS0200
INPUT-OUTPUT SECTION (optional)	IS0200
Intrinsic functions: 1. CURRENT-DATE 2. MAX 3. MEAN 4. MEDIAN 5. MIN 6. STANDARD-DEVIATION 7. UPPER-CASE 8. VARIANCE 9. WHEN-COMPILED	1. IA9005 2. IA9235 3. IA9215 4. IA9220 5. IA9240 6. IA9230 7. IA9015 8. IA9225 9. IA9000
IS (optional in all clauses)	IS0700
LABEL RECORDS (optional)	IS1150
LINKAGE SECTION	IS4900
Mixing of indexes and subscripts	IS3500

Language element or concept	Sequence string
Mnemonic names	IA1000
MOVE	IS0903
MOVE CORRESPONDING statement	IA4810, IA4830
MULTIPLY . . . GIVING	IS3000
Nested IF statement, using END-IF	IA5460-5830
Nested program	IS1000
NEXT SENTENCE	IS4300
NOT AT END	IS1600
NULL	IS4800
OBJECT-COMPUTER (optional)	IS0200
OCCURS DEPENDING ON	IS0710
ODO uses maximum length for receiving item	IS1550
OPEN EXTEND	IB2210
OPEN INPUT	IS1400
OPEN OUTPUT	IS1500
ORGANIZATION (optional)	IS1100
Page eject	IA7180-7210
Parenthesis in abbreviated conditions	IS4850
PERFORM . . . WITH TEST AFTER (Do-until)	IA4900-5010, IA7690-7770
PERFORM . . . WITH TEST BEFORE (Do-while)	IS1660
PERFORM . . . UNTIL	IS5000
PERFORM . . . VARYING statement	IA7690-7770
POINTER function	IS4700
Print file FD entry	IA1570-1620
Print report	IA7100-7360
PROCEDURE DIVISION . . . USING	IB1320-IB1650
PROGRAM-ID (30 characters allowed)	IS0120
READ . . . INTO . . . AT END	IS1550
REDEFINES statement	IA1940, IA2060, IA2890, IA3320
Reference modification	IS2425
Relational operator <= (less than or equal)	IS4400
Relational operator >= (greater than or equal)	IS2425
Relative subscripting	IS4000
REPLACE	IS4100
SEARCH statement	IS3300

Language element or concept	Sequence string
SELECT	IS1100
Sequence number can contain any character	IA, IB, IS
Sequential file processing	IA4480-4510, IA4840-4870
Sequential table search, using PERFORM	IA7690-7770
Sequential table search, using SEARCH	IA5270-5320, IA5340-5390
SET INDEX	IS3200
SET . . . TO TRUE statement	IA4390, IA4500, IA4860, IA4980
SOURCE - COMPUTER (optional)	IS0200
SPECIAL - NAMES paragraph (optional)	IS0200
STRING statement	IA6950, IA7050
Support for lowercase letters	IS0100
TALLY	IS1650
TITLE statement for nested programs	IS0100
Update commuter record	IA6200-6610
Update transaction work value spaces	IB0790-IB1000
USAGE BINARY	IS1300
USAGE PACKED-DECIMAL	IS1301
Validate elements	IB0810, IB0860, IB1000
VALUE with OCCURS	IS0600
VALUE SPACE (S)	IS0601
VALUE ZERO (S) (ES)	IS0600
Variable-length table control variable	IA5100
Variable-length table definition	IA2090-2210
Variable-length table loading	IA4840-4990
VSAM indexed file key definition	IA1170
VSAM return-code display	IA7800-7900
WORKING-STORAGE SECTION	IS0250



---

## Appendix I. Accessing JCL parameters

You can pass a parameter string from JCL to a COBOL program using the PARM= keyword of the EXEC statement. You can access these parameters either by standard COBOL coding, or by calling the CEE3PR2 Language Environment callable service.

### Using COBOL coding

You must define the LINKAGE SECTION record (level-01) that is to receive the *user\_parameter* data passed by the PARM string, taking into account the halfword parameter list length field that is inserted in front of the string by the system.

The program can test this field length for nonzero to verify that PARM-string data has in fact been passed. For example:

```
LINKAGE SECTION.  
01 PARMDATA.  
    05 STRINGLEN PIC 9(4) USAGE COMP.  
    05 STRINGPARM PIC X(80).  
PROCEDURE DIVISION USING PARMDATA.  
    IF STRINGLEN > 0 . . .
```

For more information, see [“Coding the LINKAGE SECTION” on page 469](#).

### Using CEE3PR2

You must define parameters to the CEE3PR2 callable service, without the need to add parameters to your PROCEDURE DIVISION USING statement.

```
WORKING-STORAGE SECTION.  
01 PARMLen PIC S9(9) BINARY.  
01 PARMSTR.  
    02 STR1-LENGTH PIC S9(4) BINARY.  
    02 STR1-STRING.  
        03 STR1-CHAR PIC X  
            OCCURS 0 TO 256 TIMES  
            DEPENDING ON STR1-LENGTH.  
    . . .  
    CALL "CEE3PR2" USING PARMLen,PARMSTR, FC.
```

For more information about the CEE3PR2 callable service, see CEE3PR2 in the [Language Environment Programming Reference](#).

### Related tasks

[“Accessing main program parameters under z/OS” on page 478](#)



# Appendix J. Accessibility features for Enterprise COBOL for z/OS

Accessibility features assist users who have a disability, such as restricted mobility or limited vision, to use information technology content successfully. The accessibility features in z/OS provide accessibility for Enterprise COBOL for z/OS.

## Accessibility features

z/OS includes the following major accessibility features:

- Interfaces that are commonly used by screen readers and screen-magnifier software
- Keyboard-only navigation
- Ability to customize display attributes such as color, contrast, and font size

z/OS uses the latest W3C Standard, [WAI-ARIA 1.0](http://www.w3.org/TR/wai-aria/) (<http://www.w3.org/TR/wai-aria/>), to ensure compliance to [US Section 508](https://www.access-board.gov/ict/) (<https://www.access-board.gov/ict/>) and [Web Content Accessibility Guidelines \(WCAG\) 2.0](http://www.w3.org/TR/WCAG20/) (<http://www.w3.org/TR/WCAG20/>). To take advantage of accessibility features, use the latest release of your screen reader in combination with the latest web browser that is supported by this product.

The Enterprise COBOL for z/OS online product documentation in IBM Knowledge Center is enabled for accessibility. The accessibility features of IBM Knowledge Center are described at <http://www.ibm.com/support/knowledgecenter/en/about/releasenotes.html>.

## Keyboard navigation

Users can access z/OS user interfaces by using TSO/E or ISPF.

Users can also access z/OS services by using IBM Developer for z/OS.

For information about accessing these interfaces, see the following publications:

- *z/OS TSO/E Primer* (<http://publib.boulder.ibm.com/cgi-bin/bookmgr/BOOKS/ikj4p120>)
- *z/OS TSO/E User's Guide* (<http://publib.boulder.ibm.com/cgi-bin/bookmgr/BOOKS/ikj4c240/APPENDIX1.3>)
- *z/OS ISPF User's Guide Volume I* (<http://publib.boulder.ibm.com/cgi-bin/bookmgr/BOOKS/ispzug70>)
- *IBM Developer for z/OS Knowledge Center* ([http://www.ibm.com/support/knowledgecenter/SSQ2R2/rdz\\_welcome.html?lang=en](http://www.ibm.com/support/knowledgecenter/SSQ2R2/rdz_welcome.html?lang=en))

These guides describe how to use TSO/E and ISPF, including the use of keyboard shortcuts or function keys (PF keys). Each guide includes the default settings for the PF keys and explains how to modify their functions.

## Interface information

The Enterprise COBOL for z/OS online product documentation is available in IBM Knowledge Center, which is viewable from a standard web browser.

PDF files have limited accessibility support. With PDF documentation, you can use optional font enlargement, high-contrast display settings, and can navigate by keyboard alone.

To enable your screen reader to accurately read syntax diagrams, source code examples, and text that contains period or comma PICTURE symbols, you must set the screen reader to speak all punctuation.

Assistive technology products work with the user interfaces that are found in z/OS. For specific guidance information, see the documentation for the assistive technology product that you use to access z/OS interfaces.

## **Related accessibility information**

In addition to standard IBM help desk and support websites, IBM has established a TTY telephone service for use by deaf or hard of hearing customers to access sales and support services:

TTY service 800-IBM-3383 (800-426-3383) (within North America)

## **IBM and accessibility**

For more information about the commitment that IBM has to accessibility, see [IBM Accessibility \(www.ibm.com/able\)](http://www.ibm.com/able).

## Notices

---

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing IBM Corporation North Castle Drive, MD-NC119 Armonk, NY 10504-1785 U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

Intellectual Property Licensing Legal and Intellectual Property Law IBM Japan, Ltd. 19-21, Nihonbashi-Hakozakicho, Chuo-ku Tokyo 103-8510, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:** INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who want to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

Intellectual Property Dept. for Rational Software IBM Corporation 5 Technology Park Drive Westford, MA 01886 U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurements may have been estimated

through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

#### **COPYRIGHT LICENSE:**

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work, must include a copyright notice as follows:

© (your company name) (year). Portions of this code are derived from IBM Corp. Sample Programs. © Copyright IBM Corp. 1991, 2021.

#### **PRIVACY POLICY CONSIDERATIONS:**

IBM Software products, including software as a service solutions, ("Software Offerings") may use cookies or other technologies to collect product usage information, to help improve the end user experience, or to tailor interactions with the end user, or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering's use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> in the section entitled "Cookies, Web Beacons and Other Technologies," and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

## **Trademarks**

---

IBM, the IBM logo, and [ibm.com](http://www.ibm.com)® are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be

trademarks of IBM or other companies. A current list of IBM trademarks is available on the Web at “Copyright and trademark information” at [www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Intel is a registered trademark of Intel Corporation or its subsidiaries in the United States and other countries.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Microsoft and Windows are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other product and service names might be trademarks of IBM or other companies.



# Glossary

---

The terms in this glossary are defined in accordance with their meaning in COBOL. These terms might or might not have the same meaning in other languages.

This glossary includes terms and definitions from the following publications:

- *ANSI INCITS 23-1985, Programming languages - COBOL*, as amended by *ANSI INCITS 23a-1989, Programming Languages - COBOL - Intrinsic Function Module for COBOL*, and *ANSI INCITS 23b-1993, Programming Languages - Correction Amendment for COBOL*
- *ANSI X3.172-2002, American National Standard Dictionary for Information Systems*

American National Standard definitions are preceded by an asterisk (\*).

## A

### \* **abbreviated combined relation condition**

The combined condition that results from the explicit omission of a common subject or a common subject and common relational operator in a consecutive sequence of relation conditions.

### **abend**

Abnormal termination of a program.

### **above the 16 MB line**

Storage above the so-called 16 MB line (or boundary) but below the 2 GB bar. This storage is addressable only in 31-bit mode. Before IBM introduced the MVS/XA architecture in the 1980s, the virtual storage for a program was limited to 16 MB. Programs that have been compiled with a 24-bit mode can address only 16 MB of space, as though they were kept under an imaginary storage line. Since VS COBOL II, a program that has been compiled with a 31-bit mode can be above the 16 MB line.

### \* **access mode**

The manner in which records are to be operated upon within a file.

### \* **actual decimal point**

The physical representation, using the decimal point characters period (.) or comma (,), of the decimal point position in a data item.

### **actual document encoding**

For an XML document, one of the following encoding categories that the XML parser determines by examining the first few bytes of the document:

- ASCII
- EBCDIC
- UTF-8
- UTF-16, either big-endian or little-endian
- Other unsupported encoding
- No recognizable encoding

### \* **alphabet-name**

A user-defined word, in the SPECIAL-NAMES paragraph of the ENVIRONMENT DIVISION, that assigns a name to a specific character set or collating sequence or both.

### \* **alphabetic character**

A letter or a space character.

### **alphabetic data item**

A data item that is described with a PICTURE character string that contains only the symbol A. An alphabetic data item has USAGE DISPLAY.

### \* **alphanumeric character**

Any character in the single-byte character set of the computer.

**alphanumeric data item**

A general reference to a data item that is described implicitly or explicitly as USAGE DISPLAY, and that has category alphanumeric, alphanumeric-edited, or numeric-edited.

**alphanumeric-edited data item**

A data item that is described by a PICTURE character string that contains at least one instance of the symbol A or X and at least one of the simple insertion symbols B, 0, or /. An alphanumeric-edited data item has USAGE DISPLAY.

**\* alphanumeric function**

A function whose value is composed of a string of one or more characters from the alphanumeric character set of the computer.

**alphanumeric group item**

A group item that is defined without a GROUP-USAGE NATIONAL clause. For operations such as INSPECT, STRING, and UNSTRING, an alphanumeric group item is processed as though all its content were described as USAGE DISPLAY regardless of the actual content of the group. For operations that require processing of the elementary items within a group, such as MOVE CORRESPONDING, ADD CORRESPONDING, or INITIALIZE, an alphanumeric group item is processed using group semantics.

**alphanumeric literal**

A literal that has an opening delimiter from the following set: ' , " , X ' , X " , Z ' , or Z " . The string of characters can include any character in the character set of the computer.

**\* alternate record key**

A key, other than the prime record key, whose contents identify a record within an indexed file.

**ANSI (American National Standards Institute)**

An organization that consists of producers, consumers, and general-interest groups and establishes the procedures by which accredited organizations create and maintain voluntary industry standards in the United States.

**argument**

(1) An identifier, a literal, an arithmetic expression, or a function-identifier that specifies a value to be used in the evaluation of a function. (2) An operand of the USING phrase of a CALL or INVOKE statement, used for passing values to a called program or an invoked method.

**\* arithmetic expression**

An identifier of a numeric elementary item, a numeric literal, such identifiers and literals separated by arithmetic operators, two arithmetic expressions separated by an arithmetic operator, or an arithmetic expression enclosed in parentheses.

**\* arithmetic operation**

The process caused by the execution of an arithmetic statement, or the evaluation of an arithmetic expression, that results in a mathematically correct solution to the arguments presented.

**\* arithmetic operator**

A single character, or a fixed two-character combination that belongs to the following set:

Character	Meaning
+	Addition
-	Subtraction
*	Multiplication
/	Division
**	Exponentiation

**\* arithmetic statement**

A statement that causes an arithmetic operation to be executed. The arithmetic statements are ADD, COMPUTE, DIVIDE, MULTIPLY, and SUBTRACT.

**array**

An aggregate that consists of data objects, each of which can be uniquely referenced by subscripting. An array is roughly analogous to a COBOL table.

**\* ascending key**

A key upon the values of which data is ordered, starting with the lowest value of the key up to the highest value of the key, in accordance with the rules for comparing data items.

**ASCII**

American National Standard Code for Information Interchange. The standard code uses a coded character set that is based on 7-bit coded characters (8 bits including parity check). The standard is used for information interchange between data processing systems, data communication systems, and associated equipment. The ASCII set consists of control characters and graphic characters.

IBM has defined an extension to ASCII (characters 128-255).

**assignment-name**

A name that identifies the organization of a COBOL file and the name by which it is known to the system.

**\* assumed decimal point**

A decimal point position that does not involve the existence of an actual character in a data item. The assumed decimal point has logical meaning but no physical representation.

**AT END condition**

A condition that is caused during the execution of a READ, RETURN, or SEARCH statement under certain conditions:

- A READ statement runs on a sequentially accessed file when no next logical record exists in the file, or when the number of significant digits in the relative record number is larger than the size of the relative key data item, or when an optional input file is not available.
- A RETURN statement runs when no next logical record exists for the associated sort or merge file.
- A SEARCH statement runs when the search operation terminates without satisfying the condition specified in any of the associated WHEN phrases.

**B**

**big-endian**

The default format that the mainframe and the AIX workstation use to store binary data and UTF-16 characters. In this format, the least significant byte of a binary data item is at the highest address and the least significant byte of a UTF-16 character is at the highest address. Compare with *little-endian*.

**binary item**

A numeric data item that is represented in binary notation (on the base 2 numbering system). The decimal equivalent consists of the decimal digits 0 through 9, plus an operational sign. The leftmost bit of the item is the operational sign.

**binary search**

A dichotomizing search in which, at each step of the search, the set of data elements is divided by two; some appropriate action is taken in the case of an odd number.

**\* block**

A physical unit of data that is normally composed of one or more logical records. For mass storage files, a block can contain a portion of a logical record. The size of a block has no direct relationship to the size of the file within which the block is contained or to the size of the logical records that are either contained within the block or that overlap the block. Synonymous with *physical record*.

**breakpoint**

A place in a computer program, usually specified by an instruction, where external intervention or a monitor program can interrupt the program as it runs.

**buffer**

A portion of storage that is used to hold input or output data temporarily.

**built-in function**

See *intrinsic function*.

**business method**

A method of an enterprise bean that implements the business logic or rules of an application. (Oracle)

**byte**

A string that consists of a certain number of bits, usually eight, treated as a unit, and representing a character or a control function.

**byte order mark (BOM)**

A Unicode character that can be used at the start of UTF-16 or UTF-32 text to indicate the byte order of subsequent text; the byte order can be either big-endian or little-endian.

**bytecode**

Machine-independent code that is generated by the Java compiler and executed by the Java interpreter. (Oracle)

**C****callable services**

In Language Environment, a set of services that a COBOL program can invoke by using the conventional Language Environment-defined call interface. All programs that share the Language Environment conventions can use these services.

**called program**

A program that is the object of a CALL statement. At run time the called program and calling program are combined to produce a *run unit*.

**\* calling program**

A program that executes a CALL to another program.

**case structure**

A program-processing logic in which a series of conditions is tested in order to choose between a number of resulting actions.

**cataloged procedure**

A set of job control statements that are placed in a partitioned data set called the procedure library (SYS1.PROCLIB). You can use cataloged procedures to save time and reduce errors in coding JCL.

**CCSID**

See *coded character set identifier*.

**century window**

A 100-year interval within which any two-digit year is unique. Several types of century window are available to COBOL programmers:

- For the windowing intrinsic functions DATE-TO-YYYYMMDD, DAY-TO-YYYYDDD, and YEAR-TO-YYYY, you specify the century window with *argument-2*.
- For Language Environment callable services, you specify the century window in CEEScen.

**\* character**

The basic indivisible unit of the language.

**character encoding unit**

A unit of data that corresponds to one code point in a coded character set. One or more character encoding units are used to represent a character in a coded character set. Also known as *encoding unit*.

For USAGE NATIONAL, a character encoding unit corresponds to one 2-byte code point of UTF-16.

For USAGE DISPLAY, a character encoding unit corresponds to a byte.

For USAGE DISPLAY-1, a character encoding unit corresponds to a 2-byte code point in the DBCS character set.

**character position**

The amount of physical storage or presentation space required to hold or present one character. The term applies to any class of character. For specific classes of characters, the following terms apply:

- *Alphanumeric character position*, for characters represented in USAGE DISPLAY
- *DBCS character position*, for DBCS characters represented in USAGE DISPLAY-1

- *National character position*, for characters represented in USAGE NATIONAL; synonymous with *character encoding unit* for UTF-16

### **character set**

A collection of elements that are used to represent textual information, but for which no coded representation is assumed. See also *coded character set*.

### **character string**

A sequence of contiguous characters that form a COBOL word, a literal, a PICTURE character string, or a comment-entry. A character string must be delimited by separators.

### **checkpoint**

A point at which information about the status of a job and the system can be recorded so that the job step can be restarted later.

### **\* class**

The entity that defines common behavior and implementation for zero, one, or more objects. The objects that share the same implementation are considered to be objects of the same class. Classes can be defined hierarchically, allowing one class to inherit from another.

### **\* class condition**

The proposition (for which a truth value can be determined) that the content of an item is wholly alphabetic, is wholly numeric, is wholly DBCS, is wholly Kanji, or consists exclusively of the characters that are listed in the definition of a class-name.

### **\* class definition**

The COBOL source unit that defines a class.

### **class hierarchy**

A tree-like structure that shows relationships among object classes. It places one class at the top and one or more layers of classes below it. Synonymous with *inheritance hierarchy*.

### **\* class identification entry**

An entry in the CLASS-ID paragraph of the IDENTIFICATION DIVISION; this entry contains clauses that specify the class-name and assign selected attributes to the class definition.

### **class-name (object-oriented)**

The name of an object-oriented COBOL class definition.

### **\* class-name (of data)**

A user-defined word that is defined in the SPECIAL-NAMES paragraph of the ENVIRONMENT DIVISION; this word assigns a name to the proposition (for which a truth value can be defined) that the content of a data item consists exclusively of the characters that are listed in the definition of the class-name.

### **class object**

The runtime object that represents a class.

### **\* clause**

An ordered set of consecutive COBOL character strings whose purpose is to specify an attribute of an entry.

### **client**

In object-oriented programming, a program or method that requests services from one or more methods in a class.

### **COBOL character set**

The set of characters used in writing COBOL syntax. The complete COBOL character set consists of these characters:

<b>Character</b>	<b>Meaning</b>
0,1, . . . ,9	Digit
A,B, . . . ,Z	Uppercase letter
a,b, . . . ,z	Lowercase letter
	Space

Character	Meaning
+	Plus sign
-	Minus sign (hyphen)
*	Asterisk
/	Slant (forward slash)
=	Equal sign
\$	Currency sign
,	Comma
;	Semicolon
.	Period (decimal point, full stop)
"	Quotation mark
'	Apostrophe
(	Left parenthesis
)	Right parenthesis
>	Greater than
<	Less than
:	Colon
_	Underscore

**\* COBOL word**

See *word*.

**code page**

An assignment of graphic characters and control function meanings to all code points. For example, one code page could assign characters and meanings to 256 code points for 8-bit code, and another code page could assign characters and meanings to 128 code points for 7-bit code. For example, one of the IBM code pages for English on the workstation is IBM-1252 and on the host is IBM-1047. A *coded character set*.

**code point**

A unique bit pattern that is defined in a coded character set (code page). Graphic symbols and control characters are assigned to code points.

**coded character set**

A set of unambiguous rules that establish a character set and the relationship between the characters of the set and their coded representation. Examples of coded character sets are the character sets as represented by ASCII or EBCDIC code pages or by the UTF-16 encoding scheme for Unicode.

**coded character set identifier (CCSID)**

An IBM-defined number in the range 1 to 65,535 that identifies a specific code page.

**\* collating sequence**

The sequence in which the characters that are acceptable to a computer are ordered for purposes of sorting, merging, comparing, and for processing indexed files sequentially.

**\* column**

A byte position within a print line or within a reference format line. The columns are numbered from 1, by 1, starting at the leftmost position of the line and extending to the rightmost position of the line. A column holds one single-byte character.

**\* combined condition**

A condition that is the result of connecting two or more conditions with the AND or the OR logical operator. See also *condition* and *negated combined condition*.

**\* comment-entry**

An entry in the IDENTIFICATION DIVISION that is used for documentation and has no effect on execution.

**comment line**

A source program line represented by an asterisk (\*) in the indicator area of the line or by an asterisk followed by greater-than sign (\*>) as the first character string in the program text area (Area A plus Area B), and any characters from the character set of the computer that follow in Area A and Area B of that line. A comment line serves only for documentation. A special form of comment line represented by a slant (/) in the indicator area of the line and any characters from the character set of the computer in Area A and Area B of that line causes page ejection before the comment is printed.

**\* common program**

A program that, despite being directly contained within another program, can be called from any program directly or indirectly contained in that other program.

**\* compile**

(1) To translate a program expressed in a high-level language into a program expressed in an intermediate language, assembly language, or a computer language. (2) To prepare a machine-language program from a computer program written in another programming language by making use of the overall logic structure of the program, or generating more than one computer instruction for each symbolic statement, or both, as well as performing the function of an assembler.

**\* compile time**

The time at which COBOL source code is translated, by a COBOL compiler, to a COBOL object program.

**compiler**

A program that translates source code written in a higher-level language into machine-language object code.

**compiler-directing statement**

A statement that causes the compiler to take a specific action during compilation. The standard compiler-directing statements are COPY, REPLACE, and USE.

**\* complex condition**

A condition in which one or more logical operators act upon one or more conditions. See also *condition*, *negated simple condition*, and *negated combined condition*.

**complex ODO**

Certain forms of the OCCURS DEPENDING ON clause:

- Variably located item or group: A data item described by an OCCURS clause with the DEPENDING ON option is followed by a nonsubordinate data item or group. The group can be an alphanumeric group or a national group.
- Variably located table: A data item described by an OCCURS clause with the DEPENDING ON option is followed by a nonsubordinate data item described by an OCCURS clause.
- Table with variable-length elements: A data item described by an OCCURS clause contains a subordinate data item described by an OCCURS clause with the DEPENDING ON option.
- Index name for a table with variable-length elements.
- Element of a table with variable-length elements.

**component**

(1) A functional grouping of related files. (2) In object-oriented programming, a reusable object or program that performs a specific function and is designed to work with other components and applications. JavaBeans is Oracle's architecture for creating components.

**\* computer-name**

A system-name that identifies the computer where the program is to be compiled or run.

**condition (exception)**

An exception that has been enabled, or recognized, by Language Environment and thus is eligible to activate user and language condition handlers. Any alteration to the normal programmed flow of an application. Conditions can be detected by the hardware or the operating system and result in an interrupt. They can also be detected by language-specific generated code or language library code.

**condition (expression)**

A status of data at run time for which a truth value can be determined. Where used in this information in or in reference to "condition" (*condition-1*, *condition-2*, . . .) of a general format, the term refers to a conditional expression that consists of either a simple condition optionally parenthesized or a combined condition (consisting of the syntactically correct combination of simple conditions, logical operators, and parentheses) for which a truth value can be determined. See also *simple condition*, *complex condition*, *negated simple condition*, *combined condition*, and *negated combined condition*.

**\* conditional expression**

A simple condition or a complex condition specified in an EVALUATE, IF, PERFORM, or SEARCH statement. See also *simple condition* and *complex condition*.

**\* conditional phrase**

A phrase that specifies the action to be taken upon determination of the truth value of a condition that results from the execution of a conditional statement.

**\* conditional statement**

A statement that specifies that the truth value of a condition is to be determined and that the subsequent action of the object program depends on this truth value.

**\* conditional variable**

A data item one or more values of which has a condition-name assigned to it.

**\* condition-name**

A user-defined word that assigns a name to a subset of values that a conditional variable can assume; or a user-defined word assigned to a status of an implementor-defined switch or device.

**\* condition-name condition**

The proposition (for which a truth value can be determined) that the value of a conditional variable is a member of the set of values attributed to a condition-name associated with the conditional variable.

**\* CONFIGURATION SECTION**

A section of the ENVIRONMENT DIVISION that describes overall specifications of source and object programs and class definitions.

**CONSOLE**

A COBOL environment-name associated with the operator console.

**contained program**

A COBOL program that is nested within another COBOL program.

**\* contiguous items**

Items that are described by consecutive entries in the DATA DIVISION, and that bear a definite hierarchic relationship to each other.

**copybook**

A file or library member that contains a sequence of code that is included in the source program at compile time using the COPY statement. The file can be created by the user, supplied by COBOL, or supplied by another product. Synonymous with *copy file*.

**\* counter**

A data item used for storing numbers or number representations in a manner that permits these numbers to be increased or decreased by the value of another number, or to be changed or reset to zero or to an arbitrary positive or negative value.

**cross-reference listing**

The portion of the compiler listing that contains information on where files, fields, and indicators are defined, referenced, and modified in a program.

**currency-sign value**

A character string that identifies the monetary units stored in a numeric-edited item. Typical examples are \$, USD, and EUR. A currency-sign value can be defined by either the CURRENCY compiler option or the CURRENCY SIGN clause in the SPECIAL -NAMES paragraph of the ENVIRONMENT DIVISION. If the CURRENCY SIGN clause is not specified and the NOCURRENCY compiler option is in effect, the dollar sign (\$) is used as the default currency-sign value. See also *currency symbol*.

**currency symbol**

A character used in a PICTURE clause to indicate the position of a currency sign value in a numeric-edited item. A currency symbol can be defined by either the CURRENCY compiler option or the CURRENCY SIGN clause in the SPECIAL -NAMES paragraph of the ENVIRONMENT DIVISION. If the CURRENCY SIGN clause is not specified and the NOCURRENCY compiler option is in effect, the dollar sign (\$) is used as the default currency sign value and currency symbol. Multiple currency symbols and currency sign values can be defined. See also *currency sign value*.

**\* current record**

In file processing, the record that is available in the record area associated with a file.

**\* current volume pointer**

A conceptual entity that points to the current volume of a sequential file.

**D****\* data clause**

A clause, appearing in a data description entry in the DATA DIVISION of a COBOL program, that provides information describing a particular attribute of a data item.

**\* data description entry**

An entry in the DATA DIVISION of a COBOL program that is composed of a level-number followed by a data-name, if required, and then followed by a set of data clauses, as required.

**DATA DIVISION**

The division of a COBOL program or method that describes the data to be processed by the program or method: the files to be used and the records contained within them; internal WORKING-STORAGE records that will be needed; data to be made available in more than one program in the COBOL run unit.

**\* data item**

A unit of data (excluding literals) defined by a COBOL program or by the rules for function evaluation.

**data set**

Synonym for *file*.

**\* data-name**

A user-defined word that names a data item described in a data description entry. When used in the general formats, data-name represents a word that must not be reference-modified, subscripted, or qualified unless specifically permitted by the rules for the format.

**DBCS**

See *double-byte character set (DBCS)*.

**DBCS character**

Any character defined in IBM's double-byte character set.

**DBCS character position**

See *character position*.

**DBCS data item**

A data item that is described by a PICTURE character string that contains at least one symbol G, or, when the NSYMBOL (DBCS) compiler option is in effect, at least one symbol N. A DBCS data item has USAGE DISPLAY-1.

**\* debugging line**

Any line with a D in the indicator area of the line.

**\* debugging section**

A section that contains a USE FOR DEBUGGING statement.

**\* declarative sentence**

A compiler-directing sentence that consists of a single USE statement terminated by the separator period.

**\* declaratives**

A set of one or more special-purpose sections, written at the beginning of the PROCEDURE DIVISION, the first of which is preceded by the key word DECLARATIVE and the last of which is followed by the key words END DECLARATIVES. A declarative is composed of a section header,

followed by a USE compiler-directing sentence, followed by a set of zero, one, or more associated paragraphs.

**\* de-edit**

The logical removal of all editing characters from a numeric-edited data item in order to determine the unedited numeric value of the item.

**\* delimited scope statement**

Any statement that includes its explicit scope terminator.

**\* delimiter**

A character or a sequence of contiguous characters that identify the end of a string of characters and separate that string of characters from the following string of characters. A delimiter is not part of the string of characters that it delimits.

**dependent region**

In IMS, the MVS virtual storage region that contains message-driven programs, batch programs, or online utilities.

**\* descending key**

A key upon the values of which data is ordered starting with the highest value of key down to the lowest value of key, in accordance with the rules for comparing data items.

**digit**

Any of the numerals from 0 through 9. In COBOL, the term is not used to refer to any other symbol.

**\* digit position**

The amount of physical storage required to store a single digit. This amount can vary depending on the usage specified in the data description entry that defines the data item.

**\* direct access**

The facility to obtain data from storage devices or to enter data into a storage device in such a way that the process depends only on the location of that data and not on a reference to data previously accessed.

**display floating-point data item**

A data item that is described implicitly or explicitly as USAGE DISPLAY and that has a PICTURE character string that describes an external floating-point data item.

**\* division**

A collection of zero, one, or more sections or paragraphs, called the division body, that are formed and combined in accordance with a specific set of rules. Each division consists of the division header and the related division body. There are four divisions in a COBOL program: Identification, Environment, Data, and Procedure.

**\* division header**

A combination of words followed by a separator period that indicates the beginning of a division. The division headers are:

```
IDENTIFICATION DIVISION.  
ENVIRONMENT DIVISION.  
DATA DIVISION.  
PROCEDURE DIVISION.
```

**DLL**

See *dynamic link library (DLL)*.

**DLL application**

An application that references imported programs, functions, or variables.

**DLL linkage**

A CALL in a program that has been compiled with the DLL and NODYNAM options; the CALL resolves to an exported name in a separate module, or to an INVOKE of a method that is defined in a separate module.

**do construct**

In structured programming, a DO statement is used to group a number of statements in a procedure. In COBOL, an inline PERFORM statement functions in the same way.

**do-until**

In structured programming, a do-until loop will be executed at least once, and until a given condition is true. In COBOL, a TEST AFTER phrase used with the PERFORM statement functions in the same way.

**do-while**

In structured programming, a do-while loop will be executed if, and while, a given condition is true. In COBOL, a TEST BEFORE phrase used with the PERFORM statement functions in the same way.

**document type declaration**

An XML element that contains or points to markup declarations that provide a grammar for a class of documents. This grammar is known as a document type definition, or DTD.

**document type definition (DTD)**

The grammar for a class of XML documents. See *document type declaration*.

**double-byte character set (DBCS)**

A set of characters in which each character is represented by 2 bytes. Languages such as Japanese, Chinese, and Korean, which contain more symbols than can be represented by 256 code points, require double-byte character sets. Because each character requires 2 bytes, entering, displaying, and printing DBCS characters requires hardware and supporting software that are DBCS-capable.

**DWARF**

DWARF was developed by the UNIX International Programming Languages Special Interest Group (SIG). It is designed to meet the symbolic, source-level debugging needs of different languages in a unified fashion by supplying language-independent debugging information. A DWARF file contains debugging data organized into different elements. For more information, see [DWARF program information](#) in the *DWARF/ELF Extensions Library Reference*.

**\* dynamic access**

An access mode in which specific logical records can be obtained from or placed into a mass storage file in a nonsequential manner and obtained from a file in a sequential manner during the scope of the same OPEN statement.

**dynamic CALL**

A CALL *literal* statement in a program that has been compiled with the DYNAM option and the NODLL option, or a CALL *identifier* statement in a program that has been compiled with the NODLL option.

**dynamic link library (DLL)**

A file that contains executable code and data that are bound to a program at load time or run time, rather than during linking. Several applications can share the code and data in a DLL simultaneously. Although a DLL is not part of the executable file for a program, it can be required for an executable file to run properly.

**dynamic storage area (DSA)**

Dynamically acquired storage composed of a register save area and an area available for dynamic storage allocation (such as program variables). A DSA is allocated upon invocation of a program or function and persists for the duration of the invocation instance. DSAs are generally allocated within stack segments managed by Language Environment.

**\* EBCDIC (Extended Binary-Coded Decimal Interchange Code)**

A coded character set based on 8-bit coded characters.

**EBCDIC character**

Any one of the symbols included in the EBCDIC (Extended Binary-Coded-Decimal Interchange Code) set.

**edited data item**

A data item that has been modified by suppressing zeros or inserting editing characters or both.

**\* editing character**

A single character or a fixed two-character combination belonging to the following set:

Character	Meaning
	Space

Character	Meaning
0	Zero
+	Plus
-	Minus
CR	Credit
DB	Debit
Z	Zero suppress
*	Check protect
\$	Currency sign
,	Comma (decimal point)
.	Period (decimal point)
/	Slant (forward slash)

## EJB

See *Enterprise JavaBeans*.

## EJB container

A container that implements the EJB component contract of the J2EE architecture. This contract specifies a runtime environment for enterprise beans that includes security, concurrency, life cycle management, transaction, deployment, and other services. An EJB container is provided by an EJB or J2EE server. (Oracle)

## EJB server

Software that provides services to an EJB container. An EJB server can host one or more EJB containers. (Oracle)

## element (text element)

One logical unit of a string of text, such as the description of a single data item or verb, preceded by a unique code identifying the element type.

## \* elementary item

A data item that is described as not being further logically subdivided.

## encapsulation

In object-oriented programming, the technique that is used to hide the inherent details of an object. The object provides an interface that queries and manipulates the data without exposing its underlying structure. Synonymous with *information hiding*.

## enclave

When running under Language Environment, an enclave is analogous to a run unit. An enclave can create other enclaves by using LINK and by using the system() function in C.

## encoding unit

See *character encoding unit*.

## end class marker

A combination of words, followed by a separator period, that indicates the end of a COBOL class definition. The end class marker is:

```
END CLASS class-name.
```

## end method marker

A combination of words, followed by a separator period, that indicates the end of a COBOL method definition. The end method marker is:

```
END METHOD method-name.
```

**\* end of PROCEDURE DIVISION**

The physical position of a COBOL source program after which no further procedures appear.

**\* end program marker**

A combination of words, followed by a separator period, that indicates the end of a COBOL source program. The end program marker is:

```
END PROGRAM program-name.
```

**enterprise bean**

A component that implements a business task and resides in an EJB container. (Oracle)

**Enterprise JavaBeans**

A component architecture defined by Oracle for the development and deployment of object-oriented, distributed, enterprise-level applications.

**\* entry**

Any descriptive set of consecutive clauses terminated by a separator period and written in the IDENTIFICATION DIVISION, ENVIRONMENT DIVISION, or DATA DIVISION of a COBOL program.

**\* environment clause**

A clause that appears as part of an ENVIRONMENT DIVISION entry.

**ENVIRONMENT DIVISION**

One of the four main component parts of a COBOL program, class definition, or method definition. The ENVIRONMENT DIVISION describes the computers where the source program is compiled and those where the object program is run. It provides a linkage between the logical concept of files and their records, and the physical aspects of the devices on which files are stored.

**environment-name**

A name, specified by IBM, that identifies system logical units, printer and card punch control characters, report codes, program switches or all of these. When an environment-name is associated with a mnemonic-name in the ENVIRONMENT DIVISION, the mnemonic-name can be substituted in any format in which such substitution is valid.

**environment variable**

Any of a number of variables that define some aspect of the computing environment, and are accessible to programs that operate in that environment. Environment variables can affect the behavior of programs that are sensitive to the environment in which they operate.

**escape sequence**

A sequence of characters that are used to represent certain special characters within string literals and character literals.

Escape sequences consist of two or more characters, the first of which is the backslash (\) character, which is called the "escape character"; the remaining characters determine the interpretation of the escape sequence. For example, \n is an escape sequence that denotes a newline character.

Escape sequences are used in programming languages such as C, C++, Java, or Python. COBOL does not have the concept of "escape sequence" or "escape character". To handle special characters within COBOL literals, see *Basic alphanumeric literals* and *DBCS literals* in the *Enterprise COBOL for z/OS Language Reference*.

**execution time**

See *run time*.

**execution-time environment**

See *runtime environment*.

**\* explicit scope terminator**

A reserved word that terminates the scope of a particular PROCEDURE DIVISION statement.

**exponent**

A number that indicates the power to which another number (the base) is to be raised. Positive exponents denote multiplication; negative exponents denote division; and fractional exponents denote a root of a quantity. In COBOL, an exponential expression is indicated with the symbol \*\* followed by the exponent.

**\* expression**

An arithmetic or conditional expression.

**\* extend mode**

The state of a file after execution of an OPEN statement, with the EXTEND phrase specified for that file, and before the execution of a CLOSE statement, without the REEL or UNIT phrase for that file.

**Extensible Markup Language**

See *XML*.

**extensions**

COBOL syntax and semantics supported by IBM compilers in addition to those described in the 85 COBOL Standard.

**external code page**

For XML documents, the value specified by the CODEPAGE compiler option.

**\* external data**

The data that is described in a program as external data items and external file connectors.

**\* external data item**

A data item that is described as part of an external record in one or more programs of a run unit and that can be referenced from any program in which it is described.

**\* external data record**

A logical record that is described in one or more programs of a run unit and whose constituent data items can be referenced from any program in which they are described.

**external decimal data item**

See *zoned decimal data item* and *national decimal data item*.

**\* external file connector**

A file connector that is accessible to one or more object programs in the run unit.

**external floating-point data item**

See *display floating-point data item* and *national floating-point data item*.

**external program**

The outermost program. A program that is not nested.

**\* external switch**

A hardware or software device, defined and named by the implementor, which is used to indicate that one of two alternate states exists.

**F**

**factory data**

Data that is allocated once for a class and shared by all instances of the class. Factory data is declared in the WORKING-STORAGE SECTION of the DATA DIVISION in the FACTORY paragraph of the class definition, and is equivalent to Java private static data.

**factory method**

A method that is supported by a class independently of an object instance. Factory methods are declared in the FACTORY paragraph of the class definition, and are equivalent to Java public static methods. They are typically used to customize the creation of objects.

**\* figurative constant**

A compiler-generated value referenced through the use of certain reserved words.

**\* file**

A collection of logical records.

**\* file attribute conflict condition**

An unsuccessful attempt has been made to execute an input-output operation on a file and the file attributes, as specified for that file in the program, do not match the fixed attributes for that file.

**\* file clause**

A clause that appears as part of any of the following DATA DIVISION entries: file description entry (FD entry) and sort-merge file description entry (SD entry).

**\* file connector**

A storage area that contains information about a file and is used as the linkage between a file-name and a physical file and between a file-name and its associated record area.

**\* file control entry**

A SELECT clause and all its subordinate clauses that declare the relevant physical attributes of a file.

**FILE-CONTROL paragraph**

A paragraph in the ENVIRONMENT DIVISION in which the data files for a given source unit are declared.

**\* file description entry**

An entry in the FILE SECTION of the DATA DIVISION that is composed of the level indicator FD, followed by a file-name, and then followed by a set of file clauses as required.

**\* file-name**

A user-defined word that names a file connector described in a file description entry or a sort-merge file description entry within the FILE SECTION of the DATA DIVISION.

**\* file organization**

The permanent logical file structure established at the time that a file is created.

**file position indicator**

A conceptual entity that contains the value of the current key within the key of reference for an indexed file, or the record number of the current record for a sequential file, or the relative record number of the current record for a relative file, or indicates that no next logical record exists, or that an optional input file is not available, or that the AT END condition already exists, or that no valid next record has been established.

**\* FILE SECTION**

The section of the DATA DIVISION that contains file description entries and sort-merge file description entries together with their associated record descriptions.

**file system**

The collection of files that conform to a specific set of data-record and file-description protocols, and a set of programs that manage these files.

**\* fixed file attributes**

Information about a file that is established when a file is created and that cannot subsequently be changed during the existence of the file. These attributes include the organization of the file (sequential, relative, or indexed), the prime record key, the alternate record keys, the code set, the minimum and maximum record size, the record type (fixed or variable), the collating sequence of the keys for indexed files, the blocking factor, the padding character, and the record delimiter.

**\* fixed-length record**

A record associated with a file whose file description or sort-merge description entry requires that all records contain the same number of bytes.

**fixed-point item**

A numeric data item defined with a PICTURE clause that specifies the location of an optional sign, the number of digits it contains, and the location of an optional decimal point. The format can be either binary, packed decimal, or external decimal.

**floating comment indicators (\*>)**

A floating comment indicator indicates a comment line if it is the first character string in the program-text area (Area A plus Area B), or indicates an inline comment if it is after one or more character strings in the program-text area.

**floating point**

A format for representing numbers in which a real number is represented by a pair of distinct numerals. In a floating-point representation, the real number is the product of the fixed-point part (the first numeral) and a value obtained by raising the implicit floating-point base to a power denoted by the exponent (the second numeral). For example, a floating-point representation of the number 0.0001234 is 0.1234 -3, where 0.1234 is the mantissa and -3 is the exponent.

**floating-point data item**

A numeric data item that contains a fraction and an exponent. Its value is obtained by multiplying the fraction by the base of the numeric data item raised to the power that the exponent specifies.

**\* format**

A specific arrangement of a set of data.

**\* function**

A temporary data item whose value is determined at the time the function is referenced during the execution of a statement.

**\* function-identifier**

A syntactically correct combination of character strings and separators that references a function. The data item represented by a function is uniquely identified by a function-name with its arguments, if any. A function-identifier can include a reference-modifier. A function-identifier that references an alphanumeric function can be specified anywhere in the general formats that an identifier can be specified, subject to certain restrictions. A function-identifier that references an integer or numeric function can be referenced anywhere in the general formats that an arithmetic expression can be specified.

**function-name**

A word that names the mechanism whose invocation, along with required arguments, determines the value of a function.

**function-pointer data item**

A data item in which a pointer to an entry point can be stored. A data item defined with the USAGE IS FUNCTION-POINTER clause contains the address of a function entry point. Typically used to communicate with C and Java programs.

**G****garbage collection**

The automatic freeing by the Java runtime system of the memory for objects that are no longer referenced.

**\* global name**

A name that is declared in only one program but that can be referenced from the program and from any program contained within the program. Condition-names, data-names, file-names, record-names, report-names, and some special registers can be global names.

**global reference**

A reference to an object that is outside the scope of a method.

**group item**

(1) A data item that is composed of subordinate data items. See *alphanumeric group item* and *national group item*. (2) When not qualified explicitly or by context as a national group or an alphanumeric group, the term refers to groups in general.

**grouping separator**

A character used to separate units of digits in numbers for ease of reading. The default is the character comma.

**H****header label**

(1) A data-set label that precedes the data records in a unit of recording media. (2) Synonym for *beginning-of-file label*.

**hide**

To redefine a factory or static method (inherited from a parent class) in a subclass.

**\* high-order end**

The leftmost character of a string of characters.

**hiperspace**

In a z/OS environment, a range of up to 2 GB of contiguous virtual storage addresses that a program can use as a buffer.

## I

### **IBM COBOL extension**

COBOL syntax and semantics supported by IBM compilers in addition to those described in the 85 COBOL Standard.

### **IDENTIFICATION DIVISION**

One of the four main component parts of a COBOL program, class definition, or method definition.

The IDENTIFICATION DIVISION identifies the program, class, or method. The IDENTIFICATION DIVISION can include the following documentation: author name, installation, or date.

#### **\* identifier**

A syntactically correct combination of character strings and separators that names a data item.

When referencing a data item that is not a function, an identifier consists of a data-name, together with its qualifiers, subscripts, and reference-modifier, as required for uniqueness of reference. When referencing a data item that is a function, a function-identifier is used.

#### **\* imperative statement**

A statement that either begins with an imperative verb and specifies an unconditional action to be taken or is a conditional statement that is delimited by its explicit scope terminator (delimited scope statement). An imperative statement can consist of a sequence of imperative statements.

#### **\* implicit scope terminator**

A separator period that terminates the scope of any preceding unterminated statement, or a phrase of a statement that by its occurrence indicates the end of the scope of any statement contained within the preceding phrase.

#### **\* index**

A computer storage area or register, the content of which represents the identification of a particular element in a table.

#### **\* index data item**

A data item in which the values associated with an index-name can be stored in a form specified by the implementor.

### **indexed data-name**

An identifier that is composed of a data-name, followed by one or more index-names enclosed in parentheses.

#### **\* indexed file**

A file with indexed organization.

#### **\* indexed organization**

The permanent logical file structure in which each record is identified by the value of one or more keys within that record.

### **indexing**

Synonymous with *subscripting* using index-names.

#### **\* index-name**

A user-defined word that names an index associated with a specific table.

### **inheritance**

A mechanism for using the implementation of a class as the basis for another class. By definition, the inheriting class conforms to the inherited classes. Enterprise COBOL does not support *multiple inheritance*; a subclass has exactly one immediate superclass.

### **inheritance hierarchy**

See *class hierarchy*.

#### **\* initial program**

A program that is placed into an initial state every time the program is called in a run unit.

#### **\* initial state**

The state of a program when it is first called in a run unit.

### **inline**

In a program, instructions that are executed sequentially, without branching to routines, subroutines, or other programs.

**inline comments**

An inline comment is identified by a floating comment indicator (\*>) preceded by one or more character-strings in the program-text area, and can be written on any line of a compilation group. All characters that follow the floating comment indicator up to the end of area B are comment text.

**\* input file**

A file that is opened in the input mode.

**\* input mode**

The state of a file after execution of an OPEN statement, with the INPUT phrase specified, for that file and before the execution of a CLOSE statement, without the REEL or UNIT phrase for that file.

**\* input-output file**

A file that is opened in the I-O mode.

**\* INPUT-OUTPUT SECTION**

The section of the ENVIRONMENT DIVISION that names the files and the external media required by an object program or method and that provides information required for transmission and handling of data at run time.

**\* input-output statement**

A statement that causes files to be processed by performing operations on individual records or on the file as a unit. The input-output statements are ACCEPT (with the identifier phrase), CLOSE, DELETE, DISPLAY, OPEN, READ, REWRITE, SET (with the TO ON or TO OFF phrase), START, and WRITE.

**\* input procedure**

A set of statements, to which control is given during the execution of a format 1 SORT statement, for the purpose of controlling the release of specified records to be sorted.

**instance data**

Data that defines the state of an object. The instance data introduced by a class is defined in the WORKING-STORAGE SECTION of the DATA DIVISION in the OBJECT paragraph of the class definition. The state of an object also includes the state of the instance variables introduced by classes that are inherited by the current class. A separate copy of the instance data is created for each object instance.

**\* integer**

(1) A numeric literal that does not include any digit positions to the right of the decimal point. (2) A numeric data item defined in the DATA DIVISION that does not include any digit positions to the right of the decimal point. (3) A numeric function whose definition provides that all digits to the right of the decimal point are zero in the returned value for any possible evaluation of the function.

**integer function**

A function whose category is numeric and whose definition does not include any digit positions to the right of the decimal point.

**Interactive System Productivity Facility (ISPF)**

An IBM software product that provides a menu-driven interface for the TSO or VM user. ISPF includes library utilities, a powerful editor, and dialog management.

**interlanguage communication (ILC)**

The ability of routines written in different programming languages to communicate. ILC support lets you readily build applications from component routines written in a variety of languages.

**intermediate result**

An intermediate field that contains the results of a succession of arithmetic operations.

**\* internal data**

The data that is described in a program and excludes all external data items and external file connectors. Items described in the LINKAGE SECTION of a program are treated as internal data.

**\* internal data item**

A data item that is described in one program in a run unit. An internal data item can have a global name.

**internal decimal data item**

A data item that is described as USAGE PACKED-DECIMAL or USAGE COMP-3, and that has a PICTURE character string that defines the item as numeric (a valid combination of symbols 9, S, P, or V). Synonymous with *packed-decimal data item*.

**\* internal file connector**

A file connector that is accessible to only one object program in the run unit.

**internal floating-point data item**

A data item that is described as USAGE COMP-1 or USAGE COMP-2. COMP-1 defines a single-precision floating-point data item. COMP-2 defines a double-precision floating-point data item. There is no PICTURE clause associated with an internal floating-point data item.

**\* intrarecord data structure**

The entire collection of groups and elementary data items from a logical record that a contiguous subset of the data description entries defines. These data description entries include all entries whose level-number is greater than the level-number of the first data description entry describing the intra-record data structure.

**intrinsic function**

A predefined function, such as a commonly used arithmetic function, called by a built-in function reference.

**\* invalid key condition**

A condition, at run time, caused when a specific value of the key associated with an indexed or relative file is determined to be not valid.

**\* I-O-CONTROL**

The name of an ENVIRONMENT DIVISION paragraph in which object program requirements for rerun points, sharing of same areas by several data files, and multiple file storage on a single input-output device are specified.

**\* I-O-CONTROL entry**

An entry in the I-O-CONTROL paragraph of the ENVIRONMENT DIVISION; this entry contains clauses that provide information required for the transmission and handling of data on named files during the execution of a program.

**\* I-O mode**

The state of a file after execution of an OPEN statement, with the I-O phrase specified, for that file and before the execution of a CLOSE statement without the REEL or UNIT phrase for that file.

**\* I-O status**

A conceptual entity that contains the two-character value indicating the resulting status of an input-output operation. This value is made available to the program through the use of the FILE STATUS clause in the file control entry for the file.

**is-a**

A relationship that characterizes classes and subclasses in an inheritance hierarchy. Subclasses that have an is-a relationship to a class inherit from that class.

**ISPF**

See *Interactive System Productivity Facility (ISPF)*.

**iteration structure**

A program processing logic in which a series of statements is repeated while a condition is true or until a condition is true.

**J****J2EE**

See *Java 2 Platform, Enterprise Edition (J2EE)*.

**Java 2 Platform, Enterprise Edition (J2EE)**

An environment for developing and deploying enterprise applications, defined by Oracle. The J2EE platform consists of a set of services, application programming interfaces (APIs), and protocols that provide the functionality for developing multitiered, Web-based applications. (Oracle)

**Java batch-processing program (JBP)**

An IMS batch-processing program that has access to online databases and output message queues. JBPs run online, but like programs in a batch environment, they are started with JCL or in a TSO session.

**Java batch-processing region**

An IMS dependent region in which only Java batch-processing programs are scheduled.

**Java Database Connectivity (JDBC)**

A specification from Oracle that defines an API that enables Java programs to access databases.

**Java message-processing program (JMP)**

A Java application program that is driven by transactions and has access to online IMS databases and message queues.

**Java message-processing region**

An IMS dependent region in which only Java message-processing programs are scheduled.

**Java Native Interface (JNI)**

A programming interface that lets Java code that runs inside a Java virtual machine (JVM) interoperate with applications and libraries written in other programming languages.

**Java virtual machine (JVM)**

A software implementation of a central processing unit that runs compiled Java programs.

**JavaBeans**

A portable, platform-independent, reusable component model. (Oracle)

**JBP**

See *Java batch-processing program (JBP)*.

**JDBC**

See *Java Database Connectivity (JDBC)*.

**JMP**

See *Java message-processing program (JMP)*.

**job control language (JCL)**

A control language used to identify a job to an operating system and to describe the job's requirements.

**JVM**

See *Java virtual machine (JVM)*.

**K****K**

When referring to storage capacity, two to the tenth power; 1024 in decimal notation.

**\* key**

A data item that identifies the location of a record, or a set of data items that serve to identify the ordering of data.

**\* key of reference**

The key, either prime or alternate, currently being used to access records within an indexed file.

**\* keyword**

A context-sensitive word or a reserved word whose presence is required when the format in which the word appears is used in a source unit.

**kilobyte (KB)**

One kilobyte equals 1024 bytes.

**L****\* language-name**

A system-name that specifies a particular programming language.

**Language Environment-conforming**

A characteristic of compiler products (such as Enterprise COBOL, COBOL for OS/390 & VM, COBOL for MVS & VM, C/C++ for MVS & VM, PL/I for MVS & VM) that produce object code conforming to the Language Environment conventions.

**last-used state**

A state that a program is in if its internal values remain the same as when the program was exited (the values are not reset to their initial values).

**\* letter**

A character belonging to one of the following two sets:

1. Uppercase letters: A, B, C, D, E, F, G, H, I, J, K, L, M, N, O, P, Q, R, S, T, U, V, W, X, Y, Z
2. Lowercase letters: a, b, c, d, e, f, g, h, i, j, k, l, m, n, o, p, q, r, s, t, u, v, w, x, y, z

**\* level indicator**

Two alphabetic characters that identify a specific type of file or a position in a hierarchy. The level indicators in the DATA DIVISION are: CD, FD, and SD.

**\* level-number**

A user-defined word (expressed as a two-digit number) that indicates the hierarchical position of a data item or the special properties of a data description entry. Level-numbers in the range from 1 through 49 indicate the position of a data item in the hierarchical structure of a logical record. Level-numbers in the range 1 through 9 can be written either as a single digit or as a zero followed by a significant digit. Level-numbers 66, 77, and 88 identify special properties of a data description entry.

**\* library-name**

A user-defined word that names a COBOL library that the compiler is to use for compiling a given source program.

**\* library text**

A sequence of text words, comment lines, inline comments, the separator space, or the separator pseudo-text delimiter in a COBOL library.

**Lilian date**

The number of days since the beginning of the Gregorian calendar. Day one is Friday, October 15, 1582. The Lilian date format is named in honor of Luigi Lilio, the creator of the Gregorian calendar.

**\* lineage-counter**

A special register whose value points to the current position within the page body.

**link**

(1) The combination of the link connection (the transmission medium) and two link stations, one at each end of the link connection. A link can be shared among multiple links in a multipoint or token-ring configuration. (2) To interconnect items of data or portions of one or more computer programs; for example, linking object programs by a linkage-editor to produce an executable file.

**LINKAGE SECTION**

The section in the DATA DIVISION of the called program or invoked method that describes data items available from the calling program or invoking method. Both the calling program or invoking method and the called program or invoked method can refer to these data items.

**linker**

A term that refers to either the z/OS binder (linkage-editor).

**literal**

A character string whose value is specified either by the ordered set of characters comprising the string or by the use of a figurative constant.

**little-endian**

The default format that Intel processors use to store binary data and UTF-16 characters. In this format, the most significant byte of a binary data item is at the highest address and the most significant byte of a UTF-16 character is at the highest address. Compare with *big-endian*.

**local reference**

A reference to an object that is within the scope of your method.

**locale**

A set of attributes for a program execution environment that indicates culturally sensitive considerations, such as character code page, collating sequence, date and time format, monetary value representation, numeric value representation, or language.

**\* LOCAL-STORAGE SECTION**

The section of the DATA DIVISION that defines storage that is allocated and freed on a per-invocation basis, depending on the value assigned in the VALUE clauses.

**\* logical operator**

One of the reserved words AND, OR, or NOT. In the formation of a condition, either AND, or OR, or both can be used as logical connectives. NOT can be used for logical negation.

**\* logical record**

The most inclusive data item. The level-number for a record is 01. A record can be either an elementary item or a group of items. Synonymous with *record*.

**\* low-order end**

The rightmost character of a string of characters.

**M****main program**

In a hierarchy of programs and subroutines, the first program that receives control when the programs are run within a process.

**makefile**

A text file that contains a list of the files for your application. The make utility uses this file to update the target files with the latest changes.

**\* mass storage**

A storage medium in which data can be organized and maintained in both a sequential manner and a nonsequential manner.

**\* mass storage device**

A device that has a large storage capacity, such as a magnetic disk.

**\* mass storage file**

A collection of records that is stored in a mass storage medium.

**\* megabyte (MB)**

One megabyte equals 1,048,576 bytes.

**\* merge file**

A collection of records to be merged by a MERGE statement. The merge file is created and can be used only by the merge function.

**message-processing program (MPP)**

An IMS application program that is driven by transactions and has access to online IMS databases and message queues.

**message queue**

The data set on which messages are queued before being processed by an application program or sent to a terminal.

**method**

Procedural code that defines an operation supported by an object and that is executed by an INVOKE statement on that object.

**\* method definition**

The COBOL source code that defines a method.

**\* method identification entry**

An entry in the METHOD-ID paragraph of the IDENTIFICATION DIVISION; this entry contains a clause that specifies the method-name.

**method invocation**

A communication from one object to another that requests the receiving object to execute a method.

**method-name**

The name of an object-oriented operation. When used to invoke the method, the name can be an alphanumeric or national literal or a category alphanumeric or category national data item. When used in the METHOD-ID paragraph to define the method, the name must be an alphanumeric or national literal.

**\* mnemonic-name**

A user-defined word that is associated in the ENVIRONMENT DIVISION with a specified implementor-name.

**module definition file**

A file that describes the code segments within a program object.

**MPP**

See *message-processing program (MPP)*.

**multitasking**

A mode of operation that provides for the concurrent, or interleaved, execution of two or more tasks.

**multithreading**

Concurrent operation of more than one path of execution within a computer. Synonymous with *multiprocessing*.

**N****name**

A word (composed of not more than 30 characters) that defines a COBOL operand.

**namespace**

See *XML namespace*.

**national character**

(1) A UTF-16 character in a USAGE NATIONAL data item or national literal. (2) Any character represented in UTF-16.

**national character position**

See *character position*.

**national data item**

A data item of category national, national-edited, or numeric-edited of USAGE NATIONAL.

**national decimal data item**

An external decimal data item that is described implicitly or explicitly as USAGE NATIONAL and that contains a valid combination of PICTURE symbols 9, S, P, and V.

**national-edited data item**

A data item that is described by a PICTURE character string that contains at least one instance of the symbol N and at least one of the simple insertion symbols B, 0, or /. A national-edited data item has USAGE NATIONAL.

**national floating-point data item**

An external floating-point data item that is described implicitly or explicitly as USAGE NATIONAL and that has a PICTURE character string that describes a floating-point data item.

**national group item**

A group item that is explicitly or implicitly described with a GROUP-USAGE NATIONAL clause. A national group item is processed as though it were defined as an elementary data item of category national for operations such as INSPECT, STRING, and UNSTRING. This processing ensures correct padding and truncation of national characters, as contrasted with defining USAGE NATIONAL data items within an alphanumeric group item. For operations that require processing of the elementary items within a group, such as MOVE CORRESPONDING, ADD CORRESPONDING, and INITIALIZE, a national group is processed using group semantics.

**\* native character set**

The implementor-defined character set associated with the computer specified in the OBJECT-COMPUTER paragraph.

**\* native collating sequence**

The implementor-defined collating sequence associated with the computer specified in the OBJECT-COMPUTER paragraph.

**native method**

A Java method with an implementation that is written in another programming language, such as COBOL.

**\* negated combined condition**

The NOT logical operator immediately followed by a parenthesized combined condition. See also *condition* and *combined condition*.

**\* negated simple condition**

The NOT logical operator immediately followed by a simple condition. See also *condition* and *simple condition*.

**nested program**

A program that is directly contained within another program.

**\* next executable sentence**

The next sentence to which control will be transferred after execution of the current statement is complete.

**\* next executable statement**

The next statement to which control will be transferred after execution of the current statement is complete.

**\* next record**

The record that logically follows the current record of a file.

**\* noncontiguous items**

Elementary data items in the WORKING-STORAGE SECTION and LINKAGE SECTION that bear no hierarchic relationship to other data items.

**null**

A figurative constant that is used to assign, to pointer data items, the value of an address that is not valid. NULLS can be used wherever NULL can be used.

**\* numeric character**

A character that belongs to the following set of digits: 0, 1, 2, 3, 4, 5, 6, 7, 8, 9.

**numeric data item**

(1) A data item whose description restricts its content to a value represented by characters chosen from the digits 0 through 9. If signed, the item can also contain a +, -, or other representation of an operational sign. (2) A data item of category numeric, internal floating-point, or external floating-point. A numeric data item can have USAGE DISPLAY, NATIONAL, PACKED-DECIMAL, BINARY, COMP, COMP-1, COMP-2, COMP-3, COMP-4, or COMP-5.

**numeric-edited data item**

A data item that contains numeric data in a form suitable for use in printed output. The data item can consist of external decimal digits from 0 through 9, the decimal separator, commas, the currency sign, sign control characters, and other editing characters. A numeric-edited item can be represented in either USAGE DISPLAY or USAGE NATIONAL.

**\* numeric function**

A function whose class and category are numeric but that for some possible evaluation does not satisfy the requirements of integer functions.

**\* numeric literal**

A literal composed of one or more numeric characters that can contain a decimal point or an algebraic sign, or both. The decimal point must not be the rightmost character. The algebraic sign, if present, must be the leftmost character.

**O**

**object**

An entity that has state (its data values) and operations (its methods). An object is a way to encapsulate state and behavior. Each object in the class is said to be an instance of the class.

**object code**

Output from a compiler or assembler that is itself executable machine code or is suitable for processing to produce executable machine code.

**\* OBJECT-COMPUTER**

The name of an ENVIRONMENT DIVISION paragraph in which the computer environment, where the object program is run, is described.

**\* object computer entry**

An entry in the OBJECT-COMPUTER paragraph of the ENVIRONMENT DIVISION; this entry contains clauses that describe the computer environment in which the object program is to be executed.

**object deck**

A portion of an object program suitable as input to a linkage-editor. Synonymous with *object module* and *text deck*.

**object instance**

See *object*.

**object module**

Synonym for *object deck* or *text deck*.

**\* object of entry**

A set of operands and reserved words, within a DATA DIVISION entry of a COBOL program, that immediately follows the subject of the entry.

**object-oriented programming**

A programming approach based on the concepts of encapsulation and inheritance. Unlike procedural programming techniques, object-oriented programming concentrates on the data objects that comprise the problem and how they are manipulated, not on how something is accomplished.

**object program**

A set or group of executable machine-language instructions and other material designed to interact with data to provide problem solutions. In this context, an object program is generally the machine language result of the operation of a COBOL compiler on a source program or class definition. Where there is no danger of ambiguity, the word *program* can be used in place of *object program*.

**object reference**

A value that identifies an instance of a class. If the class is not specified, the object reference is universal and can apply to instances of any class.

**\* object time**

The time at which an object program is executed. Synonymous with *run time*.

**\* obsolete element**

A COBOL language element in the 85 COBOL Standard that was deleted from the 2002 COBOL Standard.

**ODO object**

In the example below, X is the object of the OCCURS DEPENDING ON clause (ODO object).

```
WORKING-STORAGE SECTION
01  TABLE-1.
    05  X                                PICS9.
    05  Y OCCURS 3 TIMES
        DEPENDING ON X                PIC X.
```

The value of the ODO object determines how many of the ODO subject appear in the table.

**ODO subject**

In the example above, Y is the subject of the OCCURS DEPENDING ON clause (ODO subject). The number of Y ODO subjects that appear in the table depends on the value of X.

**\* open mode**

The state of a file after execution of an OPEN statement for that file and before the execution of a CLOSE statement without the REEL or UNIT phrase for that file. The particular open mode is specified in the OPEN statement as either INPUT, OUTPUT, I-O, or EXTEND.

**\* operand**

(1) The general definition of operand is "the component that is operated upon." (2) For the purposes of this document, any lowercase word (or words) that appears in a statement or entry format can be considered to be an operand and, as such, is an implied reference to the data indicated by the operand.

**operation**

A service that can be requested of an object.

**\* operational sign**

An algebraic sign that is associated with a numeric data item or a numeric literal, to indicate whether its value is positive or negative.

**optional file**

A file that is declared as being not necessarily available each time the object program is run.

**\* optional word**

A reserved word that is included in a specific format only to improve the readability of the language. Its presence is optional to the user when the format in which the word appears is used in a source unit.

**\* output file**

A file that is opened in either output mode or extend mode.

**\* output mode**

The state of a file after execution of an OPEN statement, with the OUTPUT or EXTEND phrase specified, for that file and before the execution of a CLOSE statement without the REEL or UNIT phrase for that file.

**\* output procedure**

A set of statements to which control is given during execution of a format 1 SORT statement after the sort function is completed, or during execution of a MERGE statement after the merge function reaches a point at which it can select the next record in merged order when requested.

**overflow condition**

A condition that occurs when a portion of the result of an operation exceeds the capacity of the intended unit of storage.

**overload**

To define a method with the same name as another method that is available in the same class, but with a different signature. See also *signature*.

**override**

To redefine an instance method (inherited from a parent class) in a subclass.

**P****package**

A group of related Java classes, which can be imported individually or as a whole.

**packed-decimal data item**

See *internal decimal data item*.

**padding character**

An alphanumeric or national character that is used to fill the unused character positions in a physical record.

**page**

A vertical division of output data that represents a physical separation of the data. The separation is based on internal logical requirements or external characteristics of the output medium or both.

**\* page body**

That part of the logical page in which lines can be written or spaced or both.

**\* paragraph**

In the PROCEDURE DIVISION, a paragraph-name followed by a separator period and by zero, one, or more sentences. In the IDENTIFICATION DIVISION and ENVIRONMENT DIVISION, a paragraph header followed by zero, one, or more entries.

**\* paragraph header**

A reserved word, followed by the separator period, that indicates the beginning of a paragraph in the IDENTIFICATION DIVISION and ENVIRONMENT DIVISION. The permissible paragraph headers in the IDENTIFICATION DIVISION are:

```
PROGRAM-ID. (Program IDENTIFICATION
            DIVISION)
CLASS-ID. (Class IDENTIFICATION DIVISION)
METHOD-ID. (Method IDENTIFICATION
            DIVISION)
AUTHOR.
INSTALLATION.
DATE-WRITTEN.
DATE-COMPILED.
SECURITY.
```

The permissible paragraph headers in the ENVIRONMENT DIVISION are:

```
SOURCE-COMPUTER.
OBJECT-COMPUTER.
SPECIAL-NAMES.
REPOSITORY. (Program or Class
            CONFIGURATION SECTION)
FILE-CONTROL.
I-O-CONTROL.
```

**\* paragraph-name**

A user-defined word that identifies and begins a paragraph in the PROCEDURE DIVISION.

**parameter**

(1) Data passed between a calling program and a called program. (2) A data element in the USING phrase of a method invocation. Arguments provide additional information that the invoked method can use to perform the requested operation.

**Persistent Reusable JVM**

A JVM that can be serially reused for transaction processing by resetting the JVM between transactions. The reset phase restores the JVM to a known initialization state.

**\* phrase**

An ordered set of one or more consecutive COBOL character strings that form a portion of a COBOL procedural statement or of a COBOL clause.

**\* physical record**

See *block*.

**pointer data item**

A data item in which address values can be stored. Data items are explicitly defined as pointers with the USAGE IS POINTER clause. ADDRESS OF special registers are implicitly defined as pointer data items. Pointer data items can be compared for equality or moved to other pointer data items.

**port**

(1) To modify a computer program to enable it to run on a different platform. (2) In the Internet suite of protocols, a specific logical connector between the Transmission Control Protocol (TCP) or the User Datagram Protocol (UDP) and a higher-level protocol or application. A port is identified by a port number.

**portability**

The ability to transfer an application program from one application platform to another with relatively few changes to the source program.

**preinitialization**

The initialization of the COBOL runtime environment in preparation for multiple calls from programs, especially non-COBOL programs. The environment is not terminated until an explicit termination.

**\* prime record key**

A key whose contents uniquely identify a record within an indexed file.

**\* priority-number**

A user-defined word that classifies sections in the PROCEDURE DIVISION for purposes of segmentation. Segment numbers can contain only the characters 0 through 9. A segment number can be expressed as either one or two digits.

**private**

As applied to factory data or instance data, accessible only by methods of the class that defines the data.

**\* procedure**

A paragraph or group of logically successive paragraphs, or a section or group of logically successive sections, within the PROCEDURE DIVISION.

**\* procedure branching statement**

A statement that causes the explicit transfer of control to a statement other than the next executable statement in the sequence in which the statements are written in the source code. The procedure branching statements are: ALTER, CALL, EXIT, EXIT PROGRAM, GO TO, MERGE (with the OUTPUT PROCEDURE phrase), PERFORM and SORT (with the INPUT PROCEDURE or OUTPUT PROCEDURE phrase), XML PARSE.

**PROCEDURE DIVISION**

The COBOL division that contains instructions for solving a problem.

**procedure integration**

One of the functions of the COBOL optimizer is to simplify calls to performed procedures or contained programs.

PERFORM procedure integration is the process whereby a PERFORM statement is replaced by its performed procedures. Contained program procedure integration is the process where a call to a contained program is replaced by the program code.

**\* procedure-name**

A user-defined word that is used to name a paragraph or section in the PROCEDURE DIVISION. It consists of a paragraph-name (which can be qualified) or a section-name.

**procedure-pointer data item**

A data item in which a pointer to an entry point can be stored. A data item defined with the USAGE IS PROCEDURE-POINTER clause contains the address of a procedure entry point. Typically used to communicate with COBOL and Language Environment programs.

**process**

The course of events that occurs during the execution of all or part of a program. Multiple processes can run concurrently, and programs that run within a process can share resources.

**program**

(1) A sequence of instructions suitable for processing by a computer. Processing may include the use of a compiler to prepare the program for execution, as well as a runtime environment to execute it. (2) A logical assembly of one or more interrelated modules. Multiple copies of the same program can be run in different processes.

**\* program identification entry**

In the PROGRAM-ID paragraph of the IDENTIFICATION DIVISION, an entry that contains clauses that specify the program-name and assign selected program attributes to the program.

**program-name**

In the IDENTIFICATION DIVISION and the end program marker, a user-defined word or alphanumeric literal that identifies a COBOL source program.

**project**

The complete set of data and actions that are required to build a target, such as a dynamic link library (DLL) or other executable (EXE).

**\* pseudo-text**

A sequence of text words, comment lines, inline comments, or the separator space in a source program or COBOL library bounded by, but not including, pseudo-text delimiters.

**\* pseudo-text delimiter**

Two contiguous equal sign characters (==) used to delimit pseudo-text.

**\* punctuation character**

A character that belongs to the following set:

Character	Meaning
,	Comma
;	Semicolon
:	Colon
.	Period (full stop)
"	Quotation mark
(	Left parenthesis
)	Right parenthesis
	Space
=	Equal sign

**Q**

**QSAM (Queued Sequential Access Method)**

An extended version of the basic sequential access method (BSAM). When this method is used, a queue is formed of input data blocks that are awaiting processing or of output data blocks that have been processed and are awaiting transfer to auxiliary storage or to an output device.

**\* qualified data-name**

An identifier that is composed of a data-name followed by one or more sets of either of the connectives OF and IN followed by a data-name qualifier.

**\* qualifier**

(1) A data-name or a name associated with a level indicator that is used in a reference either together with another data-name (which is the name of an item that is subordinate to the qualifier) or together with a condition-name. (2) A section-name that is used in a reference together with a paragraph-name specified in that section. (3) A library-name that is used in a reference together with a text-name associated with that library.

**R**

**\* random access**

An access mode in which the program-specified value of a key data item identifies the logical record that is obtained from, deleted from, or placed into a relative or indexed file.

**\* record**

See *logical record*.

**\* record area**

A storage area allocated for the purpose of processing the record described in a record description entry in the FILE SECTION of the DATA DIVISION. In the FILE SECTION, the current number of character positions in the record area is determined by the explicit or implicit RECORD clause.

**\* record description**

See *record description entry*.

**\* record description entry**

The total set of data description entries associated with a particular record. Synonymous with *record description*.

**record key**

A key whose contents identify a record within an indexed file.

**\* record-name**

A user-defined word that names a record described in a record description entry in the DATA DIVISION of a COBOL program.

**\* record number**

The ordinal number of a record in the file whose organization is sequential.

**recording mode**

The format of the logical records in a file. Recording mode can be F (fixed length), V (variable length), S (spanned), or U (undefined).

**recursion**

A program calling itself or being directly or indirectly called by one of its called programs.

**recursively capable**

A program is recursively capable (can be called recursively) if the RECURSIVE attribute is on the PROGRAM-ID statement.

**reel**

A discrete portion of a storage medium, the dimensions of which are determined by each implementor that contains part of a file, all of a file, or any number of files. Synonymous with *unit* and *volume*.

**reentrant**

The attribute of a program or routine that lets more than one user share a single copy of a program object.

**\* reference format**

A format that provides a standard method for describing COBOL source programs.

**reference modification**

A method of defining a new category alphanumeric, category DBCS, or category national data item by specifying the leftmost character and length relative to the leftmost character position of a USAGE DISPLAY, DISPLAY-1, or NATIONAL data item.

**\* reference-modifier**

A syntactically correct combination of character strings and separators that defines a unique data item. It includes a delimiting left parenthesis separator, the leftmost character position, a colon separator, optionally a length, and a delimiting right parenthesis separator.

**\* relation**

See *relational operator* or *relation condition*.

**\* relation character**

A character that belongs to the following set:

Character	Meaning
>	Greater than
<	Less than
=	Equal to

**\* relation condition**

The proposition (for which a truth value can be determined) that the value of an arithmetic expression, data item, alphanumeric literal, or index-name has a specific relationship to the value of another arithmetic expression, data item, alphanumeric literal, or index name. See also *relational operator*.

**\* relational operator**

A reserved word, a relation character, a group of consecutive reserved words, or a group of consecutive reserved words and relation characters used in the construction of a relation condition. The permissible operators and their meanings are:

Character	Meaning
IS GREATER THAN	Greater than

<b>Character</b>	<b>Meaning</b>
IS >	Greater than
IS NOT GREATER THAN	Not greater than
IS NOT >	Not greater than
IS LESS THAN	Less than
IS <	Less than
IS NOT LESS THAN	Not less than
IS NOT <	Not less than
IS EQUAL TO	Equal to
IS =	Equal to
IS NOT EQUAL TO	Not equal to
IS NOT =	Not equal to
IS GREATER THAN OR EQUAL TO	Greater than or equal to
IS >=	Greater than or equal to
IS LESS THAN OR EQUAL TO	Less than or equal to
IS <=	Less than or equal to

**\* relative file**

A file with relative organization.

**\* relative key**

A key whose contents identify a logical record in a relative file.

**\* relative organization**

The permanent logical file structure in which each record is uniquely identified by an integer value greater than zero, which specifies the logical ordinal position of the record in the file.

**\* relative record number**

The ordinal number of a record in a file whose organization is relative. This number is treated as a numeric literal that is an integer.

**\* reserved word**

A COBOL word that is specified in the list of words that can be used in a COBOL source program, but that must not appear in the program as a user-defined word or system-name.

**\* resource**

A facility or service, controlled by the operating system, that an executing program can use.

**\* resultant identifier**

A user-defined data item that is to contain the result of an arithmetic operation.

**reusable environment**

A reusable environment is created when you establish an assembler program as the main program by using either the old COBOL interfaces for preinitialization (RTEREUS runtime option), or the Language Environment interface, CEEPIPI.

**routine**

A set of statements in a COBOL program that causes the computer to perform an operation or series of related operations. In Language Environment, refers to either a procedure, function, or subroutine.

**\* routine-name**

A user-defined word that identifies a procedure written in a language other than COBOL.

**\* run time**

The time at which an object program is executed. Synonymous with *object time*.

**runtime environment**

The environment in which a COBOL program executes.

**\* run unit**

A stand-alone object program, or several object programs, that interact by means of COBOL CALL or INVOKE statements and function at run time as an entity.

A run unit is also called an enclave in Language Environment terminology.

**S****SBCS**

See *single-byte character set (SBCS)*.

**scope terminator**

A COBOL reserved word that marks the end of certain PROCEDURE DIVISION statements. It can be either explicit (END-ADD, for example) or implicit (separator period).

**\* section**

A set of zero, one, or more paragraphs or entities, called a section body, the first of which is preceded by a section header. Each section consists of the section header and the related section body.

**\* section header**

A combination of words followed by a separator period that indicates the beginning of a section in any of these divisions: ENVIRONMENT, DATA, or PROCEDURE. In the ENVIRONMENT DIVISION and DATA DIVISION, a section header is composed of reserved words followed by a separator period. The permissible section headers in the ENVIRONMENT DIVISION are:

```
CONFIGURATION SECTION.  
INPUT-OUTPUT SECTION.
```

The permissible section headers in the DATA DIVISION are:

```
FILE SECTION.  
WORKING-STORAGE SECTION.  
LOCAL-STORAGE SECTION.  
LINKAGE SECTION.
```

In the PROCEDURE DIVISION, a section header is composed of a section-name, followed by the reserved word SECTION, followed by a separator period.

**\* section-name**

A user-defined word that names a section in the PROCEDURE DIVISION.

**selection structure**

A program processing logic in which one or another series of statements is executed, depending on whether a condition is true or false.

**\* sentence**

A sequence of one or more statements, the last of which is terminated by a separator period.

**\* separately compiled program**

A program that, together with its contained programs, is compiled separately from all other programs.

**\* separator**

A character or two or more contiguous characters used to delimit character strings.

**\* separator comma**

A comma (,) followed by a space used to delimit character strings.

**\* separator period**

A period (.) followed by a space used to delimit character strings.

**\* separator semicolon**

A semicolon (;) followed by a space used to delimit character strings.

**sequence structure**

A program processing logic in which a series of statements is executed in sequential order.

**\* sequential access**

An access mode in which logical records are obtained from or placed into a file in a consecutive predecessor-to-successor logical record sequence determined by the order of records in the file.

**\* sequential file**

A file with sequential organization.

**\* sequential organization**

The permanent logical file structure in which a record is identified by a predecessor-successor relationship established when the record is placed into the file.

**serial search**

A search in which the members of a set are consecutively examined, beginning with the first member and ending with the last.

**session bean**

In EJB, an enterprise bean that is created by a client and that usually exists only for the duration of a single client/server session. (Oracle)

**77-level-description-entry**

A data description entry that describes a noncontiguous data item that has level-number 77.

**\* sign condition**

The proposition (for which a truth value can be determined) that the algebraic value of a data item or an arithmetic expression is either less than, greater than, or equal to zero.

**signature**

(1) The name of an operation and its parameters. (2) The name of a method and the number and types of its formal parameters.

**\* simple condition**

Any single condition chosen from this set:

- Relation condition
- Class condition
- Condition-name condition
- Switch-status condition
- Sign condition

See also *condition* and *negated simple condition*.

**single-byte character set (SBCS)**

A set of characters in which each character is represented by a single byte. See also *ASCII* and *EBCDIC (Extended Binary-Coded Decimal Interchange Code)*.

**slack bytes**

Bytes inserted between data items or records to ensure correct alignment of some numeric items. Slack bytes contain no meaningful data. In some cases, they are inserted by the compiler; in others, it is the responsibility of the programmer to insert them. The SYNCHRONIZED clause instructs the compiler to insert slack bytes when they are needed for proper alignment. Slack bytes between records are inserted by the programmer.

**\* sort file**

A collection of records to be sorted by a format 1 SORT statement. The sort file is created and can be used by the sort function only.

**\* sort-merge file description entry**

An entry in the FILE SECTION of the DATA DIVISION that is composed of the level indicator SD, followed by a file-name, and then followed by a set of file clauses as required.

**\* SOURCE-COMPUTER**

The name of an ENVIRONMENT DIVISION paragraph in which the computer environment, where the source program is compiled, is described.

**\* source computer entry**

An entry in the SOURCE - COMPUTER paragraph of the ENVIRONMENT DIVISION; this entry contains clauses that describe the computer environment in which the source program is to be compiled.

**\* source item**

An identifier designated by a SOURCE clause that provides the value of a printable item.

**source program**

Although a source program can be represented by other forms and symbols, in this document the term always refers to a syntactically correct set of COBOL statements. A COBOL source program commences with the IDENTIFICATION DIVISION or a COPY statement and terminates with the end program marker, if specified, or with the absence of additional source program lines.

**source unit**

A unit of COBOL source code that can be separately compiled: a program or a class definition. Also known as a *compilation unit*.

**special character**

A character that belongs to the following set:

Character	Meaning
+	Plus sign
-	Minus sign (hyphen)
*	Asterisk
/	Slant (forward slash)
=	Equal sign
\$	Currency sign
,	Comma
;	Semicolon
.	Period (decimal point, full stop)
"	Quotation mark
'	Apostrophe
(	Left parenthesis
)	Right parenthesis
>	Greater than
<	Less than
:	Colon
_	Underscore

**SPECIAL - NAMES**

The name of an ENVIRONMENT DIVISION paragraph in which environment-names are related to user-specified mnemonic-names.

**\* special names entry**

An entry in the SPECIAL - NAMES paragraph of the ENVIRONMENT DIVISION; this entry provides means for specifying the currency sign; choosing the decimal point; specifying symbolic characters; relating implementor-names to user-specified mnemonic-names; relating alphabet-names to character sets or collating sequences; and relating class-names to sets of characters.

**\* special registers**

Certain compiler-generated storage areas whose primary use is to store information produced in conjunction with the use of a specific COBOL feature.

**\* statement**

A syntactically valid combination of words, literals, and separators, beginning with a verb, written in a COBOL source program.

**structured programming**

A technique for organizing and coding a computer program in which the program comprises a hierarchy of segments, each segment having a single entry point and a single exit point. Control is passed downward through the structure without unconditional branches to higher levels of the hierarchy.

**\* subclass**

A class that inherits from another class. When two classes in an inheritance relationship are considered together, the subclass is the inheritor or inheriting class; the superclass is the inheritee or inherited class.

**\* subject of entry**

An operand or reserved word that appears immediately following the level indicator or the level-number in a DATA DIVISION entry.

**\* subprogram**

See *called program*.

**\* subscript**

An occurrence number that is represented by either an integer, a data-name optionally followed by an integer with the operator + or -, or an index-name optionally followed by an integer with the operator + or -, that identifies a particular element in a table. A subscript can be the word ALL when the subscripted identifier is used as a function argument for a function allowing a variable number of arguments.

**\* subscripted data-name**

An identifier that is composed of a data-name followed by one or more subscripts enclosed in parentheses.

**substitution character**

A character that is used in a conversion from a source code page to a target code page to represent a character that is not defined in the target code page.

**\* superclass**

A class that is inherited by another class. See also *subclass*.

**surrogate pair**

In the UTF-16 format of Unicode, a pair of encoding units that together represents a single Unicode graphic character. The first unit of the pair is called a *high surrogate* and the second a *low surrogate*. The code value of a high surrogate is in the range X'D800' through X'DBFF'. The code value of a low surrogate is in the range X'DC00' through X'DFFF'. Surrogate pairs provide for more characters than the 65,536 characters that fit in the Unicode 16-bit coded character set.

**switch-status condition**

The proposition (for which a truth value can be determined) that an UPSI switch, capable of being set to an on or off status, has been set to a specific status.

**\* symbolic-character**

A user-defined word that specifies a user-defined figurative constant.

**syntax**

(1) The relationship among characters or groups of characters, independent of their meanings or the manner of their interpretation and use. (2) The structure of expressions in a language. (3) The rules governing the structure of a language. (4) The relationship among symbols. (5) The rules for the construction of a statement.

**\* system-name**

A COBOL word that is used to communicate with the operating environment.

**T**

**\* table**

A set of logically consecutive items of data that are defined in the DATA DIVISION by means of the OCCURS clause.

**\* table element**

A data item that belongs to the set of repeated items comprising a table.

**text deck**

Synonym for *object deck* or *object module*.

**\* text-name**

A user-defined word that identifies library text.

**\* text word**

A character or a sequence of contiguous characters between margin A and margin R in a COBOL library, source program, or pseudo-text that is any of the following characters:

- A separator, except for space; a pseudo-text delimiter; and the opening and closing delimiters for alphanumeric literals. The right parenthesis and left parenthesis characters, regardless of context within the library, source program, or pseudo-text, are always considered text words.
- A literal including, in the case of alphanumeric literals, the opening quotation mark and the closing quotation mark that bound the literal.
- Any other sequence of contiguous COBOL characters except comment lines and the word COPY bounded by separators that are neither a separator nor a literal.

**thread**

A stream of computer instructions (initiated by an application within a process) that is in control of a process.

**token**

In the COBOL editor, a unit of meaning in a program. A token can contain data, a language keyword, an identifier, or other part of the language syntax.

**top-down design**

The design of a computer program using a hierarchic structure in which related functions are performed at each level of the structure.

**top-down development**

See *structured programming*.

**trailer-label**

(1) A data-set label that follows the data records on a unit of recording medium. (2) Synonym for *end-of-file label*.

**troubleshoot**

To detect, locate, and eliminate problems in using computer software.

**\* truth value**

The representation of the result of the evaluation of a condition in terms of one of two values: true or false.

**typed object reference**

A data-name that can refer only to an object of a specified class or any of its subclasses.

**U****\* unary operator**

A plus (+) or a minus (-) sign that precedes a variable or a left parenthesis in an arithmetic expression and that has the effect of multiplying the expression by +1 or -1, respectively.

**Unicode**

A universal character encoding standard that supports the interchange, processing, and display of text that is written in any of the languages of the modern world. There are multiple encoding schemes to represent Unicode, including UTF-8, UTF-16, and UTF-32. Enterprise COBOL supports Unicode using UTF-16 in big-endian format as the representation for the national data type.

**Uniform Resource Identifier (URI)**

A sequence of characters that uniquely names a resource; in Enterprise COBOL, the identifier of a namespace. URI syntax is defined by the document *Uniform Resource Identifier (URI): Generic Syntax*.

**unit**

A module of direct access, the dimensions of which are determined by IBM.

**universal object reference**

A data-name that can refer to an object of any class.

**unrestricted storage**

Storage below the 2 GB bar. It can be above or below the 16 MB line. If it is above the 16 MB line, it is addressable only in 31-bit mode.

**\* unsuccessful execution**

The attempted execution of a statement that does not result in the execution of all the operations specified by that statement. The unsuccessful execution of a statement does not affect any data referenced by that statement, but can affect status indicators.

**UPSI switch**

A program switch that performs the functions of a hardware switch. Eight are provided: UPSI-0 through UPSI-7.

**URI**

See *Uniform Resource Identifier (URI)*.

**\* user-defined word**

A COBOL word that must be supplied by the user to satisfy the format of a clause or statement.

**V****\* variable**

A data item whose value can be changed by execution of the object program. A variable used in an arithmetic expression must be a numeric elementary item.

**variable-length item**

A group item that contains a table described with the *DEPENDING* phrase of the *OCCURS* clause.

**\* variable-length record**

A record associated with a file whose file description or sort-merge description entry permits records to contain a varying number of character positions.

**\* variable-occurrence data item**

A variable-occurrence data item is a table element that is repeated a variable number of times. Such an item must contain an *OCCURS DEPENDING ON* clause in its data description entry or be subordinate to such an item.

**\* variably located group**

A group item following, and not subordinate to, a variable-length table in the same record. The group item can be an alphanumeric group or a national group.

**\* variably located item**

A data item following, and not subordinate to, a variable-length table in the same record.

**\* verb**

A word that expresses an action to be taken by a COBOL compiler or object program.

**volume**

A module of external storage. For tape devices it is a reel; for direct-access devices it is a unit.

**volume switch procedures**

System-specific procedures that are executed automatically when the end of a unit or reel has been reached before end-of-file has been reached.

**VSAM file system**

A file system that supports COBOL sequential, relative, and indexed organizations.

**W**

**web service**

A modular application that performs specific tasks and is accessible through open protocols like HTTP and SOAP.

**white space**

Characters that introduce space into a document. They are:

- Space
- Horizontal tabulation
- Carriage return
- Line feed
- Next line

as named in the Unicode Standard.

**\* word**

A character string of not more than 30 characters that forms a user-defined word, a system-name, a reserved word, or a function-name.

**\* WORKING-STORAGE SECTION**

The section of the DATA DIVISION that describes WORKING-STORAGE data items, composed either of noncontiguous items or WORKING-STORAGE records or of both.

**workstation**

A generic term for computers, including personal computers, 3270 terminals, intelligent workstations, and UNIX terminals. Often a workstation is connected to a mainframe or to a network.

**wrapper**

An object that provides an interface between object-oriented code and procedure-oriented code. Using wrappers lets programs be reused and accessed by other systems.

**X****x**

The symbol in a PICTURE clause that can hold any character in the character set of the computer.

**XML**

Extensible Markup Language. A standard metalanguage for defining markup languages that was derived from and is a subset of SGML. XML omits the more complex and less-used parts of SGML and makes it much easier to write applications to handle document types, author and manage structured information, and transmit and share structured information across diverse computing systems. The use of XML does not require the robust applications and processing that is necessary for SGML. XML is developed under the auspices of the World Wide Web Consortium (W3C).

**XML data**

Data that is organized into a hierarchical structure with XML elements. The data definitions are defined in XML element type declarations.

**XML declaration**

XML text that specifies characteristics of the XML document such as the version of XML being used and the encoding of the document.

**XML document**

A data object that is well formed as defined by the W3C XML specification.

**XML namespace**

A mechanism, defined by the W3C XML Namespace specifications, that limits the scope of a collection of element names and attribute names. A uniquely chosen XML namespace ensures the unique identity of an element name or attribute name across multiple XML documents or multiple contexts within an XML document.

**XML schema**

A mechanism, defined by the W3C, for describing and constraining the structure and content of XML documents. An XML schema, which is itself expressed in XML, effectively defines a class of XML documents of a given type, for example, purchase orders.

## **Z**

### **z/OS UNIX file system**

A collection of files and directories that are organized in a hierarchical structure and can be accessed by using z/OS UNIX.

### **zoned decimal data item**

An external decimal data item that is described implicitly or explicitly as USAGE DISPLAY and that contains a valid combination of PICTURE symbols 9, S, P, and V. The content of a zoned decimal data item is represented in characters 0 through 9, optionally with a sign. If the PICTURE string specifies a sign and the SIGN IS SEPARATE clause is specified, the sign is represented as characters + or -. If SIGN IS SEPARATE is not specified, the sign is one hexadecimal digit that overlays the first 4 bits of the sign position (leading or trailing).

## **#**

### **85 COBOL Standard**

The COBOL language defined by the following standards:

- *ANSI INCITS 23-1985, Programming languages - COBOL*, as amended by *ANSI INCITS 23a-1989, Programming Languages - COBOL - Intrinsic Function Module for COBOL* and *ANSI INCITS 23b-1993, Programming Languages - Correction Amendment for COBOL*
- *ISO 1989:1985, Programming languages - COBOL*, as amended by *ISO/IEC 1989/AMD1:1992, Programming languages - COBOL: Intrinsic function module* and *ISO/IEC 1989/AMD2:1994, Programming languages - Correction and clarification amendment for COBOL*

### **2002 COBOL Standard**

The COBOL language defined by the following standards:

- *INCITS/ISO/IEC 1989-2002, Information Technology - Programming Languages - COBOL*
- *ISO/IEC 1989:2002, Information technology -- Programming languages -- COBOL*



## List of resources

---

### Enterprise COBOL for z/OS

---

#### COBOL for z/OS publications

You can find the following publications in the [Enterprise COBOL for z/OS library](#):

- *What's new*
- *Customization Guide*, SC27-8712
- *Language Reference*, SC27-8713
- *Programming Guide*, SC27-8714
- *Migration Guide*, GC27-8715
- *Program Directory*, GI13-4526
- *Licensed Program Specifications*, GI13-4532

#### Softcopy publications

The following collection kits contain Enterprise COBOL and other product publications. You can find them at <http://www.ibm.com/e-business/linkweb/publications/servlet/pbi.wss>.

- *z/OS Software Products Collection*
- *z/OS and Software Products DVD Collection*

#### Support

*Enterprise COBOL Version 6 Release 1 Performance Tuning Guide*, [www.ibm.com/support/docview.wss?uid=swg27047580](http://www.ibm.com/support/docview.wss?uid=swg27047580)

If you have a problem using Enterprise COBOL for z/OS, see the following site that provides up-to-date support information: [https://www.ibm.com/support/home/product/B984385H82239E03/Enterprise\\_COBOL\\_for\\_z/OS](https://www.ibm.com/support/home/product/B984385H82239E03/Enterprise_COBOL_for_z/OS).

### Related publications

---

#### z/OS library publications

You can find the following publications in the [z/OS Internet Library](#).

##### Run-Time Library Extensions

- *Common Debug Architecture Library Reference*
- *Common Debug Architecture User's Guide*
- *DWARF/ELF Extensions Library Reference*

##### z/Architecture

- *Principles of Operation*

##### z/OS DFSMS

- *Access Method Services for Catalogs*
- *Checkpoint/Restart*
- *Macro Instructions for Data Sets*

- *Using Data Sets*
- *Utilities*

### **z/OS DFSORT**

- *Application Programming Guide*
- *Installation and Customization*

### **z/OS ISPF**

- *Dialog Developer's Guide and Reference*
- *User's Guide Vol I*
- *User's Guide Vol II*

### **z/OS Language Environment**

- *Concepts Guide*
- *Customization*
- *Debugging Guide*
- *Language Environment Vendor Interfaces*
- *Programming Guide*
- *Programming Reference*
- *Run-Time Messages*
- *Run-Time Application Migration Guide*
- *Writing Interlanguage Communication Applications*

### **z/OS MVS**

- *JCL Reference*
- *JCL User's Guide*
- *Programming: Callable Services for High-Level Languages*
- *Program Management: User's Guide and Reference*
- *System Commands*
- *z/OS Unicode Services User's Guide and Reference*
- *z/OS XML System Services User's Guide and Reference*

### **z/OS TSO/E**

- *Command Reference*
- *Primer*
- *User's Guide*

### **z/OS UNIX System Services**

- *Command Reference*
- *Programming: Assembler Callable Services Reference*
- *User's Guide*

### **z/OS XL C/C++**

- *Programming Guide*
- *Run-Time Library Reference*

## **CICS Transaction Server for z/OS**

You can find the following publications in the [CICS library](#):

- *Developing CICS Applications*
- *API (EXEC CICS) Reference*
- *Developing CICS System Programs*
- *Global User Exit Reference*
- *XPI Reference*
- *Using EXCI with CICS*

## **COBOL Report Writer Precompiler**

- *Programmer's Manual*, SC26-4301
- *Installation and Operation*, SC26-4302

## **DB2 for z/OS**

You can find the following publications in the [DB2 Library](#):

- *Application Programming and SQL Guide*
- *Command Reference*
- *SQL Reference*

## **IBM Debug for z/OS (formerly IBM Debug for z Systems and IBM Debug Tool for z/OS)**

You can find information about IBM Debug for z/OS in the [IBM Debug for z/OS Library](#).

IBM Debug for z/OS supersedes IBM Debug for z Systems® and IBM Debug Tool for z/OS. Not all references to IBM Debug for z Systems and IBM Debug Tool for z/OS have been changed in the COBOL documentation library. It is recommended that you upgrade your debugger to the latest level in order to have the full range of debugging features available. In some cases, you must upgrade your debugger to a certain version depending on what level of Enterprise COBOL you are using to create the COBOL application:

- IBM Debug Tool V13.1 supports Enterprise COBOL V5.1 and earlier versions
- IBM Debug for z Systems V14.0 supports Enterprise COBOL V6.1 and earlier versions

To find out which IBM debug product best suits your needs, see [https://www.ibm.com/support/knowledgecenter/SSQ2R2\\_14.2.0/com.ibm.debug.cg.doc/common/dcompo.html?sc=SSQ2R2\\_latest](https://www.ibm.com/support/knowledgecenter/SSQ2R2_14.2.0/com.ibm.debug.cg.doc/common/dcompo.html?sc=SSQ2R2_latest).

## **IMS**

- *Application Programming API Reference*, SC18-9699
- *Application Programming Guide*, SC18-9698

## **WebSphere Application Server for z/OS**

- *Applications*, SA22-7959

## **Softcopy publications for z/OS**

The following collection kit contains z/OS and related product publications:

- *z/OS CD Collection Kit*, SK3T-4269

## **Java**

- *IBM SDK for Java - Tools Documentation*, [publib.boulder.ibm.com/infocenter/javasdk/tools/index.jsp](http://publib.boulder.ibm.com/infocenter/javasdk/tools/index.jsp)

- *The Java 2 Enterprise Edition Developer's Guide*, [download.oracle.com/javase/1.2.1/devguide/html/DevGuideTOC.html](http://download.oracle.com/javase/1.2.1/devguide/html/DevGuideTOC.html)
- *Java 2 on z/OS*, [www.ibm.com/servers/eserver/zseries/software/java/](http://www.ibm.com/servers/eserver/zseries/software/java/)
- *The Java EE 5 Tutorial*, [download.oracle.com/javase/5/tutorial/doc/](http://download.oracle.com/javase/5/tutorial/doc/)
- *The Java Language Specification, Third Edition*, by Gosling et al., [java.sun.com/docs/books/jls/](http://java.sun.com/docs/books/jls/)
- *The Java Native Interface*, [download.oracle.com/javase/1.5.0/docs/guide/jni/](http://download.oracle.com/javase/1.5.0/docs/guide/jni/)
- *JDK 5.0 Documentation*, [download.oracle.com/javase/1.5.0/docs/](http://download.oracle.com/javase/1.5.0/docs/)

## Unicode and character representation

- *Unicode*, [www.unicode.org/](http://www.unicode.org/)
- *Character Data Representation Architecture Reference and Registry*, SC09-2190

## XML

- *Extensible Markup Language (XML)*, [www.w3.org/XML/](http://www.w3.org/XML/)
- *Namespaces in XML 1.0*, [www.w3.org/TR/xml-names/](http://www.w3.org/TR/xml-names/)
- *Namespaces in XML 1.1*, [www.w3.org/TR/xml-names11/](http://www.w3.org/TR/xml-names11/)
- *XML specification*, [www.w3.org/TR/xml/](http://www.w3.org/TR/xml/)

# Index

## Special Characters

- [\\_BPX\\_SHAREAS environment variable 439](#)
- [\\_CEE\\_ENVFILE environment variable](#)
  - [description 437](#)
  - [indicating Java settings 278](#)
- [\\_CEE\\_RUNOPTS environment variable](#)
  - [description 437](#)
  - [setting XPLINK 280](#)
  - [specifying runtime options 435](#)
- [\\_IGZ\\_SYSOUT environment variable](#)
  - [setting 437](#)
  - [writing to stdout or stderr 35](#)
- [-# cob2 option for displaying compile and link steps 270](#)
- [-b cob2 option](#)
  - [for creating DLLs 268](#)
  - [for passing information to the linker 269](#)
- [-c cob2 option for compiling but not linking 269](#)
- [-comprc\\_ok cob2 option for controlling compiler based on return code 269](#)
- [-e cob2 option for specifying entry point 269](#)
- [-g cob2 option equivalent to specifying TEST 269](#)
- [-I cob2 option for searching copybooks 269](#)
- [-l cob2 option for specifying archive library name 270](#)
- [-L cob2 option for specifying archive library path 270](#)
- [-o cob2 option for specifying output file 270](#)
- [-q cob2 option for specifying compiler options 270](#)
- [-v cob2 option for displaying and executing compile and link steps 270](#)
- [! character, hexadecimal values 526](#)
- [.a suffix with cob2 270](#)
- [.adt file 288](#)
- [.adt suffix with cob2 271](#)
- [.cbl suffix with cob2 270](#)
- [.dek suffix with cob2 271](#)
- [.lst suffix with cob2 271](#)
- [.o suffix with cob2 270, 271](#)
- [.x suffix with cob2 270, 271](#)
- [\[ character, hexadecimal values 526](#)
- [\] character, hexadecimal values 526](#)
- [\\*CBL statement 357](#)
- [\\*CONTROL statement 357](#)
- [# character, hexadecimal values 526](#)
- [| character, hexadecimal values 526](#)

## Numerics

- [16 MB line](#)
  - [CICS programs 408](#)
  - [IMS programs 408](#)
  - [performance options 641](#)
- [24-bit addressing mode 37](#)
- [31-bit addressing mode](#)
  - [dynamic call 454](#)
- [64-bit addressing](#)
  - [no support 37](#)
- [85 COBOL Standard](#)

- [85 COBOL Standard \(continued\)](#)
  - [checkpoints 619](#)
  - [required compiler options 286](#)
  - [required runtime options 286](#)

## A

- [a suffix with cob2 270](#)
- [a.out file from cob2 271](#)
- [abends, compile-time 304](#)
- [ACCEPT statement](#)
  - [assigning input 33](#)
  - [reading from stdin 33](#)
  - [under CICS 409](#)
- [access JCL parameters](#)
  - [CEE3PR2 825](#)
  - [coding 825](#)
  - [LINKAGE SECTION 825](#)
- [access method services](#)
  - [build alternate indexes in advance 195](#)
  - [defining VSAM data sets to z/OS 190](#)
  - [loading a VSAM data set 184](#)
- [accessibility](#)
  - [of Enterprise COBOL for z/OS 827](#)
  - [of this information 827](#)
  - [using z/OS 827](#)
- [accessibility features for this product 827](#)
- [ADATA compiler option 288](#)
- [adding records](#)
  - [to line-sequential files 203](#)
  - [to QSAM files 161](#)
  - [to VSAM files 186](#)
- [ADDRESS OF special register](#)
  - [use in CALL statement 466](#)
- [addresses](#)
  - [incrementing 472](#)
  - [NULL value 471](#)
  - [passing between programs 471](#)
  - [passing entry-point addresses 461](#)
- [addressing mode, definition 37](#)
- [ADEXIT suboption of EXIT option](#)
  - [processing of 690](#)
  - [syntax 306](#)
- [ADMODE attribute](#)
  - [with multithreading 497](#)
- [adt suffix with cob2 271](#)
- [ADV compiler option 288](#)
- [AFP compiler option](#)
  - [performance considerations 640](#)
- [AIXBLD runtime option](#)
  - [effect on performance 644](#)
- [ALL subscript](#)
  - [examples 86](#)
  - [processing table elements iteratively 86](#)
  - [table elements as function arguments 55](#)
- [ALL31 runtime option](#)

- ALL31 runtime option (*continued*)
  - multioption interaction [38](#)
  - OFF for AMODE switching [454](#)
- ALLOCATE command (TSO)
  - compiler data sets [244](#)
  - with z/OS UNIX files [244](#)
- allocation of files
  - description [148](#)
  - line-sequential [200](#)
  - QSAM [164](#)
  - under TSO [244](#)
  - VSAM [192](#)
- ALPHABET clause, establishing collating sequence with [6](#)
- alphabetic data
  - comparing to national [142](#)
  - MOVE statement with [30](#)
- alphanumeric comparison [93](#)
- alphanumeric data
  - comparing
    - effect of ZWB [355](#)
    - to national [142](#)
  - converting
    - to DBCS with IGZCA2D [665](#)
    - to national with MOVE [131](#)
    - to national with NATIONAL-OF [132](#)
  - MOVE statement with [30](#)
  - with double-byte characters [665](#)
- alphanumeric group item
  - a group without GROUP-USAGE NATIONAL [23](#)
  - definition [22](#)
- alphanumeric literals
  - conversion of mixed DBCS/EBCDIC [665](#)
  - description [23](#)
  - with DBCS content [143](#)
  - with double-byte characters [665](#)
- alphanumeric-edited data
  - initializing
    - example [27](#)
    - using INITIALIZE [72](#)
  - MOVE statement with [30](#)
- alternate collating sequence
  - choosing [214](#)
  - example [7](#)
- alternate entry point, calling [464](#)
- alternate index
  - creating [190](#)
  - example of [191](#)
  - password for [189](#)
  - path [191](#)
  - performance considerations [196](#)
  - using [177](#)
- ALTERNATE RECORD KEY clause
  - identify alternate indexes [191](#)
  - identifying alternate keys in KSDS files [177](#)
- alternate reserved-word
  - table
    - CICS [414](#)
    - specifying [349](#)
- AMODE
  - and DLLs [485](#)
  - description [37](#)
  - of EXIT modules [684](#)
  - switching
    - AMODE (*continued*)
      - switching (*continued*)
        - ALL31(OFF) [454](#)
        - examples [454](#)
        - overview [454](#)
- AMODE [64](#)
  - considerations [443–445](#)
- AMP parameter [193](#)
- ANNUITY intrinsic function [58](#)
- APIs, UNIX and POSIX
  - calling [438](#)
- APOST compiler option [289](#)
- APPLY WRITE-ONLY clause [10](#)
- ARCH compiler option
  - performance considerations [640](#)
- arguments
  - describing in calling program [468](#)
  - from main program
    - accessing in z/OS [478](#)
    - accessing in z/OS UNIX [440](#)
  - passing BY VALUE [468](#)
  - specifying OMITTED [469](#)
  - testing for OMITTED arguments [469](#)
- ARITH compiler option
  - description [291](#)
  - performance considerations [640](#)
- arithmetic
  - COMPUTE statement simpler to code [53](#)
  - error handling [224](#)
  - with intrinsic functions [54](#)
- arithmetic comparisons [60](#)
- arithmetic evaluation
  - conversions and precision [50](#)
  - data format conversion [49](#)
  - examples [59](#), [61](#)
  - fixed-point contrasted with floating-point [59](#)
  - intermediate results [655](#)
  - performance tips [634](#)
  - precedence [54](#), [656](#)
  - precision [655](#)
- arithmetic expression
  - as reference modifier [109](#)
  - description of [54](#)
  - in nonarithmetic statement [663](#)
  - in parentheses [54](#)
- arrays
  - COBOL [37](#)
  - Java
    - declaring [606](#)
    - manipulating [608](#)
- ASCII
  - alphabet, QSAM [171](#)
  - code pages supported in XML documents [522](#)
  - converting to EBCDIC [114](#)
  - job control language (JCL) [171](#)
  - record formats, QSAM [171](#)
  - tape files, QSAM [171](#)
- ASCII files
  - CODE-SET clause [13](#)
  - OPTCD= parameter in DCB [13](#)
- assembler
  - expansion of PROCEDURE DIVISION [381](#)
  - programs

- assembler (*continued*)
  - programs (*continued*)
    - calls from (in CICS) [409](#)
    - compiling from [246](#)
    - listing of [315](#), [638](#)
    - with multithreading [496](#)
- ASSIGN clause
  - corresponds to ddname [8](#)
  - QSAM files [151](#)
- assigning values [25](#)
- assistive technologies [827](#)
- associated-data file, creating [254](#)
- asynchronous signals with multithreading [497](#)
- AT END (end-of-file) phrase [228](#)
- ATTACH macro [246](#)
- attribute methods [573](#)
- automatic restart [622](#)
- available files
  - QSAM [161](#)
  - VSAM [189](#)
- AWO compiler option
  - APPLY-WRITE ONLY clause performance [10](#)
  - description [292](#)
  - performance considerations [640](#)

## B

- Base class
  - equating to java.lang.Object [566](#)
  - using for java.lang.Object [565](#)
- base cluster name [191](#)
- base locator [376](#), [378](#)
- base locator table [396](#)
- basis libraries [252](#)
- BASIS statement [357](#)
- batch compilation
  - description [258](#)
  - LANGUAGE option
    - example [261](#)
  - precedence of options
    - example [260](#)
    - overview [259](#)
- Bibliography [873](#)
- big-endian, converting to little-endian [124](#)
- binary data [320](#)
- binary data item
  - general description [46](#)
  - intermediate results [660](#)
  - synonyms [44](#)
  - using efficiently [46](#), [635](#)
- binary search
  - description [84](#)
  - example [84](#)
- binder
  - c89 command [267](#)
  - options needed for DLLs [483](#)
  - recommended for DLLs [482](#)
- binding OO applications
  - example [279](#)
  - using JCL or TSO/E [278](#)
- BLANK WHEN ZERO clause
  - coded for numeric data [125](#)
  - example with numeric-edited data [43](#)

- BLOCK CONTAINS clause
  - FILE SECTION entry [12](#)
  - no meaning for VSAM files [179](#)
  - QSAM files [153](#), [158](#), [293](#)
- block size
  - ASCII files [172](#)
  - compiler data sets [250](#)
  - QSAM files
    - fixed-length [152](#)
    - record layout [154](#)
    - using DCB [165](#)
    - variable-length [153](#)
  - system-determined
    - compiler data sets [251](#)
    - QSAM files [158](#), [293](#)
- BLOCK0 compiler option
  - description [293](#)
  - performance considerations [640](#)
- blocking factor, definition [153](#)
- blocking QSAM files
  - using BLOCK CONTAINS clause [158](#)
  - using BLOCK0 [293](#)
- blocking records [158](#)
- BPXBATCH utility
  - calling z/OS UNIX programs [436](#)
  - running OO applications [278](#)
- branch, implicit [97](#)
- buffers
  - best use of [10](#)
  - obtaining for QSAM [170](#)
- BUFSIZE compiler option [294](#)
- BY CONTENT [465](#)
- BY REFERENCE [465](#)
- BY VALUE
  - description [465](#)
  - restrictions [468](#)
  - valid data types [468](#)
- byte order mark not generated [550](#)
- byte-stream files
  - processing with QSAM [170](#)

## C

- C/C++ programs
  - with COBOL DLLs [488](#)
  - with multithreading [496](#)
- c89 command for link step [267](#)
- CALL command (TSO) [244](#)
- CALL identifier
  - always dynamic [454](#)
  - dynamic calls [452](#)
  - making from DLLs [484](#)
  - with NODLL [452](#)
  - with NODYNAM [456](#)
- CALL literal
  - dynamic calls [452](#)
  - static calls [452](#)
  - with DYNAM [452](#)
  - with NODLL [452](#)
  - with NODYNAM [452](#), [456](#)
- CALL statement
  - AMODE processing [454](#)
  - BY CONTENT [465](#)

- CALL statement (*continued*)
  - BY REFERENCE [465](#)
  - BY VALUE
    - description [465](#)
    - restrictions [468](#)
  - CICS restrictions [409](#)
  - effect of EXIT option on registers [684](#)
  - exception condition [233](#)
  - for error handling [233](#)
  - function-pointer [463](#)
  - handling of program-name in [328](#)
  - Language Environment callable services [651](#)
  - overflow condition [233](#)
  - RETURNING [475](#)
  - to alternate entry points [464](#)
  - USING [468](#)
  - with CANCEL [454](#)
  - with DYNAM [305](#)
  - with ON EXCEPTION [233](#)
  - with ON OVERFLOW [18](#), [233](#)
- calls
  - 31-bit addressing mode [454](#)
  - AMODE switching for 24-bit programs [454](#)
  - between COBOL and non-COBOL programs [449](#)
  - between COBOL programs [449](#), [451](#)
  - CICS restrictions [409](#)
  - dynamic
    - example [456](#)
    - making [452](#)
    - performance [456](#)
    - restrictions [453](#)
    - with static calls [456](#)
  - exception condition [233](#)
  - interlanguage [449](#)
  - LINKAGE SECTION [469](#)
  - OMITTED arguments [469](#)
  - overflow condition [233](#)
  - passing arguments [468](#)
  - passing data [465](#)
  - receiving parameters [468](#)
  - recursive [461](#)
  - static
    - example [456](#)
    - making [452](#)
    - performance [456](#)
    - with dynamic calls [456](#)
  - to and from object-oriented programs [461](#)
  - to JNI services [601](#)
  - to Language Environment callable services [651](#)
- CANCEL statement
  - cannot use with DLL linkage [485](#)
  - for subprograms [453](#)
  - handling of program-name in [328](#)
  - with dynamic CALL [453](#)
- case structure, EVALUATE statement for [91](#)
- cataloged procedure
  - JCL for compiling [238](#)
  - to compile (IGYWC) [238](#)
  - to compile and link-edit (IGYWCL) [240](#)
  - to compile, link-edit, run (IGYWCLG) [241](#)
- CBL statement
  - overview [357](#)
  - specifying compiler options [256](#)
- cbl suffix with cob2 [270](#)
- CBLPSHPOP runtime option [415](#)
- CBLQDA runtime option [161](#)
- CCSID
  - conflict in XML documents [529](#), [530](#)
  - definition [123](#)
  - EBCDIC multibyte CCSIDs [296](#)
  - in PARSE statement [508](#)
  - of DB2 string data [422](#)
  - of XML documents [522](#)
  - of XML documents to be parsed [508](#)
  - specifying with CODEPAGE option [295](#)
- chained-list processing
  - example [472](#)
  - overview [471](#)
- changing
  - characters to numbers [113](#)
  - file-name [9](#)
  - title on source listing [5](#)
- CHAR intrinsic function, example [115](#)
- character set, definition [123](#)
- checking for valid data
  - conditional expressions [93](#)
- checkpoint
  - 85 COBOL Standard [619](#)
  - designing [620](#)
  - example of JCL for restart [624](#)
  - messages generated during [622](#)
  - methods [619](#)
  - multiple [619](#), [621](#)
  - overview [619](#)
  - record data set [620](#)
  - restart during DFSORT [221](#)
  - restrictions during sort [620](#)
  - setting [619](#)
  - single
    - disk [621](#)
    - tape [621](#)
  - testing [620](#)
- Chinese GB 18030 data
  - processing [139](#)
- CHKPT keyword [221](#)
- CICS
  - alternate reserved-word table [414](#)
  - calling nested programs [410](#)
  - CICS HANDLE
    - example [415](#)
    - LABEL value [415](#)
  - coding programs to run under
    - calls [409](#)
    - DISPLAY statement [408](#)
    - I/O [408](#)
    - overview [407](#)
    - restrictions [407](#)
    - SORT statement [415](#)
  - command-level interface [407](#)
  - commands and the PROCEDURE DIVISION [407](#)
  - compiling with CICS option [411](#)
  - developing programs for [407](#)
  - DFHCOMMAREA parameter
    - calling nested programs [410](#)
    - calling separately compiled programs [409](#)
  - DFHEIBLK parameter
    - calling nested programs [410](#)
    - calling separately compiled programs [409](#)

- CICS (*continued*)
  - ECI calls and RETURN-CODE special register [410](#)
  - EXIT compiler option and [701](#)
  - in a multithreaded environment [496](#)
  - integrated translator
    - advantages [412](#)
    - calling nested programs [410](#)
    - compiler options for [411](#)
    - overview [412](#)
  - interlanguage communication under [409](#)
  - macro-level interface [407](#)
  - NODYNAM compiler option [409](#)
  - performance
    - overview [633](#)
  - performance considerations [415](#), [644](#)
  - restrictions
    - 16 MB line [408](#)
    - files [5](#)
    - OO programs [407](#), [561](#)
    - OUTDD compiler option [327](#)
    - parsing with validation using FILE [517](#)
    - separate translator [412](#)
    - sorting [222](#)
  - separate translator
    - calling nested programs [410](#)
    - compiler options for [413](#)
    - restrictions [412](#)
    - using [413](#)
  - sorting under
    - change reserved-word table [415](#)
    - overview [221](#)
    - restrictions [222](#)
    - system date, getting [409](#)
- CICS compiler option
  - description [294](#)
  - enables integrated translator [412](#)
  - multioption interaction [287](#)
  - specifying suboptions [294](#), [412](#)
  - using [411](#)
- CISZ (control interval size), performance considerations [196](#), [644](#)
- CKPT keyword [221](#)
- class
  - defining [564](#)
  - definition of [561](#)
  - factory data [591](#)
  - instance data [567](#)
  - instantiating
    - COBOL [585](#)
    - Java [584](#)
  - name
    - external [566](#), [577](#)
    - in a program [565](#)
  - object, obtaining reference with JNI [602](#)
  - user-defined [8](#)
- class condition
  - testing
    - for DBCS [144](#)
    - for Kanji [144](#)
    - for numeric [52](#)
    - overview [93](#)
    - validating data [363](#)
- CLASSPATH environment variable
  - description [437](#)
  - example of setting [278](#)
  - specifying location of Java classes [275](#)
- client
  - defining [576](#)
  - definition of [576](#)
- CLIST for compiling under TSO [245](#)
- CLOSE statement
  - line-sequential files [201](#)
  - QSAM [160](#)
  - VSAM [180](#)
- closing files
  - line-sequential [203](#)
  - multithreading serialization [494](#)
  - QSAM
    - overview [162](#)
    - with multithreading [163](#)
  - VSAM
    - overview [187](#)
    - with multithreading [188](#)
- closing files, automatic
  - line-sequential [203](#)
  - QSAM [162](#)
  - VSAM [187](#)
- cluster, VSAM [190](#)
- cob2 command
  - compiling with
    - examples [268](#)
    - overview [267](#)
  - description [269](#)
  - for compiling OO applications [273](#)
  - for creating DLLs [268](#)
  - for linking OO applications [274](#)
  - input and output [270](#)
  - linking with
    - examples [268](#)
    - overview [267](#)
    - options and syntax [269](#)
- COBJVMINITOPTIONS environment variable
  - description [437](#)
  - specifying JVM options [276](#)
- COBOL
  - and Java
    - binding [278](#)
    - communicating between [601](#)
    - compatibility [281](#)
    - compiling under z/OS UNIX [273](#)
    - compiling using JCL or TSO/E [277](#)
    - linking [274](#)
    - running [275](#), [278](#)
    - structuring applications [598](#)
    - under IMS [431](#)
  - object-oriented
    - binding [278](#)
    - compiling under z/OS UNIX [273](#)
    - compiling using JCL or TSO/E [277](#)
    - linking [274](#)
    - running [275](#)
    - under IMS [431](#)
- COBOL client
  - example [593](#)
  - example of passing object references [582](#)
- COBOL DLL programs, calling [486](#)

- COBOL terms [21](#)
- COBOL3 translator option [413](#)
- COBOPT environment variable [265](#)
- code
  - copy [647](#)
  - optimized [638](#)
- code page
  - conflict in XML documents [529](#), [530](#)
  - DBCS [296](#)
  - definition [123](#)
  - euro currency support [62](#)
  - hexadecimal values of special characters [526](#)
  - of DB2 string data [422](#)
  - overriding [133](#)
  - specifying [295](#)
  - specifying for alphanumeric XML document [525](#)
- code point, definition [123](#)
- CODE-SET clause [13](#)
- coded character set
  - definition [123](#)
  - in XML documents [522](#)
- CODEPAGE compiler option
  - DBCS code pages [296](#)
  - description [295](#)
  - for national literals [131](#)
  - items that are not affected [296](#)
  - operations that override [296](#)
- coding
  - class definition [564](#)
  - clients [576](#)
  - condition tests [94](#)
  - constructor methods [591](#)
  - DATA DIVISION [10](#)
  - decisions [89](#)
  - efficiently [633](#)
  - ENVIRONMENT DIVISION [5](#)
  - errors, avoiding [633](#)
  - EVALUATE statement [91](#)
  - factory definition [590](#)
  - factory methods [591](#)
  - file input/output (overview) [145](#)
  - IDENTIFICATION DIVISION [3](#)
  - IF statement [89](#)
  - input/output overview [147](#)
  - input/output statements
    - for line-sequential files [201](#)
    - for QSAM files [160](#)
    - for VSAM files [180](#)
  - instance methods [568](#), [588](#)
  - interoperable data types with Java [606](#)
  - loops [96](#)
  - OO programs
    - must be reentrant [464](#)
    - overview [561](#)
  - PROCEDURE DIVISION [16](#)
  - programs to run under CICS
    - calls [409](#)
    - DISPLAY statement [408](#)
    - I/O [408](#)
    - must be reentrant [464](#)
    - overview [407](#)
    - restrictions [407](#)
    - SORT statement [415](#)
    - system date, getting [409](#)

- coding (*continued*)
  - programs to run under DB2
    - CCSID of string data [422](#)
    - overview [417](#)
    - stored procedures must be reentrant [464](#)
  - programs to run under IMS
    - must be reentrant [464](#)
    - overview [427](#)
    - restrictions [427](#)
  - simplifying [647](#)
  - SQL statements
    - overview [418](#)
    - restriction [418](#)
  - SQLIMS statements
    - overview [428](#)
  - subclasses
    - example [589](#)
    - overview [586](#)
  - tables [65](#)
  - techniques [10](#), [633](#)
  - test conditions [94](#)
- collating sequence
  - alternate
    - choosing [214](#)
    - example [7](#)
  - ASCII [7](#)
  - binary for national keys [213](#)
  - EBCDIC [7](#)
  - HIGH-VALUE [6](#)
  - ISO 7-bit code [7](#)
  - LOW-VALUE [6](#)
  - MERGE [6](#), [214](#)
  - NATIVE [7](#)
  - nonnumeric comparisons [6](#)
  - ordinal position of a character [115](#)
  - SEARCH ALL [6](#)
  - SORT [6](#), [214](#)
  - specifying [6](#)
  - STANDARD-1 [7](#)
  - STANDARD-2 [7](#)
  - symbolic characters in the [8](#)
- COLLATING SEQUENCE phrase
  - does not apply to national keys [213](#)
  - overrides PROGRAM COLLATING SEQUENCE clause [6](#), [214](#)
  - use in SORT or MERGE [214](#)
- columns in tables [65](#)
- comment lines [839](#)
- comments [839](#)
- COMMON attribute [4](#), [458](#)
- COMP (COMPUTATIONAL) [46](#)
- COMP-1 (COMPUTATIONAL-1)
  - format [47](#)
  - performance tips [635](#)
- COMP-2 (COMPUTATIONAL-2)
  - format [47](#)
  - performance tips [635](#)
- COMP-3 (COMPUTATIONAL-3) [47](#)
- COMP-4 (COMPUTATIONAL-4) [46](#)
- COMP-5 (COMPUTATIONAL-5) [46](#)
- comparing data items
  - national
    - overview [140](#)
    - to alphabetic, alphanumeric, or DBCS [142](#)

- comparing data items (*continued*)
  - national (*continued*)
    - to alphanumeric groups [142](#)
    - to numeric [141](#)
    - two operands [140](#)
  - object references [579](#)
  - zoned decimal and alphanumeric, effect of ZWB [355](#)
- compatibility
  - Java and COBOL [281](#)
  - object-oriented syntax [281](#)
- compatibility mode [41](#), [655](#)
- compilation
  - conformance to 85 COBOL Standard [286](#)
  - results [257](#)
  - with z/OS UNIX files [239](#)
- compilation statistics [374](#)
- COMPILE compiler option
  - description [297](#)
  - use NOCOMPILE to find syntax errors [365](#)
- compile-time considerations
  - compiler-directed errors [262](#)
  - display compile and link steps [270](#)
  - dump, generating a [304](#)
  - error messages
    - determining what severity level to produce [308](#)
    - severity levels [263](#)
  - executing compile and link steps after display [270](#)
- compiler
  - calculation of intermediate results [656](#)
  - environment variables under z/OS UNIX [265](#)
  - generating list of error messages [262](#)
  - invoking in the z/OS UNIX
    - shell
      - examples [268](#)
      - overview [267](#)
  - limits
    - DATA DIVISION [10](#)
  - messages
    - choosing severity to be flagged [367](#)
    - customizing [693](#)
    - determining what severity level to produce [308](#)
    - embedding in source listing [367](#)
    - from exit modules [700](#)
    - sending to terminal [253](#)
    - severity levels [263](#), [694](#)
  - return code
    - depends on highest severity [264](#)
    - effect of message customization [695](#)
    - overview [263](#)
- compiler data sets
  - in the z/OS UNIX file system [238](#), [243](#)
  - input and output [248](#)
  - required for compilation [248](#)
  - SYSADATA (ADATA records) [254](#)
  - SYSIN [251](#)
  - SYSJAVA [254](#)
  - SYSLIB (libraries) [252](#)
  - SYSLIN (object code) [253](#)
  - SYSMDECK (library processing) [254](#)
  - SYSOPTF [252](#)
  - SYSOUT (listing) [253](#)
  - SYSPUNCH (object code) [253](#)
  - SYSTEM (messages) [253](#)

- compiler data sets (*continued*)
  - with cob2 [270](#)
- compiler listings
  - getting [370](#)
- compiler options
  - 85 COBOL Standard conformance [286](#)
  - abbreviations [283](#)
  - ADATA [288](#)
  - ADV [288](#)
  - AFP
    - performance considerations [640](#)
  - APOST [289](#)
  - ARCH
    - performance considerations [640](#)
  - ARITH
    - description [291](#)
    - performance considerations [640](#)
  - AWO
    - description [292](#)
    - performance considerations [640](#)
  - BLOCK0
    - description [293](#)
    - performance considerations [640](#)
  - BUFSIZE [294](#)
  - CICS [294](#)
  - CODEPAGE [295](#)
  - COMPILE [297](#)
  - conflicting [287](#)
  - COPYLOC [298](#)
  - COPYRIGHT [299](#)
  - CURRENCY [299](#)
  - DATA [300](#)
  - DBCS [301](#)
  - DECK [301](#)
  - DIAGTRUNC [302](#)
  - DISPSIGN [302](#)
  - DLL [303](#)
  - DUMP [304](#)
  - DYNAM [305](#), [641](#)
  - EXIT [305](#)
  - EXPORTALL [307](#)
  - FASTSRT
    - performance considerations [641](#)
  - FLAG [308](#), [367](#)
  - FLAGSTD [309](#)
  - for CICS integrated translator [411](#)
  - for CICS separate translator [411](#), [413](#)
  - for debugging
    - overview [365](#)
    - TEST restriction [364](#)
    - THREAD restriction [364](#)
  - HGPR
    - performance considerations [641](#)
  - IMS, recommended for [430](#)
  - in effect [382](#)
  - INITCHECK [311](#)
  - INLINE
    - performance considerations [641](#)
  - INTDATE [313](#)
  - LANGUAGE
    - description [313](#)
    - example in batch compilation [261](#)
  - LINECOUNT [314](#)
  - LIST [315](#), [370](#)

compiler options (*continued*)

- MAP [316, 369, 370](#)
- MAXPCF [317](#)
- MAXPCF(nnn)
  - performance considerations [641](#)
- MDECK [318](#)
- NAME [319](#)
- NOCOMPILE [365](#)
- NOFASTSRT [218](#)
- NSYMBOL [319](#)
- NUMBER [320, 372](#)
- NUMCHECK [320](#)
- NUMPROC [322](#)
- NUMPROC(PFD)
  - performance considerations [642](#)
- NUMPROC(PFD|NOPFD) [51](#)
- OBJECT [323](#)
- OFFSET [324](#)
- on compiler invocation [374](#)
- OPTFILE [324](#)
- OPTIMIZE
  - description [325](#)
  - performance considerations [638, 642](#)
- OUTDD [326](#)
- PARMCHECK [327](#)
- performance considerations [640](#)
- PGMNAME [328](#)
- precedence of
  - example [260](#)
  - in batch [259](#)
  - in SYSOPTF data sets [252, 325](#)
  - under z/OS [255](#)
  - under z/OS UNIX [266](#)
- QUALIFY [330](#)
- QUOTE [289](#)
- RENT
  - description [330](#)
  - performance considerations [642](#)
- RMODE
  - description [331](#)
  - performance considerations [642](#)
- RULES [332](#)
- SEQUENCE [333](#)
- SERVICE [334](#)
- signature information bytes [382](#)
- SOURCE [334, 370](#)
- SPACE [335](#)
- specifying
  - using PROCESS (CBL) [256](#)
- specifying under TSO [256](#)
- specifying under z/OS [256](#)
- specifying under z/OS UNIX [266](#)
- specifying with SYSOPTF data set [252](#)
- SQL
  - description [335](#)
  - using with DB2 [421](#)
- SQLCCSID
  - description [336](#)
  - effect on CCSID of string data [422](#)
  - performance considerations [424](#)
  - recommended with DB2 coprocessor [423](#)
- SQLIMS [337](#)
- SSRANGE
  - performance considerations [642](#)

compiler options (*continued*)

- status [374](#)
- STGOPT [339](#)
- SUPPRESS [340](#)
- table of [283](#)
- TERMINAL [340](#)
- TEST
  - description [340](#)
  - performance considerations [642](#)
  - use for debugging [370](#)
- THREAD
  - debugging restriction [364](#)
  - description [343](#)
  - performance considerations [642](#)
- TRUNC
  - description [344](#)
  - performance considerations [643](#)
- under IMS and CICS [408](#)
- VBREF [347, 370](#)
- VLR
  - description [347](#)
- VSAMOPENFS [349](#)
- WORD [349](#)
- XMLPARSE [350](#)
- XREF [350, 369](#)
- ZONECHECK [352](#)
- ZONEDATA [353](#)
- ZWB [355](#)
- Compiler options
  - listing example [392](#)
- compiler-directing statements
  - description [357](#)
  - overview [19](#)
- compiling
  - AMODE 64 programs [443–445](#)
  - batch [258](#)
  - control of [255](#)
  - data sets for [248](#)
  - DLLs [268](#)
  - from an assembler program [246](#)
  - OO applications
    - cob2 command [273](#)
    - example [275, 279](#)
    - under z/OS UNIX [273](#)
    - using JCL or TSO/E [277](#)
  - under TSO
    - example CLIST [245](#)
    - overview [244](#)
  - under z/OS [237](#)
  - under z/OS UNIX [265](#)
  - using shell script [271](#)
  - using the cob2 command
    - examples [268](#)
    - overview [267](#)
  - with cataloged procedures
    - compile [238](#)
    - compile and link-edit [240](#)
    - compile, link-edit, run [241](#)
    - with JCL (job control language) [237](#)
- compiling and linking in the z/OS UNIX shell
  - DLLs [268](#)
  - examples [268](#)
  - OO applications

- compiling and linking in the z/OS UNIX shell (*continued*)
  - OO applications (*continued*)
    - cob2 command [274](#)
    - example [275](#)
    - overview [267](#)
- completion code
  - merge [215](#)
  - sort [215](#)
- complex OCCURS DEPENDING ON
  - basic forms of [79](#)
  - complex ODO item [79](#)
  - variably located data item [80](#)
  - variably located group [80](#)
- computation
  - arithmetic data items [635](#)
  - of indexes [70](#)
  - of subscripts [637](#)
- COMPUTATIONAL (COMP) [46](#)
- COMPUTATIONAL-1 (COMP-1)
  - format [47](#)
  - performance tips [635](#)
- COMPUTATIONAL-2 (COMP-2)
  - format [47](#)
  - performance tips [635](#)
- COMPUTATIONAL-3 (COMP-3)
  - description [47](#)
- COMPUTATIONAL-4 (COMP-4) [46](#)
- COMPUTATIONAL-5 (COMP-5) [46](#)
- COMPUTE statement
  - assigning arithmetic results [32](#)
  - simpler to code [53](#)
- computer, describing [5](#)
- concatenating data items (STRING) [101](#)
- condition handling
  - closing QSAM files [162](#)
  - closing VSAM files [187](#)
  - in input or output procedures [211](#)
  - using Language Environment [649](#)
- condition testing [94](#)
- conditional expression
  - EVALUATE statement [89](#)
  - IF statement [89](#)
  - PERFORM statement [98](#)
- conditional statement
  - overview [18](#)
  - with NOT phrase [18](#)
  - with object references [579](#)
- CONFIGURATION SECTION [5](#)
- conflicting compiler options [287](#)
- conformance requirements
  - 85 COBOL Standard [286](#)
  - example of passing object references in INVOKE [582](#)
  - RETURNING phrase of INVOKE [583](#)
  - USING phrase of INVOKE [581](#)
- considerations
  - for AMODE 64 [443–445](#)
- Constant area [395](#)
- constants
  - data items [634](#)
  - definition [24](#)
  - figurative, definition [24](#)
- contained program integration [639](#)
- CONTENT-CHARACTERS XML event
  - example [542](#)
- CONTENT-CHARACTERS XML event (*continued*)
  - when parsing segments [520](#)
- continuation
  - entry [220](#)
  - of program [225](#)
  - syntax checking [298](#)
- CONTINUE statement [89](#)
- control
  - in nested programs [458](#)
  - program flow [89](#)
  - transfer [449](#)
- control interval size (CISZ), performance considerations [196, 644](#)
- CONTROL statement [357](#)
- converting data items
  - between code pages [114](#)
  - between data formats [49](#)
  - exceptions with national data [133](#)
  - precision [50](#)
  - reversing order of characters [112](#)
  - to alphanumeric
    - with DISPLAY [34](#)
    - with DISPLAY-OF [133](#)
  - to Chinese GB 18030 from national [139](#)
  - to integers with INTEGER, INTEGER-PART [110](#)
  - to national
    - from Chinese GB 18030 [139](#)
    - from UTF-8 [134](#)
    - with ACCEPT [33](#)
    - with MOVE [131](#)
    - with NATIONAL-OF [132](#)
  - to numbers with NUMVAL, NUMVAL-C [113](#)
  - to uppercase or lowercase
    - with INSPECT [111](#)
    - with intrinsic functions [112](#)
  - to UTF-8 from national [134](#)
  - with INSPECT [110](#)
  - with intrinsic functions [111](#)
- CONVERTING phrase (INSPECT), example [111](#)
- coprocessor, DB2
  - CCSID determination of string data [422](#)
  - differences from the precompiler [424](#)
  - enable with SQL compiler option [421](#)
  - overview [417](#)
  - recommended compiler option SQLCCSID [423](#)
  - using SQL INCLUDE with [418](#)
- coprocessor, IMS
  - enable with SQLIMS compiler option [429](#)
  - overview [427](#)
- copy libraries
  - COPY statement [357](#)
  - data set [248](#)
  - example [648](#)
  - search order [358](#)
  - specifying [252](#)
  - SYSLIB [252](#)
  - z/OS UNIX search order [265, 269](#)
- COPY statement
  - description [357](#)
  - example [648](#)
  - nested [647, 686](#)
  - z/OS considerations [252](#)

- COPY statement (*continued*)
  - z/OS UNIX considerations [358](#)
- copybook
  - description [357](#)
  - obtaining from user-supplied module [306](#)
  - searching for [269](#), [358](#)
- copybook cross-reference, description [369](#)
- copybooks
  - cross-reference [400](#)
  - using [647](#)
- COPYLOC compiler option [298](#)
- COPYRIGHT compiler option [299](#)
- COUNT IN phrase
  - UNSTRING [103](#)
  - XML GENERATE [551](#)
- counting
  - characters (INSPECT) [110](#)
  - generated XML characters [546](#)
- creating
  - associated-data file [254](#)
  - library-processing output file [254](#)
  - line-sequential files in z/OS [200](#)
  - object code [253](#)
  - objects [584](#)
  - QSAM files, z/OS [164](#), [166](#)
  - SYSJAVA file [254](#)
  - variable-length tables [76](#)
- cross-reference
  - COPY/BASIS [400](#)
  - COPY/BASIS statements [370](#)
  - copybooks [370](#)
  - data and procedure-names [369](#)
  - embedded [370](#)
  - list [350](#)
  - program-name [399](#)
  - special definition symbols [401](#)
  - statement list [347](#)
  - statements [370](#)
  - text-names and data sets [369](#)
- CRP (file position indicator) [182](#), [185](#)
- CURRENCY compiler option [299](#)
- currency signs
  - euro [62](#)
  - hexadecimal literals [62](#)
  - multiple-character [62](#)
  - using [61](#)
- CURRENT-DATE intrinsic function
  - example [58](#)
  - under CICS [409](#)
- customer support [xxviii](#), [873](#)

## D

- D-format record
  - layout [154](#)
  - requesting [153](#)
- DASD (direct-access storage device) [196](#)
- data
  - concatenating (STRING) [101](#)
  - converting between alphanumeric and DBCS [665](#)
  - efficient execution [633](#)
  - format conversion of [49](#)
  - format, numeric types [44](#)

- data (*continued*)
  - grouping [470](#)
  - incompatible [51](#)
  - naming [12](#)
  - numeric [41](#)
  - passing [465](#)
  - record size [12](#)
  - splitting (UNSTRING) [103](#)
  - validating [51](#)
- data and procedure-name cross-reference, description [369](#)
- data areas, dynamic [305](#)
- DATA compiler option
  - description [300](#)
  - influencing data location [39](#)
  - multioption interaction [37](#)
  - performance considerations [641](#)
  - when passing data [39](#)
- data compression [627](#)
- data definition [376](#)
- data description entry [11](#)
- DATA DIVISION
  - client [578](#)
  - coding [10](#)
  - description [10](#)
  - entries for line-sequential files [200](#)
  - entries for QSAM files [152](#)
  - entries for VSAM files [179](#)
  - factory data [591](#)
  - factory method [592](#)
  - FD entry [10](#)
  - FILE SECTION [10](#)
  - GROUP-USAGE NATIONAL clause [66](#)
  - instance data [567](#), [588](#)
  - instance method [570](#)
  - items present in [382](#)
  - limits [10](#)
  - LINKAGE SECTION [10](#), [15](#)
  - listing [370](#)
  - LOCAL-STORAGE SECTION [10](#)
  - mapping of items [316](#), [370](#)
  - OCCURS clause [65](#)
  - OCCURS DEPENDING ON (ODO) clause [76](#)
  - REDEFINES clause [73](#)
  - restrictions [10](#)
  - signature information bytes [382](#)
  - USAGE clause at the group level [23](#)
  - USAGE IS INDEX clause [70](#)
  - USAGE NATIONAL clause at the group level [128](#)
  - WORKING-STORAGE SECTION [10](#)
- data item
  - alphanumeric with double-byte characters [665](#)
  - coding Java types [605](#)
  - common, in subprogram linkage [468](#)
  - concatenating (STRING) [101](#)
  - converting characters (INSPECT) [110](#)
  - converting characters to numbers [113](#)
  - converting to uppercase or lowercase [112](#)
  - converting with intrinsic functions [111](#)
  - counting characters (INSPECT) [110](#)
  - DBCS [665](#)
  - elementary, definition [22](#)
  - evaluating with intrinsic functions [114](#)
  - finding the smallest or largest item [115](#)
  - group, definition [22](#)

- data item (*continued*)
  - index, referring to table elements with [68](#)
  - initializing, examples of [26](#)
  - map [257](#)
  - numeric [41](#)
  - reference modification [107](#)
  - referring to a substring [107](#)
  - replacing characters (INSPECT) [110](#)
  - reversing characters [112](#)
  - splitting (UNSTRING) [103](#)
  - unused [325](#), [376](#)
  - variably located [80](#)
- data manipulation
  - character data [101](#)
  - DBCS data [665](#)
- DATA RECORDS clause [12](#)
- data set
  - alternate data-set names [246](#)
  - checkpoint record [620](#)
  - compiler-option [252](#)
  - defining with environment variable [148](#)
  - example of checkpoint/restart [624](#)
  - file, same meaning as [5](#)
  - JAVAERR [278](#)
  - JAVAIN [278](#)
  - JAVAOUT [278](#)
  - names, alternate [246](#)
  - output [253](#)
  - source code [251](#)
  - SYSADATA [254](#)
  - SYSIN [251](#)
  - SYSJAVA [254](#)
  - SYSLIB [252](#)
  - SYSLIN [253](#)
  - SYSMDECK [254](#)
  - SYSOPTF [252](#)
  - SYSPRINT [253](#)
  - SYSPUNCH [253](#)
  - SYSTEM [253](#)
- data sets used for compiling [248](#)
- data-definition attribute codes [376](#)
- data-name
  - cross-reference [398](#)
  - cross-reference list [257](#)
  - in MAP listing [376](#)
  - OMITTED [12](#)
  - password for VSAM files [188](#)
- date and time operations
  - Language Environment callable services [649](#)
- date operations
  - finding date of compilation [118](#)
- DATE-COMPILED paragraph [3](#)
- DATE-OF-INTEGER intrinsic function [58](#)
- DB2
  - coding considerations [417](#)
  - coprocessor
    - CCSID determination of string data [422](#)
    - database request module (DBRM) [417](#), [421](#)
    - differences from the precompiler [424](#)
    - enable with SQL compiler option [421](#)
    - overview [417](#)
    - recommended compiler option SQLCCSID [423](#)
    - using SQL INCLUDE with [418](#)
  - DYNAM compiler option with TSO or IMS [426](#)
  - DB2 (*continued*)
    - NODYNAM compiler option with CICS or CAF [426](#)
    - precompiler
      - differences from the coprocessor [424](#)
      - recommended compiler option NOSQLCCSID [423](#)
      - specifying code page for host variables [419](#)
    - SQL compiler option [421](#)
    - SQL statements
      - CCSID determination [422](#)
      - coding [418](#)
      - overview [417](#)
      - return codes [421](#)
      - SQL DECLARE [419](#)
      - SQL INCLUDE [418](#)
      - using binary data in [420](#)
      - using character data in [419](#)
      - using national decimal data [420](#)
    - SQLCCSID compiler option [422](#)
  - DBCS comparison [93](#)
  - DBCS compiler option
    - description [301](#)
    - for Java interoperability [273](#), [277](#)
    - for OO COBOL [273](#), [277](#)
    - multioption interaction [287](#)
  - DBCS data
    - comparing
      - to national [142](#)
    - converting
      - to alphanumeric with IGZCD2A [667](#)
      - to and from alphanumeric [665](#)
      - to national, overview [144](#)
    - declaring [143](#)
    - encoding and storage [131](#)
    - literals
      - description [24](#)
      - maximum length [143](#)
      - using [143](#)
    - MOVE statement with [30](#)
    - notation for [665](#)
    - testing for [144](#)
  - DBRM data set
    - defining [421](#)
    - description [417](#)
  - DBRMLIB DD statement [417](#), [421](#)
  - DCB [159](#)
  - DD control statement
    - allocating line-sequential files [200](#)
    - AMP parameter [193](#)
    - ASCII tape files [171](#)
    - creating QSAM files [164](#), [166](#)
    - DBRMLIB [421](#)
    - DCB overrides data-set label [165](#)
    - define file [8](#)
    - defining merge data sets [211](#)
    - defining sort data sets [211](#)
    - JAVAERR [278](#)
    - JAVAIN [278](#)
    - JAVAOUT [278](#)
    - RLS parameter [193](#)
    - SYSADATA [254](#)
    - SYSIN [251](#)
    - SYSJAVA [254](#)
    - SYSLIB [252](#)
    - SYSLIN [253](#)

- DD control statement (*continued*)
  - [SYSMDCK 254](#)
  - [SYSOPTF 252](#)
  - [SYSPRINT 253](#)
  - [SYSPUNCH 253](#)
- ddname definition [8](#)
- deadlock in I/O error declarative [228](#)
- Debug Tool
  - compiler options for [370](#)
  - description [361](#)
- debugging
  - and performance [341](#)
  - compiler options for
    - overview [365](#)
    - TEST restriction [364](#)
    - THREAD restriction [364](#)
  - overview [361](#)
  - runtime options for [364](#)
  - using COBOL language features [361](#)
  - using the debugger [370](#)
- debugging, language features
  - class test [363](#)
  - debugging lines [364](#)
  - debugging statements [364](#)
  - declaratives [363](#)
  - DISPLAY statements [362](#)
  - file status keys [362](#)
  - INITIALIZE statements [363](#)
  - scope terminators [362](#)
  - SET statements [363](#)
  - WITH DEBUGGING MODE clause [364](#)
- DECK compiler option [301](#)
- declarative procedures
  - EXCEPTION/ERROR
    - with multithreading [228](#)
  - USE FOR DEBUGGING [363](#)
- deferred restart [623](#)
- defining
  - files, overview [8](#), [145](#)
  - libraries [252](#)
  - line-sequential files to z/OS [200](#)
  - QSAM files
    - to z/OS [164](#), [166](#)
  - sort or merge files under z/OS [211](#)
  - VSAM files
    - to z/OS [190](#)
- dek suffix with cob2 [271](#)
- DELETE statement
  - compiler-directing [359](#)
  - multithreading serialization [494](#)
  - VSAM, coding [180](#)
- deleting records from VSAM file [187](#)
- delimited scope statement
  - description of [18](#)
  - nested [20](#)
- DEPENDING ON clause [154](#), [180](#)
- depth in tables [67](#)
- device
  - classes [248](#)
  - requirements [248](#)
- DFHCOMMAREA parameter
  - calling nested CICS programs [410](#)
  - calling separately compiled CICS programs [409](#)
- DFHEIBLK parameter
  - calling nested CICS programs [410](#)
  - calling separately compiled CICS programs [409](#)
- DFSORT
  - defining data sets for [211](#)
  - error message for RETURN statement [210](#)
- diagnostics, program [374](#)
- DIAGTRUNC compiler option [302](#)
- direct-access
  - direct indexing [70](#)
  - file organization [146](#)
  - storage device (DASD) [196](#)
- directories
  - adding a path to [269](#)
- disability [827](#)
- DISPLAY (USAGE IS)
  - encoding and storage [131](#)
  - external decimal [45](#)
  - floating point [46](#)
- display floating-point data (USAGE DISPLAY) [45](#)
- DISPLAY statement
  - directing output [326](#)
  - displaying data values [33](#)
  - displaying on the system logical output device [34](#)
  - interaction with OUTDD [34](#)
  - suppressing line spacing [35](#)
  - under CICS [408](#)
  - using in debugging [362](#)
  - writing to stdout or stderr [35](#)
- DISPLAY-1 (USAGE IS)
  - encoding and storage [131](#)
- DISPLAY-OF intrinsic function
  - example with Chinese data [139](#)
  - example with Greek data [133](#)
  - example with UTF-8 data [134](#)
  - using [133](#)
  - with XML documents [523](#)
- DISPSIGN compiler option [302](#)
- DLL compiler option
  - description [303](#)
  - for Java interoperability [273](#), [277](#)
  - for OO COBOL [273](#), [277](#)
  - multioption interaction [287](#)
- DLL igzcjava.x
  - binding with
    - example [279](#)
    - preparing OO applications [278](#)
  - linking with
    - example [275](#)
    - preparing OO applications [274](#)
- DLL libjvm.x
  - binding with
    - example [279](#)
    - preparing OO applications [278](#)
  - linking with
    - example [275](#)
    - preparing OO applications [274](#)
  - with EBCDIC services [612](#)
- DLLs (see dynamic link libraries) [481](#)
- do loop [97](#)
- do-until [98](#)
- do-while [98](#)
- documentation of program [5](#)
- DSA memory map [381](#)

- dump
  - requesting [223](#)
  - with DUMP compiler option [257](#)

- DUMP compiler option
  - description [304](#)
  - output [257](#)

- DYNAM compiler option
  - description [305](#)
  - multioption interaction [287](#)
  - performance considerations [641](#)
  - under DB2 with TSO or IMS [426](#)
  - with dynamic calls [452](#)

- dynamic calls
  - example [456](#)
  - making [452](#)
  - performance [456](#)
  - restrictions [453](#)
  - using with DLL linkage [485](#)
  - when to use [453](#)
  - with static calls [456](#)

- dynamic data areas, allocating storage [39](#)

- dynamic file allocation
  - order of allocation [149](#)
  - using CBLQDA [161](#)
  - using environment variables
    - line-sequential files [200](#)
    - QSAM files [164](#)
    - VSAM files [192](#)

- dynamic link libraries
  - about [481](#)
  - binder options for DLLs [483](#)
  - compiler options required [268](#)
  - compiling [482](#)
  - creating
    - from the z/OS UNIX shell [268](#)
    - overview [481](#)
  - creating for OO [274](#)
  - for Java interoperability [274](#)
  - in OO COBOL applications [488](#)
  - linking [482](#)
  - programs with DLL support must be reentrant [464](#)
  - search order for in z/OS UNIX file system [484](#)
  - using CALL identifier with [484](#)
  - using with C/C++ programs [488](#)
  - using with dynamic calls [485](#)
  - using with Java interoperability [275](#)
  - using with OO [275](#)

## E

- E-level error message [264](#), [367](#)

- EBCDIC
  - code pages supported in XML documents [522](#)
  - converting to ASCII [114](#)
  - JNI services [611](#)
  - multibyte CCSIDs supported for DBCS [296](#)

- ECI calls and RETURN-CODE special register [410](#)

- efficiency of coding [633](#)

- EJECT statement [359](#)

- embedded cross-reference
  - description [370](#)
  - example [401](#)

- embedded error messages [367](#)

- embedded MAP summary [369](#), [377](#)

- enclave [449](#)

- encoding
  - conflicts in XML documents [529](#), [530](#)
  - controlling in generated XML output [550](#)
  - description [131](#)
  - language characters [123](#)
  - of XML documents [522](#), [523](#)
  - of XML documents to be parsed [508](#)
  - specifying for alphanumeric XML document [525](#)
  - specifying with CODEPAGE option [295](#)

- encoding declaration
  - preferable to omit [525](#)
  - specifying [525](#)

- end-of-file (AT END phrase) [228](#)

- END-OF-INPUT XML event
  - example [542](#)
  - when parsing segments [519](#)

- enhancing XML output
  - example of modifying data definitions [556](#)
  - rationale and techniques [555](#)

- ENTER statement [359](#)

- entry point
  - alternate [464](#)
  - alternate in ENTRY statement [462](#)
  - ENTRY label [464](#)
  - passing entry addresses of [461](#)
  - procedure-pointer data item [461](#)

- ENTRY statement
  - for alternate entry points [462](#)
  - handling of program-name in [328](#)

- ENVAR runtime option [278](#)

- ENVIRONMENT DIVISION
  - class [566](#)
  - client [577](#)
  - collating sequence coding [6](#)
  - CONFIGURATION SECTION [5](#)
  - description [5](#)
  - entries for line-sequential files [199](#)
  - entries for QSAM files [151](#)
  - entries for VSAM files [175](#)
  - INPUT-OUTPUT SECTION [5](#)
  - instance method [570](#)
  - items present in, program initialization code [382](#)
  - signature information bytes [382](#)
  - subclass [588](#)

- environment variables
  - \_BPX\_SHAREAS [439](#)
  - \_CEE\_ENVFILE
    - description [437](#)
    - indicating Java settings [278](#)
  - \_CEE\_RUNOPTS
    - description [437](#)
    - setting XPLINK [280](#)
    - specifying runtime options [435](#)
  - \_IGZ\_SYSOUT [437](#)
  - allocating line-sequential files [200](#)
  - and copybooks [357](#)
  - CLASSPATH
    - description [437](#)
    - example of setting [278](#)
    - specifying location of Java classes [275](#)
  - COBJVMINIOPTIONS
    - description [437](#)

- environment variables (*continued*)
  - COBJVMINITOPTIONS (*continued*)
    - specifying JVM options [276](#)
  - COBOPT [265](#)
  - compiler [265](#)
  - defining files, example [8](#)
  - defining QSAM files [164](#)
  - example of setting and accessing [438](#)
  - LIBPATH
    - description [437](#)
    - example of setting [278](#)
    - specifying location for COBOL classes [275](#)
  - library-name [266](#), [357](#)
  - PATH
    - description [437](#)
    - example of setting [278](#)
  - runtime [437](#)
  - setting and accessing [436](#)
  - STEPLIB
    - description [437](#)
    - example [267](#)
  - SYSLIB
    - description [265](#)
    - specifying location of JNI.cpy [273](#)
  - text-name [266](#), [357](#)
  - using to allocate files [148](#)
- environment-name [5](#)
- ERRMSG, for generating list of error messages [262](#)
- error
  - arithmetic [224](#)
  - compiler options, conflicting [287](#)
  - handling [223](#)
  - handling for I/O [149](#)
  - listing [257](#)
  - message table
    - example using indexing [75](#)
    - example using subscripting [74](#)
  - processing
    - line-sequential files [204](#)
    - QSAM files [163](#)
    - VSAM files [188](#)
    - XML GENERATE [550](#)
    - XML PARSE [529](#)
  - routines for handling [234](#)
- error messages
  - compiler
    - choosing severity to be flagged [367](#)
    - correcting source [262](#)
    - customizing [693](#)
    - determining what severity level to produce [308](#)
    - embedding in source listing [367](#)
    - format [263](#)
    - from exit modules [700](#)
    - generating a list of [262](#)
    - location in listing [263](#)
    - sending to terminal [253](#)
    - severity levels [263](#), [694](#)
  - compiler-directed [262](#)
- ESDS (entry-sequenced data sets)
  - file access mode [178](#)
  - organization [176](#)
- euro currency sign [62](#)
- EVALUATE statement
  - case structure [91](#)
- EVALUATE statement (*continued*)
  - coding [91](#)
  - contrasted with nested IFs [92](#)
  - example that tests several conditions [92](#)
  - example with multiple WHEN phrases [92](#)
  - example with THRU phrase [91](#)
  - performance [91](#)
  - structured programming [634](#)
  - testing multiple values, example [95](#), [96](#)
  - use to test multiple conditions [89](#)
- evaluating data item contents
  - class test
    - for numeric [52](#)
    - overview [93](#)
  - INSPECT statement [110](#)
  - intrinsic functions [114](#)
- exception condition
  - CALL [233](#)
  - XML GENERATE [550](#)
  - XML PARSE [529](#)
- exception handling
  - with Java [602](#)
  - with XML GENERATE [550](#)
  - with XML PARSE [527](#)
- EXCEPTION XML event [529](#)
- EXCEPTION/ERROR declarative
  - description [228](#)
  - file status key [230](#)
  - line-sequential error processing [204](#)
  - QSAM error processing [163](#)
  - VSAM error processing [188](#)
- EXEC control statement, RD parameter of [622](#)
- EXIT compiler option
  - considerations for SQL and CICS statements [701](#)
  - description [305](#)
  - MSGEXIT suboption [691](#)
  - register usage [684](#)
  - user-exit work area [683](#)
  - using [305](#)
- exit modules
  - called for SYSADATA data set [690](#)
  - calling COBOL programs [684](#)
  - error messages generated [700](#)
  - message severity customization [691](#)
  - used in place of library-name [685](#)
  - used in place of SYSLIB [685](#)
  - used in place of SYSPRINT [688](#)
- EXIT PROGRAM statement
  - in subprogram [450](#)
  - with multithreading [450](#)
- explicit scope terminator [19](#)
- exponentiation
  - evaluated in fixed-point arithmetic [658](#)
  - evaluated in floating-point arithmetic [662](#)
  - performance tips [636](#)
- EXPORTALL compiler option
  - description [307](#)
  - DLL considerations [482](#)
  - multioption interaction [287](#)
- extended mode [41](#), [655](#)
- external class-name [566](#), [577](#)
- EXTERNAL clause
  - example for files [476](#)
  - for data items [475](#)

EXTERNAL clause (*continued*)

for sharing files [11](#), [475](#)

external data

obtaining storage for [39](#)

sharing [475](#)

storage location of [39](#)

external decimal data

national [45](#)

zoned [45](#)

external file [475](#)

external floating-point data

display [45](#)

national [46](#)

External symbols [397](#)

## F

F-format record

layout [153](#)

requesting [152](#)

factoring expressions [634](#)

factory data

defining [591](#)

definition of [561](#)

making it accessible [591](#)

private [591](#)

factory definition, coding [590](#)

factory methods

defining [591](#)

definition of [561](#)

hiding [592](#)

invoking [593](#)

using to wrap procedural programs [598](#)

FACTORY paragraph

factory data [591](#)

factory methods [591](#)

factory section, defining [590](#)

FASTSORT compiler option

description [308](#)

improving sort performance [216](#), [641](#)

information message [216](#)

requirements

JCL [216](#)

QSAM [217](#)

sort input and output files [216](#)

VSAM [218](#)

FD (file description) entry [12](#)

figurative constants

definition [24](#)

HIGH-VALUE restriction  
[126](#)

national-character [126](#)

file access mode

choosing [146](#)

dynamic [178](#)

example [179](#)

for indexed files (KSDS) [178](#)

for relative files (RRDS) [178](#)

for sequential files (ESDS) [178](#)

performance considerations [195](#)

random [178](#)

sequential [178](#)

summary table of [175](#)

file allocation [148](#)

file availability

QSAM files under z/OS

[161](#)

VSAM files under z/OS [189](#)

file description (FD) entry [12](#)

file organization

choosing [146](#)

comparison of ESDS, KSDS, RRDS [174](#)

indexed [145](#), [176](#)

line-sequential [199](#)

overview [145](#)

QSAM [151](#)

relative [146](#)

relative-record [177](#)

sequential [145](#), [176](#)

VSAM [174](#)

file position indicator (CRP) [182](#), [185](#)

FILE SECTION

BLOCK CONTAINS clause [12](#)

CODE-SET clause [13](#)

DATA RECORDS clause [12](#)

description [11](#)

EXTERNAL clause [11](#)

FD entry [12](#)

GLOBAL clause [11](#)

LABEL RECORDS clause [12](#)

LINAGE clause [12](#)

OMITTED [12](#)

RECORD CONTAINS clause [12](#)

record description [11](#)

RECORD IS VARYING [12](#)

RECORDING MODE clause [13](#)

VALUE OF [12](#)

FILE STATUS clause

description [149](#)

example [233](#)

line-sequential error processing [204](#)

NOFASTSORT error processing [218](#)

QSAM error processing [163](#)

using [229](#)

VSAM error processing [188](#)

with VSAM status code [230](#)

file status code

02 [185](#)

30 [184](#)

37 [160](#)

39 [160](#), [167](#), [170](#)

49 [187](#)

90 [158](#), [163](#), [188](#)

92 [187](#), [438](#)

file status key

05 [182](#)

35 [182](#)

39 [183](#)

checking for I/O errors [229](#)

checking for successful OPEN [229](#), [230](#)

error handling [362](#)

set for error handling [149](#)

used with VSAM status code [230](#)

VSAM, importance of in [188](#)

FILE-CONTROL paragraph

example of entries [6](#)

relation to FD entries [8](#)

files

- files (*continued*)
  - associating program files to external files [5](#)
  - attributes [167](#)
  - available
    - QSAM [161](#)
    - VSAM [189](#)
  - changing name [9](#)
  - CICS, restrictions under [5](#)
  - COBOL coding
    - DATA DIVISION entries [152](#), [179](#), [200](#)
    - ENVIRONMENT DIVISION entries [151](#), [175](#), [199](#)
    - input/output statements [160](#), [180](#), [201](#)
    - overview [147](#)
  - data sets, same meaning as [5](#)
  - defining to operating system [8](#)
  - describing [11](#)
  - external [475](#)
  - identifying to z/OS [164](#), [166](#), [190](#)
  - line-sequential, allocating [200](#)
  - multithreaded processing
    - example [495](#)
    - recommended organization [495](#)
    - recommended usage patterns [495](#)
    - serialization [494](#)
  - optional
    - QSAM [161](#)
    - VSAM [183](#)
  - overview [146](#)
  - processing
    - line-sequential [199](#)
    - QSAM [151](#)
    - VSAM [173](#)
    - with multithreading [494](#)
  - sort performance
    - FASTSORT [216](#)
    - variable-length files [212](#)
  - storage of file-definition records [494](#)
  - unavailable
    - QSAM [161](#)
    - VSAM [189](#)
  - usage explanation [9](#)
- FIPS messages
  - categories [694](#)
  - FLAGSTD compiler option [309](#)
- fixed-length records
  - QSAM
    - layout [153](#)
    - requesting [152](#)
  - VSAM
    - defining [179](#)
    - RRDS [174](#)
- fixed-point arithmetic
  - comparisons [60](#)
  - evaluation [59](#)
  - example evaluations [61](#)
  - exponentiation [658](#)
- fixed-point data
  - binary [46](#)
  - conversions and precision [50](#)
  - conversions between fixed- and floating-point [50](#)
  - external decimal [45](#)
  - intermediate results [657](#)
  - packed-decimal [47](#)
  - planning use of [634](#)
- FLAG compiler option
  - compiler output [367](#)
  - description [308](#)
  - using [367](#)
- flags and switches [94](#)
- FLAGSTD compiler option
  - multioption interaction [287](#)
- floating comment indicators (\*>) [847](#)
- floating-point arithmetic
  - comparisons [60](#)
  - evaluation [59](#)
  - example evaluations [61](#)
  - exponentiation [662](#)
- floating-point data
  - conversions and precision [50](#)
  - conversions between fixed- and floating-point [50](#)
  - external [45](#)
  - intermediate results [662](#)
  - internal
    - format [47](#)
    - performance tips [635](#)
    - planning use of [634](#)
- format of record
  - fixed-length
    - defining for VSAM [179](#)
    - layout of QSAM [153](#)
    - requesting for QSAM [152](#)
  - for QSAM ASCII tape [171](#)
  - format D
    - layout [154](#)
    - requesting [153](#)
  - format F
    - layout [153](#)
    - requesting [152](#)
  - format S
    - layout [156](#)
    - overview [156](#)
    - requesting [155](#)
  - format U
    - layout [157](#)
    - requesting [157](#)
  - format V
    - layout [154](#)
    - requesting [153](#)
  - spanned
    - layout [156](#)
    - overview [156](#)
    - requesting [155](#)
  - undefined
    - layout [157](#)
    - requesting [157](#)
  - variable-length
    - defining for VSAM [180](#)
    - layout of QSAM [154](#)
    - requesting for QSAM [153](#)
- formatted dump [223](#)
- freeing object instances [585](#)
- function-pointer data item
  - addressing JNI services [705](#)
  - CALL statement [463](#)
  - calling COBOL [463](#)
  - calling DLL program
    - example [487](#)
  - calling Language Environment services [463](#)

function-pointer data item (*continued*)  
definition [461](#)  
SET function-pointer [461](#)  
with DLLs [486](#)

## G

garbage collection [585](#)  
GB 18030 data  
    converting to or from national [139](#)  
    processing [139](#)  
generating XML output  
    example [551](#)  
    overview [545](#)  
get and set methods [573](#)  
GETMAIN, saving address of [683](#)  
GLOBAL clause for files [11](#), [15](#)  
global names [460](#)  
Glossary [833](#)  
GOBACK statement  
    in main program [450](#)  
    in subprogram [450](#)  
    with multithreading [450](#)  
group item  
    cannot subordinate alphanumeric group within national group [129](#)  
    comparing to national data [142](#)  
    definition [22](#)  
    for defining tables [65](#)  
    group move contrasted with elementary move [31](#), [129](#)  
    initializing  
        using a VALUE clause [74](#)  
        using INITIALIZE [29](#), [71](#)  
    MOVE statement with [31](#)  
    passing as an argument [470](#)  
    treated as a group item  
        example with INITIALIZE [71](#)  
        in INITIALIZE [30](#)  
    variably located [80](#)  
group move contrasted with elementary move [31](#), [129](#)  
GROUP-USAGE NATIONAL clause  
    communicating with Java [606](#)  
    defining a national group [128](#)  
    defining tables [66](#)  
    example of declaring a national group [22](#)  
    initializing a national group [29](#)  
grouping data to pass as an argument [470](#)

## H

header on listing [5](#)  
HEAP runtime option  
    influencing data location [39](#)  
    multioption interaction [38](#)  
hexadecimal literals  
    as currency sign [62](#)  
    national  
        description [24](#)  
        using [125](#)  
HGPR compiler option  
    performance considerations [641](#)  
hiding factory methods [592](#)  
hierarchy of compiler options

hierarchy of compiler options (*continued*)  
    in batch [259](#)  
    in SYSOPTF data sets [325](#)  
    under z/OS [255](#)  
    under z/OS UNIX [266](#)

## I

I-level message [263](#), [367](#)  
IDENTIFICATION DIVISION  
    class [565](#)  
    CLASS-ID paragraph [565](#),  
        [587](#)  
    client [576](#)  
    coding [3](#)  
    DATE-COMPILED paragraph [3](#)  
    errors [3](#)  
    listing header example [5](#)  
    method [569](#)  
    PROGRAM-ID paragraph [3](#)  
    required paragraphs [3](#)  
    subclass [587](#)  
    TITLE statement [5](#)  
IF statement  
    coding [89](#)  
    nested [90](#)  
    use EVALUATE instead for multiple conditions [89](#)  
    with null branch [89](#)  
IGZCA2D service routine [665](#)  
IGZCD2A service routine [667](#)  
igzcjava.x  
    binding with  
        example [279](#)  
        preparing OO applications [278](#)  
    linking with  
        example [275](#)  
        preparing OO applications [274](#)  
IGZEOPT module  
    with multithreading [497](#)  
IGZETUN module  
    with multithreading [497](#)  
IGZSRTCD data set [220](#)  
imperative statement, list [17](#)  
implicit scope terminator [19](#)  
IMS  
    COBOL-Java interoperability  
        accessing databases [433](#)  
        calling COBOL method from Java [431](#)  
        calling Java method from COBOL [432](#)  
        messages [433](#)  
        restriction on EXEC SQL [433](#)  
        STOP RUN [432](#)  
        synchronizing transactions [433](#)  
        using the AIB [433](#)  
    coding programs under  
        overview [427](#)  
        restrictions [5](#), [427](#)  
    compiling and linking for [430](#)  
    coprocessor  
        overview [427](#)  
    performance considerations [644](#)  
    SQLIMS compiler option [429](#)  
    SQLIMS statements  
        return codes [429](#)

- IMS (*continued*)
  - SQLIMS statements (*continued*)
    - SQLIMS INCLUDE [428](#)
    - using character data in [428](#)
    - using EXEC SQL under IMS [433](#)
- IMS SQL
  - coprocessor [428](#)
- incrementing addresses [472](#)
- index
  - assigning a value to [70](#)
  - computation of element displacement, example [68](#)
  - creating with OCCURS INDEXED BY clause [70](#)
  - definition [68](#)
  - incrementing or decrementing [70](#)
  - initializing [70](#)
  - key, detecting faulty [232](#)
  - range checking [366](#)
  - referencing other tables with [70](#)
- index data item
  - cannot use as subscript or index [70](#)
  - creating with USAGE IS INDEX clause [70](#)
- indexed file organization
  - description [145](#)
  - specifying [176](#)
- indexing
  - computation of element displacement, example [68](#)
  - definition [68](#)
  - example [75](#)
  - preferred to subscripting [636](#)
  - tables [70](#)
- INEXIT suboption of EXIT option
  - processing of [684](#)
  - syntax [306](#)
- inheritance hierarchy, definition of [562](#)
- INITCHECK compiler option
  - description [311](#)
- INITIAL attribute
  - effect on subprograms [452](#)
  - use of dynamic call and CANCEL instead [454](#)
- INITIAL clause
  - effect on main program [451](#)
  - effect on nested programs [4](#)
  - setting programs to initial state [4](#)
- INITIALIZE statement
  - examples [26](#)
  - loading group values [29](#)
  - loading national group values [29](#)
  - loading table values [71](#)
  - REPLACING phrase [71](#)
  - using for debugging [363](#)
- initializing
  - a group item
    - using a VALUE clause [74](#)
    - using INITIALIZE [29](#), [71](#)
  - a national group item
    - using a VALUE clause [74](#)
    - using INITIALIZE [29](#), [72](#)
  - a structure using INITIALIZE [29](#)
  - a table
    - all occurrences of an element [74](#)
    - at the group level [74](#)
    - each item individually [73](#)
    - using INITIALIZE [71](#)
    - using PERFORM VARYING [98](#)
- initializing (*continued*)
  - examples [26](#)
  - instance data [584](#)
  - variable-length group [78](#)
- inline comments [850](#)
- INLINE compiler option
  - description [312](#)
- inline PERFORM
  - example [97](#)
  - overview [97](#)
- input
  - coding for CICS [408](#)
  - coding for line-sequential files [201](#)
  - coding for QSAM files [160](#)
  - coding for VSAM files [180](#)
  - from files [145](#)
  - to compiler, under z/OS [248](#)
- input procedure
  - coding [208](#)
  - example [214](#)
  - FASTSORT option not effective [216](#)
  - requires RELEASE or RELEASE FROM [209](#)
  - restrictions [211](#)
- INPUT-OUTPUT SECTION [5](#)
- input/output
  - checking for errors [229](#)
  - coding overview [147](#)
  - controlling with FASTSORT option [308](#)
  - logic flow after error [225](#)
  - overview [145](#)
  - processing errors
    - line-sequential files [204](#)
    - QSAM files [163](#), [225](#)
    - VSAM files [188](#), [225](#)
- input/output coding
  - AT END (end-of-file) phrase [228](#)
  - checking for successful operation [229](#)
  - checking VSAM status codes [230](#)
  - detecting faulty index key [232](#)
  - error handling techniques [225](#)
  - EXCEPTION/ERROR declaratives [228](#)
- INSERT statement [359](#)
- INSPECT statement
  - avoid with UTF-8 data [526](#)
  - examples [110](#)
  - using [110](#)
- inspecting data (INSPECT) [110](#)
- instance
  - creating [584](#)
  - definition of [561](#)
  - deleting [585](#)
- instance data
  - defining [567](#), [588](#)
  - definition of [561](#)
  - initializing [584](#)
  - making it accessible [573](#)
  - private [567](#)
- instance methods
  - defining [568](#), [588](#)
  - definition of [561](#)
  - invoking overridden [583](#)
  - overloading [573](#)
  - overriding [572](#)
- INTDATE compiler option

- INTDATE compiler option (*continued*)
  - description [313](#)
  - effect on calendar starting date [57](#)
- INTEGER intrinsic function, example [110](#)
- INTEGER-OF-DATE intrinsic function [58](#)
- INTEGER-PART intrinsic function [110](#)
- integrated CICS translator
  - advantages [412](#)
  - compiler options for [411](#)
  - overview [412](#)
- interactive program, example [809](#)
- Interactive System Productivity Facility (ISPF) [809](#)
- interlanguage communication
  - and PL/I tasking [496](#)
  - between COBOL and Java [601](#)
  - IMS applications [432](#)
  - subprograms [449](#)
  - under CICS [409](#)
  - with multithreading [496](#)
- intermediate results [655](#)
- internal floating-point data (COMP-1, COMP-2) [47](#)
- interoperable data types with Java [606](#)
- interrupts [619](#)
- intrinsic functions
  - as reference modifiers [109](#)
  - converting alphanumeric data items with [111](#)
  - converting national data items with [111](#)
  - evaluating data items [114](#)
  - example of
    - ANNUITY [58](#)
    - CHAR [115](#)
    - CURRENT-DATE [58](#)
    - DISPLAY-OF [133](#)
    - INTEGER [110](#)
    - INTEGER-OF-DATE [58](#)
    - LENGTH [58](#), [116](#), [117](#)
    - LOG [59](#)
    - LOWER-CASE [112](#)
    - MAX [58](#), [86](#), [115](#), [116](#)
    - MEAN [59](#)
    - MEDIAN [59](#), [86](#)
    - MIN [109](#)
    - NATIONAL-OF [133](#)
    - NUMVAL [113](#)
    - NUMVAL-C [58](#), [113](#)
    - ORD [115](#)
    - ORD-MAX [86](#), [115](#)
    - PRESENT-VALUE [58](#)
    - RANGE [59](#), [86](#)
    - REM [59](#)
    - REVERSE [112](#)
    - SQRT [59](#)
    - SUM [86](#)
    - UPPER-CASE [112](#)
    - WHEN-COMPILED [118](#)
  - example of Unicode functions [136](#)
  - finding date of compilation [118](#)
  - finding largest or smallest item [115](#)
  - finding length of data items [117](#)
  - intermediate results [660](#), [663](#)
  - introduction to [36](#)
  - nesting [36](#)
  - numeric functions

- intrinsic functions (*continued*)
  - numeric functions (*continued*)
    - differences from Language Environment callable services [56](#)
    - equivalent Language Environment callable services [56](#)
    - examples of [55](#)
    - integer, floating-point, mixed [54](#)
    - nested [55](#)
    - special registers as arguments [55](#)
    - table elements as arguments [55](#)
    - uses for [54](#)
    - processing table elements [85](#)
    - UTF-8 [135](#)
- INVALID KEY phrase
  - description [232](#)
  - example [233](#)
- INVOKE statement
  - RETURNING phrase [583](#)
  - USING phrase [581](#)
  - using to create objects [584](#)
  - using to invoke methods [580](#)
  - with ON EXCEPTION [580](#), [593](#)
  - with PROCEDURE DIVISION RETURNING [474](#)
- invoking
  - COBOL programs under z/OS [478](#)
  - COBOL programs under z/OS UNIX [435](#)
  - factory or static methods [593](#)
  - instance methods [580](#)
  - Language Environment callable services [651](#)
- ISAM data set, analogous to VSAM KSDS data set [173](#)
- ISPF (Interactive System Productivity Facility) [809](#)

## J

- J2EE client
  - example [613](#)
  - running [276](#)
- Java
  - and COBOL
    - binding [278](#)
    - communicating between [601](#)
    - compatibility [281](#)
    - compiling under z/OS UNIX [273](#)
    - compiling using JCL or TSO/E [277](#)
    - linking [274](#)
    - running [275](#), [278](#)
    - structuring applications [598](#)
  - array classes [605](#)
  - arrays
    - declaring [606](#)
    - example [609](#)
    - manipulating [608](#)
  - boolean array [606](#)
  - boolean type [606](#)
  - byte array [606](#)
  - byte type [606](#)
  - char array [607](#)
  - char type [606](#)
  - class types [606](#)
  - double array [607](#)
  - double type [606](#)
  - example
    - exception handling [603](#)

## Java (*continued*)

- example (*continued*)
  - J2EE client [613](#)
  - processing an integer array [609](#)
- exception
  - catching [602](#)
  - example [603](#)
  - handling [602](#)
  - throwing [602](#)
- float array [607](#)
- float type [606](#)
- global references
  - JNI services for [604](#)
  - managing [603](#)
  - object [603](#)
  - passing [604](#)
- int array [606](#)
- int type [606](#)
- interoperability [601](#)
- interoperable data types, coding [606](#)
- jstring class [605](#)
- local references
  - deleting [604](#)
  - freeing [604](#)
  - JNI services for [604](#)
  - managing [603](#)
  - object [603](#)
  - passing [604](#)
  - per multithreading [604](#)
  - saving [604](#)
- long array [607](#)
- long type [606](#)
- methods
  - access control [605](#)
- object array [607](#)
- running with COBOL
  - under z/OS UNIX [275](#)
  - using JCL or TSO/E [278](#)
  - XPLINK linkage [280](#)
- sharing data with [605](#)
- short array [606](#)
- short type [606](#)
- string array [607](#)
- strings
  - declaring [606](#)
  - manipulating [610](#)

Java virtual machine

- exceptions [602](#)
- initializing [276](#)
- object references [603](#)

java.lang.Object

- referring to as Base [565](#)

javac command

- compiling Java class definitions [273](#)
- recompile for Java 5 or Java 6 [281](#)

JAVAERR data set [278](#)

JAVAIN data set [278](#)

JAVAOUT data set [278](#)

JCL

- ASCII tape files [171](#)
- cataloged procedures [238](#)
- example of checkpoint/restart [624](#)
- FASTSRT requirement [216](#)
- for compiling [237](#)

## JCL (*continued*)

- for compiling in the z/OS UNIX file system [239](#)
- for line-sequential files [200](#)
- for merge [211](#)
- for OO applications
  - example [279](#)
- for QSAM files [165](#)
- for sort [211](#)
- for VSAM data sets [192](#)

JNI

- accessing services [601](#)
- comparing object references [579](#)
- converting local references to global [584](#)
- EBCDIC services [611](#)
- environment structure
  - addressability for [601](#)
- exception handling services [602](#)
- Java array services [608](#)
- Java string services [610](#)
- obtaining class object reference [602](#)
- restrictions when using [602](#)
- Unicode services [610](#)
- UTF-8 services [613](#)

JNI.cpy

- for compiling [273](#)
- for JNINativeInterface [601](#)
- listing [705](#)

JNIEnvPtr special register

- use for JNI callable services [601](#)

JNINativeInterface

- environment structure [601](#)
- JNI.cpy [601](#)

JOB control statement, RD parameter of [622](#)

job resubmission [624](#)

job stream [449](#)

JSON exception codes

- for generating [681](#)

JSON-CODE special register

- exception codes for generating [681](#)

jstring Java class [605](#)

## K

Kanji comparison [93](#)

Kanji data, testing for [144](#)

keyboard navigation [827](#)

keys

- alternate in KSDS file [177](#)
- for binary search [84](#)
- for merging
  - defining [213](#)
  - overview [206](#)
- for sorting
  - defining [213](#)
  - overview [206](#)
- permissible data types
  - in MERGE statement [213](#)
  - in OCCURS clause [66](#)
  - in SORT statement [213](#)
- prime in KSDS file [176](#)
- relative-record [177](#)
- to specify order of table elements [66](#)

keyword [852](#)

KSDS (key-sequenced data sets)  
file access mode [178](#)  
organization [176](#)

## L

LABEL RECORDS clause  
FILE SECTION entry [12](#)

LANGUAGE compiler option  
description [313](#)

Language Environment callable services  
condition handling [649](#)  
corresponding math intrinsic functions [56](#)  
date and time computations [649](#)  
differences from intrinsic functions [56](#)  
dynamic storage services [649](#)  
example of using [651](#)  
feedback code [651](#)  
for date and time [57](#)  
for mathematics [56](#)  
invoking with CALL [651](#)  
mathematics [649](#)  
message handling [649](#)  
national language support [649](#)  
omitted feedback code [651](#)  
overview [649](#)  
return code [651](#)  
RETURN-CODE special register [651](#)  
sample list of [650](#)  
types of [649](#)

large block interface (LBI) [159](#)

largest or smallest item, finding [115](#)

last-used state  
subprograms with EXIT PROGRAM or GOBACK [451](#)  
subprograms without INITIAL attribute [452](#)

LBI (large block interface) [159](#)

LENGTH intrinsic function  
compared with LENGTH OF special register [117](#)  
example [58](#), [117](#)  
using [114](#)  
variable-length results [116](#)  
with national data [117](#)

length of data items, finding [117](#)

LENGTH OF special register  
passing [466](#)  
using [117](#)

level-88 item  
conditional expressions [93](#)  
setting switches off, example [96](#)  
setting switches on, example [95](#)  
switches and flags [94](#)  
testing multiple values, example [95](#)  
testing single values, example [94](#)

level-number [376](#)

LIBEXIT suboption of EXIT option  
processing of [685](#)  
syntax [306](#)

libjvm.x  
binding with  
example [279](#)  
preparing OO applications [278](#)  
linking with  
example [275](#)  
preparing OO applications [274](#)

libjvm.x (*continued*)  
with EBCDIC services [612](#)

LIBPATH environment variable  
description [437](#)  
example of setting [278](#)  
specifying location for COBOL classes [275](#)

library  
BASIS [252](#)  
COPY [252](#)  
defining [252](#)  
directory entry [246](#)  
specifying path for [357](#)

library-name  
alternative if not specified [269](#)  
cross-reference to data-set names [400](#)  
when not used [685](#)

library-name environment variable [266](#)

limits of the compiler  
DATA DIVISION [10](#)  
user data [10](#)

line number [375](#)

line-sequential files  
adding records to [203](#)  
blocking [11](#)  
closing [203](#)  
closing to prevent reopening [202](#)  
control characters in [200](#)  
DATA DIVISION entries [200](#)  
ENVIRONMENT DIVISION entries [199](#)  
input/output error processing [204](#)  
input/output statements for [201](#)  
national data not supported [203](#)  
opening [202](#)  
organization [199](#)  
processing [199](#)  
reading from [201](#)  
reading records from [202](#)  
under z/OS  
allocating [200](#)  
creating [200](#)  
job control language (JCL) [200](#)  
writing to [201](#)

LINECOUNT compiler option [314](#)

LINK macro [246](#)

LINKAGE SECTION  
coding [469](#)  
for describing parameters [468](#)  
with recursive calls [15](#)  
with the THREAD option [15](#)  
linked-list processing, example [472](#)  
linking in the z/OS UNIX shell  
c89 command [267](#)  
passing information to cob2 [269](#)  
using the cob2 command  
DLLs [268](#)  
examples [268](#)  
overview [267](#)

linking OO applications  
cob2 command [274](#)  
under z/OS UNIX  
example [275](#)  
overview [274](#)  
using JCL or TSO/E  
example [279](#)

linking OO applications (*continued*)  
    using JCL or TSO/E (*continued*)  
        overview [278](#)

LIST compiler option  
    assembler code for source program [381](#)  
    base locator table [396](#)  
    compiler output [382](#), [390](#)  
    conflict with OFFSET option [370](#)  
    Constant area section [395](#)  
    description [315](#)  
    DSA memory map [381](#), [397](#)  
    External symbols section [397](#)  
    getting output [370](#)  
    MD5 signature example [391](#)  
    multioption interaction [287](#)  
    reading output [381](#)  
    special register table [396](#)  
    Static map section [394](#)  
    symbols used in output [379](#)  
    Timestamp and version information example [392](#)

List of resources [873](#)

listings  
    assembler expansion of PROCEDURE DIVISION [381](#)  
    data and procedure-name cross-reference [369](#)  
    embedded error messages [367](#)  
    generating a short listing [370](#)  
    line numbers, user-supplied [372](#)  
    sorted cross-reference of program-names [399](#)  
    sorted cross-reference of text-names [400](#)  
    terms used in MAP output [378](#)  
    text-name cross-reference [369](#)

literals  
    alphanumeric  
        description [23](#)  
        with DBCS content [143](#)  
    DBCS  
        description [24](#)  
        maximum length [143](#)  
        using [143](#)  
    definition [23](#)  
    hexadecimal  
        using [125](#)  
    national  
        description [24](#)  
        using [125](#)  
    numeric [23](#)  
    using [23](#)

little-endian, converting to big-endian [124](#)

loading a table dynamically [71](#)

local names [460](#)

local references, converting to global [584](#)

LOCAL-STORAGE SECTION  
    client [578](#)  
    comparison with WORKING-STORAGE  
        example [14](#)  
        OO client [578](#)  
        overview [13](#)  
    determining location [39](#)

LOG intrinsic function [59](#)

logical record  
    description [145](#)  
    fixed-length format  
        defining for VSAM [179](#)

logical record (*continued*)  
    fixed-length format (*continued*)  
        requesting for QSAM [152](#)  
    QSAM, definition [152](#)  
    variable-length format  
        defining for VSAM [180](#)  
        layout for QSAM [154](#)  
        requesting for QSAM [153](#)

loops  
    coding [96](#)  
    conditional [98](#)  
    do [97](#)  
    in a table [98](#)  
    performed an explicit number of times [97](#)  
LOWER-CASE intrinsic function [112](#)  
lowercase, converting to [112](#)  
lst suffix with cob2 [271](#)

## M

main program  
    accessing parameter list in  
        z/OS  
            example [479](#)  
            overview [478](#)  
    accessing parameter list in z/OS  
        UNIX  
            example [440](#)  
            overview [440](#)  
    and subprograms [449](#)  
    dynamic calls [452](#)

main storage, allocating to buffers [294](#)

MAP compiler option  
    data items and relative addresses [257](#)  
    description [316](#)  
    embedded MAP summary [370](#)  
    example [375](#), [381](#)  
    nested program map  
        example [381](#)  
    symbols used in output [379](#)  
    terms used in output [378](#)  
    using [369](#), [370](#)

mapping of DATA DIVISION items [370](#)

mathematics  
    intrinsic functions [55](#), [59](#)  
    Language Environment callable services [56](#), [649](#)

MAX intrinsic function  
    example table calculation [86](#)  
    example with functions [58](#)  
    using [115](#)

MAXPCF compiler option [317](#)

MDECK compiler option  
    description [318](#)

MEAN intrinsic function  
    example statistics calculation [59](#)  
    example table calculation [86](#)

MEDIAN intrinsic function  
    example statistics calculation [59](#)  
    example table calculation [86](#)

memory map  
    DSA [381](#)

merge  
    alternate collating sequence [214](#)  
    completion code [215](#)

- merge (*continued*)
  - criteria [213](#)
  - data sets needed under z/OS [211](#)
  - DD statements for defining z/OS data sets [211](#)
  - description [205](#)
  - determining success [215](#)
  - diagnostic message [215](#)
  - files, describing [207](#)
  - keys
    - defining [213](#)
    - overview [206](#)
  - pass control statements to [220](#)
  - process [206](#)
  - restrictions [205](#)
  - storage use [220](#)
  - terminating [216](#)
  - work files
    - describing [206](#)
- MERGE statement
  - ASCENDING|DESCENDING KEY phrase [213](#)
  - COLLATING SEQUENCE phrase [6](#), [214](#)
  - description [212](#)
  - GIVING phrase [212](#)
  - overview [205](#)
  - restrictions [205](#)
  - USING phrase [212](#)
- message handling, Language Environment callable services [649](#)
- messages
  - compiler
    - choosing severity to be flagged [367](#)
    - customizing [693](#)
    - determining what severity level to produce [308](#)
    - embedding in source listing [367](#)
    - generating a list of [262](#)
    - sending to terminal [253](#)
    - severity levels [263](#), [694](#)
  - compiler-directed [262](#)
  - from exit modules [700](#)
  - sending to SYSTERM [340](#)
- METHOD-ID paragraph [569](#)
- methods
  - constructor [591](#)
  - factory [591](#)
  - hiding factory [592](#)
  - instance [568](#), [588](#)
  - invoking [580](#), [593](#)
  - invoking superclass [583](#)
  - Java access control [605](#)
  - obtaining passed arguments [571](#)
  - overloading [573](#)
  - overriding [572](#), [592](#)
  - returning a value from [571](#)
  - signature [569](#)
- migration considerations
  - Java and COBOL [281](#)
- MIN intrinsic function
  - example [109](#)
  - using [115](#)
- Mixed AMODE [443](#)
- mixed DBCS/EBCDIC literal
  - alphanumeric to DBCS conversion [665](#)
  - DBCS to alphanumeric conversion [667](#)
- mnemonic-name
  - SPECIAL-NAMES paragraph [5](#)
- MOVE statement
  - assigning arithmetic results [32](#)
  - converting to national data [131](#)
  - CORRESPONDING [31](#)
  - effect of ODO on lengths of sending and receiving items [77](#)
  - group move contrasted with elementary move [31](#), [129](#)
  - with elementary receiving items [30](#)
  - with group receiving items [31](#)
  - with national items [30](#)
- MSGEXIT suboption of EXIT option
  - effect on compilation return code [695](#)
  - example user exit [695](#)
  - message severity levels [694](#)
  - processing of [691](#)
  - syntax [306](#)
- MSGFILE runtime option [326](#)
- multiple currency signs
  - example [63](#)
  - using [62](#)
- multiple inheritance, not permitted [564](#), [587](#)
- multiple thread environment, running in [343](#)
- multithreading
  - AMODE setting [497](#)
  - asynchronous signals [497](#)
  - choosing data section
    - in an OO client [578](#)
  - closing QSAM files [163](#)
  - closing VSAM files [188](#)
  - COBOL programs [491](#)
  - coding file I/O
    - example [495](#)
    - recommended organization [495](#)
    - recommended usage patterns [495](#)
    - serialization [494](#)
  - control transfer [493](#)
  - ending programs [493](#)
  - EXIT PROGRAM statement [450](#)
  - GOBACK statement [450](#)
  - I/O error declaratives [228](#)
  - IGZEOPT [497](#)
  - IGZETUN [497](#)
  - interlanguage communication [496](#)
  - limitations [496](#)
  - nested programs [496](#)
  - older compilers [497](#)
  - overview [491](#)
  - preinitializing [493](#)
  - preparing COBOL programs for [491](#)
  - recursion [493](#)
  - recursive requirement [496](#)
  - reentrancy [496](#)
  - reentrancy requirement [496](#)
  - runtime restrictions [497](#)
  - sort and merge restriction [205](#)
  - STOP RUN statement [450](#)
  - synchronizing access to resources [496](#)
  - terminology [491](#)
  - THREAD compiler option
    - restrictions with [344](#)
    - when to choose [492](#)
  - UPSI switches [497](#)

multithreading (*continued*)  
with PL/I tasks [496](#)

## N

N delimiter for national or DBCS literals [24](#)

NAME compiler option  
description [319](#)  
using [3](#)

name declaration  
searching for [461](#)

NAMESPACE-DECLARATION XML event [515](#)

naming  
files [8](#)  
programs [3](#)

NATIONAL (USAGE IS)  
external decimal [45](#)  
floating point [46](#)

national comparison [93](#)

national data  
communicating with Java [606](#)  
comparing  
overview [140](#)  
to alphabetic, alphanumeric, or DBCS [142](#)  
to alphanumeric groups [142](#)  
to numeric [141](#)  
two operands [140](#)  
concatenating (STRING) [101](#)  
converting  
exceptions [133](#)  
from alphanumeric or DBCS with NATIONAL-OF [132](#)  
from alphanumeric, DBCS, or integer with MOVE [131](#)  
overview [131](#)  
to alphanumeric with DISPLAY-OF [133](#)  
to numbers with NUMVAL, NUMVAL-C [113](#)  
to or from Chinese GB 18030 [139](#)  
to or from Greek alphanumeric, example [133](#)  
to or from UTF-8 [134](#)  
to uppercase or lowercase [112](#)  
with INSPECT [110](#)

defining [125](#)  
displaying on output [34](#)  
encoding in XML documents [523](#)  
evaluating with intrinsic functions [114](#)  
external decimal [45](#)  
external floating-point [46](#)  
figurative constants [126](#)  
finding the smallest or largest item [115](#)  
in conditional expressions [140](#)  
in generated XML documents [546](#)  
in keys  
in MERGE statement [213](#)  
in OCCURS clause [66](#)  
in SORT statement [213](#)  
initializing, example of [27](#)  
input with ACCEPT [33](#)  
inspecting (INSPECT) [110](#)  
LENGTH intrinsic function and [117](#)  
LENGTH OF special register [117](#)  
literals  
using [125](#)  
MOVE statement with [30](#), [131](#)  
NSYMBOL compiler option if no USAGE clause [125](#)

national data (*continued*)  
reference modification of [107](#)  
reversing characters [112](#)  
specifying [124](#)  
splitting (UNSTRING) [103](#)  
VALUE clause with alphanumeric literal, example [116](#)

national decimal data (USAGE NATIONAL)  
defining [127](#)  
example [41](#)  
format [45](#)  
initializing, example of [28](#)  
national floating-point data (USAGE NATIONAL)  
defining [127](#)  
definition [46](#)

national group item  
advantages over alphanumeric groups [127](#)  
can contain only national data [22](#), [129](#)  
communicating with Java [606](#)  
contrasted with USAGE NATIONAL group [23](#)  
defining [128](#)  
example [22](#)  
for defining tables [66](#)  
in generated XML documents [546](#)  
initializing  
using a VALUE clause [74](#)  
using INITIALIZE [29](#), [72](#)  
LENGTH intrinsic function and [117](#)  
MOVE statement with [31](#)  
overview [127](#)  
passing as an argument [470](#)  
treated as a group item  
example with INITIALIZE [129](#)  
in INITIALIZE [30](#)  
in MOVE CORRESPONDING [31](#)  
summary [130](#)  
treated as an elementary item  
example with MOVE [31](#)  
in most cases [22](#), [127](#)  
using  
as an elementary item [129](#)  
overview [128](#)  
VALUE clause with alphanumeric literal, example [74](#)

national language support (NLS)  
DBCS [142](#)  
LANGUAGE compiler option [313](#)  
processing data [119](#)

national literals  
description [24](#)  
using [125](#)  
national-edited data  
defining [125](#)  
editing symbols [125](#)  
initializing

example [27](#)  
using INITIALIZE [72](#)  
MOVE statement with [30](#)  
PICTURE clause [125](#)  
NATIONAL-OF intrinsic function  
example with Chinese data [139](#)  
example with Greek data [133](#)  
example with UTF-8 data [134](#)  
using [132](#)  
with XML documents [523](#)  
nested COPY statement [647](#), [686](#)

- nested delimited scope statements [20](#)
- nested IF statement
  - coding [90](#)
  - CONTINUE statement [89](#)
  - EVALUATE statement preferred [90](#)
  - with null branches [89](#)
- nested intrinsic functions [55](#)
- nested program integration [639](#)
- nested program map
  - description [370](#)
  - example [381](#)
- nested programs
  - calling [458](#)
  - description [459](#)
  - effect of INITIAL clause [4](#)
  - guidelines [458](#)
  - map [370](#), [381](#)
  - scope of names [460](#)
  - transfer of control [458](#)
- nesting level
  - program [375](#), [381](#)
  - statement [375](#)
- NOCBLCARD translator option [413](#)
- NOCOMPILE compiler option
  - use to find syntax errors [365](#)
- NODLL compiler option
  - with dynamic calls [452](#)
  - with static calls [452](#)
- NODYNAM compiler option
  - under CICS [409](#)
  - under DB2 with CICS or CAF [426](#)
  - with static and dynamic calls [456](#)
  - with static calls [452](#)
  - with stored procedures [426](#)
- NOFASTSORT compiler option [218](#), [221](#)
- NORENT compiler option
  - multioption interaction [287](#)
- NOSIMVRD runtime option [178](#)
- NOSQLCCSID compiler option recommended for compatibility with DB2 precompiler [423](#)
- Notices [829](#)
- NSYMBOL compiler option
  - description [319](#)
  - effect on N literals [24](#)
  - for DBCS literals [125](#)
  - for national data items [125](#)
  - for national literals [125](#)
  - multioption interaction [287](#)
- null branch [89](#)
- null-terminated strings
  - example [106](#)
  - handling [471](#)
  - manipulating [106](#)
- NUMBER compiler option
  - description [320](#)
  - for debugging [372](#)
- NUMCHECK compiler option [320](#)
- NUMCLS installation option, effect on numeric class test [52](#)
- numeric class test
  - checking for valid data [52](#)
  - effect of NUMPROC, NUMCLS [52](#)
- numeric comparison [93](#)
- numeric data
  - binary

- numeric data (*continued*)
  - binary (*continued*)
    - USAGE BINARY [46](#)
    - USAGE COMPUTATIONAL (COMP) [46](#)
    - USAGE COMPUTATIONAL-4 (COMP-4) [46](#)
    - USAGE COMPUTATIONAL-5 (COMP-5) [46](#)
  - can compare algebraic values regardless of USAGE [141](#)
  - comparing to national [141](#)
  - converting
    - between fixed- and floating-point [49](#)
    - precision [50](#)
    - to national with MOVE [131](#)
  - defining [41](#)
  - display floating-point (USAGE DISPLAY) [45](#)
  - editing symbols [43](#)
  - external decimal
    - USAGE DISPLAY [45](#)
    - USAGE NATIONAL [45](#)
  - external floating-point
    - USAGE DISPLAY [45](#)
    - USAGE NATIONAL [46](#)
  - internal floating-point
    - USAGE COMPUTATIONAL-1 (COMP-1) [47](#)
    - USAGE COMPUTATIONAL-2 (COMP-2) [47](#)
  - national decimal (USAGE NATIONAL) [45](#)
  - national floating-point (USAGE NATIONAL) [46](#)
  - packed-decimal
    - sign representation [51](#)
    - USAGE COMPUTATIONAL-3 (COMP-3) [47](#)
    - USAGE PACKED-DECIMAL [47](#)
  - PICTURE clause [41](#), [43](#)
  - storage formats [44](#)
  - USAGE DISPLAY [41](#)
  - USAGE NATIONAL [41](#)
  - zoned decimal (USAGE DISPLAY)
    - format [45](#)
    - sign representation [51](#)
- numeric intrinsic functions
  - differences from Language Environment callable services [56](#)
  - equivalent Language Environment callable services [56](#)
  - example of
    - ANNUITY [58](#)
    - CURRENT-DATE [58](#)
    - INTEGER [110](#)
    - INTEGER-OF-DATE [58](#)
    - LENGTH [58](#), [116](#)
    - LOG [59](#)
    - MAX [58](#), [86](#), [115](#), [116](#)
    - MEAN [59](#)
    - MEDIAN [59](#), [86](#)
    - MIN [109](#)
    - NUMVAL [113](#)
    - NUMVAL-C [58](#), [113](#)
    - ORD [115](#)
    - ORD-MAX [86](#)
    - PRESENT-VALUE [58](#)
    - RANGE [59](#), [86](#)
    - REM [59](#)
    - SQRT [59](#)
    - SUM [86](#)
  - integer, floating-point, mixed [54](#)
  - nested [55](#)
  - special registers as arguments [55](#)

- numeric intrinsic functions (*continued*)
  - table elements as arguments [55](#)
  - uses for [54](#)
- numeric literals, description [23](#)
- numeric-edited data
  - BLANK WHEN ZERO clause
    - coding with numeric data [125](#)
    - example [43](#)
  - defining [125](#)
  - editing symbols [43](#)
  - initializing
    - examples [28](#)
    - using INITIALIZE [72](#)
  - PICTURE clause [43](#)
  - USAGE DISPLAY
    - displaying [43](#)
    - initializing, example of [28](#)
  - USAGE NATIONAL
    - displaying [43](#)
    - initializing, example of [28](#)
- NUMPROC compiler option
  - affected by NUMCLS [52](#)
  - description [322](#)
  - effect on sign processing [51](#)
  - performance considerations [642](#)
- NUMVAL intrinsic function
  - description [113](#)
- NUMVAL-C intrinsic function
  - description [113](#)
  - example [58](#)
- NX delimiter for national literals [24](#)

## O

- o suffix with cob2 [270](#), [271](#)
- object
  - creating [584](#)
  - definition of [561](#)
  - deleting [585](#)
- object code
  - compilation and listing [257](#)
  - creating [253](#)
  - generating [297](#)
  - producing in 80-column record [301](#)
- OBJECT compiler option
  - description [323](#)
  - multioption interaction [287](#)
- object instances, definition of [561](#)
- OBJECT paragraph
  - instance data [567](#), [588](#)
  - instance methods [568](#)
- object references
  - comparing [579](#)
  - converting from local to global [584](#)
  - example of passing [582](#)
  - setting [579](#)
  - typed [578](#)
  - universal [578](#)
- OBJECT-COMPUTER paragraph [5](#)
- object-oriented COBOL
  - binding
    - example [279](#)
    - overview [278](#)
  - calls to and from OO programs [461](#)

- object-oriented COBOL (*continued*)
  - communicating with Java [606](#)
  - compatibility [281](#)
  - compiling
    - under z/OS UNIX [273](#)
    - using JCL or TSO/E [277](#)
  - DLLs in [488](#)
  - IMS
    - accessing databases [433](#)
    - calling COBOL method from Java [431](#)
    - calling Java method from COBOL [432](#)
  - linking
    - example [275](#)
    - overview [274](#)
  - preparing applications
    - under z/OS UNIX [274](#)
    - using JCL or TSO/E [278](#)
  - programs must be reentrant [464](#)
  - restrictions
    - cannot run under CICS [407](#)
    - CICS [561](#)
    - EXEC CICS statements [561](#)
    - EXEC SQL statements [561](#)
    - sort and merge [205](#)
    - SQL compiler option [561](#)
    - SQL statements [418](#)
  - running
    - under z/OS UNIX [275](#)
    - using JCL or TSO/E [278](#)
    - XPLINK linkage [280](#)
  - writing OO programs [561](#)
- OCCURS clause
  - ASCENDING|DESCENDING KEY phrase
    - example [84](#)
    - needed for binary search [84](#)
    - specify order of table elements [66](#)
  - cannot use in a level-01 item [66](#)
  - defining tables [65](#)
  - for defining table elements [66](#)
  - INDEXED BY phrase for creating indexes [70](#)
  - nested for creating multidimensional tables [66](#)
- OCCURS DEPENDING ON (ODO) clause
  - complex [79](#)
  - for creating variable-length tables [76](#)
  - initializing ODO elements [78](#)
  - ODO object [76](#)
  - ODO subject [76](#)
  - optimization [637](#)
  - simple [76](#)
  - variable-length records
    - QSAM [154](#)
    - VSAM [180](#)
- OCCURS INDEXED BY clause, creating indexes with [70](#)
- ODO object [76](#)
- ODO subject [76](#)
- OFFSET compiler option
  - description [324](#)
  - multioption interaction [287](#)
  - output [402](#)
- OMITTED clause, FILE SECTION [12](#)
- OMITTED parameters [651](#)
- OMITTED phrase for omitting arguments [469](#)
- ON EXCEPTION phrase
  - INVOKE statement [580](#), [593](#)

- OPEN statement
  - file availability [160, 182, 202](#)
  - file status key [229](#)
  - line-sequential files [201](#)
  - multithreading serialization [494](#)
  - QSAM files [160](#)
  - VSAM files [180](#)
- opening files
  - line-sequential [202](#)
  - multithreading serialization [494](#)
  - QSAM [160](#)
  - VSAM
    - empty [183](#)
    - overview [182](#)
- OPTFILE compiler option [324](#)
- optimization
  - avoid ALTER statement [634](#)
  - BINARY data items [635](#)
  - consistent data [635](#)
  - constant data items [634](#)
  - contained program integration [639](#)
  - effect of compiler options on [639](#)
  - effect on parameter passing [469](#)
  - effect on performance [633](#)
  - factor expressions [634](#)
  - index computations [637](#)
  - indexing [636](#)
  - nested program integration [639](#)
  - OCCURS DEPENDING ON [637](#)
  - out-of-line PERFORM [634](#)
  - packed-decimal data items [635](#)
  - performance implications [637](#)
  - procedure integration [639](#)
  - structured programming [633](#)
  - subscript computations [637](#)
  - subscripting [636](#)
  - table elements [636](#)
  - top-down programming [634](#)
  - unreachable code [639](#)
  - unused data items [325, 376](#)
- OPTIMIZE compiler option
  - description [325](#)
  - effect on parameter passing [469](#)
  - performance considerations [638, 642](#)
- optimizer
  - overview [638](#)
- optional files
  - QSAM [161](#)
  - VSAM [183](#)
- ORD intrinsic function, example [115](#)
- ORD-MAX intrinsic function
  - example table calculation [86](#)
  - using [115](#)
- ORD-MIN intrinsic function [115](#)
- order of evaluation
  - arithmetic operators [54, 656](#)
  - compiler options [287](#)
- out-of-line PERFORM [97](#)
- OUTDD compiler option
  - DD not allocated [35](#)
  - description [326](#)
  - interaction with DISPLAY [34](#)
- output
  - coding for CICS [408](#)

- output (*continued*)
  - coding for line-sequential files [201](#)
  - coding for QSAM files [160](#)
  - coding for VSAM files [180](#)
  - data set [253](#)
  - from compiler, under z/OS [250](#)
  - to files [145](#)
- output files with cob2 [270](#)
- output procedure
  - coding [210](#)
  - example [210, 214](#)
  - FASTSRT option not effective [216](#)
  - requires RETURN or RETURN INTO [210](#)
  - restrictions [211](#)
- overflow condition
  - CALL [233](#)
  - joining and splitting strings [224](#)
  - UNSTRING [103](#)
- overloading instance methods [573](#)
- overriding
  - factory methods [592](#)
  - instance methods [572](#)

## P

- packed decimal data [320](#)
- packed-decimal data item
  - description [47](#)
  - sign representation [51](#)
  - synonym [44](#)
  - using efficiently [47, 635](#)
- page
  - control [162](#)
  - depth [12](#)
- paragraph
  - definition [17](#)
  - grouping [99](#)
- parameters
  - accessing from main program in
    - z/OS
      - example [479](#)
      - overview [478](#)
    - accessing from main program in z/OS
      - UNIX
        - example [440](#)
        - overview [440](#)
  - ADEXIT [690](#)
  - describing in called program [468](#)
  - INEXIT [684](#)
  - LIBEXIT [687](#)
  - MSGEXIT [692](#)
  - PRTEXIT [689](#)
- PARMCHECK compiler option [327](#)
- parse data item, definition [508](#)
- parsing XML documents
  - description [508](#)
  - one segment at a time
    - example [540](#)
    - overview [519](#)
  - overview [506](#)
  - UTF-8 [526](#)
  - white space [523](#)
  - with validation
    - example [542](#)

- parsing XML documents *(continued)*
  - with validation *(continued)*
    - overview [516](#)
    - performance considerations [517](#)
    - restrictions [517](#)
  - XML declaration [523](#)

- passing data between programs
  - addresses [471](#)
  - arguments in calling program [468](#)
  - BY CONTENT [465](#)
  - BY REFERENCE [465](#)
  - BY VALUE
    - overview [465](#)
    - restrictions [468](#)
  - EXTERNAL data [475](#)
  - JNI services [602](#)
  - OMITTED arguments [469](#)
  - options considerations [39](#)
  - parameters in called program [468](#)
  - RETURN-CODE special register [474](#)
  - with Java [605](#)

- password
  - alternate index [189](#)
  - example [189](#)
  - VSAM files [188](#)
- PASSWORD clause [188](#)
- PATH environment variable
  - description [437](#)
  - example of setting [278](#)

- path name
  - for copybook search [269](#), [357](#)
- PERFORM statement
  - coding loops [96](#)
  - for a table
    - example using indexing [75](#)
    - example using subscripting [74](#)
  - for changing an index [70](#)
  - inline [97](#)
  - out-of-line [97](#)
  - performed an explicit number of times [97](#)
  - TEST AFTER [98](#)
  - TEST BEFORE [98](#)
  - THRU [99](#)
  - TIMES [97](#)
  - UNTIL [98](#)
  - VARYING [98](#)
  - VARYING WITH TEST AFTER [98](#)
  - WITH TEST AFTER . . . UNTIL [98](#)
  - WITH TEST BEFORE . . . UNTIL [98](#)

- performance
  - AIXBLD runtime option [644](#)
  - and debugging [341](#)
  - APPLY WRITE-ONLY clause [10](#)
  - arithmetic evaluations [634](#)
  - arithmetic expressions [635](#)
  - blocking QSAM files [158](#), [293](#)
  - calls [456](#)
  - CBLPSHPOP considerations [415](#)
  - CBLPSHPOP runtime option [415](#)
  - CICS
    - overview [633](#)
  - CICS coding [644](#)
  - coding for [633](#)
  - coding tables [636](#)

- performance *(continued)*

- compiler option
  - AFP [640](#)
  - ARCH [640](#)
  - ARITH [640](#)
  - AWO [640](#)
  - BLOCK0 [640](#)
  - DYNAM [641](#)
  - FASTSRT [641](#)
  - HGPR [641](#)
  - INLINE [641](#)
  - MAXPCF [641](#)
  - NUMPROC [51](#), [642](#)
  - OPTIMIZE [638](#), [642](#)
  - RENT [642](#)
  - RMODE [642](#)
  - SQLCCSID [424](#)
  - SSRANGE [642](#)
  - TEST [642](#)
  - THREAD [344](#), [642](#)
  - TRUNC [345](#), [643](#)

- consistent data types [635](#)

- data usage [635](#)
- effect of compiler options on [639](#)
- effects of buffer size [294](#)
- exponentiations [636](#)
- FASTSRT [216](#)
- IMS environment [430](#), [644](#)
- OCCURS DEPENDING ON [637](#)

- optimizer
  - overview [638](#)
- order of WHEN phrases in EVALUATE [91](#)
- out-of-line PERFORM compared with inline [97](#)
- parsing XML documents with validation [517](#)
- programming style [633](#)
- sorting with FASTSRT [216](#)
- striped extended-format QSAM data sets [169](#)
- table handling [637](#)
- table searching
  - binary compared with serial [83](#)
  - improving serial search [83](#)
- tape, QSAM [159](#)
- tuning [633](#)
- variable subscript data format [69](#)
- VSAM files [195](#), [644](#)
- worksheet [643](#)

- period as scope terminator [19](#)

- PGMNAME compiler option
  - COMPAT suboption [328](#)
  - description [328](#)
  - LONGMIXED suboption [329](#)
  - LONGUPPER suboption [328](#)

- phrase, definition of [17](#)

- physical block [145](#)

- physical record [13](#), [145](#)

- PICTURE clause
  - cannot use for internal floating point [42](#)
  - determining symbol used [299](#)
  - incompatible data [51](#)
  - N for national data [125](#)
  - national-edited data [125](#)
  - numeric data [41](#)
  - numeric-edited data [125](#)
  - Z for zero suppression [43](#)

- PL/I tasking
  - POSIX runtime option [496](#)
  - with COBOL [496](#)
- pointer data item
  - description [37](#)
  - incrementing addresses with [472](#)
  - NULL value [471](#)
  - passing addresses [471](#)
  - processing chained lists [471](#)
  - used to process chained list [472](#)
- porting applications
  - effect of separate sign [42](#)
- POSIX
  - calling APIs [438](#)
  - threads [496](#)
- POSIX runtime option
  - effect on DLL search order [484](#)
  - use in OO applications [278](#)
- precedence
  - arithmetic operators [54](#), [656](#)
  - CICS options [411](#)
  - compiler options
    - in batch [259](#)
    - in SYSOPTF data sets [252](#), [325](#)
    - under z/OS [255](#)
    - under z/OS UNIX [266](#)
  - copybook search order [265](#)
- preferred sign [51](#)
- preinitializing the COBOL environment
  - with multithreading [493](#)
- PRESENT-VALUE intrinsic function [58](#)
- preserving original sequence in a sort [215](#)
- priority numbers, segmentation [640](#)
- procedure and data-name cross-reference, description [369](#)
- PROCEDURE DIVISION
  - additional information [382](#)
  - client [576](#)
  - description [16](#)
  - in subprograms [470](#)
  - instance method [571](#)
  - RETURNING
    - to return a value [16](#)
    - using [474](#)
  - signature information bytes [382](#)
  - statements
    - compiler-directing [19](#)
    - conditional [18](#)
    - delimited scope [18](#)
    - imperative [17](#)
  - terminology [16](#)
  - USING
    - BY VALUE [470](#)
    - to receive parameters [16](#), [468](#)
  - verbs present in [382](#)
- procedure integration [639](#)
- procedure-pointer data item
  - calling C/C++ [463](#)
  - calling JNI services [463](#)
  - definition [461](#)
  - entry address for entry point [461](#)
  - passing parameters to callable services [461](#)
  - SET procedure-pointer [461](#)
  - with DLLs [486](#)
- process
  - process (continued)*
    - definition [491](#)
  - PROCESS (CBL) statement
    - batch compiling [259](#)
    - conflicting options in [287](#)
    - overview [359](#)
    - precedence
      - in batch [259](#)
      - under z/OS [255](#)
      - under z/OS UNIX [266](#)
    - specifying compiler options [256](#)
  - processing
    - chained lists
      - example [472](#)
      - overview [471](#)
    - tables
      - example using indexing [75](#)
      - example using subscripting [74](#)
- producing XML output [545](#)
- product support [xxviii](#), [873](#)
- program
  - attribute codes [381](#)
  - compiling and linking using cob2
    - DLLs [268](#)
    - examples [268](#)
    - overview [267](#)
  - compiling under z/OS [237](#)
  - compiling under z/OS UNIX [265](#)
  - decisions
    - EVALUATE statement [89](#)
    - IF statement [89](#)
    - loops [97](#)
    - PERFORM statement [97](#)
    - switches and flags [94](#)
  - developing for z/OS UNIX [435](#)
  - diagnostics [374](#)
  - initialization code [390](#)
  - limitations [633](#)
  - main [449](#)
  - nesting level [375](#)
  - reentrant [464](#)
  - restarting [622](#)
  - signature information bytes [382](#)
  - statistics [374](#)
  - structure [3](#)
  - subprogram [449](#)
- PROGRAM COLLATING SEQUENCE clause
  - does not affect national or DBCS operands [7](#)
  - establishing collating sequence [6](#)
  - overridden by COLLATING SEQUENCE phrase [6](#)
  - overrides default collating sequence [214](#)
- Program information
  - listing example [392](#)
- program processing table [409](#)
- Program prolog area
  - listing example [393](#)
- program termination
  - actions taken in main and subprogram [450](#)
  - statements [450](#)
- PROGRAM-ID paragraph
  - coding [3](#)
  - COMMON attribute [4](#)
  - INITIAL clause [4](#)

- program-names
  - avoid using certain prefixes [3](#)
  - cross-reference [399](#)
  - handling of case [328](#)
  - specifying [3](#)
- protecting VSAM files [188](#)
- PRTEXIT suboption of EXIT option
  - processing of [688](#)
  - syntax [306](#)

## Q

- QSAM files
  - adding records to [161](#)
  - ASCII tape file [171](#)
  - ASSIGN clause [151](#)
  - attributes [167](#)
  - BLOCK CONTAINS clause [158](#), [293](#)
  - block size [158](#), [293](#)
  - blocking enhances performance [158](#), [293](#)
  - blocking records [158](#), [170](#)
  - closing [162](#)
  - closing to prevent reopening [160](#)
  - DATA DIVISION entries [152](#)
  - ENVIRONMENT DIVISION entries [151](#)
  - FASTSRT requirements [217](#)
  - input/output error processing [163](#), [225](#)
  - input/output statements for [160](#)
  - obtaining buffers for [170](#)
  - opening [160](#)
  - processing
    - existing files [168](#)
    - in reverse order [161](#)
    - new files [169](#)
    - overview [151](#)
    - z/OS UNIX files [170](#)
  - replacing records [161](#)
  - retrieving [166](#)
  - striped extended-format [169](#)
  - tape performance [159](#)
  - under z/OS
    - creating files [164](#), [166](#)
    - DD statement for [164](#), [166](#)
    - defining [164](#), [166](#)
    - environment variable for [164](#)
    - file availability [161](#)
    - job control language (JCL) [165](#)
  - updating files [161](#)
  - using same input/output file under FASTSRT [217](#)
  - writing to a printer [162](#)
- QUALIFY compiler option [330](#)
- QUOTE compiler option [289](#)

## R

- railroad track diagrams, how to read [xxvi](#)
- random numbers, generating [56](#)
- RANGE intrinsic function
  - example statistics calculation [59](#)
  - example table calculation [86](#)
- RD parameter of JOB or EXEC statement [622](#)
- READ INTO for format-V VSAM files [180](#)

- READ NEXT statement [180](#)
- READ statement
  - AT END phrase [228](#)
  - line-sequential files [201](#)
  - multithreading serialization [494](#)
  - QSAM [160](#)
  - VSAM [180](#)
- reading records
  - block size [158](#)
  - from line-sequential files [202](#)
- reading records from VSAM files
  - dynamically [185](#)
  - randomly [185](#)
  - sequentially [185](#)
- reason code from XML parsing [527](#), [671](#)
- record
  - description [11](#)
  - format
    - fixed-length QSAM [152](#), [153](#)
    - fixed-length VSAM [179](#)
    - format D [153](#), [154](#), [171](#)
    - format F [152](#), [153](#), [171](#)
    - format S [155](#), [156](#)
    - format U [157](#), [171](#)
    - format V [153](#), [154](#), [171](#)
    - QSAM ASCII tape [171](#)
    - spanned [155](#), [156](#)
    - undefined [157](#)
    - variable-length QSAM [153](#), [154](#)
    - variable-length VSAM [180](#)
  - order, effect of organization on [145](#)
- RECORD CONTAINS clause
  - FILE SECTION entry [12](#)
- RECORD KEY clause
  - identifying prime key in KSDS files [176](#)
- RECORDING MODE clause
  - fixed-length records, QSAM [152](#)
  - QSAM files [13](#)
  - specify record format [152](#)
  - variable-length records, QSAM [153](#), [154](#)
- recursive calls
  - and the LINKAGE SECTION [15](#)
  - coding [461](#)
  - identifying [4](#)
- REDEFINES clause, making a record into a table using [73](#)
- reentrant programs [464](#)
- reference modification
  - example [108](#)
  - expression checking with SSRANGE [338](#)
  - generated XML documents [546](#)
  - intrinsic functions [107](#)
  - national data [107](#)
  - out-of-range values [108](#)
  - tables [69](#), [107](#)
  - UTF-8 documents [135](#)
- reference modifier
  - arithmetic expression as [109](#)
  - intrinsic function as, example [109](#)
  - variables as [108](#)
- registers used by EXIT compiler option [684](#)
- relation condition [93](#)
- relative file organization [146](#)
- RELEASE FROM statement
  - compared to RELEASE [209](#)

RELEASE FROM statement (*continued*)

example [208](#)

RELEASE statement

compared to RELEASE FROM [209](#)

with SORT [208](#), [209](#)

REM intrinsic function [59](#)

RENT compiler option

description [330](#)

for DLLs [482](#)

for IMS [430](#)

for Java interoperability [273](#), [277](#)

for OO COBOL [273](#), [277](#)

influencing addressability [39](#)

multioption interaction [38](#), [287](#)

performance considerations [642](#)

when passing data [39](#)

REPLACE statement

DB2 considerations [424](#)

description [359](#)

replacing

data items (INSPECT) [110](#)

records in QSAM file [161](#)

records in VSAM file [187](#)

text, DB2 considerations [424](#)

REPLACING phrase (INSPECT), example [110](#)

REPOSITORY paragraph

class [566](#)

client [577](#)

coding [5](#)

subclass [588](#)

representation

data [51](#)

sign [51](#)

RERUN clause

checkpoint/restart [221](#)

reserved-word table, CICS

alternate

overview [414](#)

specifying with WORD [349](#)

residency mode, definition [37](#)

restart

automatic [622](#)

automatic or deferred [619](#)

deferred [623](#)

overview [619](#)

restarting a program [622](#)

restrictions

CICS

16 MB line [408](#)

calls [409](#)

coding [407](#)

files [5](#)

OUTDD compiler option [327](#)

parsing with validation using FILE [517](#)

separate translator [412](#)

sorting [222](#)

DB2 coprocessor [421](#)

IMS

16 MB line [408](#)

coding [5](#), [427](#)

IMS SQL coprocessor [429](#)

input/output procedures [211](#)

OO programs [561](#)

SQL compiler option [421](#)

restrictions (*continued*)

SQL statements [418](#)

SQLIMS compiler option [429](#)

subscripting [69](#)

resubmitting a job [624](#)

return code

compiler

depends on highest severity [264](#)

effect of message customization [695](#)

overview [263](#)

feedback code from Language Environment services [651](#)

from CICS ECI [410](#)

from DB2 SQL statements [421](#)

from XML parsing [527](#), [671](#)

RETURN-CODE special register [474](#), [651](#)

VSAM files

description [230](#)

example [231](#)

RLS mode [194](#)

when control returns to operating system [474](#)

RETURN statement

required in output procedure [210](#)

with INTO phrase [210](#)

RETURN-CODE special register

calls to Language Environment services [651](#)

CICS ECI calls [410](#)

considerations for DB2 [421](#)

not set by INVOKE [580](#)

passing data between programs [474](#)

sharing return codes between programs [474](#)

when control returns to operating system [474](#)

RETURNING phrase

CALL statement [475](#)

INVOKE statement [583](#)

PROCEDURE DIVISION header [474](#), [571](#)

REVERSE intrinsic function [112](#)

reverse order of tape files [161](#)

reversing characters [112](#)

REWRITE statement

multithreading serialization [494](#)

QSAM [160](#)

VSAM [180](#)

RLS parameter [193](#)

RMODE

description [37](#)

of EXIT modules [684](#)

RMODE compiler option

description [331](#)

influencing addressability [37](#)

multioption interaction [37](#)

performance considerations [642](#)

when passing data [39](#)

ROUNDED phrase [656](#)

rows in tables [67](#)

RRDS (relative-record data sets)

file access mode [178](#)

fixed-length records [174](#), [178](#)

organization [177](#)

performance considerations [196](#)

simulating variable-length records [178](#)

variable-length records [174](#), [178](#)

RULES compiler option

description [332](#)

- run time
  - accessing arguments in
    - z/OS
      - example [479](#)
      - overview [478](#)
    - accessing arguments in z/OS UNIX
      - example [440](#)
      - overview [440](#)
  - changing file-name [9](#)
  - multithreading restrictions [497](#)
  - performance [633](#)
- run unit
  - description [449](#)
  - role in multithreading [491](#)
- running OO applications
  - under z/OS UNIX
    - overview [275](#)
    - XPLINK linkage [280](#)
  - using JCL or TSO/E [278](#)
  - XPLINK linkage [280](#)
- runtime options
  - 85 COBOL Standard conformance [286](#)
  - AIXBLD [644](#)
  - ALL31 [454](#)
  - CBLOPTS [478](#)
  - CBLPSHPOP [415](#)
  - DEBUG [364](#)
  - ENVAR [278](#)
  - MSGFILE [326](#)
  - NOSIMVRD [178](#)
  - POSIX
    - DLL search order [484](#)
    - use in OO applications [278](#)
  - specifying under z/OS [478](#)
  - specifying under z/OS UNIX [435](#)
  - TRAP
    - closing files in QSAM [162](#)
    - closing files in VSAM [187](#)
    - closing line-sequential files [203](#)
    - ON SIZE ERROR [224](#)
  - XPLINK
    - not recommended as a default [280](#)
    - setting [280](#)

## S

- S-format record
  - layout [156](#)
  - overview [156](#)
  - requesting [155](#)
- S-level error message [264](#), [367](#)
- sample programs [805](#)
- scope of names
  - global [460](#)
  - local [460](#)
- scope terminator
  - aids in debugging [362](#)
  - explicit [18](#), [19](#)
  - implicit [19](#)
- SD (sort description) entry, example [208](#)
- SEARCH ALL statement
  - binary search [84](#)
  - example [84](#)

- SEARCH ALL statement (*continued*)
  - for changing an index [70](#)
  - table must be ordered [84](#)
- search order
  - DLLs in the z/OS UNIX file system [484](#)
- SEARCH statement
  - example [83](#)
  - for changing an index [70](#)
  - nesting to search more than one level of a table [83](#)
  - serial search [83](#)
- searching
  - for name declarations [461](#)
  - tables
    - binary search [84](#)
    - overview [82](#)
    - performance [83](#)
    - serial search [83](#)
- section
  - declarative [20](#)
  - definition [17](#)
  - grouping [99](#)
- segmentation [640](#)
- SELECT clause
  - ASSIGN clause [8](#)
  - naming files [8](#)
  - vary input-output file [9](#)
- SELECT OPTIONAL
  - QSAM [161](#)
  - VSAM [183](#)
- SELF [579](#)
- sentence, definition of [17](#)
- separate CICS translator
  - compiler options for [411](#), [413](#)
  - restrictions [412](#)
  - using [413](#)
- separate sign
  - for line-sequential files [203](#)
  - portability [42](#)
  - printing [42](#)
  - required for signed national decimal [42](#)
- SEQUENCE compiler option [333](#)
- sequential file organization [145](#)
- sequential search
  - description [83](#)
  - example [83](#)
- sequential storage device [146](#)
- serial search
  - description [83](#)
  - example [83](#)
- serialization of files with multithreading [494](#)
- SERVICE compiler option [334](#)
- SERVICE LABEL statement [359](#)
- SET condition-name TO TRUE statement
  - example [97](#), [98](#)
  - switches and flags [95](#)
- SET statement
  - for changing an index [70](#)
  - for changing index data items [70](#)
  - for function-pointer data items [461](#)
  - for object references [579](#)
  - for procedure-pointer data items [461](#)
  - for setting a condition, example [95](#)
  - handling of program-name in [328](#)

- SET statement (*continued*)
  - using for debugging [363](#)
- setting
  - index data items [70](#)
  - indexes [70](#)
  - switches and flags [95](#)
- sharing
  - data
    - between separately compiled programs [475](#)
    - coding the LINKAGE SECTION [469](#)
    - from another program [15](#)
    - in recursive or multithreaded programs [15](#)
    - in separately compiled programs [15](#)
    - overview [465](#)
    - parameter-passing mechanisms [465](#)
    - passing arguments to a method [581](#)
    - PROCEDURE DIVISION header [470](#)
    - RETURN-CODE special register [474](#)
    - returning a value from a method [583](#)
    - scope of names [460](#)
    - with Java [605](#)
  - files
    - scope of names [460](#)
    - using EXTERNAL clause [11](#), [475](#)
    - using GLOBAL clause [11](#)
- short listing, example [372](#)
- sign condition
  - testing sign of numeric operand [93](#)
- SIGN IS SEPARATE clause
  - for line-sequential files [203](#)
  - portability [42](#)
  - printing [42](#)
  - required for signed national decimal data [42](#)
- sign representation [51](#)
- signature
  - definition of [569](#)
  - must be unique [569](#)
- signature information bytes
  - compiler options in effect [382](#)
  - DATA DIVISION [382](#)
  - ENVIRONMENT DIVISION [382](#)
  - PROCEDURE DIVISION [382](#)
- size of printed page, control [162](#)
- skip a block of records [158](#)
- softcopy information [xxviii](#)
- sort
  - alternate collating sequence [214](#)
  - checkpoint/restart [221](#)
  - completion code [215](#)
  - controlling behavior of [219](#)
  - criteria [213](#)
  - data sets needed under z/OS [211](#)
  - DD statements for defining z/OS data sets [211](#)
  - description [205](#)
  - determining success [215](#)
  - diagnostic message [215](#)
  - FASTSRT compiler option
    - improving performance [216](#)
    - requirements [216](#)
    - using same QSAM file for input and output [217](#)
  - files, describing [207](#)
  - input procedures
    - coding [208](#)
    - example [214](#)
  - sort (*continued*)
    - keys
      - defining [213](#)
      - overview [206](#)
    - NOFASTSRT compiler option [218](#)
    - output procedures
      - coding [210](#)
      - example [210](#), [214](#)
    - pass control statements to [220](#)
    - performance
      - FASTSRT [216](#)
      - variable-length files [212](#)
    - preserving original sequence [215](#)
    - process [206](#)
    - restrictions [205](#)
    - restrictions on input/output procedures [211](#)
    - special registers [219](#)
    - storage use [220](#)
    - terminating [216](#)
    - under CICS [221](#)
    - variable-length records [212](#)
    - work files
      - describing [206](#)
      - workspace [221](#)
- SORT statement
  - ASCENDING|DESCENDING KEY phrase [213](#)
  - COLLATING SEQUENCE phrase [6](#), [214](#)
  - description [212](#)
  - GIVING phrase [212](#)
  - overview [205](#)
  - restrictions [205](#)
  - restrictions for CICS applications [222](#)
  - under CICS
    - change reserved-word table [415](#)
    - USING phrase [212](#)
  - SORT-CONTROL special register [219](#)
  - SORT-CORE-SIZE special register [219](#)
  - SORT-FILE-SIZE special register [219](#)
  - SORT-MESSAGE special register [219](#)
  - SORT-MODE-SIZE special register [219](#)
  - SORT-RETURN special register
    - determining sort or merge success [215](#)
    - terminating sort or merge [216](#)
- SORTCKPT DD statement [221](#)
- sorting
  - tables
    - overview [85](#)
- SOURCE and NUMBER output, example [375](#)
- source code
  - compiler data set [251](#)
  - line number [375](#), [376](#), [381](#)
  - listing, description [370](#)
  - program listing [257](#)
- SOURCE compiler option
  - description [334](#)
  - getting output [370](#)
- SOURCE-COMPUTER paragraph [5](#)
- SPACE compiler option [335](#)
- spanned files [156](#)
- spanned record format
  - description [155](#)
  - layout [156](#)
  - requesting [155](#)

- special feature specification [5](#)
- special register
  - ADDRESS OF
    - use in CALL statement [466](#)
  - arguments in intrinsic functions [55](#)
  - JNIEnvPtr
    - use for JNI callable services [601](#)
  - LENGTH OF [117](#), [466](#)
  - RETURN-CODE [474](#)
  - SORT-RETURN
    - determining sort or merge success [215](#)
    - terminating sort or merge [216](#)
  - using in XML parsing [509](#), [511](#)
  - WHEN-COMPILED [118](#)
  - XML-CODE [510](#), [512](#)
  - XML-EVENT [509](#), [511](#)
  - XML-INFORMATION [510](#)
  - XML-NAMESPACE [510](#), [515](#)
  - XML-NAMESPACE-PREFIX [510](#), [515](#)
  - XML-NNAMESPACE [510](#), [515](#)
  - XML-NNAMESPACE-PREFIX [510](#), [515](#)
  - XML-NTEXT [510](#), [514](#)
  - XML-TEXT [510](#), [514](#)
- special register table [396](#)
- SPECIAL-NAMES paragraph
  - coding [5](#)
  - QSAM files [171](#)
- splitting data items (UNSTRING) [103](#)
- SQL compiler option
  - description [335](#)
  - restrictions
    - compiling in batch [421](#)
    - OO programs [561](#)
  - using [421](#)
- SQL statements
  - CCSID determination [422](#)
  - coding
    - overview [418](#)
    - restriction [418](#)
  - EXIT compiler option and [701](#)
  - overview [417](#)
  - restrictions [418](#)
  - return codes [421](#)
  - SQL DECLARE [419](#)
  - SQL INCLUDE [418](#)
  - use for DB2 services [417](#)
  - using binary data in [420](#)
  - using character data in [419](#)
  - using national decimal data [420](#)
- SQLCA
  - declare for programs that use SQL statements [418](#)
  - declare for programs that use SQLIMS statements [428](#)
  - return codes from DB2 [421](#)
- SQLCCSID compiler option
  - description [336](#)
  - effect on CCSID of string data [422](#)
  - performance considerations [424](#)
  - recommended with DB2 coprocessor [423](#)
- SQLIMS compiler option
  - restrictions
    - compiling in batch [429](#)
  - using [429](#)
- SQLIMS statements
  - coding
    - SQLIMS statements (*continued*)
      - coding (*continued*)
        - overview [428](#)
      - EXIT compiler option and [701](#)
      - SQLIMS INCLUDE [428](#)
    - SQRT intrinsic function [59](#)
    - SSRANGE compiler option
      - description [338](#)
      - performance considerations [642](#)
      - reference modification [108](#)
      - using [366](#)
    - STACK runtime option
      - influencing data location [39](#)
      - multioption interaction [38](#)
    - STANDARD clause, FD entry [12](#)
    - START statement
      - multithreading serialization [494](#)
      - VSAM [180](#)
    - statement
      - compiler-directing [19](#)
      - conditional [18](#)
      - definition [17](#)
      - delimited scope [18](#)
      - explicit scope terminator [19](#)
      - imperative [17](#)
      - implicit scope terminator [19](#)
      - nesting level [375](#)
    - statement cross-reference listing
      - description [370](#)
    - statements used in program [370](#)
    - static calls
      - example [456](#)
      - making [452](#)
      - performance [456](#)
      - with dynamic calls [456](#)
    - static data areas, allocating storage [39](#)
    - static data, definition of [561](#)
    - Static map [394](#)
    - static methods
      - definition of [561](#)
      - invoking [593](#)
    - statistics intrinsic functions [59](#)
    - status code, VSAM files
      - description [230](#)
      - example [231](#)
    - stderr
      - controlling line spacing [35](#)
      - directing with DISPLAY [35](#)
      - setting DISPLAY to [437](#)
    - stdin
      - reading with ACCEPT [33](#)
    - stdout
      - controlling line spacing [35](#)
      - directing with DISPLAY [35](#)
      - setting DISPLAY to [437](#)
    - STEPLIB environment variable
      - description [437](#)
      - example of specifying compiler [267](#)
    - STGOPT compiler option [339](#)
    - STOP RUN statement
      - in main program [450](#)
      - in subprogram [450](#)
      - with multithreading [450](#)
    - storage

- storage (*continued*)
  - character data [131](#)
  - device
    - direct-access [146](#)
    - sequential [146](#)
  - for arguments [468](#)
  - management with Language Environment callable services [649](#)
  - mapping [370](#)
  - use during sort [220](#)
- stride, table [637](#)
- STRING statement
  - example [102](#)
  - overflow condition [224](#)
  - using [101](#)
  - with DBCS data [665](#)
- strings
  - handling [101](#)
  - Java
    - declaring [606](#)
    - manipulating [610](#)
    - null-terminated [471](#)
  - striped extended-format QSAM file [169](#)
  - structure, initializing using INITIALIZE [29](#)
  - structured programming [634](#)
  - structuring OO applications [598](#)
- subclass
  - coding
    - example [589](#)
    - overview [586](#)
  - instance data [588](#)
- subprogram
  - and main program [449](#)
  - definition [465](#)
  - description [449](#)
  - linkage
    - common data items [468](#)
  - PROCEDURE DIVISION in [470](#)
  - termination
    - effects [450](#)
- subscript
  - definition [68](#)
  - literal, example [68](#)
  - range checking [366](#)
  - variable, example [68](#)
- subscripting
  - definition [68](#)
  - example [74](#)
  - literal, example [68](#)
  - reference modification [69](#)
  - relative [69](#)
  - restrictions [69](#)
  - use data-name or literal [69](#)
  - variable, example [68](#)
- substitution character [126](#)
- substrings
  - of table elements [107](#)
  - reference modification of [107](#)
- SUM intrinsic function, example table calculation [86](#)
- SUPER [583](#)
- support xxviii, [873](#)
- SUPPRESS compiler option [340](#)
- switch-status condition [93](#)
- switches and flags (*continued*)
  - defining [94](#)
  - description [94](#)
  - resetting [95](#)
  - setting switches off, example [96](#)
  - setting switches on, example [95](#)
  - testing multiple values, example [95](#)
  - testing single values, example [94](#)
- SYMBOLIC CHARACTERS clause [8](#)
- symbolic constant [634](#)
- syntax diagrams, how to read xxvi
- syntax errors
  - finding with NOCOMPILE compiler option [365](#)
- SYSABEND file
  - description [250](#)
- SYSADATA
  - file, creating [254](#)
  - output [288](#)
  - records, exit module [690](#)
- SYSADATA file
  - description [250](#)
  - example [713](#)
  - file contents [711](#)
  - record descriptions [714](#)
  - record types [712](#)
- SYSIN data set
  - defining [251](#)
  - description [248](#)
- SYSJAVA file
  - defining [254](#)
  - description [250](#)
- SYSLIB data set
  - defining [252](#)
  - description [248](#)
  - when not used [685](#)
- SYSLIB environment variable
  - description [265](#)
  - specifying location of JNI.cpy [273](#)
- SYSLIN data set
  - description [250](#)
- SYSMDECK file
  - defining [254](#)
  - description [250](#)
- SYSMDUMP file
  - description [250](#)
- SYSOPTF data set
  - defining [252](#)
  - description [248](#)
- SYSPRINT data set
  - defining [253](#)
  - description [250](#)
  - when not used [688](#)
- SYSPUNCH data set
  - description [250](#), [253](#)
  - requirements for DECK compiler option [301](#)
- system date
  - under CICS [409](#)
- system dump [223](#)
- system-determined block size
  - compiler data sets [251](#)
  - QSAM files [158](#), [293](#)
- system-name [5](#)
- SYSTERM data set
  - defining [253](#)

SYSTEM data set (*continued*)  
description [250](#)  
sending messages to [340](#)  
SYSUDUMP file  
description [250](#)  
SYSUT data set [249](#)

## T

### table

- assigning values to [72](#)
- columns [65](#)
- compare to array [37](#)
- defining with OCCURS clause [65](#)
- definition [65](#)
- depth [67](#)
- description [37](#)
- dynamically loading [71](#)
- efficient coding [636](#), [637](#)
- elements [65](#)
- identical element specifications [636](#)
- index, definition [68](#)
- initializing
  - all occurrences of an element [74](#)
  - at the group level [74](#)
  - each item individually [73](#)
  - using INITIALIZE [71](#)
  - using PERFORM VARYING [98](#)
- loading values in [71](#)
- looping through [98](#)
- multidimensional [66](#)
- one-dimensional [65](#)
- processing with intrinsic functions [85](#)
- redefining a record as [73](#)
- reference modification [69](#)
- referencing substrings of elements [107](#)
- referencing with indexes, example [68](#)
- referencing with subscripts, example [68](#)
- referring to elements [68](#)
- rows [67](#)
- searching
  - binary [84](#)
  - overview [82](#)
  - performance [83](#)
  - sequential [83](#)
  - serial [83](#)
- sorting
  - overview [85](#)
- stride computation [637](#)
- subscript, definition [68](#)
- three-dimensional [67](#)
- two-dimensional [67](#)
- variable-length
  - creating [76](#)
  - example of loading [78](#)
  - initializing [78](#)
  - preventing overlay in [81](#)

TALLYING phrase (INSPECT), example [110](#)  
tape files

- performance [159](#)
- reverse order [161](#)

TERMINAL compiler option [340](#)  
terminal, sending messages to the [340](#)  
terminating XML parsing [531](#)

termination [450](#)  
terminology  
VSAM [173](#)  
terms used in MAP output [378](#)  
test

- conditions [97](#)
- data [93](#)
- numeric operand [93](#)
- UPSI switch [93](#)

TEST AFTER [98](#)  
TEST BEFORE [98](#)  
TEST compiler option

- description [340](#)
- multioption interaction [287](#)
- performance considerations [642](#)
- use for debugging [370](#)

text-name cross-reference, description [369](#)  
text-name environment variable [266](#)  
THREAD compiler option

- and the LINKAGE SECTION [15](#)
- cannot use with nested programs [458](#)
- description [343](#)
- for Java interoperability [273](#), [277](#)
- for OO COBOL [273](#), [277](#)
- multioption interaction [287](#)
- performance considerations [642](#)

threading

- and preinitialization [493](#)
- control transfer [493](#)
- ending programs [493](#)
- z/OS UNIX considerations [435](#)

TITLE statement

- controlling header on listing [5](#)

top-down programming

- constructs to avoid [634](#)

TRACK OVERFLOW option [159](#)  
Trademarks [830](#)  
transferring control

- between COBOL and non-COBOL programs [449](#)
- between COBOL programs [451](#), [458](#)
- called program [449](#)
- calling program [449](#)
- main and subprograms [449](#)
- nested programs [459](#)

transforming COBOL data to XML

- example [551](#)
- overview [545](#)

TRAP runtime option

- closing line-sequential files [203](#)
- closing QSAM files [162](#)
- closing VSAM files [187](#)
- ON SIZE ERROR [224](#)

TRUNC compiler option

- description [344](#)
- performance considerations [643](#)
- suboptions for separate CICS translator [414](#)

TSO

- ALLOCATE command [244](#)
- CALL command [244](#)
- compiling under
  - example CLIST [245](#)
  - overview [244](#)
- SYSTEM for compiler messages [253](#)

tuning considerations, performance [639](#), [640](#)  
typed object references [578](#)

## U

U-format record  
  layout [157](#)  
  requesting [157](#)  
U-level error message [264](#), [367](#)  
unavailable files  
  QSAM [161](#)  
  VSAM [189](#)  
UNBOUNDED groups  
  processing [86](#)  
undefined record format  
  layout [157](#)  
  QSAM [171](#)  
  requesting [157](#)  
unfilled tracks [159](#)  
Unicode  
  description [123](#)  
  encoding and storage [131](#)  
  JNI services [610](#)  
  processing data [119](#)  
  using with DB2 [419](#)  
universal object references [578](#)  
UNIX  
  calling APIs [438](#)  
  unreachable code [639](#)  
UNSTRING statement  
  example [104](#)  
  overflow condition [224](#)  
  using [103](#)  
  with DBCS data [665](#)  
updating VSAM records [185](#)  
UPPER-CASE intrinsic function [112](#)  
uppercase, converting to [112](#)  
UPSI switches with multithreading [497](#)  
USAGE clause  
  at the group level [23](#)  
  incompatible data [51](#)  
  INDEX phrase, creating index data items with [70](#)  
  NATIONAL phrase at the group level [128](#)  
  OBJECT REFERENCE [578](#)  
USE FOR DEBUGGING declaratives  
  overview [363](#)  
USE statement [359](#)  
user-defined condition [93](#)  
user-exit work area [683](#)  
USING phrase  
  INVOKE statement [581](#)  
  PROCEDURE DIVISION header [470](#), [571](#)  
UTF-16  
  definition [123](#)  
  encoding for national data [123](#)  
UTF-8  
  avoid INSPECT [526](#)  
  avoid moves that truncate [526](#)  
  avoid reference modification with XML documents [135](#)  
  converting to or from national [134](#)  
  definition [123](#)  
  encoding and storage [131](#)  
  encoding for ASCII invariant characters [123](#)  
  example of generating an XML document [547](#)

UTF-8 (*continued*)  
  JNI services [613](#)  
  parsing XML documents [526](#)  
  processing data items [134](#)  
  using intrinsic functions [135](#)  
UTF-8 data  
  using Unicode intrinsic functions [136](#)

## V

V-format record  
  layout [154](#)  
  requesting [153](#)  
validating XML documents  
  example [542](#)  
  overview [516](#)  
  performance considerations [517](#)  
  restrictions [517](#)  
VALUE clause  
  alphanumeric literal with national data, example [116](#)  
  alphanumeric literal with national group, example [74](#)  
  assigning table values  
    at the group level [74](#)  
    to each item individually [73](#)  
    to each occurrence of an element [74](#)  
  assigning to a variable-length group [78](#)  
  cannot use for external floating point [46](#)  
  initializing internal floating-point literals [42](#)  
  large literals with COMP-5 [47](#)  
  large, with TRUNC(BIN) [345](#)  
VALUE IS NULL [471](#)  
VALUE OF clause [12](#)  
variable  
  as reference modifier [108](#)  
  definition [21](#)  
variable-length records  
  OCCURS DEPENDING ON (ODO) clause [637](#)  
  QSAM  
    layout [154](#)  
    requesting [153](#)  
  sorting [212](#)  
  VSAM  
    defining [180](#)  
    RRDS [174](#)  
variable-length table  
  assigning values to [78](#)  
  creating [76](#)  
  example [77](#)  
  example of loading [78](#)  
  preventing overlay in [81](#)  
variables, environment  
  example of setting and accessing [438](#)  
  library-name [357](#)  
  runtime [437](#)  
variably located data item [80](#)  
variably located group [80](#)  
VBREF compiler option  
  description [347](#)  
  output example [403](#)  
  using [370](#)  
VLR compiler option  
  description [347](#)  
VSAM files  
  adding records to [186](#)

## VSAM files *(continued)*

- allocating with environment variable [192](#)
  - closing [187](#)
  - coding input/output statements [180](#)
  - comparison of file organizations [174](#)
  - creating alternate indexes [190](#)
  - DATA DIVISION entries [179](#)
  - deleting records from [187](#)
  - ENVIRONMENT DIVISION entries [175](#)
  - error processing [225](#)
  - extended addressability [196](#)
  - file position indicator (CRP) [182](#), [185](#)
  - file status key [188](#)
  - input/output error processing [188](#)
  - loading
    - dynamically or randomly [183](#)
    - extended format [184](#)
    - sequentially [183](#)
    - with access method services [184](#)
  - opening
    - empty [183](#)
    - overview [182](#)
  - performance considerations [195](#)
  - processing files [173](#)
  - protecting with password [188](#)
  - reading records from [185](#)
  - record-level sharing (RLS)
    - error handling [194](#)
    - overview [193](#)
    - preventing update problems [194](#)
    - restrictions [194](#)
  - replacing records in [187](#)
  - status codes
    - description [230](#)
    - example [231](#)
  - under z/OS
    - defining data sets [190](#)
    - file availability [189](#)
    - JCL [192](#)
    - RLS mode [193](#)
  - updating records [185](#)
- ## VSAM terminology
- BDAM data set [173](#)
  - comparison to non-VSAM terms [173](#)
  - ESDS for QSAM [173](#)
  - KSDS for ISAM [173](#)
  - RRDS for BDAM [173](#)
- ## VSAMOPENFS compiler option [349](#)

## W

- W-level message [263](#), [367](#)
- WHEN phrase
  - EVALUATE statement [91](#)
  - SEARCH ALL statement [84](#)
  - SEARCH statement [83](#)
- WHEN-COMPILED intrinsic function [118](#)
- WHEN-COMPILED special register [118](#)
- white space in XML documents [523](#)
- WITH DEBUGGING MODE clause
  - for debugging lines [364](#)
  - for debugging statements [364](#)
- WITH POINTER phrase

## WITH POINTER phrase *(continued)*

- STRING [101](#)
- UNSTRING [103](#)
- WORD compiler option
  - description [349](#)
  - multioption interaction [287](#)
  - recommended for CICS integrated translator [411](#)
  - recommended for CICS separate translator [413](#)
- work data sets for compiling [248](#)
- WORKING-STORAGE SECTION
  - client [578](#)
  - comparison with LOCAL-STORAGE
    - example [14](#)
    - OO client [578](#)
    - overview [13](#)
  - factory data [591](#)
  - instance data [567](#), [588](#)
  - instance method [570](#)
  - multithreading considerations [578](#)
  - storage location for data [300](#)
- workspace
  - use during sort [221](#)
- wrapper, definition of [598](#)
- wrapping procedure-oriented programs [598](#)
- Writable static area [394](#)
- write a block of records [158](#)
- WRITE ADVANCING statement [162](#)
- WRITE statement
  - line-sequential files [201](#)
  - multithreading serialization [494](#)
  - QSAM [160](#)
  - VSAM [180](#)

## X

- x suffix with cob2 [270](#), [271](#)
- XML declaration
  - generating [547](#)
  - specifying encoding declaration [525](#)
  - white space cannot precede [523](#)
- XML document
  - accessing [507](#)
  - code pages supported [522](#)
  - controlling the encoding of [550](#)
  - EBCDIC special characters [526](#)
  - encoding [522](#), [523](#)
  - enhancing
    - example of modifying data definitions [556](#)
    - rationale and techniques [555](#)
  - events
    - example [537](#)
  - generating
    - example [551](#)
    - overview [545](#)
  - handling parsing exceptions [527](#)
  - national language [523](#)
  - parser [506](#)
  - parsing
    - description [508](#)
    - example [532](#), [537](#), [540](#)
    - large documents [521](#)
    - one segment at a time [519](#)
    - UTF-8 [526](#)

- XML document (*continued*)
  - parsing with validation
    - example [542](#)
    - overview [516](#)
    - performance considerations [517](#)
    - restrictions [517](#)
  - processing [505](#)
  - specifying encoding if alphanumeric [525](#)
  - white space [523](#)
  - XML declaration [523](#)
- XML event
  - CONTENT-CHARACTERS
    - example [542](#)
    - when parsing segments [520](#)
  - encoding conflicts [529](#), [530](#)
  - END-OF-INPUT
    - example [542](#)
    - when parsing segments [519](#)
  - EXCEPTION [529](#)
  - fatal errors [529](#)
  - NAMESPACE-DECLARATION [515](#)
  - overview [511](#)
  - processing [506](#), [509](#)
  - processing procedure [508](#)
- XML exception codes
  - for generating [679](#)
  - for parsing [671](#)
  - for parsing with XMLPARSE(COMPAT)
    - handleable [673](#)
    - not handleable [676](#)
  - for parsing with XMLPARSE(XMLSS) [671](#)
- XML GENERATE statement
  - COUNT IN [551](#)
  - NAME [548](#)
  - NAMESPACE [547](#)
  - NAMESPACE-PREFIX [547](#)
  - NOT ON EXCEPTION [549](#)
  - ON EXCEPTION [550](#)
  - SUPPRESS [548](#)
  - TYPE [549](#)
  - WITH ATTRIBUTES [546](#)
  - WITH ENCODING [550](#)
  - XML-DECLARATION [547](#)
- XML generation
  - controlling type of XML data [549](#)
  - counting generated characters [546](#)
  - description [545](#)
  - enhancing output
    - example of modifying data definitions [556](#)
    - rationale and techniques [555](#)
  - example [551](#)
  - generating attributes [546](#)
  - generating elements [546](#)
  - handling errors [550](#)
  - ignored data items [546](#)
  - naming attributes or elements [548](#)
  - no byte order mark [550](#)
  - overview [545](#)
  - suppressing generation of specified attributes or elements [548](#)
  - using namespace prefixes [547](#)
  - using namespaces [547](#)
- XML output
  - controlling the encoding of [550](#)
- XML output (*continued*)
  - enhancing
    - example of modifying data definitions [556](#)
    - rationale and techniques [555](#)
  - generating
    - example [551](#)
    - overview [545](#)
  - XML PARSE statement
    - NOT ON EXCEPTION [508](#)
    - ON EXCEPTION [508](#)
    - overview [506](#)
    - using [508](#)
  - XML parser
    - error handling [529](#)
    - overview [506](#)
  - XML parsing
    - control flow with processing procedure [512](#)
    - description [508](#)
    - fatal errors [529](#)
    - handling encoding conflicts [529](#), [530](#)
    - handling exceptions [527](#)
    - one segment at a time
      - example [540](#)
      - overview [519](#)
    - overview [505](#)
    - reason code [527](#), [671](#)
    - return code [527](#), [671](#)
    - special registers [509](#), [511](#)
    - terminating [531](#)
    - with validation
      - example [542](#)
      - overview [516](#)
      - performance considerations [517](#)
      - restrictions [517](#)
  - XML processing procedure
    - control flow with parser [512](#)
    - error with EXIT PROGRAM or GOBACK [510](#)
    - example
      - one segment at a time [540](#)
      - parsing with validation [542](#)
      - program for processing XML [532](#)
    - handling encoding conflicts [530](#)
    - handling parsing exceptions [527](#)
    - multiple segments [519](#)
    - restriction on XML PARSE [510](#)
    - setting XML-CODE in [530](#)
    - specifying [508](#)
    - using special registers [509](#), [511](#)
    - writing [509](#)
  - XML schemas [518](#)
  - XML-CODE special register
    - content [512](#)
    - continuation after nonzero value [530](#)
    - control flow between parser and processing procedure [512](#)
    - description [510](#)
    - exception codes for generating [679](#)
    - exception codes for parsing [671](#)
    - exception codes for parsing with XMLPARSE(COMPAT)
      - encoding conflicts [528](#)
      - handleable [673](#)
      - not handleable [676](#)
    - exception codes for parsing with XMLPARSE(XMLSS) [671](#)

## XML-CODE special register *(continued)*

- fatal errors [529](#)
- reason code [527](#), [671](#)
- return code [527](#), [671](#)
- setting to -1 [512](#), [531](#)
- setting to 1 [519](#)
- subtracting 100,000 from [530](#)
- terminating parsing [531](#)
- using in generating [549](#)
- using in parsing [505](#)
- with code-page conflicts [529](#)
- with encoding conflicts [530](#)
- with generating exceptions [550](#)
- with parsing exceptions [529](#)

## XML-EVENT special register

- content [511](#), [532](#)
- description [509](#)
- using [505](#), [509](#)
- with parsing exceptions [529](#)

## XML-INFORMATION special

- register
- content [514](#)
- description [510](#)

## XML-NAMESPACE special register

- content [515](#)
- description [510](#)
- using [505](#)

## XML-NAMESPACE-PREFIX special register

- content [515](#)
- description [510](#)
- using [505](#)

## XML-NNAMESPACE special register

- content [515](#)
- description [510](#)
- using [505](#)

## XML-NNAMESPACE-PREFIX special register

- content [515](#)
- description [510](#)
- using [505](#)

## XML-NTEXT special register

- content [514](#)
- description [510](#)
- using [505](#)
- with parsing exceptions [529](#)

## XML-TEXT special register

- content [514](#), [532](#)
- description [510](#)
- using [505](#)
- with parsing exceptions [529](#)

## XMLPARSE compiler option

- choosing the parser [505](#)
- description [350](#)

## XPLINK linkage convention in OO applications [280](#)

## XPLINK runtime option

- not recommended as a default [280](#)
- setting [280](#)

## XREF compiler option

- description [350](#)
- finding copybook data sets [369](#)
- finding data- and procedure-names [369](#)
- getting output [370](#)

## XREF output

- COPY/BASIS cross-references [400](#)
- data-name cross-references [398](#)

## XREF output *(continued)*

- program-name cross-references [399](#)

## Z

### z/OS

- accessing main parameters under
  - example [479](#)
  - overview [478](#)
- compiling under [237](#)
- running programs under [478](#)

### z/OS UNIX

- accessing environment variables
  - example [438](#)
  - overview [436](#)
- accessing main parameters under
  - example [440](#)
  - overview [440](#)
- compiler environment variables [265](#)
- compiling from script [271](#)
- compiling OO applications
  - example [275](#)
  - overview [273](#)
- compiling under [265](#)
- copybook search order [265](#), [269](#), [358](#)
- copybooks [358](#)
- developing programs [435](#)
- execution environments [435](#)
- linking OO applications
  - example [275](#)
  - overview [274](#)
- preparing OO applications
  - example [275](#)
  - overview [274](#)
- programs must be reentrant [464](#)
- restrictions [435](#)
- running OO applications
  - overview [275](#)
  - XPLINK linkage [280](#)
- running programs [435](#)
- setting environment variables
  - example [438](#)
  - overview [436](#)
- sort and merge restriction [205](#)
- specifying compiler options [266](#)

### z/OS UNIX file system

- compiler data sets [239](#)
- defining file with environment variable [148](#)
- processing files with QSAM [170](#)
- reading file with ACCEPT [33](#)
- search order for DLLs in [484](#)
- writing files with DISPLAY [35](#)

### zero suppression

- example of BLANK WHEN ZERO clause [43](#)
- PICTURE symbol Z [43](#)

### zlib [627](#)

### ZONECHECK compiler option [352](#)

### zoned decimal data (USAGE DISPLAY)

- effect of ZWB on comparison to alphanumeric [355](#)
- example [41](#)
- format [45](#)
- sign representation [51](#)

### ZONEDATA compiler option [353](#)

### ZWB compiler option [355](#)





Product Number: 5655-EC6

SC27-8714-00

