

Personal Communications for Windows



# Host Code Page Reference



Personal Communications for Windows



# Host Code Page Reference

**Note**

Before using this information and the product it supports, read the information in "Notices," on page 49.

**First Edition (September 2004)**

This edition applies to Version 5.8 of IBM Personal Communications for Windows (program number: 5639-I70) and to all subsequent releases and modifications until otherwise indicated in new editions.

© Copyright International Business Machines Corporation 2004. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

## Host Code Page Tables . . . . . 1

Host Code Page 037-1/697-1 Brazil, Canada, Netherlands, Portugal, U.S., and 037/1175 Traditional Chinese . . . . .	1
Host Code Page 273-1/697-1 Austria, Germany . . . . .	2
Host Code Page 275-1/697-1 Brazil . . . . .	3
Host Code Page 277-1/697-1 Denmark, Norway . . . . .	4
Host Code Page 278-1/697-1 Finland, Sweden . . . . .	5
Host Code Page 280-1/697-1 Italy . . . . .	6
Host Code Page 284-1/697-1 Latin America, Spain . . . . .	7
Host Code Page 285-1/697-1 United Kingdom . . . . .	8
Host Code Page 290 Japan (Katakana) Extended . . . . .	9
Host Code Page 297-1/697-1 France . . . . .	10
Host Code Page 420 Arabic Bilingual . . . . .	11
Host Code Page 424/941 Israel (Hebrew - Bulletin Code) . . . . .	12
Host Code Page 500-1/697-1 International . . . . .	13
Host Code Page 803 Israel (Hebrew - Old Code) . . . . .	14
Host Code Page 833/1173 Hangeul . . . . .	15
Host Code Page 836/1174 Simplified Chinese . . . . .	16
Host Code Page 870/959 Latin 2 - EBCDIC Multilingual . . . . .	17
Host Code Page 871-1/697-1 Iceland . . . . .	18
Host Code Page 875 Greece . . . . .	19
Host Code Page 924-1/1353-1 International . . . . .	20
Host Code Page 1025/1150 Cyrillic . . . . .	21
Host Code Page 1026/1152 Latin 5 - Turkey . . . . .	22
Host Code Page 1027/1172 Japan (Latin) Extended . . . . .	23
Host Code Page 1047/103 Latin 1 (Open Systems) . . . . .	24
Host Code Page 1112/1035 Latvia, Lithuania . . . . .	25

Host Code Page 1122/1037 Estonia . . . . .	26
Host Code Page 1123 Ukraine . . . . .	27
Host Code Page 1130 Vietnam . . . . .	28
Host Code Page 1132 Laos . . . . .	29
Host Code Page 1137 India . . . . .	30
Host Code Page 1140-1/695-1 Brazil, Canada, Netherlands, Portugal, U.S., and 1140/1175 Traditional Chinese . . . . .	31
Host Code Page 1141-1/695-1 Austria, Germany . . . . .	32
Host Code Page 1142-1/695-1 Denmark, Norway . . . . .	33
Host Code Page 1143-1/695-1 Finland, Sweden . . . . .	34
Host Code Page 1144-1/695-1 Italy . . . . .	35
Host Code Page 1145-1/695-1 Latin America, Spain . . . . .	36
Host Code Page 1146-1/695-1 United Kingdom . . . . .	37
Host Code Page 1147-1/695-1 France . . . . .	38
Host Code Page 1148-1/695-1 International . . . . .	39
Host Code Page 1149-1/695-1 Iceland . . . . .	40
Host Code Page 1153/1375 Latin 2 - EBCDIC Multilingual . . . . .	41
Host Code Page 1154/1381 Cyrillic . . . . .	42
Host Code Page 1155/1378 Latin 5 - Turkey . . . . .	43
Host Code Page 1156/1393 Latvia, Lithuania . . . . .	44
Host Code Page 1157/1391 Estonia . . . . .	45
Host Code Page 1158/1388 Ukraine . . . . .	46
Host Code Page 1160/1395 Thailand . . . . .	47
Host Code Page 1164/1397 Vietnam . . . . .	48

## Appendix. Notices . . . . . 49

Trademarks . . . . .	50
----------------------	----



# Host Code Page Tables

## Host Code Page 037-1/697-1 Brazil, Canada, Netherlands, Portugal, U.S., and 037/1175 Traditional Chinese

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	^ SD150000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	Ê LE120000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	• SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO100000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	β LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	¢ SC040000	! SP020000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	[ SM060000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	] SM080000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ø LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	∟ SM660000	? SP150000	" SP040000	± SA020000	☒ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00037

# Host Code Page 273-1/697-1 Austria, Germany

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ä LA170000	ü LU170000	Ö LO180000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	β LS610000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	{ SM110000	ë LE170000	[ SM060000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	@ SM050000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	~ SD190000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	Ä LA180000	Ü LU180000	ö LO170000	: SP130000	« SP170000	ª SM210000	¡ SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	§ SM240000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	! SM650000	}	\	] SM080000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	ϝ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00273



## Host Code Page 275-1/697-1 Brazil

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	õ LO190000	é LE110000	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	} SM140000	/ SP120000	[ SM060000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	• SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	` SD130000	î LI150000	@ SM050000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ı SM650000	ì LI130000	Ĵ SM080000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	ã LA190000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	É LE120000	\$ SC030000	ç LC410000	: SP130000	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SİY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	Ç LC420000	, SP080000	Õ LO200000	» SP180000	º SM200000	ı SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ã LA200000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	Ɔ SC010000	® SM530000	× SA070000	{ SM110000	ÿ LY170000	# SM010000	(EO)

Code Page 00275

## Host Code Page 277-1/697-1 Denmark, Norway

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ı SM650000	@ SM050000	° SM190000	μ SM170000	¢ SC040000	æ LA510000	å LA270000	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	ü LU170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	} SM140000	ï LI170000	§ SC030000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	# SM010000	☉ SC010000	ø LO610000	: SP130000	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	. SP110000	Å LA280000	, SP080000	Æ LA520000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ø LO620000	ð LD630000	{ SM110000	Ð LD620000	- SM150000	ö LO170000	~ SD190000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	[ SM060000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	] SM080000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00277

## Host Code Page 278-1/697-1 Finland, Sweden

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ä LA170000	å LA270000	É LE120000	0 ND100000
<b>-1</b>	(RSP) SP300000	` SD130000	/ SP120000	\ SM070000	a LA010000	j LJ010000	ü LU170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	{ SM110000	ë LE170000	# SM010000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	[ SM060000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	} SM140000	ï LI170000	\$ SC030000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	é LE110000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	§ SM240000	⊘ SC010000	ö LO170000	:	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	Å LA280000	, SP080000	Ä LA180000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ö LO180000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	! SM650000	~ SD190000	@ SM050000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	´ SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	] SM080000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00278

## Host Code Page 280-1/697-1 Italy

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	[ SM060000	μ SM170000	¢ SC040000	à LA130000	è LE130000	ç LC410000	0 ND100000
<b>-1</b>	(RSP) SP300000	] SM080000	/ SP120000	É LE120000	a LA010000	j LJ010000	ì LI130000	# SM010000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	{ SM110000	} SM140000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	@ SM050000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	\ SM070000	~ SD190000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	ù LU130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	° SM190000	é LE110000	ò LO130000	:	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	£ SC020000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	§ SM240000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	´ SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	¡ SM650000	¸ SD130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Ɔ LT640000	´ SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	∩ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00280

## Host Code Page 284-1/697-1 Latin America, Spain

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM140000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	¨ SD170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ı SM650000	ß LS610000	# SM010000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	ñ LN190000	: SP130000	« SP170000	ª SM210000	ı SP030000	^ SD150000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	Ñ LN200000	» SP180000	º SM200000	¿ SP160000	! SP020000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	~ SD190000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	¬ SM660000	? SP150000	" SP040000	± SA020000	Ϸ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00284

Host Code Page 285-1/697-1 United Kingdom

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM140000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	– SM150000	[ SM060000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	\$ SC030000	! SP020000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	^ SD150000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	. SP110000	£ SC020000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	] SM080000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ð LD630000	æ LA510000	Ð LD620000	~ SD190000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	¬ SM660000	? SP150000	" SP040000	± SA020000	œ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00285

## Host Code Page 290 Japan (Katakana) Extended

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	[ SM060000	] SM080000	ソ JS500000	~ SD190000	^ SD150000	{ SM110000	}	\$ SC030000	0 ND100000
-1	。 JQ700000	エ JE010000	/ SP120000	i LI010000	ア JA000000	タ JT100000	- SM150000	¢ SC040000	A LA020000	J LJ020000	€ SC200000	1 ND010000
-2	「 JQ710000	オ JO010000	a LA010000	j LJ010000	イ JI000000	チ JT200000	へ JH400000	\ SM070000	B LB020000	K LK020000	S LS020000	2 ND020000
-3	」 JQ720000	ヤ JY110000	b LB010000	k LK010000	ウ JU000000	ツ JT300000	ホ JH500000	t LT010000	C LC020000	L LL020000	T LT020000	3 ND030000
-4	、 JQ730000	ユ JY310000	c LC010000	l LL010000	エ JE000000	テ JT400000	マ JM100000	u LU010000	D LD020000	M LM020000	U LU020000	4 ND040000
-5	・ JQ740000	ヨ JY510000	d LD010000	m LM010000	オ JO000000	ト JT500000	ミ JM200000	v LV010000	E LE020000	N LN020000	V LV020000	5 ND050000
-6	ヲ JW500000	ッ JT310000	e LE010000	n LN010000	カ JK100000	ナ JN100000	ム JM300000	w LW010000	F LF020000	O LO020000	W LW020000	6 ND060000
-7	ア JA010000		f LF010000	o LO010000	キ JK200000	ニ JN200000	メ JM400000	x LX010000	G LG020000	P LP020000	X LX020000	7 ND070000
-8	イ JI010000	ー JX700000	g LG010000	p LP010000	ク JK300000	ヌ JN300000	モ JM500000	y LY010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	ウ JU010000		h LH010000	` SD130000	ケ JK400000	ネ JN400000	ヤ JY100000	z LZ010000	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	£ SC020000	! SP020000		: SP130000	コ JK500000	ノ JN500000	ユ JY300000	レ JR400000				
-B	・ SP110000	¥ SC050000	,	# SM010000	q LQ010000	r LR010000	s LS010000	ロ JR500000				
-C	< SA030000	* SM040000	% SM020000	@ SM050000	サ JS100000		ヨ JY500000	ワ JW100000				
-D	( SP060000	) SP070000	_ SP090000	' SP050000	シ JS200000	ハ JH100000	ラ JR100000	ン JN000000				
-E	+ SA010000	; SP140000	> SA050000	= SA040000	ス JS300000	ヒ JH200000	リ JR200000	ゝ JX710000				
-F	 SM130000	フ SM660000	? SP150000	" SP040000	セ JS400000	フ JH300000	ル JR300000	。 JX720000				(EO)

Code Page 00290

# Host Code Page 297-1/697-1 France

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	[ SM060000	` SD130000	¢ SC040000	é LE110000	è LE130000	ç LC410000	0 ND100000
<b>-1</b>	(RSP) SP300000	{ SM110000	/ SP120000	É LE120000	a LA010000	j LJ010000	¨ SD170000	# SM010000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	@ SM050000	}	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	] SM080000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	\ SM070000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	μ SM170000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	° SM190000	§ SM240000	ù LU130000	:	« SP170000	ª SM210000	¡ SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	£ SC020000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	à LA130000	ð LD630000	æ LA510000	Ð LD620000	¯ SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	´ SP050000	ý LY110000	¸ SD410000	Ý LY120000	~ SD190000	ò LO130000	¡ SM650000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	∩ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00297



## Host Code Page 420 Arabic Bilingual

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ح AH450003	ش AS230000	ظ AZ450000	غ AG310003	ك AK010003	؛ SP140007	؟ SP150007	× SA070000	0 ND100000
<b>-1</b>	(RSP) SP300000	أ AA310002	/ SP120000	خ AH470000	a LA010000	j LJ010000	÷ SA060000	ل AL010000	A LA020000	J LJ020000	(NSP) SP310000	1 ND010000
<b>-2</b>	س AX100000	و AW310000	ة AT020000	ذ AH470003	b LB010000	k LK010000	s LS010000	لآ AL220000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	و AX100004		ت AT010000	د AD010000	c LC010000	l LL010000	t LT010000	لآ AL220003	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	- SM860000		ت AT010003	ذ AD470000	d LD010000	m LM010000	u LU010000	لآ AL320000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	ل SM870000	ء AY310000	ث AT470000	ر AR010000	e LE010000	n LN010000	v LV010000	لآ AL320003	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ء AX300000	ا AA010000	ث AT470003	ز AZ010000	f LF010000	o LO010000	w LW010000		F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	آ AA210000	ا AA010002	ج AG230000	س AS010000	g LG010000	p LP010000	x LX010000		G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	آ AA210002	ب AB010000	ج AG230003	س AS010003	h LH010000	q LQ010000	y LY010000	لا AL020000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	أ AA310000	ب AB010003	ح AH450000	، SP080007	i LI010000	r LR010000	z LZ010000	لا AL020003	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	ؔ SC040000	! SP020000	! SM650000	: SP130000	ش AS230003	ع AC470000	غ AG310004	ل AL010003	(SHY) SP320000	ى AA020000	ا ND010001	
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	# SM010000	ص AS450000	ع AC470002	ف AF010000	م AM010000	ه AH010003	ى AA020002	٢ ND020001	٦ ND060001
<b>-C</b>	< SA030000	* SM040007	% SM020007	@ SM050000	ص AS450003	ع AC470003	ف AF010003	م AM010003		ي AY010000		٧ ND070001
<b>-D</b>	( SP060000	) SP070000	_ SP090000	ٴ SP050000	ض AD450000	ع AC470004	ق AQ010000	ن AN010000	ف AH010004	ي AY010002	٣ ND030001	٨ ND080001
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ض AD450003	غ AG310000	ق AQ010003	ن AN010003		ي AY010003	٤ ND040001	٩ ND090001
<b>-F</b>	 SM130000	ٶ SM660000	? SP150000	" SP040000	ط AT450000	غ AG310002	ك AK010000	ه AH010000	و AW010000	. ND100001	٥ ND050001	(EO)

Code Page 00420

Host Code Page 424/941 Israel (Hebrew - Bulletin Code)

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000			° SM190000	μ SM170000	^ SD150000	{ SM110000	} SM140000	\ SM070000	0 ND100000
-1	א HX330000	י HY010000	/ SP120000	ח HT010000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
-2	ב HB010000	ך HK610000	ע HX350000		b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
-3	ג HG010000	כ HK010000	ף HP610000		c LC010000	l LL010000	t LT010000	• SM570000	C LC020000	L LL020000	T LT020000	3 ND030000
-4	ד HD010000	ל HL010000	פ HP010000	(RSP) SP300000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
-5	ה HH010000	מ HM610000	ץ HS610000		e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
-6	ו HW010000	מ HM010000	צ HS450000		f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
-7	ז HZ010000	ן HN610000	ק HQ010000		g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
-8	ח HH450000	נ HN010000	ך HR010000	= SM100000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	ט HT450000	ס HS010000	ש HS210000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	¢ SC040000	! SP020000	! SM650000	:	« SP130000			[ SM060000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
-B	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000			] SM080000				
-C	< SA030000	* SM040000	% SM020000	@ SM050000				- SM150000				
-D	( SP060000	) SP070000	— SP090000	‘ SP050000		’ SD410000		“ SD170000				
-E	+ SA010000	; SP140000	> SA050000	= SA040000				’ SD110000				
-F	 SM130000	⌋ SM660000	? SP150000	" SP040000	± SA020000	⊗ SC010000	® SM530000	× SA070000				(EO)

Code Page 00424

## Host Code Page 500-1/697-1 International

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM140000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	! SM650000	: SP130000	« SP170000	ª SM210000	¡ SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	ϝ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00500

Israel (Hebrew)

Host Code Page 803 Israel (Hebrew - Old Code)

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	א HX330000	- SP100000									0 ND100000
-1			/ SP120000		ב HB010000	ג HK610000			A LA020000	J LJ020000		1 ND010000
-2					ד HG010000	ה HK010000	ו HP610000		B LB020000	K LK020000	S LS020000	2 ND020000
-3					ז HD010000	ח HL010000	ט HP010000		C LC020000	L LL020000	T LT020000	3 ND030000
-4					י HH010000	כ HM610000	ל HS610000		D LD020000	M LM020000	U LU020000	4 ND040000
-5					מ HW010000	נ HM010000	ס HS450000		E LE020000	N LN020000	V LV020000	5 ND050000
-6					ע HZ010000	פ HN610000	צ HQ010000		F LF020000	O LO020000	W LW020000	6 ND060000
-7					ק HH450000	ר HN010000	ש HR010000		G LG020000	P LP020000	X LX020000	7 ND070000
-8					ת HT450000	י HS010000	ך HS210000		H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9					ך HY010000	ל HX350000	ם HT010000		I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	\$ SC030000	! SP020000		:	SP130000							
-B	. SP110000	א SC150000	,	#	SP080000	SM010000						
-C	< SA030000	* SM040000	%	@	SM020000	SM050000						
-D	( SP060000	) SP070000	_	'	SP090000	SP050000						
-E	+ SA010000	; SP140000	>	=	SA050000	SA040000						
-F	 SM130000	א SM660000	?	"	SP150000	SP040000						(EO)

Code Page 00803

# Host Code Page 833/1173 Hangeul

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	[ SM060000	] SM080000		- SM150000	^ SD150000	{ SM110000	}	W SM140000	0 ND100000
-1			/ SP120000		a LA010000	j LJ010000	~ SD190000		A LA020000	J LJ020000		1 ND010000
-2	SP490000	ㄸ OD100000	ㄹ OL300000	ㅈ OJ000000	b LB010000	k LK010000	s LS010000	\ SM070000	B LB020000	K LK020000	S LS020000	2 ND020000
-3	ㄱ OG000000	ㄴ OL000000	ㄷ OM000000	ㄸ OJ100000	c LC010000	l LL010000	t LT010000		C LC020000	L LL020000	T LT020000	3 ND030000
-4	ㄷ OG100000	ㄹ OL200000	ㅂ OB000000	ㅅ OC200000	d LD010000	m LM010000	u LU010000		D LD020000	M LM020000	U LU020000	4 ND040000
-5	ㅈ OG200000	ㅊ OL400000	ㅋ OB100000	ㅋ OK000000	e LE010000	n LN010000	v LV010000		E LE020000	N LN020000	V LV020000	5 ND050000
-6	ㄴ ON000000	ㄷ OL100000	ㅅ OB200000	ㅈ OT000000	f LF010000	o LO010000	w LW010000		F LF020000	O LO020000	W LW020000	6 ND060000
-7	ㅈ ON150000	ㅊ OL600000	ㅊ OS000000	ㅊ OP000000	g LG010000	p LP010000	x LX010000		G LG020000	P LP020000	X LX020000	7 ND070000
-8	ㅊ ON100000	ㅊ OL700000	ㅊ OS100000	ㅊ OH000000	h LH010000	q LQ010000	y LY010000		H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	ㄷ OD000000	ㅊ OL500000	ㅇ ON200000	` SD130000	i LI010000	r LR010000	z LZ010000		I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	¢ SC040000	! SP020000	! SM650000	: SP130000	ㅂ OA000000	ㅋ OY400000	ㅊ OY500000	ㅊ OE300000				
-B	. SP110000	\$ SC030000	, SP080000	# SM010000	ㅂ OA200000	ㅋ OY300000	ㅊ OU000000	ㅊ OE400000				
-C	< SA030000	* SM040000	% SM020000	@ SM050000	ㅂ OY200000	ㅊ OO000000	ㅊ OU300000	ㅊ OI000000				
-D	( SP060000	) SP070000	_ SP090000	' SP050000	ㅂ OY250000	ㅊ OO100000	ㅊ OU200000					
-E	+ SA010000	; SP140000	> SA050000	= SA040000	ㅂ OE200000	ㅊ OO200000	ㅊ OU400000					
-F	 SM130000	ㅊ SM660000	? SP150000	" SP040000	ㅂ OE000000	ㅊ OO300000	ㅊ OY600000					(EO)

Code Page 00833

## Host Code Page 836/1174 Simplified Chinese

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000				~ SD190000	^ SD150000	{ SM110000	} SM140000	\$ SC030000	0 ND100000
<b>-1</b>		/ SP120000		a LA010000	j LJ010000	- SM150000		A LA020000	J LJ020000			1 ND010000
<b>-2</b>				b LB010000	k LK010000	s LS010000	\ SM070000	B LB020000	K LK020000	S LS020000		2 ND020000
<b>-3</b>				c LC010000	l LL010000	t LT010000		C LC020000	L LL020000	T LT020000		3 ND030000
<b>-4</b>				d LD010000	m LM010000	u LU010000		D LD020000	M LM020000	U LU020000		4 ND040000
<b>-5</b>				e LE010000	n LN010000	v LV010000		E LE020000	N LN020000	V LV020000		5 ND050000
<b>-6</b>				f LF010000	o LO010000	w LW010000		F LF020000	O LO020000	W LW020000		6 ND060000
<b>-7</b>				g LG010000	p LP010000	x LX010000		G LG020000	P LP020000	X LX020000		7 ND070000
<b>-8</b>				h LH010000	q LQ010000	y LY010000		H LH020000	Q LQ020000	Y LY020000		8 ND080000
<b>-9</b>			` SD130000	i LI010000	r LR010000	z LZ010000		I LI020000	R LR020000	Z LZ020000		9 ND090000
<b>-A</b>	£ SC020000	! SP020000	! SM650000	: SP130000				[ SM060000				
<b>-B</b>	. SP110000	¥ SC120000	, SP080000	# SM010000				] SM080000				
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000								
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000								
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000								
<b>-F</b>	 SM130000	∟ SM660000	? SP150000	" SP040000								(EO)

Code Page 00836

## Host Code Page 870/959 Latin 2 - EBCDIC Multilingual

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	∨ SD210000	˘ SD230000	◦ SM190000	ą LA430000	· SD290000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	Ą LA440000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ę LE430000	Â LA160000	Ę LE440000	b LB010000	k LK010000	s LS010000	ż LZ290000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	Ť LT420000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	ı LT410000	û LU270000	" SD250000	Û LU280000	d LD010000	m LM010000	u LU010000	Ź LZ300000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ă LA230000	î LI150000	Ă LA240000	Î LI160000	f LF010000	o LO010000	w LW010000	ż LZ210000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	č LC210000	ř LL210000	Č LC220000	Ř LL220000	g LG010000	p LP010000	x LX010000	ź LZ110000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	í LI110000	Ç LC420000	Í LI120000	h LH010000	q LQ010000	y LY010000	Ź LZ220000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ć LC110000	ß LS610000	Ć LC120000	` SD130000	i LI010000	r LR010000	z LZ010000	Ź LZ120000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	 SM130000	: SP130000	ś LS110000	ł LL610000	Ś LS120000	Ł LL620000	(SHY) SP320000	Ě LE220000	ď LD210000	Ď LD220000
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	# SM010000	ň LN210000	ń LN110000	Ń LN220000	Ň LN120000	ô LO150000	ů LU250000	Ô LO160000	Ů LU260000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	đ LD610000	š LS210000	Đ LD620000	Š LS220000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	‚ SD410000	Ý LY120000	“ SD170000	í LR110000	ř LT210000	Ř LR120000	Ť LT220000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ř LR210000	ć SD430000	Ř LR220000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	ş LS410000	Ϡ SC010000	Ş LS420000	× SA070000	ő LO250000	ě LE210000	Ő LO260000	(EO)

Code Page 00870

## Host Code Page 871-1/697-1 Iceland

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	þ LT630000	æ LA510000	' SD110000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	ö LO170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	ö LD630000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	þ LT640000	Æ LA520000	ı SM650000	: SP130000	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	ı SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ð LD620000	` SD130000	}	@ SM050000	- SM150000	~ SD190000	ü LU170000	^ SD150000	Û LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	{ SM110000	] SM080000	[ SM060000	\ SM070000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	Ö LO180000	? SP150000	" SP040000	± SA020000	⌘ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00871



## Host Code Page 875 Greece

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	.. SD170000	.' SD730000	o SM190000	' SD110000	£ SC020000	{ SM110000	} SM140000	\ SM070000	0 ND100000
-1	A GA020000	K GK020000	/ SP120000	À GA120000	a LA010000	j LJ010000	~ SD190000	á GA110000	A LA020000	J LJ020000		1 ND010000
-2	B GB020000	Λ GL020000	T GT020000	Έ GE120000	b LB010000	k LK010000	s LS010000	é GE110000	B LB020000	K LK020000	S LS020000	2 ND020000
-3	Γ GG020000	M GM020000	Υ GU020000	Ή GE720000	c LC010000	l LL010000	t LT010000	ή GE710000	C LC020000	L LL020000	T LT020000	3 ND030000
-4	Δ GD020000	N GN020000	Φ GF020000	(RSP) SP300000	d LD010000	m LM010000	u LU010000	ï GI170000	D LD020000	M LM020000	U LU020000	4 ND040000
-5	E GE020000	Ξ GX020000	X GH020000	Ί GI120000	e LE010000	n LN010000	v LV010000	í GI110000	E LE020000	N LN020000	V LV020000	5 ND050000
-6	Z GZ020000	O GO020000	Ψ GP020000	Ό GO120000	f LF010000	o LO010000	w LW010000	ó GO110000	F LF020000	O LO020000	W LW020000	6 ND060000
-7	H GE320000	Π GP020000	Ω GO320000	Υ GU120000	g LG010000	p LP010000	x LX010000	ύ GU110000	G LG020000	P LP020000	X LX020000	7 ND070000
-8	Θ GT620000	P GR020000	Ϊ GI180000	Ω GO720000	h LH010000	q LQ010000	y LY010000	ÿ GU170000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	I GI020000	Σ GS020000	ÿ GU180000	` SD130000	i LI010000	r LR010000	z LZ010000	ώ GO710000	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	[ SM060000	] SM080000	 SM130000	:	α GA010000	η GE310000	ν GN010000	ς GS610000	(SHY) SP320000	± SA020000	<sup>2</sup> ND021000	<sup>3</sup> ND031000
-B	. SP110000	\$ SC030000	, SP080000	# SM010000	β GB010000	θ GT610000	ξ GX010000	τ GT010000	ω GO310000	½ NF010000	§ SM240000	© SM520000
-C	< SA030000	* SM040000	% SM020000	@ SM050000	γ GG010000	ι GI010000	ο GO010000	υ GU010000	ί GI730000			€ SC200000
-D	( SP060000	) SP070000	_ SP090000	' SP050000	δ GD010000	κ GK010000	π GP010000	φ GF010000	ύ GU730000	· SD630000		
-E	+ SA010000	; SP140000	> SA050000	= SA040000	ε GE010000	λ GL010000	ρ GR010000	χ GH010000	‘ SP190000	’ SP200000	« SP170000	» SP180000
-F	! SP020000	^ SD150000	? SP150000	" SP040000	ζ GZ010000	μ GM010000	σ GS010000	ψ GP610000	— SM120000	 SM650000	⌋ SM660000	(EO)

Code Page 00875

# Host Code Page 924-1/1353-1 International

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM140000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	á LA010000	ĵ LJ010000	~ SD190000	£ SC020000	À LA020000	Ĵ LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	Æ LO520000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	œ LO510000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	ÿ LY180000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	Ý LY120000	! SP020000	Š LS220000	: SP130000	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	ı̇ SP160000	š LS210000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ď LD630000	æ LA510000	Ð LD640000	- SD310000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	ž LZ210000	[ SM060000	] SM080000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Ɔ LT640000	Ž LZ220000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	^ SD150000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 00924

## Host Code Page 1025/1150 Cyrillic

The column indicates the first digit, and the row indicates the second digit. If this code page is not used with a Cyrillic host machine, certain characters might not display properly.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	Ъ KN120000	Ц KC010000	Й KJ110000	Я KA150000	Ь KX110000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	Љ KL410000	/ SP120000	Ѡ KC120000	а LA010000	ј LJ010000	~ SD190000	Ы KY010000	А LA020000	Ј LJ020000	§ SM240000	1 ND010000
<b>-2</b>	ђ KD610000	њ KN110000	ѓ KG120000	ќ KK120000	б LB010000	к LK010000	ѕ LS010000	з KZ010000	В LB020000	К LK020000	Ѕ LS020000	2 ND020000
<b>-3</b>	ѓ KG110000	ћ KC110000	Ё KE180000	(SHY) SP320000	с LC010000	l LL010000	t LT010000	ш KS210000	С LC020000	Л LL020000	Т LT020000	3 ND030000
<b>-4</b>	ё KE170000	ќ KK110000	Є KE160000	Ў KU240000	d LD010000	m LM010000	u LU010000	э KE130000	Д LD020000	М LM020000	У LU020000	4 ND040000
<b>-5</b>	е KE150000	ђ KU230000	Ѕ KZ160000	Ц KG220000	e LE010000	n LN010000	v LV010000	щ KS150000	Е LE020000	Н LN020000	В LV020000	5 ND050000
<b>-6</b>	s KZ150000	ц KG210000	l KI120000	ю KU150000	f LF010000	o LO010000	w LW010000	ч KC210000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	i KI110000	ѡ KU220000	ї KI180000	а KA010000	g LG010000	p LP010000	x LX010000	ъ KU210000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ï KI170000	№ SM000000	J KJ020000	б KB010000	h LH010000	q LQ010000	y LY010000	Ю KU160000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	j KJ010000	Ѣ KD620000	Љ KL420000	` SD130000	i LI010000	r LR010000	z LZ010000	А KA020000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	 SM130000	: SP130000	д KD010000	к KK010000	р KR010000	Б KB020000	X KH020000	Н KN020000	Т KT020000	З KZ020000
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	# SM010000	е KE010000	л KL010000	с KS010000	Ц KC020000	И KI020000	О KO020000	У KU020000	Ш KS220000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ф KF010000	м KM010000	т KT010000	Д KD020000	Й KJ120000	П KP020000	Ж KZ220000	Э KE140000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	‘ SP050000	г KG010000	н KN010000	у KU010000	Е KE020000	К KK020000	Я KA160000	В KV020000	Щ KS160000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	х KH010000	о KO010000	ж KZ210000	Ф KF020000	Л KL020000	Р KR020000	Ь KX120000	Ч KC220000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	и KI010000	п KP010000	в KV010000	Г KG020000	М KM020000	С KS020000	Ы KY020000	(EO)

Code Page 01025

Host Code Page 1026/1152 Latin 5 - Turkey

The column indicates the first digit, and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ç LC410000	ğ LG230000	ü LU170000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	ö LO170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	{ SM110000	ì LI130000	[ SM060000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	ı LI610000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	Ç LC420000	Ğ LG240000	Ş LS410000	: SP130000	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	İ LI300000	, SP080000	Ö LO180000	» SP180000	º SM200000	ı̇ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ş LS420000	} SM140000	æ LA510000	] SM080000	- SM150000	~ SD190000	\ SM070000	# SM010000	" SP040000
<b>-D</b>	( SP060000	) SP070000	— SP090000	‘ SP050000	` SD130000	´ SD410000	\$ SC030000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	! SM650000	Æ LA520000	@ SM050000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	Û LU180000	± SA020000	ϝ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01026

Host Code Page 1027/1172 Japan (Latin) Extended

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	コ JK500000			- SM150000	^ SD150000	{ SM110000	}	\ SM070000	0 ND100000
-1		ウ JU010000	/ SP120000	サ JS100000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	€ SC200000	1 ND010000
-2	。 JQ700000	エ JE010000	イ JI000000	シ JS200000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
-3	「 JQ710000	オ JO010000	ウ JU000000	ス JS300000	c LC010000	l LL010000	t LT010000	ヤ JY100000	C LC020000	L LL020000	T LT020000	3 ND030000
-4	」 JQ720000	ヤ JY110000	エ JE000000	セ JS400000	d LD010000	m LM010000	u LU010000	ユ JY300000	D LD020000	M LM020000	U LU020000	4 ND040000
-5	、 JQ730000	ユ JY310000	オ JO000000	ソ JS500000	e LE010000	n LN010000	v LV010000	ヨ JY500000	E LE020000	N LN020000	V LV020000	5 ND050000
-6	・ JQ740000	ヨ JY510000	カ JK100000	タ JT100000	f LF010000	o LO010000	w LW010000	ラ JR100000	F LF020000	O LO020000	W LW020000	6 ND060000
-7	ヲ JW500000	ツ JT310000	キ JK200000	チ JT200000	g LG010000	p LP010000	x LX010000	リ JR200000	G LG020000	P LP020000	X LX020000	7 ND070000
-8	ア JA010000	ー JX700000	ク JK300000	ツ JT300000	h LH010000	q LQ010000	y LY010000	ル JR300000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	イ JI010000	ア JA000000	ケ JK400000	、 SD130000	i LI010000	r LR010000	z LZ010000	レ JR400000	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	¢ SC040000	! SP020000		: SP130000	テ JT400000	ノ JN500000	マ JM100000	ロ JR500000				
-B	・ SP110000	\$ SC030000	,	# SM010000	ト JT500000	ハ JH100000	ミ JM200000	ワ JW100000				
-C	< SA030000	* SM040000	% SM020000	@ SM050000	ナ JN100000	ヒ JH200000	ム JM300000	ン JN000000				
-D	( SP060000	) SP070000	_ SP090000	' SP050000	ニ JN200000	フ JH300000	[ SM060000	] SM080000				
-E	+ SA010000	; SP140000	> SA050000	= SA040000	ヌ JN300000	へ JH400000	メ JM400000	° JX710000				
-F	 SM130000	⌋ SM660000	? SP150000	" SP040000	ネ JN400000	ホ JH500000	モ JM500000	° JX720000				(EO)

Code Page 01027

## Host Code Page 1047/103 Latin 1 (Open Systems)

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	∟ SM660000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	á LA010000	â LJ010000	ã SD190000	£ SC020000	À LA020000	Å LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Ï LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	ø SC040000	! SP020000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	Ý LY120000	(S̄Y) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	¨ SD170000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ð LD630000	æ LA510000	Ð LD620000	ˉ SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	[ SM060000	] SM080000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Ɔ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	^ SD150000	? SP150000	" SP040000	± SA020000	Ɔ SC010000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

## Host Code Page 1112/1035 Latvia, Lithuania

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	^ SD150000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	š LS210000	ę LE430000	Š LS220000	Ę LE440000	b LB010000	k LK010000	s LS010000	ī LI310000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	é LE290000	Ä LA180000	Ë LE300000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	ą LA430000	č LC210000	Ą LA440000	Č LC220000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	ì LI430000	ų LU430000	Į LI440000	Ų LU440000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ū LU310000	” SP230000	Ū LU320000	Ī LI320000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	ą LA270000	“ SP210000	Ą LA280000	Ł LL420000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ē LE310000	ġ LG410000	Ē LE320000	Ģ LG420000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ž LZ210000	β LS610000	Ž LZ220000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	¢ SC040000	! SP020000	¡ SM650000	: SP130000	« SP170000	Ŕ LR420000	” SP220000	[ SM060000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	ŗ LR410000	ż LZ110000	] SM080000	ō LO310000	ć LC110000	ō LO320000	Ć LC120000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ā LA310000	æ LA510000	Ā LA320000	Ž LZ120000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ż LZ290000	ķ LK410000	Ž LZ300000	Ķ LK420000	ņ LN410000	ł LL610000	Ń LN420000	Ł LL620000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ń LN110000	Æ LA520000	Ń LN120000	↓ LL410000	ó LO110000	ś LS110000	Ó LO120000	Ś LS120000
<b>-F</b>	 SM130000	¬ SM660000	? SP150000	" SP040000	± SA020000	Ϟ SC010000	® SM530000	× SA070000	õ LO190000	' SP200000	õ LO200000	(EO)

Code Page 01112

# Host Code Page 1122/1037 Estonia

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ä LA170000	å LA270000	É LE120000	0 ND100000
<b>-1</b>	(RSP) SP300000	` SD130000	/ SP120000	\ SM070000	a LA010000	j LJ010000	ü LU170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	{ SM110000	ë LE170000	# SM010000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	[ SM060000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	} SM140000	ï LI170000	\$ SC030000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	é LE110000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	§ SM240000	⊘ SC010000	ö LO170000	:	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	Å LA280000	,	Ä LA180000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ö LO180000	š LS210000	æ LA510000	š LS220000	- SM150000	¡ SM650000	~ SD190000	@ SM050000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ž LZ210000	Æ LA520000	Ž LZ220000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	] SM080000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01122



## Host Code Page 1123 Ukraine

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	Ь KN120000	Ц KC010000	Й KJ110000	Я KA150000	Ь KX110000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	Љ KL410000	/ SP120000	Ѡ KC120000	а LA010000	ј LJ010000	~ SD190000	Ы KY010000	А LA020000	Ј LJ020000	§ SM240000	1 ND010000
<b>-2</b>	ђ KD610000	њ KN110000	Г KG300000	Ѓ KK120000	б LB010000	к LK010000	ѕ LS010000	з KZ010000	В LB020000	К LK020000	Ѕ LS020000	2 ND020000
<b>-3</b>	г KG290000	ћ KC110000	Ё KE180000	(SHY) SP320000	с LC010000	l LL010000	t LT010000	ш KS210000	С LC020000	Л LL020000	Т LT020000	3 ND030000
<b>-4</b>	ё KE170000	ќ KK110000	Є KE160000	Ў KU240000	d LD010000	m LM010000	u LU010000	э KE130000	Д LD020000	М LM020000	У LU020000	4 ND040000
<b>-5</b>	є KE150000	ђ KU230000	Ѕ KZ160000	Ц KG220000	e LE010000	n LN010000	v LV010000	ш KS150000	Е LE020000	Н LN020000	В LV020000	5 ND050000
<b>-6</b>	s KZ150000	ц KG210000	І KI120000	Ю KU150000	f LF010000	o LO010000	w LW010000	ч KC210000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	i KI110000	Ђ KU220000	Ї KI180000	а KA010000	g LG010000	p LP010000	x LX010000	ь KU210000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ï KI170000	№ SM000000	Ј KJ020000	б KB010000	h LH010000	q LQ010000	y LY010000	Ю KU160000	Н LH020000	Q LQ020000	У LY020000	8 ND080000
<b>-9</b>	j KJ010000	Ђ KD620000	Љ KL420000	` SD130000	i LI010000	r LR010000	z LZ010000	А KA020000	І LI020000	Р LR020000	З LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	 SM130000	: SP130000	д KD010000	к KK010000	р KR010000	Б KB020000	Х KH020000	Н KN020000	Т KT020000	З KZ020000
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	# SM010000	е KE010000	л KL010000	с KS010000	Ц KC020000	И KI020000	О KO020000	У KU020000	Ш KS220000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ф KF010000	м KM010000	т KT010000	Д KD020000	Й KJ120000	П KP020000	Ж KZ220000	Э KE140000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	г KG010000	н KN010000	у KU010000	Е KE020000	К KK020000	Я KA160000	В KV020000	Щ KS160000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	х KH010000	о KO010000	ж KZ210000	Ф KF020000	Л KL020000	Р KR020000	Ь KX120000	Ч KC220000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	и KI010000	п KP010000	в KV010000	Г KG020000	М KM020000	С KS020000	Ы KY020000	(EO)

Code Page 01123

# Host Code Page 1130 Vietnam

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA230000	î LI150000	Ă LA240000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ñ SD198000	Ç LC420000	đ SC180000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	β LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SĦY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	đ LD610000	æ LA510000	Ð LD600000	- SD310000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	◌ SD918000	Œ LO520000	◌ SD458000	œ LO510000	ƒ LU910000	ù LU130000	Ɔ LU920000	Û LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	◌ SD138000	Æ LA520000	◌ SD118000	ÿ LY180000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	☒ SC010000	® SM530000	× SA070000	σ LO910000	ÿ LY170000	Œ LO920000	(EO)

Code Page 01130

# Host Code Page 1132 Laos

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	ᵏ SC190000				○ U0000ED0	{ SM110000	}	\ SM070000	0 ND100000
-1	(RSP) SP300000		/ SP120000		a LA010000	j LJ010000	~ SD190000	ᵒ U0000ED1	A LA020000	J LJ020000		1 ND010000
-2	ກ U0000E81	ຍ U0000E8D	ປ U0000E9B	ສ U0000EA3	b LB010000	k LK010000	s LS010000	໒ U0000ED2	B LB020000	K LK020000	S LS020000	2 ND020000
-3	ຂ U0000E82	ດ U0000E84	ຜ U0000E9C	ລ U0000EA5	c LC010000	l LL010000	t LT010000	໓ U0000ED3	C LC020000	L LL020000	T LT020000	3 ND030000
-4	ຄ U0000E84	ຕ U0000E95	ຝ U0000E9D	ວ U0000EA7	d LD010000	m LM010000	u LU010000	໔ U0000ED4	D LD020000	M LM020000	U LU020000	4 ND040000
-5	ງ U0000E87	ຖ U0000E96	ພ U0000E9E	ທ U0000EAB	e LE010000	n LN010000	v LV010000	໕ U0000ED5	E LE020000	N LN020000	V LV020000	5 ND050000
-6	ຈ U0000E88	ທ U0000E97	ຝ U0000E9F	ອ U0000EAD	f LF010000	o LO010000	w LW010000	໖ U0000ED6	F LF020000	O LO020000	W LW020000	6 ND060000
-7	ສ U0000EAA	ນ U0000E99	ມ U0000EA1	ຮ U0000EAE	g LG010000	p LP010000	x LX010000	໗ U0000ED7	G LG020000	P LP020000	X LX020000	7 ND070000
-8	ຊ U0000E8A	ບ U0000E9A	ຢ U0000EA2		h LH010000	q LQ010000	y LY010000	໘ U0000ED8	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	[ SM060000	] SM080000	^ SD150000	` SD130000	i LI010000	r LR010000	z LZ010000	໙ U0000ED9	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	¢ SC040000	! SP020000	! SM650000	: SP130000		ິ U0000EB4	ື U0000EBC			ໍ U0000ECD		
-B	. SP110000	\$ SC030000	, SP080000	# SM010000		ີ U0000EB5	ື U0000EB1	່ U0000EC0	ໍ U0000EC8	ູ U0000EC6		
-C	< SA030000	* SM040000	% SM020000	@ SM050000	ູ U0000EAF	ິ U0000EB6	ື U0000EBB	່ U0000EC1	ໍ U0000EC9			
-D	( SP060000	) SP070000	_ SP090000	' SP050000	ູ U0000EB0	ິ U0000EB7	ື U0000EBD	່ U0000EC2	ໍ U0000ECA	ູ U0000EDC		
-E	+ SA010000	; SP140000	> SA050000	= SA040000	ູ U0000EB2	ິ U0000EB8		່ U0000EC3	ໍ U0000ECB	ູ U0000EDD		
-F	 SM130000	∟ SM660000	? SP150000	" SP040000	ູ U0000EB3	ິ U0000EB9		່ U0000EC4	ໍ U0000ECC			(EO)

Code Page 01132

# Host Code Page 1137 India

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	झ U000091D	द U0000926	म U000092E	(ZW) SP5300Z0	ा U000093E	{ SM110000	}	\ SM070000	0 ND100000
-1	(RSP) SP300000	ॠ U000090B	/ SP120000	अ U000091E	a LA010000	j LJ010000	~ SD190000	ि U000093F	A LA020000	J LJ020000	(ZW) SP5400Z0	1 ND010000
-2	ँ U0000901	ॡ U000090C	औ U0000914	ट U000091F	b LB010000	k LK010000	s LS010000	ी U0000940	B LB020000	K LK020000	S LS020000	2 ND020000
-3	ं U0000902	ँ U000090D	क U0000915	ठ U0000920	c LC010000	l LL010000	t LT010000	ु U0000941	C LC020000	L LL020000	T LT020000	3 ND030000
-4	ः U0000903	ऐ U000090E	ख U0000916	ड U0000921	d LD010000	m LM010000	u LU010000	ू U0000942	D LD020000	M LM020000	U LU020000	4 ND040000
-5	अ U0000905	ए U000090F	ग U0000917	ढ U0000922	e LE010000	n LN010000	v LV010000	ृ U0000943	E LE020000	N LN020000	V LV020000	5 ND050000
-6	आ U0000906	ऐ U0000910	घ U0000918	ण U0000923	f LF010000	o LO010000	w LW010000	्र U0000944	F LF020000	O LO020000	W LW020000	6 ND060000
-7	इ U0000907	औ U0000911	ङ U0000919	त U0000924	g LG010000	p LP010000	x LX010000	ँ U0000945	G LG020000	P LP020000	X LX020000	7 ND070000
-8	ई U0000908	ओ U0000912	च U000091A	थ U0000925	h LH010000	q LQ010000	y LY010000	े U0000946	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	उ U0000909	ओ U0000913	छ U000091B	ँ SD130000	i LI010000	r LR010000	z LZ010000	े U0000947	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	ऊ U000090A	!	ज U000091C	:	ध U0000927	य U000092F	ष U0000937	ै U0000948	् U000094D	ॠ U0000960	० U0000966	६ U000096C
-B	.	\$	,	#	न U0000928	र U0000930	स U0000938	ाँ U0000949	ऊँ U0000950	ॡ U0000961	१ U0000967	७ U000096D
-C	<	*	%	@	प U000092A	ल U0000932	ह U0000939	ो U000094A	ं U0000951	्र U0000962	२ U0000968	८ U000096E
-D	(	)	_	,	फ U000092B	ळ U0000933	[	]	ं U0000952	्र U0000963	३ U0000969	९ U000096F
-E	+	;	>	=	ब U000092C	व U0000935	्र U000093C	ो U000094B		। U0000964	४ U000096A	० U0000970
-F		^	?	"	भ U000092D	ष U0000936	ऽ U000093D	ी U000094C		॥ U0000965	५ U000096B	(EO)

Code Page 01137

## Host Code Page 1140-1/695-1 Brazil, Canada, Netherlands, Portugal, U.S., and 1140/1175 Traditional Chinese

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	^ SD150000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	¢ SC040000	! SP020000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	[ SM060000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	]	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	∟ SM660000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01140

## Host Code Page 1141-1/695-1 Austria, Germany

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ä LA170000	ü LU170000	Ö LO180000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	β LS610000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	{ SM110000	ë LE170000	[ SM060000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	@ SM050000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	~ SD190000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	Ä LA180000	Ü LU180000	ö LO170000	: SP130000	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	§ SM240000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	¡ SM650000	}	\	] SM080000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	, SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01141

## Host Code Page 1142-1/695-1 Denmark, Norway

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	 SM650000	@ SM050000	° SM190000	μ SM170000	¢ SC040000	æ LA510000	å LA270000	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	ü LU170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	} SM140000	ï LI170000	§ SC030000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	# SM010000	€ SC200000	ø LO610000	: SP130000	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	Å LA280000	, SP080000	Æ LA520000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ø LO620000	ð LD630000	{ SM110000	Ð LD620000	- SM150000	ö LO170000	~ SD190000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	, SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	[ SM060000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	] SM080000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01142

# Host Code Page 1143-1/695-1 Finland, Sweden

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ä LA170000	å LA270000	É LE120000	0 ND100000
<b>-1</b>	(RSP) SP300000	` SD130000	/ SP120000	\ SM070000	a LA010000	j LJ010000	ü LU170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	{ SM110000	ë LE170000	# SM010000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	[ SM060000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	} SM140000	ï LI170000	\$ SC030000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	é LE110000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	§ SM240000	€ SC200000	ö LO170000	:	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	Å LA280000	, SP080000	Ä LA180000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ö LO180000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	¡ SM650000	~ SD190000	@ SM050000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	] SM080000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01143



## Host Code Page 1144-1/695-1 Italy

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	[ SM060000	μ SM170000	¢ SC040000	à LA130000	è LE130000	ç LC410000	0 ND100000
<b>-1</b>	(RSP) SP300000	] SM080000	/ SP120000	É LE120000	a LA010000	j LJ010000	ì LI130000	# SM010000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	{ SM110000	} SM140000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	@ SM050000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	\ SM070000	~ SD190000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	ù LU130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	° SM190000	é LE110000	ò LO130000	: SP130000	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	£ SC020000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	§ SM240000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	, SD410000	Ý LY120000	¨ SD170000	¡ SM650000	` SD130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01144

## Host Code Page 1145-1/695-1 Latin America, Spain

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM140000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	á LA010000	¡ LJ010000	¨ SD170000	£ SC020000	À LA020000	Ê LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ı SM650000	ß LS610000	# SM010000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	]	ñ LN190000	: SP130000	« SP170000	à SM210000	ı SP030000	^ SD150000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	Ñ LN200000	» SP180000	ó SM200000	¿ SP160000	! SP020000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ð LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	~ SD190000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	¬ SM660000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01145

## Host Code Page 1146-1/695-1 United Kingdom

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	á LA010000	ĵ LJ010000	– SM150000	[ SM060000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	\$ SC030000	! SP020000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	^ SD150000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	£ SC020000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	] SM080000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	đ LD630000	æ LA510000	Ð LD620000	~ SD190000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	 SM130000	¬ SM660000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01146

# Host Code Page 1147-1/695-1 France

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	[ SM060000	` SD130000	¢ SC040000	é LE110000	è LE130000	ç LC410000	0 ND100000
-1	(RSP) SP300000	{ SM110000	/ SP120000	É LE120000	á LA010000	¡ LJ010000	¨ SD170000	# SM010000	À LA020000	Ê LJ020000	÷ SA060000	1 ND010000
-2	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
-3	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
-4	@ SM050000	}	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
-5	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	] SM080000	E LE020000	N LN020000	V LV020000	5 ND050000
-6	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
-7	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
-8	\ SM070000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	ñ LN190000	ß LS610000	Ñ LN200000	μ SM170000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	° SM190000	§ SM240000	ù LU130000	:	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
-B	· SP110000	\$ SC030000	,	£ SC020000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
-C	< SA030000	* SM040000	% SM020000	à LA130000	đ LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
-D	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	~ SD190000	ò LO130000	¡ SM650000	Ò LO140000	Ù LU140000
-E	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
-F	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01147

## Host Code Page 1148-1/695-1 International

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	á LA010000	ĵ LJ010000	~ SD190000	£ SC020000	À LA020000	Ĵ LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	]	¡ SM650000	:	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	,	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	đ LD630000	æ LA510000	Ð LD620000	- SM150000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	þ LT630000	Æ LA520000	Þ LT640000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01148

## Host Code Page 1149-1/695-1 Iceland

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	þ LT630000	æ LA510000	' SD110000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	ö LO170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	Ð LD630000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	þ LT640000	Æ LA520000	ı SM650000	: SP130000	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ð LD620000	` SD130000	}	@ SM050000	- SM150000	~ SD190000	ü LU170000	^ SD150000	Û LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	, SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	{ SM110000	] SM080000	[ SM060000	\ SM070000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	Ö LO180000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01149

## Host Code Page 1153/1375 Latin 2 - EBCDIC Multilingual

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	∨ SD210000	˘ SD230000	◊ SM190000	ą LA430000	· SD290000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	Ą LA440000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ę LE430000	Â LA160000	Ę LE440000	b LB010000	k LK010000	s LS010000	ż LZ290000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	Ť LT420000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	ı LT410000	û LU270000	" SD250000	Û LU280000	d LD010000	m LM010000	u LU010000	Ź LZ300000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ă LA230000	î LI150000	Ă LA240000	Î LI160000	f LF010000	o LO010000	w LW010000	ż LZ210000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	č LC210000	ř LL210000	Č LC220000	Ř LL220000	g LG010000	p LP010000	x LX010000	ź LZ110000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	í LL110000	Ç LC420000	Í LL120000	h LH010000	q LQ010000	y LY010000	Ź LZ220000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ć LC110000	ß LS610000	Ć LC120000	` SD130000	i LI010000	r LR010000	z LZ010000	Ż LZ120000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	]	 SM130000	:	ś LS110000	ł LL610000	Ś LS120000	Ł LL620000	(SHY) SP320000	Ě LE220000	ď LD210000	Ď LD220000
<b>-B</b>	· SP110000	\$ SC030000	,	# SM010000	ň LN210000	ń LN110000	Ń LN220000	Ň LN120000	ô LO150000	ů LU250000	Ô LO160000	Ů LU260000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	đ LD610000	š LS210000	Đ LD600000	Š LS220000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ý LY110000	‚ SD410000	Ý LY120000	“ SD170000	í LR110000	ř LT210000	Ř LR120000	Ť LT220000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ř LR210000	ċ SD430000	Ř LR220000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	ş LS410000	€ SC200000	Ş LS420000	× SA070000	ő LO250000	ě LE210000	Ő LO260000	(EO)

Code Page 01153

## Host Code Page 1154/1381 Cyrillic

The column indicates the first digit, and the row indicates the second digit. If this code page is not used with a Cyrillic host machine, certain characters might not display properly.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	Ъ KN120000	Ц KC010000	Й KJ110000	Я KA150000	Ь KX110000	{ SM110000	}	\ SM070000	0 ND100000
-1	(RSP) SP300000	Љ KL410000	/ SP120000	Ѡ KC120000	а LA010000	ј LJ010000	~ SD190000	Ы KY010000	А LA020000	Ј LJ020000	€ SC200000	1 ND010000
-2	ђ KD610000	њ KN110000	ѓ KG120000	ќ KK120000	б LB010000	к LK010000	ѕ LS010000	з KZ010000	В LB020000	К LK020000	Ѕ LS020000	2 ND020000
-3	ѓ KG110000	ћ KC110000	Ё KE180000	(SHY) SP320000	с LC010000	l LL010000	t LT010000	ш KS210000	С LC020000	Л LL020000	Т LT020000	3 ND030000
-4	ё KE170000	ќ KK110000	Є KE160000	Ў KU240000	d LD010000	m LM010000	u LU010000	э KE130000	Д LD020000	М LM020000	У LU020000	4 ND040000
-5	є KE150000	ђ KU230000	Ѕ KZ160000	Ц KG220000	e LE010000	n LN010000	v LV010000	ш KS150000	Е LE020000	Н LN020000	В LV020000	5 ND050000
-6	s KZ150000	ц KG210000	І KI120000	Ю KU150000	f LF010000	o LO010000	w LW010000	ч KC210000	Ф LF020000	О LO020000	W LW020000	6 ND060000
-7	i KI110000	Ъ KU220000	Ї KI180000	а KA010000	g LG010000	p LP010000	x LX010000	ь KU210000	Г LG020000	Р LP020000	Х LX020000	7 ND070000
-8	ï KI170000	№ SM000000	Ј KJ020000	б KB010000	h LH010000	q LQ010000	y LY010000	Ю KU160000	Н LH020000	Q LQ020000	У LY020000	8 ND080000
-9	j KJ010000	Ѣ KD620000	Љ KL420000	` SD130000	i LI010000	r LR010000	z LZ010000	А KA020000	І LI020000	Р LR020000	З LZ020000	9 ND090000
-A	[ SM060000	]	 SM130000	: SP130000	д KD010000	к KK010000	р KR010000	Б KB020000	Х KH020000	Н KN020000	Т KT020000	З KZ020000
-B	. SP110000	\$ SC030000	, SP080000	# SM010000	е KE010000	л KL010000	с KS010000	Ц KC020000	И KI020000	О KO020000	У KU020000	Ш KS220000
-C	< SA030000	* SM040000	% SM020000	@ SM050000	ф KF010000	м KM010000	т KT010000	Д KD020000	Й KJ120000	П KP020000	Ж KZ220000	Э KE140000
-D	( SP060000	) SP070000	_ SP090000	' SP050000	г KG010000	н KN010000	у KU010000	Е KE020000	К KK020000	Я KA160000	В KV020000	Щ KS160000
-E	+ SA010000	; SP140000	> SA050000	= SA040000	х KH010000	о KO010000	ж KZ210000	Ф KF020000	Л KL020000	Р KR020000	Ь KX120000	Ч KC220000
-F	! SP020000	^ SD150000	? SP150000	" SP040000	и KI010000	п KP010000	в KV010000	Г KG020000	М KM020000	С KS020000	Ы KY020000	(EO)

Code Page 01154



## Host Code Page 1155/1378 Latin 5 - Turkey

The column indicates the first digit, and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ç LC410000	ğ LG230000	ü LU170000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	ö LO170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	{ SM110000	ì LI130000	[ SM060000	Ì LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	ı LI610000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	Ç LC420000	Ĝ LG240000	Ş LS410000	:	« SP170000	ª SM210000	ı SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	İ LI300000	, SP080000	Ö LO180000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ş LS420000	}	æ LA510000	] SM080000	- SD310000	~ SD190000	\ SM070000	# SM010000	" SP040000
<b>-D</b>	( SP060000	) SP070000	— SP090000	’ SP050000	` SD130000	´ SD410000	\$ SC030000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ı SM650000	Æ LA520000	@ SM050000	’ SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	Ü LU180000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01155

# Host Code Page 1156/1393 Latvia, Lithuania

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	^ SD150000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	á LA010000	ĵ LJ010000	~ SD190000	£ SC020000	À LA020000	Ĵ LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	š LS210000	ę LE430000	Š LS220000	Ę LE440000	b LB010000	k LK010000	s LS010000	ī LI310000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	è LE290000	Ä LA180000	È LE300000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	ą LA430000	č LC210000	Ą LA440000	Č LC220000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	ì LI430000	ų LU430000	Į LI440000	Ų LU440000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ū LU310000	” SP230000	Ū LU320000	Ī LI320000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	ą LA270000	“ SP210000	Ą LA280000	Ł LL420000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ē LE310000	ġ LG410000	Ē LE320000	Ģ LG420000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ž LZ210000	ß LS610000	Ž LZ220000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	¢ SC040000	! SP020000	¡ SM650000	: SP130000	« SP170000	Ŕ LR420000	” SP220000	[ SM060000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	ŗ LR410000	ż LZ110000	] SM080000	ō LO310000	ć LC110000	ō LO320000	Ć LC120000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ā LA310000	æ LA510000	Ā LA320000	Ž LZ120000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	ż LZ290000	ķ LK410000	Ž LZ300000	Ķ LK420000	ņ LN410000	ł LL610000	Ń LN420000	Ł LL620000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ń LN110000	Æ LA520000	Ń LN120000	↓ LL410000	ó LO110000	ś LS110000	Ó LO120000	Ś LS120000
<b>-F</b>	 SM130000	⌋ SM660000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	õ LO190000	' SP200000	Õ LO200000	(EO)

Code Page 01156

## Host Code Page 1157/1391 Estonia

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	ä LA170000	å LA270000	É LE120000	0 ND100000
<b>-1</b>	(RSP) SP300000	` SD130000	/ SP120000	\ SM070000	a LA010000	j LJ010000	ü LU170000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	{ SM110000	ë LE170000	# SM010000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	[ SM060000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ã LA190000	î LI150000	Ã LA200000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	} SM140000	ï LI170000	\$ SC030000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ì LI130000	Ç LC420000	Ï LI140000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	é LE110000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	§ SM240000	€ SC200000	ö LO170000	:	« SP170000	ä SM210000	ï SP030000	¬ SM660000	(SHY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	Å LA280000	, SP080000	Ä LA180000	» SP180000	ó SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	Ö LO180000	š LS210000	æ LA510000	Š LS220000	- SD310000	¡ SM650000	~ SD190000	@ SM050000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	ý LY110000	¸ SD410000	Ý LY120000	¨ SD170000	ò LO130000	ù LU130000	Ò LO140000	Ù LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	ž LZ210000	Æ LA520000	Ž LZ220000	' SD110000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	] SM080000	® SM530000	× SA070000	õ LO190000	ÿ LY170000	Õ LO200000	(EO)

Code Page 01157

## Host Code Page 1158/1388 Ukraine

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	Ь KN120000	ц KC010000	й KJ110000	я KA150000	ь KX110000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	Љ KL410000	/ SP120000	Ѡ KC120000	а LA010000	ј LJ010000	~ SD190000	ы KY010000	А LA020000	Ј LJ020000	€ SC200000	1 ND010000
<b>-2</b>	ђ KD610000	њ KN110000	Г KG300000	Ѓ KK120000	б LB010000	к LK010000	ѕ LS010000	з KZ010000	В LB020000	К LK020000	Ѕ LS020000	2 ND020000
<b>-3</b>	г KG290000	ћ KC110000	Ё KE180000	(SHY) SP320000	с LC010000	l LL010000	t LT010000	ш KS210000	С LC020000	Л LL020000	Т LT020000	3 ND030000
<b>-4</b>	ё KE170000	ќ KK110000	Є KE160000	Ў KU240000	d LD010000	m LM010000	u LU010000	э KE130000	Д LD020000	М LM020000	U LU020000	4 ND040000
<b>-5</b>	є KE150000	ђ KU230000	Ѕ KZ160000	Ц KG220000	e LE010000	n LN010000	v LV010000	щ KS150000	Е LE020000	Н LN020000	В LV020000	5 ND050000
<b>-6</b>	s KZ150000	ц KG210000	І KI120000	ю KU150000	f LF010000	o LO010000	w LW010000	ч KC210000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	i KI110000	Ђ KU220000	Ї KI180000	а KA010000	g LG010000	p LP010000	x LX010000	ь KU210000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ï KI170000	№ SM000000	J KJ020000	б KB010000	h LH010000	q LQ010000	y LY010000	Ю KU160000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	j KJ010000	Ђ KD620000	Љ KL420000	` SD130000	i LI010000	r LR010000	z LZ010000	А KA020000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	]	 SM130000	:	д KD010000	к KK010000	р KR010000	Б KB020000	X KH020000	Н KN020000	Т KT020000	З KZ020000
<b>-B</b>	. SP110000	\$ SC030000	, SP080000	# SM010000	е KE010000	л KL010000	с KS010000	Ц KC020000	И KI020000	О KO020000	У KU020000	Ш KS220000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	ф KF010000	м KM010000	т KT010000	Д KD020000	Й KJ120000	П KP020000	Ж KZ220000	Э KE140000
<b>-D</b>	( SP060000	) SP070000	_ SP090000	' SP050000	г KG010000	н KN010000	у KU010000	Е KE020000	К KK020000	Я KA160000	В KV020000	Щ KS160000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	х KH010000	о KO010000	ж KZ210000	Ф KF020000	Л KL020000	Р KR020000	Ь KX120000	Ч KC220000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	и KI010000	п KP010000	в KV010000	Г KG020000	М KM020000	С KS020000	Ы KY020000	(EO)

Code Page 01158

# Host Code Page 1160/1395 Thailand

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
-0	(SP) SP010000	& SM030000	- SP100000	฿ SC130000	◎ BQ400000	๓ BQ500000	๕ BQ600000	○ ND100002	{ SM110000	}	\ SM070000	0 ND100000
-1	(RSP) SP300000	' BZ100300	/ SP120000	ˆ BE400000	a LA010000	j LJ010000	~ SD190000	๑ ND010002	A LA020000	J LJ020000	๗ BZ300300	1 ND010000
-2	ก BK100000	ข BC100000	ฃ BT100000	ด BT600000	b LB010000	k LK010000	s LS010000	๒ ND020002	B LB020000	K LK020000	S LS020000	2 ND020000
-3	ข BK200000	ฃ BX100000	ฅ BT200000	ท BT700000	c LC010000	l LL010000	t LT010000	๓ ND030002	C LC020000	L LL020000	T LT020000	3 ND030000
-4	ข BK300000	ช BS100000	ฑ BT300000	ธ BT800000	d LD010000	m LM010000	u LU010000	๔ ND040002	D LD020000	M LM020000	U LU020000	4 ND040000
-5	ค BK400000	ช BX200000	ฒ BT400000	น BN300000	e LE010000	n LN010000	v LV010000	๕ ND050002	E LE020000	N LN020000	V LV020000	5 ND050000
-6	ค BK500000	ฌ BX300000	ณ BN200000	บ BB100000	f LF010000	o LO010000	w LW010000	๖ ND060002	F LF020000	O LO020000	W LW020000	6 ND060000
-7	ฌ BK600000	ญ BY100000	ด BD200000	ป BP100000	g LG010000	p LP010000	x LX010000	๗ ND070002	G LG020000	P LP020000	X LX020000	7 ND070000
-8	ง BN100000	ฌ BD100000	ต BT500000	ฝ BP200000	h LH010000	q LQ010000	y LY010000	๘ ND080002	H LH020000	Q LQ020000	Y LY020000	8 ND080000
-9	[ SM060000	] SM080000	^ SD150000	` SD130000	i LI010000	r LR010000	z LZ010000	๙ ND090002	I LI020000	R LR020000	Z LZ020000	9 ND090000
-A	๕ SC040000	! SP020000	! SM650000	: SP130000	ฝ BF100000	ร BR100000	ช BS300000	๗ BQ200000	๗ BZ200300	• BQ300000	๓ BA700000	+ BZ400000
-B	. SP110000	\$ SC030000	, SP080000	# SM010000	พ BP300000	ถ BR200000	ส BS400000	๘ BA200000	๘ BI200000	๒ BE200000	๓ BQ100000	๕ BZ500000
-C	< SA030000	* SM040000	% SM020000	@ SM050000	ฟ BF200000	ล BL100000	ห BH100000	๙ BA100000	๘ BU100000	๒ BE300000	๘ BE100000	๐ BN400000
-D	( SP060000	) SP070000	_ SP090000	' SP050000	ภ BP400000	ภ BL200000	พ BL300000	๓ BA300000	๘ BU200000	๖ BO200000	' BZ100000	+ BZ400300
-E	+ SA010000	; SP140000	> SA050000	= SA040000	ม BM100000	ว BW100000	อ BO100000	๓ BA400000	๙ BU300000	๖ BA500000	๗ BZ200000	€ SC200000
-F	 SM130000	๓ SM660000	? SP150000	" SP040000	ย BY200000	ค BS200000	๓ BH200000	๓ BI100000	๗ BU400000	๖ BA600000	๗ BZ300000	(EO)

Code Page 01160

# Host Code Page 1164/1397 Vietnam

The column indicates the first digit and the row indicates the second digit.

HEX DIGITS 1ST → 2ND ↓	4-	5-	6-	7-	8-	9-	A-	B-	C-	D-	E-	F-
<b>-0</b>	(SP) SP010000	& SM030000	- SP100000	ø LO610000	Ø LO620000	° SM190000	μ SM170000	¢ SC040000	{ SM110000	}	\ SM070000	0 ND100000
<b>-1</b>	(RSP) SP300000	é LE110000	/ SP120000	É LE120000	a LA010000	j LJ010000	~ SD190000	£ SC020000	A LA020000	J LJ020000	÷ SA060000	1 ND010000
<b>-2</b>	â LA150000	ê LE150000	Â LA160000	Ê LE160000	b LB010000	k LK010000	s LS010000	¥ SC050000	B LB020000	K LK020000	S LS020000	2 ND020000
<b>-3</b>	ä LA170000	ë LE170000	Ä LA180000	Ë LE180000	c LC010000	l LL010000	t LT010000	· SD630000	C LC020000	L LL020000	T LT020000	3 ND030000
<b>-4</b>	à LA130000	è LE130000	À LA140000	È LE140000	d LD010000	m LM010000	u LU010000	© SM520000	D LD020000	M LM020000	U LU020000	4 ND040000
<b>-5</b>	á LA110000	í LI110000	Á LA120000	Í LI120000	e LE010000	n LN010000	v LV010000	§ SM240000	E LE020000	N LN020000	V LV020000	5 ND050000
<b>-6</b>	ă LA230000	î LI150000	Ă LA240000	Î LI160000	f LF010000	o LO010000	w LW010000	¶ SM250000	F LF020000	O LO020000	W LW020000	6 ND060000
<b>-7</b>	å LA270000	ï LI170000	Å LA280000	Ï LI180000	g LG010000	p LP010000	x LX010000	¼ NF040000	G LG020000	P LP020000	X LX020000	7 ND070000
<b>-8</b>	ç LC410000	ñ SD198000	Ç LC420000	Đ SC180000	h LH010000	q LQ010000	y LY010000	½ NF010000	H LH020000	Q LQ020000	Y LY020000	8 ND080000
<b>-9</b>	ñ LN190000	ß LS610000	Ñ LN200000	` SD130000	i LI010000	r LR010000	z LZ010000	¾ NF050000	I LI020000	R LR020000	Z LZ020000	9 ND090000
<b>-A</b>	[ SM060000	] SM080000	¡ SM650000	: SP130000	« SP170000	ª SM210000	ï SP030000	¬ SM660000	(SĦY) SP320000	1 ND011000	2 ND021000	3 ND031000
<b>-B</b>	· SP110000	\$ SC030000	, SP080000	# SM010000	» SP180000	º SM200000	¿ SP160000	 SM130000	ô LO150000	û LU150000	Ô LO160000	Û LU160000
<b>-C</b>	< SA030000	* SM040000	% SM020000	@ SM050000	đ LD610000	æ LA510000	Ð LD600000	- SD310000	ö LO170000	ü LU170000	Ö LO180000	Ü LU180000
<b>-D</b>	( SP060000	) SP070000	— SP090000	' SP050000	◌ SD918000	Œ LO520000	◌ SD458000	œ LO510000	ƒ LU910000	ù LU130000	Ɔ LU920000	Û LU140000
<b>-E</b>	+ SA010000	; SP140000	> SA050000	= SA040000	◌ SD138000	Æ LA520000	◌ SD118000	ÿ LY180000	ó LO110000	ú LU110000	Ó LO120000	Ú LU120000
<b>-F</b>	! SP020000	^ SD150000	? SP150000	" SP040000	± SA020000	€ SC200000	® SM530000	× SA070000	σ LO910000	ÿ LY170000	Œ LO920000	(EO)

Code Page 01164

---

## Appendix. Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing  
IBM Corporation  
500 Columbus Avenue  
Thornwood, NY 10594  
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106, Japan

**The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:**

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM documentation or non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those documents or Web sites. The materials for those documents or Web sites are not part of the materials for this IBM product and use of those documents or Web sites is at your own risk.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created

programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation  
Department T01  
Building 062  
P.O. Box 12195  
RTP, NC 27709-2195  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

All statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrates programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. You may copy, modify, and distribute these sample programs in any form without payment to IBM for the purposes of developing, using, marketing, or distributing application programs conforming to IBM's application programming interfaces.

---

## Trademarks

The following terms are trademarks of the IBM Corporation in the United States, or other countries, or both:

IBM

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.







Program Number: 5639-I70

Printed in USA